fread

Reads up to count objects into the array buffer from the given input stream as if by calling fgetc size times for each object, and storing the results, in the order obtained, into the successive positions of buffer, which is reinterpreted as an array of unsigned char. The file position indicator for the stream is advanced by the number of characters read.

If an error occurs, the resulting value of the file position indicator for the stream is indeterminate. If a partial element is read, its value is indeterminate.

Parameters

```
buffer - pointer to the array where the read objects are stored
size - size of each object in bytes
count - the number of the objects to be read
stream - the stream to read
```

Return value

Number of objects read successfully, which may be less than count if an error or end-of-file condition occurs.

If size or count is zero, fread returns zero and performs no other action.

fread does not distinguish between end-of-file and error, and callers must use feof and ferror to determine which occurred.

Example

Run this code

```
#include <stdio.h>
enum { SIZE = 5 };
int main(void)
    double a[SIZE] = {1.,2.,3.,4.,5.};
FILE *fp = fopen("test.bin", "wb"); // must use binary mode
fwrite(a, sizeof *a, SIZE, fp); // writes an array of doubles
    fclose(fp);
    double b[SIZE];
    fp = fopen("test.bin","rb");
    size_t ret_code = fread(b, sizeof *b, SIZE, fp); // reads an array of doubles
    if(ret code == SIZE) {
         puts("Array read successfully, contents: ");
         for(int n = 0; n < SIZE; ++n) printf("%f ", b[n]);
         putchar('\n');
    } else { // error handling
        if (feof(fp))
            printf("Error reading test.bin: unexpected end of file\n");
        else if (ferror(fp)) {
             perror("Error reading test.bin");
        }
    }
    fclose(fp);
}
```

Output:

```
Array read successfully, contents: 1.000000 2.000000 3.000000 4.000000 5.000000
```

References

- C17 standard (ISO/IEC 9899:2018):
 - 7.21.8.1 The fread function (p: 243-244)
- C11 standard (ISO/IEC 9899:2011):
 - 7.21.8.1 The fread function (p: 335)
- C99 standard (ISO/IEC 9899:1999):
 - 7.19.8.1 The fread function (p: 301)
- C89/C90 standard (ISO/IEC 9899:1990):
 - 4.9.8.1 The fread function

See also

scanf fscanf sscanf scanf_s (C11) fscanf_s (C11) sscanf_s (C11)	reads formatted input from stdin, a file stream or a buffer (function)
fgets	gets a character string from a file stream (function)
fwrite	writes to a file (function)

Retrieved from "https://en.cppreference.com/mwiki/index.php?title=c/io/fread&oldid=135093"