

Knowledge Base Item 7604—Installation, Upgrade, and Configuration Procedures for Autonomy DRE 4.3.3

Summary:	This KB describes: • How to install Autonomy DRE 4.3.3 from scratch (new users) • Upgrade Autonomy DRE from 3.x to 4.3.3 (existing users) • Various procedures for common tasks
Audience:	Administrators of the Vignette Multisite Content Manager (VMCM)
Prerequisites:	• Installed Vignette Content Management Server (VCMS) version 6.0.8 or higher • Installed Vignette Multisite Content Manager (VMCM) version 3.0.5 or higher
Topics include:	• Introduction • Re-indexing the 3.x content • Stopping Autonomy DRE 3.x • Installing Autonomy DRE 4.3.3 • Testing Autonomy DRE 4.3.3 • Indexing the .idx file into Autonomy DRE 4.3.3 • Configuring Autonomy DRE 4.3.3 • Uninstalling Autonomy DRE 3.x • Stopping and Starting the Autonomy DRE • Executing Autonomy DRE Configuration Changes with DRERESET • Adding and Deleting Autonomy DRE databases • Uninstalling Autonomy DRE 4.3.3
See also:	• <i>Vignette V6 Multisite Content Manager Installation and Configuration Guide</i> • BEA's official documentation for DRE 4, available on-line at http://edocs.bea.com/wlp/docs81/

NOTE: Autonomy DRE 3.x is not supported on Windows 2003. If you plan to run Windows 2003, you must install Autonomy DRE 4.3.3.

Introduction

The 3.0.5 patch release of VMCM (Vignette Multisite Content Manager) contains Autonomy DRE 4.3.3. This Knowledge Base article contains information about:

- Installing Autonomy DRE 4.3.3 from scratch
- Upgrading Autonomy DRE from release 3.x to release 4.3.3
- Configuration and automation procedures new with release 4.3.3

NOTE: This document frequently refers to Autonomy DRE version 3.x, which refers to any release of version 3.

■ To install Autonomy DRE 4.3.3 from scratch:

Administrators installing Autonomy DRE 4.3.3 from scratch should complete the following steps (described in detail below):

- [Installing Autonomy DRE 4.3.3 on page 4](#)
- [Testing Autonomy DRE 4.3.3 on page 5](#)

■ To upgrade from Autonomy DRE 3.x to Autonomy DRE 4.3.3:

Administrators currently running Autonomy DRE 3.x who wish to upgrade to Autonomy DRE 4.3.3 should complete the following steps (described in detail below):

- [Re-indexing the 3.x content on page 2](#)
- [Stopping Autonomy DRE 3.x on page 3](#)
- [Installing Autonomy DRE 4.3.3 on page 4](#)
- [Testing Autonomy DRE 4.3.3 on page 5](#)
- [Indexing the .idx file into Autonomy DRE 4.3.3 on page 5](#)
- [Uninstalling Autonomy DRE 3.x on page 7](#)

Re-indexing the 3.x content

NOTE: This procedure is only required for upgrade installations.

The 4.3.3 version of the Autonomy DRE process (Dynamic Reasoning Engine) cannot read databases created by 3.x versions of the Autonomy DRE.

Customers must therefore re-index 3.x content before migrating data to 4.3.3. The re-indexing process requires that you have stored the plain-text content in the Autonomy DRE database.

■ **To re-index the Autonomy DRE content:**

Enter the following command in the address field of your web browser:

```
http://host:queryport/qmethod=G&xoptions=nocombine+outfile=alldocs.idx
```

- *host*: The IP address (or name) of the machine on which your 3.x Autonomy DRE is running.
- *queryport*: The port number by which queries are sent to the Autonomy DRE.
- *alldocs.idx*: The path and filename for the file in which you want the content of your old Autonomy DRE to be stored. If the file already exists, verify that it is in the idx file format.

Autonomy DRE creates the `.idx` file, which contains the Autonomy DRE's plain-text content. For example, the following command creates a `dre3indexdata.idx` file that contains all indexed data for the 3.x Autonomy DRE on localhost:

```
http://localhost:2000/qmethod=G&xoptions=nocombine+
outfile=c:\db\dre3indexdata.idx
```

After you've indexed your 3.x data, uninstall Autonomy DRE 3.x.

Stopping Autonomy DRE 3.x

Before installing Autonomy DRE 4.3.3, make sure to stop any previous version of the Autonomy DRE.

■ **Stopping the Autonomy DRE process (Windows):**

- 1 Navigate from the Control Panel to the Administrative Tools.
- 2 Open the Services console
- 3 Right-click the Autonomy DRE process and choose **Stop**.

■ **Stopping the Autonomy DRE process (AIX/Solaris):**

- 1 Log in to the Autonomy DRE host as the Vignette files owner.

NOTE: The *Vignette files owner* is the user you designated as the owner of the VCMS files and processes when you installed the VCMS. In other words, this is the user that starts and stops VCMS processes (and sometimes the web server and other third-party software as well). For more information, see the section on Solaris permissions requirements in Chapter 7, Installation—Solaris, in the *VCMS Installation and Configuration Guide*.

2 Kill the Autonomy DRE process, as follows:

a Enter the following command:

```
ps -ef | grep myAutonomyDre
```

where *myAutonomyDre* is the name of the Autonomy DRE executable file (that is, the name you gave to the Autonomy DRE process when you started it)

This command displays the process ID (PID) for the Autonomy DRE process.

b Enter the following command:

```
kill -9 PID
```

where *PID* is the ID you obtained in the previous step.

Installing Autonomy DRE 4.3.3

The procedures for installing Autonomy DRE appear in the *Multisite Content Manager Installation and Configuration Guide*. The procedures have not changed since the last update of that guide.

Choose the install option from VMCM version 3.0.5 and follow the steps as they appear in the GUI.

After installation, Windows users will find two services: VMCM_DRE and VgnAutoIndexer. AIX/Solaris users will find processes with those same names.

NOTE: The AutoIndexer service (process) is new with Autonomy DRE 4.3.3. Autonomy DRE 3.x did not include the AutoIndexer.

Testing Autonomy DRE 4.3.3

After installing Autonomy DRE, check whether the DRE and AutoIndexer services (processes) are installed and running.

■ To check that DRE is installed and running:

Enter the following command in the address field of your web browser:

```
http://host:port/action=Help
```

- *host*: The IP address (or name) of the machine on which your 4.x Autonomy DRE is installed.
- *port*: The port that client machines use to communicate with the Autonomy DRE. (See the `Port` setting in the [Server] section of the Autonomy DRE configuration file: `VMCM_DRE.cfg`.)

For example: `http://localhost:2000/action=Help`

If the service is running, the Help page displays.

■ To check that AutoIndexer is installed and running:

Enter the following command in the address field of your web browser:

```
http://ip-address:port/action=GetStatus
```

- *ip-address*: The IP address of the machine on which AutoIndexer is located.
- *port*: The port on which AutoIndexer listens for service commands. (See the `ServicePort` setting in the [Server] section of the AutoIndexer configuration file: `VgnAutoIndexer.cfg`.)

For example: `http://localhost:10224/action=GetStatus`

A page displays to indicate whether the service is running.

Indexing the .idx file into Autonomy DRE 4.3.3

NOTE: This procedure is only required for upgrade installations.

After installing Autonomy DRE 4.3.3, you must index the .idx file that you created into the new installation.

■ **To index the .idx file into Autonomy DRE 4.3.3:**

Enter the following command in the address field of your web browser:

`http://host:port/DREADD?file_name`

- *host*: The IP address or name of the machine on which the Autonomy DRE is installed.
- *port*: The port used to index files into to the Autonomy DRE.
- *file_name*: The IDX or XML file that you want to index.

For example:

`http://localhost:3001/DREADD?c:\db\dre3indexdata.idx`

Configuring Autonomy DRE 4.3.3

To configure Autonomy DRE 4.3.3 edit the `VMCM_DRE.cfg` and `VgnAutoIndexer.cfg` configuration files. On Windows, for example:

`C:\Autonomy\VMCM_DRE\VMCM_DRE.cfg`

and

`C:\Autonomy\VgnAutoindexer\VgnAutoindexer.cfg`

Configuration information for Autonomy DRE is available online. Simply issue the following command from your web browser:

`http://host:port/action=Help`

- *host*: The IP address (or name) of the machine on which the Autonomy DRE is installed.
- *port*: The port number that client machines use to communicate with the Autonomy DRE. See the `Port` setting in the `[Server]` section of the Autonomy DRE configuration, for example `\VgnDRE\VMCM_DRE.cfg`.

For example: `http://localhost:3002/action=Help`

Next, click the **Configuration Help** link in the top right-hand corner to display the configuration parameter help. (By default, the screen will display the `action` command help.) The configuration parameters display in the left pane. Choosing from the list displays complete details about the parameter,

including **Allowed in Sections**, which displays the sections of the configuration file where the particular parameter is allowed.

NOTE: Causing your configuration changes to take effect requires either:

- [Stopping and Starting the Autonomy DRE](#), or
- [Executing Autonomy DRE Configuration Changes with DRERESET](#)

Uninstalling Autonomy DRE 3.x

NOTE: This procedure is only required for administrators upgrading from 3.x to 4.3.3. If you have already installed Autonomy DRE 4.3.3 and want to remove it, see [Uninstalling Autonomy DRE 4.3.3 on page 11](#).

The following section describes the uninstall procedure, first for Windows then for AIX/Solaris. After you complete the platform-specific procedure, manually remove the files from the installation directory. Each of the procedures is described below.

NOTE: The script file discussed in this section removes only the default Autonomy DRE search engine configuration. If you added custom locations (such as paths to index files), these custom locations will not be removed. You must remove any custom locations manually.

■ Removing the Autonomy DRE 3.x Service (Windows):

- 3 Open a command window.
- 4 Change to the directory where `AutonomyRemove.bat` is located.

You specified this directory when you installed the Autonomy DRE. See the *Multisite Content Manager Installation and Configuration Guide* for details.

- 5 Enter the following command in the command window:

```
AutonomyRemove autonomy-home dre-service-name
```

where *autonomy-home* is the absolute file system path to the current folder (that is, the folder containing `AutonomySetup.bat` and `AutonomyRemove.bat`), and *dre-service-name* is the name of the Autonomy DRE service.

Note that the Autonomy DRE service name is configurable. Enter the name you gave your 3.x installation. (Since VMCM patch 3.0.2, the default value

for *dre-service-name* has been VMCM_DRE. Prior to patch 3.0.2, the default value was VgnDRE.)

- 6 Follow the prompts on your screen to stop and then delete the Autonomy DRE service.

NOTE: Start the Services application in the Control Panel, press F5 to refresh the list of services, and if the status of the Autonomy DRE service is *Disabled*, you must restart your machine to completely remove the service. This is not required in all cases.

■ Stopping the Autonomy DRE process (AIX/Solaris):

- 1 Log in to the Autonomy DRE host as the Vignette files owner.

NOTE: The *Vignette files owner* is the user you designated as the owner of the VCMS files and processes when you installed the VCMS. In other words, this is the user that starts and stops VCMS processes (and sometimes the web server and other third-party software as well). For more information, see the section on Solaris permissions requirements in Chapter 7, Installation—Solaris, in the *VCMS Installation and Configuration Guide*.

- 2 Kill the Autonomy DRE process, as follows:

- a Enter the following command:

```
ps -ef | grep myAutonomyDre
```

where *myAutonomyDre* is the name of the Autonomy DRE executable file (that is, the name you gave to the Autonomy DRE process when you started it)

This command displays the process ID (PID) for the Autonomy DRE process.

- b Enter the following command:

```
kill -9 PID
```

where *PID* is the ID you obtained in the previous step.

■ Removing Files (on both Windows and AIX/Solaris):

Remove the files and directories beginning with the directory in which you installed Autonomy DRE. The Autonomy DRE installation directory contains the *AutonomySetup.sh* file (AIX/Solaris) or *Autonomy_Source_Install.bat* file (Windows).

Stopping and Starting the Autonomy DRE

You will periodically need to stop and start the Autonomy DRE, for example to save configuration changes or to add database tables.

■ To stop the Autonomy DRE:

- 1 In AIX/Solaris use the `stop` script. For example:
`autonomy/stop-VMCM_DRE.sh`

In Windows, navigate to the **Services** window (**Start Menu > Programs > Administrative Tools > Services**). Choose the **VgnDRE** service, and click the **Stop** button to stop the Autonomy DRE.

- 2 On either Windows or AIX/Solaris, send the stop command to the Autonomy DRE's service ports:

`http://host:Service_Port/action=stop`

- *host*: The IP address (or name) of the machine on which the Autonomy DRE is running.
- *Service_Port*: The Autonomy DRE's service port, specified in the [Service] section of the appropriate configuration file. For example: `http://localhost:10000/action=stop`

■ To start the Autonomy DRE:

- 1 In Solaris/AIX use the `start` script. For example:
`autonomy/start-VMCM_DRE.sh`

- 2 In Windows, navigate to the **Services** window (**Start Menu > Programs > Administrative Tools > Services**). Choose the **VgnDRE** service, and click the **Start** button to start the Autonomy DRE.

Executing Autonomy DRE Configuration Changes with DRERESET

After you make configuration changes, you can make them permanent by running the `DRERESET` command from your browser.

■ To execute configuration changes:

Use a browser to reset the Autonomy DRE:

`http://host:port/DRERESET?`

- *host*: The IP address (or name) of the machine on which the Autonomy DRE is running.
- *port*: The port used to index files into to the Autonomy DRE.

For example: `http://localhost:3001/DRERESET?`

Adding and Deleting Autonomy DRE databases

■ To create a new database in the Autonomy DRE:

Either add the database name to the Autonomy DRE configuration file, or use the MCM API to create the new database:

- Add the database name to Autonomy DRE configuration file:
`VMCM_DRE.cfg`.

For example, imagine that the `[Databases]` section of the configuration file lists three databases:

```
[Databases]
NumDBs=3
0=DEV
1=LIVE
2=ARCHIVE
```

To add a new database, add a new line to the list:

```
[Databases]
NumDBs=4
0=DEV
1=LIVE
2=ARCHIVE
3=NewDb
```

After adding the new database(s), reset the Autonomy DRE as described in [Stopping and Starting the Autonomy DRE on page 9](#).

- As an alternative to adding the database name to the Autonomy DRE configuration file, use the MCM API to create new the new database. (See `AutonomyDREUtilities.java`.)

■ To delete a database in the Autonomy DRE:

Either delete the database name from the Autonomy DRE configuration file, or use the MCM API to delete the new database:

- Remove the database name to the Autonomy DRE configuration file: `VMCM_DRE.cfg`.

For example, if you've added 3=NewDb to the [Databases] section of the `VMCM_DRE.cfg` configuration file, simply delete that entry from the list:

```
[Databases]
NumDBs=3
0=DEV
1=LIVE
2=ARCHIVE
```

After deleting the database, reset the Autonomy DRE as described in [Stopping and Starting the Autonomy DRE on page 9](#).

- As an alternative to deleting the database name to the Autonomy DRE configuration file, use the MCM API to delete the database. (See `AutonomyDREUtilities.java`.)

Uninstalling Autonomy DRE 4.3.3

The following section describes the uninstall procedure, first for Windows then for AIX/Solaris. Run the uninstall batch file (Windows) or script (AIX/Solaris).

NOTE: The script file discussed in this section removes only the default Autonomy DRE search engine configuration. If you added custom locations (such as paths to index files), these custom locations will not be removed. You must remove any custom locations manually.

■ Removing the Autonomy DRE Service (Windows):

- 1 Open a command window.
- 2 Change to the Autonomy DRE installation directory. For example:
`c:\Autonomy\`
- 3 Run the `uninstall.bat` file. The batch process removes both the DRE service and the AutoIndexer service: `VMCM_DRE` and `VgnAutoIndexer`.

