Variable Name	Variable Type	Variable Scope
lock_order_dependencies	File name	Global
lock_order_extra_dependencies	File name	Global
lock_order_output_directory	Directory name	Global
lock_order_print_txt	Boolean	Global
lock_order_trace_loop	Boolean	Global
lock_order_trace_missing_arc	Boolean	Global
lock_order_trace_missing_key	Boolean	Global
lock_order_trace_missing_unlock	Boolean	Global

- `lock_order`

Command-Line Format	`--lock-order[={OFF|ON}]`
Introduced	8.0.17
System Variable	`lock_order`
Scope	Global
Dynamic	No
`SET_VAR` Hint Applies	No
Type	Boolean
Default Value	`OFF`

Whether to enable the LOCK_ORDER tool at runtime. If `lock_order` is disabled (the default), no other LOCK_ORDER system variables have any effect. If `lock_order` is enabled, the other system variables configure which LOCK_ORDER features to enable.

If `lock_order` is enabled, an error is raised if the server encounters a lock-acquisition sequence that is not declared in the lock-order graph.

- `lock_order_debug_loop`

Command-Line Format	`--lock-order-debug-loop[={OFF|ON}]`
Introduced	8.0.17
System Variable	`lock_order_debug_loop`
Scope	Global
Dynamic	No
`SET_VAR` Hint Applies	No
Type	Boolean
Default Value	`OFF`

Whether the LOCK_ORDER tool causes a debug assertion failure when it encounters a dependency that is flagged as a loop in the lock-order graph.

- `lock_order_debug_missing_arc`

Command-Line Format	`--lock-order-debug-missing-arc[={OFF|ON}]`