you can tell whether or not mlockall() (and thus this option) is supported by checking to see whether or not it is defined in the system mman.h file, like this:

shell> grep mlockall /usr/include/sys/mman.h

If mlockall() is supported, you should see in the output of the previous command something like the following:

extern int mlockall (int __flags) __THROW;



Important

Use of this option may require you to run the server as root, which, for reasons of security, is normally not a good idea. See Section 6.1.5, "How to Run MySQL as a Normal User".

On Linux and perhaps other systems, you can avoid the need to run the server as root by changing the limits.conf file. See the notes regarding the memlock limit in Section 8.12.3.2, "Enabling Large Page Support".

You must not use this option on a system that does not support the mlockall() system call; if you do so, mysqld is very likely to exit as soon as you try to start it.

• --myisam-block-size=N

Command-Line Format	myisam-block-size=#
Туре	Integer
Default Value	1024
Minimum Value	1024
Maximum Value	16384

The block size to be used for MyISAM index pages.

• --no-defaults

Do not read any option files. If program startup fails due to reading unknown options from an option file, --no-defaults can be used to prevent them from being read. This must be the first option on the command line if it is used.

For additional information about this and other option-file options, see Section 4.2.2.3, "Command-Line Options that Affect Option-File Handling".

• --no-dd-upgrade

Command-Line Format	no-dd-upgrade[={OFF ON}]
Deprecated	8.0.16
Туре	Boolean
Default Value	OFF



Note

This option is deprecated as of MySQL 8.0.16. It is superseded by the -- upgrade option, which provides finer control over data dictionary and server upgrade behavior.