Field Name	Description
Parameters	Displayed parameters depend on the element type. These parameters are needed for each element:
	• Text
	The font value is displayed. For SBCS systems, the value is displayed as "FONT=F", where F is 0 for the default font or 1 - 8 for a specified font local ID. For text elements on DBCS systems, the value is displayed as "SBCS FONT=F" if the element does not have a DBCS font specified, and "SBCS FONT=F DBCS FONT=F" if the element does have a DBCS font specified. The text data is displayed after the font value. There are three spaces between the font value and the first text character.
	• Line
	End position is displayed.
	• Box
	End position is displayed. If text is specified with the box, the font value and the text are also displayed after the end position.
	Bar code
	If HRI is to be printed, the HRI font value is displayed. The bar code data follows the font value. There are three spaces between the font value and the bar code data.
	Page segment
	Page segment name is displayed.
	• Graphics
	End position is displayed.
	Record layout
	None.
	No input is allowed in this field. You can display other parameters when you change the element on the Change Detail display.

Create or Change the Element

You can not enter or change parameters directly on the list. However, you can define new elements or change existing elements through the create or change element operation easily and efficiently.

Create

To define a new element in the list view, do the following.

Step 1. Press one of the following function keys depending on the type of element regardless of the cursor position.

Text	F6
Line	F9
Box	F10
Bar Code	F11
Graphics	F13 then F6
Page segment	F13 then F9
Record layout	F13 then F11

The key entry area appears at the lower part of the display. The remainder of the create element operation is the same as that in the screen view.

Step 2. Press the F4 key to specify the other parameters if necessary.