### OS2::set\_control87\_em(new=MCW\_EM,mask=MCW\_EM)

The variant of OS2::\_control87() with default values good for handling exception mask: if no mask, uses exception mask part of new only. If no new, disables all the floating point exceptions.

See §117.10.7 for details.

### OS2::DLLname([how [, \&xsub]])

Gives the information about the Perl DLL or the DLL containing the C function bound to by &xsub. The meaning of how is: default (2): full name; 0: handle; 1: module name.

(Note that some of these may be moved to different libraries - eventually).

### 117.10.6 Prebuilt variables:

# \$ OS2::emx\_rev

numeric value is the same as \_emx\_rev of EMX, a string value the same as \_emx\_vprt (similar to 0.9c).

#### \$ OS2::emx env

same as \_emx\_env of EMX, a number similar to 0x8001.

### \$ OS2::os ver

```
a number OS_MAJOR + 0.001 * OS_MINOR.
```

### \$ OS2::is\_aout

true if the Perl library was compiled in AOUT format.

### \$ OS2::can\_fork

true if the current executable is an AOUT EMX executable, so Perl can fork. Do not use this, use the portable check for \$Config::Config{dfork}.

# \$ OS2::nsyserror

This variable (default is 1) controls whether to enforce the contents of \$^E to start with SYS0003-like id. If set to 0, then the string value of \$^E is what is available from the OS/2 message file. (Some messages in this file have an SYS0003-like id prepended, some not.)

# 117.10.7 Misfeatures

- Since *flock*(3) is present in EMX, but is not functional, it is emulated by perl. To disable the emulations, set environment variable USE\_PERL\_FLOCK=0.
- Here is the list of things which may be "broken" on EMX (from EMX docs):
  - The functions *recvmsg*(3), *sendmsg*(3), and *socketpair*(3) are not implemented.
  - sock\_init(3) is not required and not implemented.
  - flock(3) is not yet implemented (dummy function). (Perl has a workaround.)
  - kill(3): Special treatment of PID=0, PID=1 and PID=-1 is not implemented.
  - waitpid(3):

### WUNTRACED

Not implemented.

waitpid() is not implemented for negative values of PID.

Note that kill -9 does not work with the current version of EMX.

• See §117.13.1.