### Set Up CUPS Print Server on Ubuntu (Bonjour, IPP, Samba, AirPrint)

This tutorial will be showing you how to share a printer attached to an Ubuntu computer with Windows, macOS, and iOS clients on the same network. CUPS (Common Unix Printing System) is the default printing system on Linux, FreeBSD, and macOS. Your Linux desktop environment may have a dedicated printer configuration utility, but they all use CUPS under the hood.

CUPS printer can be shared on the network using several protocols, including:

- Bonjour + IPP: Bonjour, also known as mDNS/DNS-SD (multicast DNS/DNS service discovery), allows a computer to find services on the local network. IPP (Internet Printing Protocol) is the transport protocol.
- **SMB**: aka Samba, mainly used to share files and printers with Windows clients.
- **AirPrint**: Allows iPhone, iPad, and macOS clients to print over Wi-Fi.

Each protocol has its advantages and disadvantages. First, I will show you how to install and configure CUPS. Then we will learn how to share the CUPS printer via the above 3

protocols. I recommend using all 3 methods to share your printer, so users can find an available printer on the local network with minimal effort.



# **Step 1: Install and Configure CUPS on Ubuntu**

Ubuntu desktop edition has CUPS pre-installed. If you use Ubuntu server edition, you need to run the following command to install CUPS from the default Ubuntu repository.

sudo apt install cups

Then start CUPS.

sudo systemctl start cups

Enable auto-start at boot time.

sudo systemctl enable cups

Check its status:

#### systemctl status cups

#### Sample output:

```
linuxbabe@bionic:-$ systemctl status cups

○ cups.service - CUPS Scheduler
Loaded: loaded (/ltb/systemd/system/cups.service; enabled; vendor preset: ena
Active: active (running) since Mon 2020-03-02 06:50:49 CST; 24s ago
Docs: man:cupsd(8)

Main PID: 5273 (cupsd)
Tasks: 6 (limit: 4915)

CGroup: /system.slice/cups.service
-5273 /usr/sbin/cupsd -l
-5279 /usr/lib/cups/notifier/dbus dbus://
-5280 /usr/lib/cups/notifier/dbus dbus://
-5281 /usr/lib/cups/notifier/dbus dbus://
-5282 /usr/lib/cups/notifier/dbus dbus://
```

Next, edit the CUPS main configuration file with a command-line text editor like Nano.

```
sudo nano /etc/cups/cupsd.conf
```

First, we need to show shared printers on the local network. Find the following line.

Browsing Off

Change it to

Browsing On

so other computers in the same network can see printers connected to your Ubuntu computer.

By default, the CUPS web interface is only available at localhost:631. If you are running Ubuntu server edition, you may also want to make CUPS listen on all available network interface, so that you will be able to access the CUPS web interface from other computers. Find the following line.

Listen localhost:631

Change it to

Port 631

So CUPS will listen on all network interfaces. Then find the following lines.

```
<Location />
  Order allow,deny
</Location>
```

The above configuration allows access to the CUPS web interface from localhost only. To allow access from other computers in the same network, add Allow @LOCAL to the configuration like below.

```
<Location />
  Order allow,deny
  Allow @LOCAL
</Location>
```

Also add it for the /admin directory to allow remote administration from local network.

```
<Location /admin>
  Order allow, deny
  Allow @LOCAL
</Location>
```

You can also allow a particular IP address like so:

```
<Location />
  Order allow, deny
  Allow 192.168.0.101
```

Save and close the file. Then restart CUPS for the changes to take effect.

```
sudo systemctl restart cups
```

Note that if you have enabled the <u>UFW firewall</u> on Ubuntu, you need to allow clients in the same network to access port 631 on your Ubuntu box. For example, my private network is using the 192.168.0.0 ~192.168.0.255 network range, so I run the following command.

```
sudo ufw allow in from 192.168.0.0/2
4 to any port 631
```

The CUPS web interface is available at https://IP-address-of-Ubuntu-box:631. We don't need to use the web interface in this article, but if you want to use it, then you need to add your user account to the lpadmin group in order to make changes in the CUPS web interface.

sudo adduser your\_username lpadmin

### Step 2: Install Driver for Your Printer on Ubuntu

You need to install driver on Ubuntu, so it can recognize and use the printer. If you have an HP printer, you can easily install the driver with the following command.

```
sudo apt install hplip
```

I also recommend installing the printer-drivergutenprint package, which provides CUPS drivers for Canon, Epson, HP and compatible printers.

```
sudo apt install printer-driver-gute
nprint
```

If you have other printers, you can find drivers on openprinting.org.

After installing the driver, you may need to re-connect the printer to the USB port of your Ubuntu computer. To test if the driver is working correctly, you can create a text file on Ubuntu:

```
echo "LinuxBabe is awesome!" > file.
txt
```

Then run the following command to print this text file from the command line.

```
lp file.txt
```

This is a very rudimentary method, so don't worry about printing quality now.

# Step 3: Share CUPS Printer via Bonjour/IPP Protocol

#### **Installing Avahi-daemon**

CUPS can announce its presence on the network via mDNS (multicast DNS) and DNS-SD (DNS Service Discovery) protocol, which is also known as Bonjour. In order to do that, you need to install and run avahi-daemon, which is a service similiar to the Apple Bonjour service that allows computers to automatically discover shared devices and services on the local network.

sudo apt install avahi-daemon

Start avahi-daemon.

sudo systemctl start avahi-daemon

Enable auto-start at boot time.

sudo systemctl enable avahi-daemon

Avahi-daemon listens on UDP port 5353. Open it in the firewall.

sudo ufw allow 5353/udp

#### **IPP Driverless Printing**

Bonjour is used to advertise the printer on the local network. To make clients and the CUPS server

communicate with each other, IPP (Internet Printing Protocol) is needed. The advantage of IPP is that clients can use the shared printer without installing any driver on their own devices. CUPS supports IPP out of the box, so you don't need to do anything else to share CUPS printer via IPP.

### Step 4: Add Printer on Client Computers

#### macOS and Linux Clients

Because macOS and most Linux desktop distributions have CUPS installed as the default printing system, once you have enabled printer sharing via Bonjour/IPP on the Ubuntu box, macOS and Linux users in the same network can automatically use the printer. When they click the print option in applications (word processors, email readers, photo editors, and web browsers), the printer will be automatically available. They don't have to explicitly add the printer. It's magic.

If your Linux computer can't find the printer, it's possible that your system doesn't have the ippfind command.

Run the following command to install it on Debian-based Linux distribution.

sudo apt install cups-ipp-utils

On CentOS 8, run the following command.


sudo dnf install cups-ipptool

Then restart CUPS on the client computer.


#### sudo systemctl restart cups

#### Windows


Windows 10 ships with an IPP client. Type in **printer** in the lower-left search bar and open **Printers & Scanners**. Then click the **Add a printer or scanner** button. It will scan available printers on the local network.




As you can see, it found my HP Deskjet printer. Select the found printer and click **Add device**. It will be added to the printer list in a few moments.



If you are using a different version of Windows that can't add printer this way, then you can install the <u>Bonjour Print</u> <u>services</u>. Once installed, launch the Bonjour printer wizard. It will automatically scan available printers on the local network. As you can see from the screenshot, it found my HP printer.




Click next, then you need to choose a driver for this printer. You can choose the Microsoft IPP class driver, which is installed on the system by default.



Click Next, and the printer will be added to your Windows system.


#### **Manually Adding Printer on Linux**

If for any reason you don't see the printer, you can manually add one. To add a Bonjour-shared printer on desktop Linux, search your system settings or the application menu for the printer configuration utility. Click the **Add** button to add a new printer.




Then click Network Printer, and it would automatically scan available printers on the local network. As you can

see, it found my HP Deskjet printer. Click the **Forward** button.




Then you can give the printer a name and description. I simply accept the default values. Click **Apply** and you are done.




#### **Manually Adding Printer on macOS**


To add a Bonjour-shared printer on macOS, go to **system preferences** -> **Printers & Scanners**. Click the plus (+) button to add a printer.



It would automatically scan available printers on the local network. As you can see, it found my HP Deskjet printer.



Click the Add button and it will appear in the printer list.



### Step 5: Share CUPS Printer via Samba

Samba is a free and open-source SMB/CIFS protocol implementation for Unix and Linux that allows for file and print sharing between Unix/Linux and Windows machines in a local area network. It's mainly used to share files and printer with Windows clients.

To install Samba on Ubuntu, simply run the following command in terminal.

sudo apt install samba samba-commonbin

To check if Samba service is running, issue the following commands.

systemctl status smbd
systemctl status nmbd

To start these two services, issue the following commands:

```
sudo systemctl start smbd
sudo systemctl start nmbd
```

Then edit the main configuration file.

```
sudo nano /etc/samba/smb.conf
```

It's recommended to enable the spoolssd service when sharing printer. This will make Samba more efficient when there's lots of printing jobs. Simply add the following two lines in the [global] section to enable the spoolssd service.

```
rpc_server:spoolss = external
rpc_daemon:spoolssd = fork
```

Next, go to the end of the file and you will see the [printers] section. In Nano text editor, you can jump to the end of a file by pressing Ctrl+W, then Pressing Ctrl+V. Find the following two lines.

```
browseable = no
guest ok = no
```

Change them to

```
browseable = yes
guest ok = yes
```

Save and close the file. Then restart Samba.

sudo systemctl restart smbd nmbd

# Adding a Samba-shared Printer in Windows.

Open file explorer, enter the IP address of the Ubuntu computer in the address bar like \\192.168.0.110. The printer should now be listed.

add samba-shared printer on Windows 10

Double-click the printer to add it to your Windows system.				
Then click OK button to select a driver to install. After				
installing the driver, the printer will be added to your				
Windows system.				
windows add printer wizard				
windows add printer wizard				

## Step 6: Share CUPS Printer with iOS Clients via AirPrint

AirPrint allows iPhone, iPad, and macOS clients to print over Wi-Fi without installing driver software on the client devices. CUPS supports AirPrint, but avahi-daemon by default doesn't announce AirPrint service on the local network. We need to create a .service file in the /etc/avahi/services/ directory for the printer with a Python script with the following command. My printer's model is DeskJet 2130 series. Replace it with your own model name.

```
sudo nano /etc/avahi/services/AirPri
nt-DeskJet-2130-series.service
```

Add the following lines in the file.

```
<txt-record>qtotal=1</txt-record
    <txt-record>Transparent=T</txt-r
ecord>
    <txt-record>URF=none</txt-record
    <txt-record>rp=printers/DeskJet-
2130-series</txt-record>
    <txt-record>note=HP DeskJet 2130
series</txt-record>
    <txt-record>product=(GPL Ghostsc
ript)</txt-record>
    <txt-record>printer-state=3</txt
-record>
    <txt-record>printer-type=0x2900c
</txt-record>
    <txt-record>pdl=application/octe
t-stream, application/pdf, application
/postscript,application/vnd.cups-ras
ter,image/gif,image/jpeg,image/png,i
mage/tiff,image/urf,text/html,text/p
lain,application/vnd.adobe-reader-po
stscript,application/vnd.cups-pdf</t
xt-record>
  </service>
</service-group>
```

Save and close the file. Restart Avahi-daemon.

```
sudo systemctl restart avahi-daemon
```

Now iOS and macOS clients in the same network should be able to use your printer. The following screenshot shows

my iPhone successfully found an AirPrint Printer.

ubuntu-cups-airprint		

### **Wrapping Up**

I hope this tutorial helped you set up a CUPS print server on Ubuntu 20.04, 18.04 and 21.10. As always, if you found this post useful, then <u>subscribe to our free newsletter</u> to get more tips and tricks. And you may also want to read the following article to set up a Samba file share server.

• Set Up Samba Server on Ubuntu for File Sharing

#### Rate this tutorial

∎∎ [Total: 20 Average: 4.8]

✔ AirPrint
 ✔ CUPS Printer
 ✔ Linux
 ✔ Samba
 ✔ Ubuntu
 ✔ Ubuntu Desktop
 ✔ Ubuntu Server