```
[WRN] OSD_DOWN: 1 osds down
    osd.4 (root=default, host=servere) is down
[WRN] PG_DEGRADED: Degraded data redundancy: 63/567 objects degraded (11.111%), 15
pgs degraded, 16 pgs undersized
    pg 2.4 is stuck undersized for 4m, current state active+undersized, last
acting [1,3]
...ouput omitted...
    pg 5.6 is stuck undersized for 4m, current state active+undersized, last
acting [2,5]
```

- **3.** Troubleshoot the down OSD issue. Use diagnostic logging to find and correct a non-working configuration.
 - 3.1. Locate the down OSD.

[ce	ph: roo	t@clienta	/]# ceph osd tree			
ID	CLASS	WEIGHT	TYPE NAME	STATUS	REWEIGHT	PRI-AFF
-1		0.08817	root default			
-3		0.02939	host serverc			
0	hdd	0.00980	osd.0	up	1.00000	1.00000
1	hdd	0.00980	osd.1	up	1.00000	1.00000
2	hdd	0.00980	osd.2	up	1.00000	1.00000
-5		0.02939	host serverd			
3	hdd	0.00980	osd.3	up	1.00000	1.00000
5	hdd	0.00980	osd.5	up	1.00000	1.00000
7	hdd	0.00980	osd.7	up	1.00000	1.00000
-7		0.02939	host servere			
4	hdd	0.00980	osd.4	down	1.00000	1.00000
6	hdd	0.00980	osd.6	up	1.00000	1.00000
8	hdd	0.00980	osd.8	up	1.00000	1.00000

3.2. Attempt to restart the OSD 4 service with the ceph orch command. OSD 4 remains down after waiting a sufficient time.

```
[ceph: root@clienta /]# ceph orch daemon restart osd.4
Scheduled to restart osd.4 on host 'servere.lab.example.com'
```

3.3. Attempt to retrieve the configuration from the OSD 4 service.

An error messages indicates a communication problem with the OSD 4 service.

```
[ceph: root@clienta /]# ceph tell osd.4 config show
Error ENXIO: problem getting command descriptions from osd.4
```

3.4. Open a second terminal and log in to servere as the admin user. On the servere system, list the Ceph units.

```
[student@workstation ~]$ ssh admin@servere
[admin@servere ~]$ systemctl list-units --all 'ceph*'

UNIT LOAD

ACTIVE SUB DESCRIPTION

ceph-2ae6...fa0c@crash.servere.service loaded active running Ceph

crash.servere for 2ae6...fa0c
```