







Linux-2.6.18

ZONE_HIGHMEM

每个zone中的真是页数，多数架构同spanned_pages
spanned_pages 整个zone区的页数

```
zone->present_pages =
zone->present_pages / 1024    zone->pages_min = min_pages
if (SWAP_CLUSTER_MAX <
min_pages < 128)
zone->pages_low =
zone->pages_min + (tmp >> 2);
zone->pages_high =
zone->pages_min + (tmp >> 1)

tmp = (u64)pages_min *
zone->present_pages;
```

此时 pages_min =
min_free_kbytes >>
(PAGE_SHIFT - 10);

ZONE_DMA和ZONE_NORMAL

zone->pages_min = tmp;
zone->pages_low与zone->pages_high计算同ZONE_HIGHMEM

PAGE_SIZE = 4096

min_free_kbytes = 4 *
sqrt(lowmem_kbytes)

lowmem_kbytes =
nr_free_buffer_pages() *
(PAGE_SIZE >> 10);

```
1174 /*
1175  * Amount of free RAM allocatable within ZONE_DMA and ZONE_NORMAL
1176  */
1177 unsigned int nr_free_buffer_pages(void)
1178 {
1179     return nr_free_zone_pages(gfp_zone(GFP_USER));
1180 }
1181
```