




RONE PLUGINS

USER MANUAL

TEMPO-SYNCD REVERSE REVERB

RONE Reverse Reverb

Drop in a sound, choose how many bars the swell should take, and RONE Reverse Reverb renders a reversed reverb tail that lands exactly on the beat - shaped with fades, filters, stereo width and a rhythmic tremolo.



VERSION 1.1 · VST3 · AU · STANDALONE

RONEAUDIO.COM

Contents

1	Welcome to RONE Reverse Reverb	the swell before the hit
2	Installation with the RONE Plugins Center	Center, account, file locations
3	Quick start	first swell in one minute
4	Interface tour	every element on screen
5	Controls reference	what every control does, its range and default
6	Step-by-step workflows	recipes
7	Recommendations	how to get the best out of it
8	Interface conventions	knobs, right-click, resize, back panel
9	Troubleshooting, specifications and support	when something is off

1 Welcome to RONE Reverse Reverb

A reverse reverb is the sound of a reverb tail played backwards: it grows out of silence and arrives exactly at the note it belongs to. Producers love it for vocal entries, risers, snare swells and transitions - and hate building it by hand, because it means bouncing, reversing, adding reverb, reversing again and nudging the result until it lands on the beat.

RONE Reverse Reverb does all of that in one step. Load a sound, choose a **TAIL LENGTH** in bars or note values, and the plugin renders a swell that is exactly that long at your song's tempo. Play it from the interface or with a MIDI note, drag the fade handles on the waveform to shape it, add a tempo-synced tremolo for a rhythmic riser, and export.

Where it shines

- **Vocal entries** - a one-bar swell of the first word before the vocal starts.
- **Snare and clap swells** - 1/4 or 1/2 tails into every second bar.
- **Risers** - 4- or 8-bar tails with the TREMOLO in RAMP mode.
- **Transitions** - TRANSITION mode glues the swell to the original hit with a shared reverb.

The 10-second version


- 1 Drop a short sound (up to 8 seconds) on the waveform.
- 2 Set TAIL LENGTH to the number of bars the swell should take.
- 3 Press PLAY - or press ARM, and it starts by itself so that it lands on the next bar.
- 4 Drag the result to your DAW, or leave the plugin on the channel: the file is saved with the project.

HOW THE RENDER WORKS

The sample is fed into a reverb whose tail is stretched to the chosen length; the whole result is reversed, filtered (LOW CUT), widened (WIDTH), faded with the handles on the waveform and, if enabled, chopped by the tremolo. Everything is rendered offline at your tempo, so it is sample-accurate whatever your buffer size. The plugin re-renders automatically after every change.

2 Installation with the RONE Plugins Center

Every RONE product is installed, updated and licensed through one application: the **RONE Plugins Center**. You never download individual installers by hand, and you never enter serial numbers into the plugin itself.



RONE Plugins Center. 1 Navigation · 2 Your account and licence · 3 Sync status · 4 Search · 5 Refresh · 6 Settings · 7 Updates summary · 8 UPDATE ALL · 9 Filters · 10 Sort · 11 A plugin card · 12 Card menu (Details, Open, Manual) · 13 OPEN the standalone app · 14 INSTALL · 15 Your plan

Step by step

- 1 Download the Center from roneaudio.com and run the installer (Windows: RONE_Plugins_Center_Installer.exe , macOS: RONE_Plugins_Center.dmg). On Windows the installer also adds the Microsoft WebView2 runtime if your PC does not have it yet; it is required for the plugin interfaces. On macOS (10.15 Catalina or later, Intel and Apple Silicon) the first launch may be blocked because the installer is not yet Apple-notarized: open **System Settings** → **Privacy & Security**, scroll to the message about the blocked app and press **Open Anyway**, then confirm. If macOS calls the file *damaged*, run `xattr -cr "/Applications/RONE Plugins Center.app"` in Terminal once.
- 2 Open the Center and sign in with your **roneaudio.com** account (the same e-mail and password you used on the website). Your licences and device slots are checked automatically: an active **ALL ACCESS** plan unlocks every plugin, and a **lifetime licence** unlocks the plugin it was bought for — so RONE Reverse Reverb opens either way.
- 3 Find **RONE Reverse Reverb** in the list and press **INSTALL**. The Center downloads the signed installer, verifies its checksum, installs it silently and registers the version.

- 4 When the card shows **INSTALLED**, start (or restart) your DAW and rescan plugins if it does not pick up new plugins automatically. All RONE plugins appear next to each other in your plugin list because every name starts with **RONE**.
- 5 Updates appear on the same card. Press **UPDATE** on one plugin or **UPDATE ALL** at the top. Close the standalone version of a plugin before updating it.

Where the files go

WINDOWS

FILE	LOCATION
VST3	C:\Program Files\Common Files\VST3\RONE\RONE Reverse Reverb.vst3
Standalone app	C:\Program Files\RONE Plugins\RONE Reverse Reverb.exe
This manual	C:\Program Files\RONE Plugins\Manuals\

MACOS

FILE	LOCATION
VST3	/Library/Audio/Plug-Ins/VST3/RONE Reverse Reverb.vst3
Audio Unit	/Library/Audio/Plug-Ins/Components/RONE Reverse Reverb.component
Standalone app	/Applications/RONE Reverse Reverb.app
This manual	/Users/Shared/RONE Plugins/Manuals/

MANUAL INSIDE THE CENTER

Every installed plugin has a **Manual** entry in its card menu (the three dots on the card). It opens this PDF from the install folder, or from roneaudio.com if the local copy is missing.

Licence and activation


Licensing is tied to your account, not to a key. The plugin checks the licence file that the Center writes when you sign in. There are two ways to own it: an **ALL ACCESS** plan, which unlocks every RONE plugin for as long as it is active, or a **lifetime licence** for this plugin alone, which never expires. Either one opens RONE Reverse Reverb, and buying the lifetime licence later does not disturb a plan you already have.

If a plugin ever shows a *RONE Bundle License Required* screen, open the Center, make sure you are signed in and the plugin shows as licensed, then reopen it. Two devices can be signed in at the same time on either kind of licence; sign out on an old machine from the Center's Account page to free a slot. A lifetime licence keeps working offline for far longer than a plan does – there is nothing for it to expire against – but the Center still needs to reach the internet occasionally to confirm it.


Uninstalling

Windows: Settings → Apps → *RONE Reverse Reverb (RONE)*. macOS: delete the bundles listed above. Presets and settings in your user folder are kept.

3 Quick start




Fresh instance. Drag a file onto the waveform area to begin.



Sample loaded. The waveform shows the rendered (reversed) result; the status line shows the file name and the tempo in use.

- 1** Insert the plugin on a channel (an empty channel is ideal, since the plugin plays its result through it). In the standalone app just open it.
- 2** Load a sound. Drag a WAV, AIFF, FLAC or MP3 of up to 8 seconds onto the waveform. Short, distinct sounds - a word, a snare, a chord stab - give the clearest swells.
- 3** Choose the length. TAIL LENGTH runs from 1/32 to 8 BAR. It is the total length of the result at the current tempo (host tempo in a DAW; the BPM slider in the standalone app).
- 4** Set the room. ROOM SIZE controls how dense and long the reverb is inside that length; LOW CUT removes rumble from the tail; WIDTH sets how wide the swell is.
- 5** Listen. Press **PLAY**. In a DAW you can also trigger playback with any MIDI note routed to the plugin - note on starts, note off stops.
- 6** Shape it. Drag the fade handles on the left and right edges of the waveform to fade the result in and out, and drag the small curve dots to bend the fades.
- 7** Choose the mode. REVERSE ONLY renders the reversed tail alone. TRANSITION renders the reversed tail followed by the original sound with a matching forward reverb - the complete 'swell into the hit'.
- 8** Add rhythm (optional). Turn the TREMOLO on. In RAMP mode it chops the swell faster and faster towards the end - the classic riser.
- 9** Export. Drag the waveform out of the plugin into your DAW. The clip is saved to `Documents\RONE Plugins\Exports\RONE Reverse Reverb\` first and that permanent file is what the DAW receives, so the project can always find it again.

4 Interface tour



RONE Reverse Reverb with a vocal phrase loaded.

- 1 **Header logo** – click to flip to the back panel (About, version, licence)
- 2 **Preset bar** – arrows step through the 12 factory presets and your own; click the name for the list
- 3 **SAVE** – stores the current settings as a user preset
- 4 **Waveform** – the rendered result, with fade handles at both ends and curve dots for the fade shapes
- 5 **Status / file name** – what is loaded and the tempo in use (BPM shown on the right)
- 6 **PLAY** – play the result through the plugin's channel; press again to stop
- 7 **ARM** – the swell starts by itself so that the hit lands on the next bar line (MIDI C2 arms too)
- 8 **ARM bars** – 1, 2 or 4: land on the next bar, or the next 2- or 4-bar line
- 9 **Mode** – REVERSE ONLY or TRANSITION
- 10 **LOW CUT** – high-pass filter on the result
- 11 **HI CUT** – low-pass filter: darkens the swell
- 12 **WIDTH** – stereo width of the swell
- 13 **TAIL LENGTH** – 1/2, 1 or 2: length of the tail
- 14 **ROOM SIZE** – 0% to 100%: size of the room
- 15 **OUTPUT** – 0% to 100%: output level
- 16 **TREMOLO** – on/off
- 17 **Power** – on/off


13 TAIL LENGTH – total length of the result in bars or note values

15 OUTPUT – level of the result, up to 200 % with a soft limiter

17 Resize grip – drag to resize the window

14 ROOM SIZE – size of the reverb

16 TREMOLO on/off – opens the tremolo section



TREMOLO section open. 1 DEPTH · 2 PAN · 3 RATE · 4 SHAPE · 5 MODE (RAMP / SYNC / FREE) · 6 FROM / TO divisions for RAMP (a single Division list appears in SYNC mode).

5 Controls reference

Source and playback

Waveform

drop zone · fade
handles · curve
dots

Drop files here. Once a sound is loaded it shows the reversed result. Drag the handle at the left edge to set FADE IN and the handle at the right edge to set FADE OUT; drag the small dots to change the fade curve from logarithmic to exponential. The playback cursor moves across the waveform while playing.

Tip: A short fade in (5-10 %) hides the abrupt start that some reversed tails have; a fade out that ends a little before the end keeps the last transient clean.

PLAY

Plays the rendered result. In a DAW, MIDI note on also triggers playback and note off stops it, so you can place a MIDI note where the swell should start.

ARM and ARM bars

1 · 2 · 4
default 1 (next bar)
Arm: momentary, automatable, MIDI C2

The swell that cannot be late. Press **ARM** and the plugin waits, then starts the result at the one moment that makes its end - the hit - fall exactly on the next bar line. With 2 or 4 the landing is the next 2- or 4-bar line, so a phrase-long swell always lands on the top of the phrase. The button reads ARMED with a countdown in beats; the start is sample-accurate, inside the audio block.

It replaces counting "one bar before" and placing a MIDI note: arm it two bars early, and it lands. The bar comes from the host's song position (in the standalone app, from the BPM slider). ARM is also a parameter, so one automation step at the top of a phrase arms it, and MIDI note C2 arms instead of playing.

Tip: TAIL LENGTH 1 BAR, ARM bars 1: press ARM anywhere in the previous bar and the swell fills the last bar exactly.

Drag to export

drag the waveform into the DAW

Press on the waveform and drag into your DAW's arrangement (or into Explorer / Finder). The rendered clip is written to Documents\RONE Plugins\Exports\RONE Reverse Reverb\ as `<source>_ReverseReverb_<date>_<time>.wav` at the session's sample rate, and never deleted by the plugin.

Tip: Drop it so that it ends on the downbeat; the clip is exactly TAIL LENGTH long.

REVERSE ONLY / TRANSITION

default REVERSE ONLY

REVERSE ONLY: the output is the reversed reverb tail; the original sound is not included. **TRANSITION:** the reversed tail is followed by the original sound, itself sent through the same reverb forwards - swell, hit and decay in one clip, already glued.

Main knobs



LOW CUT, WIDTH, TAIL LENGTH, ROOM SIZE, DRY/WET.

TAIL LENGTH

8 BAR · 4 BAR · 2 BAR · 1 BAR · 1/2 · 1/4 · 1/8 · 1/16 · 1/32
default 1/2

The total length of the rendered result at the current tempo. This is what makes the swell land: an 8 BAR tail dropped eight bars before the downbeat arrives exactly on it.

Tip: Use short values (1/4, 1/8) on drums for tight pre-hits; long values (2-8 BAR) on vocals and chords for cinematic entries.

ROOM SIZE

0 to 100 %
default 80 %

The size of the reverb used to create the tail. Larger rooms give denser, smoother swells; small rooms give short, grainy pre-echoes that still stretch to the chosen length.

LOW CUT

20 to 500 Hz
default 20 Hz

A high-pass filter on the result. Reversed tails carry a lot of low-mid rumble; 100-200 Hz keeps the swell out of the way of bass and kick.

WIDTH

0 to 100 %
default 50 %

Stereo width of the result. 0 % is mono, 50 % is the natural reverb width, 100 % is as wide as it goes.

Tip: Check the mix in mono above 80 %.

HI CUT

1 kHz to OFF
default OFF


A low-pass filter on the result. Reversed tails are bright by nature; 4-8 kHz makes a dark, cinematic swell that sits behind a lead instead of fighting it.

OUTPUT

0 to 200 %
default 100 %
automatable

The level of the result. Above 100 % a soft limiter takes over: the loud end of a swell rounds off instead of clipping, so a hot OUTPUT is a colour, not a fault.

Tremolo



The tremolo section.

TREMOLO on/off

power button

Enables a rhythmic amplitude gate on the result - the difference between a swell and a riser.

DEPTH

0 to 100 %
default 50 %

How deep the tremolo cuts. 100 % is a hard gate.

PAN

0 to 100 %
default 0 %

Turns the tremolo into an auto-pan: alternate pulses lean left and right by this amount.

RATE

0.1 to 20 Hz
default 4 Hz

Speed of the tremolo in FREE mode. In RAMP and SYNC modes the speed comes from the tempo and this knob is inactive.

SHAPE

sine · triangle ·
square
default sine

The shape of the pulse. Sine is smooth, triangle is sharper, square is a hard gate.

MODE

RAMP · SYNC · FREE
default RAMP

RAMP starts at the FROM division and accelerates to the TO division across the length of the tail - the accelerating riser gate. **SYNC** holds one tempo-synced division for the whole tail. **FREE** runs at the RATE in Hz.

Tip: RAMP from 1/4 to 1/32 over an 8 BAR tail is the riser everybody knows.

**FROM / TO
(RAMP) ·
Division (SYNC)**

8 Bar to 1/128
defaults 1/4 → 1/32

The tempo divisions the tremolo runs at. In RAMP mode FROM is the starting speed and TO the speed reached at the end of the tail.

Standalone extras

BPM

20 to 300
default 120
standalone only

A slider row appears under the knobs in the standalone app, because there is no host tempo to read. Set it to your song's tempo before exporting.

Presets and the project

Preset bar

12 factory presets
+ your own

The arrows step through the presets; click the name for the list: Default, Dreamy Pad, Short Impact, Cinematic Swell, Dark Atmosphere, Bright Shimmer, Transition Rise, Tremolo Wash, Pulsing Reverse, Lo-Fi Reverse, Snare Swell and Wide Hall, then your own. **SAVE** stores the current settings under a name of your choice; user presets can be deleted from the list. A preset sets the render (tail, room, filters, mode) and the tremolo; the loaded sound stays.

THE FILE IS SAVED WITH THE PROJECT

Since 1.1.0 the loaded sound is stored inside the plugin state, so a project that is reopened - or a channel that is copied - comes back with its file, its waveform and its render. Nothing to relocate.

6 Step-by-step workflows

Vocal entry swell

Any vocal, any genre

- 1 Bounce the first word of the vocal (or the first second of the phrase) and drop it on the plugin.
- 2 TAIL LENGTH 1 BAR, ROOM SIZE 85 %, LOW CUT 150 Hz, WIDTH 60 %. Mode REVERSE ONLY.
- 3 Fade out the last 10 % with the right handle so the swell does not step on the real vocal.
- 4 Place the result so it ends exactly where the vocal starts. Send it to the same reverb as the vocal.

Snare swell every second bar

Techno, house, pop drums

- 1 Drop the snare sample, or pick the SNARE SWELL preset. TAIL LENGTH 1/2, ROOM SIZE 50 %, LOW CUT 80 Hz.
- 2 Trigger it with a MIDI note half a bar before every second snare, or drag the result into the arrangement and repeat it.

Land it on the bar

Any swell, no counting

- 1 Set TAIL LENGTH to the swell you want (1 BAR for a vocal entry, 2 BAR for a section change) and ARM bars to 1.
- 2 Anywhere in the bar before, press ARM - or send MIDI C2, or automate one step of the Arm parameter.
- 3 The plugin starts the swell by itself at the right moment; the hit lands exactly on the bar line.
- 4 For a phrase-long swell set ARM bars to 4: the landing is the next 4-bar line, wherever you pressed.

8-bar riser with tremolo

Builds

- 1 Drop a chord stab or a held vocal note. TAIL LENGTH 8 BAR, ROOM SIZE 100 %, WIDTH 80 %.
- 2 TREMOLO on, DEPTH 80 %, SHAPE square, MODE RAMP, FROM 1/4, TO 1/32, PAN 40 %.
- 3 Fade in the first 30 % with the left handle. Place the result so it ends on the drop.

Transition hit

Section changes, FX

- 1 Drop a crash, a vocal shout or an impact. Mode TRANSITION.
- 2 TAIL LENGTH 2 BAR, ROOM SIZE 90 %. The result is the swell, the hit and a forward tail in one clip.
- 3 Align the point where the swell ends with the downbeat of the new section.

7 Recommendations

DO

- Feed it short, clean sounds. The plugin stretches the reverb to the chosen length, so the source only needs to define the character.
- Use LOW CUT generously - a reversed tail without low end sits behind the mix instead of on top of it.
- Trigger with MIDI when you want the swell to follow arrangement edits; drag the file when you want to edit it as audio.
- Re-render after changing the song tempo; the length is baked in at render time.
- Try TRANSITION mode on drum hits; the shared reverb makes the hit sound like it belongs to the swell.

AVOID

- Files longer than 8 seconds; the plugin refuses them. Trim in your DAW first.
- WIDTH at 100 % on low-frequency material; it can cancel in mono.
- Deep square tremolo on soft pads; sine or triangle keeps the swell musical.

Sound tips

- **Room size is texture, length is timing.** A small room stretched to 4 bars sounds like a grainy pre-echo; a large one like a smooth cloud. The timing is identical.
- **Two swells** - one 1 BAR, one 1/4 - layered into the same downbeat give both build and snap.
- **PAN at 100 % with a fast TO value** spins the end of a riser around the listener.

8 Interface conventions

All RONE plugins share the same graphite interface language, so once you know one, you know them all.

GESTURE	WHAT IT DOES
Drag a knob up/down	Changes the value. The lit arc shows where you are in the range; the value is printed inside the knob.
Hold Shift while dragging	Fine adjustment.
Double-click a knob	Resets it to the default value.
Right-click a control (VST3)	Opens your DAW's automation / parameter menu for that control (for example FL Studio's <i>Create automation clip, Link to controller</i>). RONE never shows a browser context menu.
Mouse wheel	Steps through segmented switches and lists where the plugin offers them.
Drag the triangle in the bottom-right corner	Resizes the window. The interface scales proportionally and keeps its aspect ratio.
Click the R logo / plugin name in the header	Flips the plugin over to its back panel : version, format, licence holder, a link to roneaudio.com and a DEACTIVATE button for this device.



The back panel. Click the header brand to open it; click CLOSE (or the panel edge) to flip back.

AUTOMATION

Every knob and switch is a host parameter. Automate it from the DAW's automation lane or by right-clicking the control inside the plugin (VST3). Values shown in the plugin always match the DAW's.

PRESETS AND STATE

The plugin's full state is saved with your DAW project, so a project reopens exactly as you left it. Where the plugin has its own preset browser (the name field with ◀▶ arrows), factory presets are built in and your own presets are stored in your user folder.

STANDALONE VERSION

The standalone app is the same plugin in its own window, useful for auditioning and exporting without a DAW. It uses your system's default audio device; when there is no DAW clock, tempo-synced controls follow the plugin's own BPM setting.

MIDI
Route a MIDI track to the plugin to trigger playback: note on plays the result from the start, note off stops it. This works in the VST3 and AU versions.

9 Troubleshooting, specifications and support

Troubleshooting

SYMPTOM	WHAT TO DO
The file does not load	Files longer than 8 seconds are rejected. Trim the sound in your DAW and try again. WAV, AIFF, FLAC and MP3 are supported.
The swell does not land on the beat	Check the tempo shown next to the status line. In the standalone app set the BPM slider; in a DAW the host tempo is used - re-render if you changed it.
PLAY is greyed out	No sound is loaded yet, or the render is still running (very long tails take a moment).
The swell sounds a semitone or so too high or too low	Fixed in 1.0.1: files are now resampled to the session's sample rate. If an old project still sounds off, re-drop the source file once.
The DAW says a dropped clip is missing	Clips are saved to Documents\RONE Plugins\Exports\RONE Reverse Reverb ; point the DAW there. Versions before 1.0.1 wrote to the temp folder - re-export those clips once.
I hear nothing when I send MIDI	The MIDI must reach the plugin's channel; in some DAWs an effect plugin needs a MIDI routing or a 'MIDI to plugin' setting. The PLAY button works regardless.
The plugin does not appear in the DAW	Rescan plugins. On Windows the VST3 lives in C:\Program Files\Common Files\VST3\RONE ; make sure that folder (or its parent) is in the DAW's VST3 search path. On macOS restart the DAW after installing; Logic and GarageBand may need a full AU rescan.
The window is blank or shows an error page (Windows)	The Microsoft WebView2 runtime is missing or damaged. Reinstall the RONE Plugins Center; it repairs WebView2. Also check that WebView2Loader.dll sits next to the standalone executable.
A licence screen appears	Open the RONE Plugins Center, sign in, confirm your plan is active, then reopen the plugin. Check that you have not exceeded your device limit.
The plugin shows an older version than the Center	Close every DAW and standalone RONE app, then press UPDATE again. A running standalone keeps the old executable locked.
Crash	RONE plugins write a crash report to your user folder; the Center uploads it the next time it runs. Please also tell us what you did right before the crash.

Specifications

Product	RONE Reverse Reverb
Version	1.1 (manual revised September 2026)
Formats	VST3 · AU · Standalone (Windows: VST3 + Standalone; macOS: VST3 + AU + Standalone)
Systems	Windows 10 / 11 (64-bit) · macOS 11 or newer (Intel and Apple silicon, universal)
Channels	Stereo in / stereo out
Sample rates	44.1 kHz to 192 kHz
Latency	None (offline render, playback only)
Engine	JUCE 8, WebView interface (WebView2 on Windows, WebKit on macOS)

Support

Website, presets, updates and support: roneaudio.com. When writing to us, include the plugin version (shown on the back panel), your DAW and operating system, and the steps to reproduce.

RONE Reverse Reverb is designed and coded in Israel by Liran "RONE" Kalifa. © 2024–2026 RONE PLUGINS. All rights reserved. All product names are trademarks of their respective owners.