DRAWN SIDECHAIN · PHASE · SPACE

RONE Sidechain

Draw the duck on your bass and let every kick restart it - silent at the kick's first sample, open exactly where you drew it. Then turn the bass's sub to meet the kick, and cut only where the two really collide.



VERSION 1.2.3 · VST3 · AU · STANDALONE

RONEAUDIO.COM

Contents

1	Welcome to RONE Sidechain	a drawn duck, a locked sub, room for the kick
2	Installation with the RONE Plugins Center	Center, account, file locations
3	Quick start	your first sidechain
4	Interface tour	every element on screen
5	The SIDECHAIN page	the curve, RATE, DEPTH, CLICK, DUCK
6	The kick: routed, dropped or the grid	where the kick comes from
7	The PHASE page	the sub turned to meet the kick
8	The SPACE page	bells only where kick and bass meet
9	Presets, undo, bypass and latency	the rest of the header
10	Step-by-step workflows	recipes
11	Interface conventions	knobs, right-click, resize, back panel
12	Troubleshooting, specifications and support	when something is off

1 Welcome to RONE Sidechain

RONE Sidechain goes on your bass and makes room for the kick in three ways, one page each.

- **SIDECHAIN** - you draw the shape of the duck. Every kick restarts the curve, and the bass is **exactly silent at the kick's first sample**: no leftover level under the kick, no tail and no click.
- **PHASE** - turns only the bass's sub so that, where the kick's tail hands over to the bass, the two add up instead of cancelling.
- **SPACE** - small dynamic bells that cut the bass only at the frequencies and moments where the kick and the bass really collide. Everything else passes untouched.

The kick can come from a sidechain route, from a kick sample you drop on the plugin (it plays silently on the host's beat), or from nothing at all - then the curve runs on the grid.

Where it shines


- **Rolling psytrance and techno basslines** - the kick's 16th closed, the bass back exactly on the next note.
- **House pump** - a slow, musical curve over the whole beat.
- **808s and sub basses** - duck only the sub and keep the bass's top.
- **Muddy low ends** - PHASE and SPACE clean up the handover without an EQ that stays on.

The 10-second version

1. Insert RONE Sidechain on the bass.
2. Route the kick into its sidechain input - or drop a kick sample on it.
3. Pick a preset for your genre.
4. Shape the curve until the bass breathes with the kick.

2 Installation with the RONE Plugins Center

Every RONE product is installed, updated and licensed through one application: the **RONE Plugins Center**. You never download individual installers by hand, and you never enter serial numbers into the plugin itself.



RONE Plugins Center. 1 Navigation · 2 Your account and licence · 3 Sync status · 4 Search · 5 Refresh · 6 Settings · 7 Updates summary · 8 UPDATE ALL · 9 Filters · 10 Sort · 11 A plugin card · 12 Card menu (Details, Open, Manual) · 13 OPEN the standalone app · 14 INSTALL · 15 Your plan

Step by step

1. Download the Center from roneaudio.com and run the installer (Windows: `RONE_Plugins_Center_Installer.exe`, macOS: `RONE_Plugins_Center.dmg`). On Windows the installer also adds the Microsoft WebView2 runtime if your PC does not have it yet; it is required for the plugin interfaces. On macOS (10.15 Catalina or later, Intel and Apple Silicon) open the .dmg and drag the Center onto Applications. It is signed and notarized by Apple, so macOS only asks once whether you want to open an app downloaded from the internet: press **Open**.
2. Open the Center and sign in with your **roneaudio.com account** (the same e-mail and password you used on the website). Your licences and device slots are checked automatically: an active **ALL ACCESS** plan unlocks every plugin, and a **lifetime licence** unlocks the plugin it was bought for — so RONE Sidechain opens either way.
3. Find **RONE Sidechain** in the list and press **INSTALL**. The Center downloads the signed installer, verifies its checksum, installs it silently and registers the version.

4. When the card shows **INSTALLED**, start (or restart) your DAW and rescan plugins if it does not pick up new plugins automatically. All RONE plugins appear next to each other in your plugin list because every name starts with **RONE**.
5. Updates appear on the same card. Press **UPDATE** on one plugin or **UPDATE ALL** at the top. Close the standalone version of a plugin before updating it.

Where the files go

WINDOWS

FILE	LOCATION
VST3	`C:\Program Files\Common Files\VST3\RONE\RONE Sidechain.vst3`
Standalone app	`C:\Program Files\RONE Plugins\RONE Sidechain.exe`
This manual	`C:\Program Files\RONE Plugins\Manuals\`

MACOS

FILE	LOCATION
VST3	`/Library/Audio/Plug-Ins/VST3/RONE Sidechain.vst3`
Audio Unit	`/Library/Audio/Plug-Ins/Components/RONE Sidechain.component`
Standalone app	`/Applications/RONE Sidechain.app`
This manual	`/Users/Shared/RONE Plugins/Manuals/`

> **MANUAL INSIDE THE CENTER**
> Every installed plugin has a **Manual** entry in its card menu (the three dots on the card). It opens this PDF from the install folder, or from roneaudio.com if the local copy is missing.

Licence and activation

Licensing is tied to your account, not to a key. The plugin checks the licence file that the Center writes when you sign in. There are two ways to own it: an **ALL ACCESS** plan, which unlocks every RONE plugin for as long as it is active, or a **lifetime licence** for this plugin alone, which never expires. Either one opens RONE Sidechain, and buying the lifetime licence later does not disturb a plan you already have.

If a plugin ever shows the *Sign in to unlock RONE Sidechain* screen, open the Center, make sure you are signed in and the plugin shows as licensed, then reopen it. Two devices can be signed in at the same time on either kind of licence; sign out on an old machine from the Center's Account page to free a slot. A lifetime licence keeps working offline for far longer than a plan does — there is nothing for it to expire against — but the Center still needs to reach the internet occasionally to confirm it.

Uninstalling

Windows: Settings → Apps → *RONE Sidechain (RONE)*. macOS: delete the bundles listed above. Presets and settings in your user folder are kept.

3 Quick start




RONE Sidechain on the SIDECHAIN page: the kick on top, the bass under it with the curve drawn over it.

1. **Insert** RONE Sidechain on the bass track (or the bass bus).
2. **Give it the kick.** Route the kick track into the plugin's sidechain input - click the KICK chip in the header for the steps in your DAW - or drag a kick sample onto the plugin. The chip shows where the kick comes from.
3. **Pick a preset** from PRESET - they are sorted by genre. PSYTRANCE · ROLLING is the opening setting.
4. **Press play.** The kick draws in the top lane, the bass under it, ducked by the curve. The readout above the lanes tells you what is left of the bass *under the kick* and when it is fully open again.
5. **Shape it:** pick another shape, drag a point or a line, set RATE to the length of your bass pattern and DEPTH to how far it closes.
6. **Optional:** switch to the PHASE and SPACE pages. Both start working as soon as there is a kick; AUTO turns the sub by itself.

> **NO SIDECHAIN IN YOUR DAW?**
>
> Drop your kick sample on the plugin (or press LOAD KICK…). It plays silently on the host's beat, so the curve follows the beat and PHASE and SPACE know your kick - no routing at all. In Cubase you can also drag an audio event from the project window or a clip from the Pool onto the plugin and it loads.

4 Interface tour



The SIDECHAIN page in LANES view.

1. **Header logo** — click to flip to the back panel (About, version, licence)
2. **PRESET** — full settings by genre and your own presets; shows CUSTOM once you change something
3. **RATE** — the curve's length: 1/16, 1/8, 1/4, 1/2 or 1 BAR, synced to the host tempo
4. **KICK chip** — where the kick comes from; click it for the routing steps and the input meters
5. **BYPASS** — lit = the plugin is out of the path
6. **Pages** — SIDECHAIN, PHASE and SPACE; the plugin remembers the last one
7. **UNDO / REDO** — step back and forward through your edits - also Ctrl+Z and Ctrl+Shift+Z (Ctrl+Y)
8. **Kick lane** — the kick as it arrives, one cycle - for looking, not drawing
9. **Bass lane + curve** — the bass before (faint) and after the duck, with the curve to draw on
10. **FREE / QUANTIZE** — free drawing, or points and lines snapped to the grid
11. **GRID** — draws the rate's musical lines (16ths, beats) clearly over the lanes
12. **Readout** — UNDER THE KICK (what is left of the bass there), OPEN AT (when it is fully back) and the DUCK range
13. **LANES / OVERLAY** — the kick above the bass, or both on one row with a taller box to draw in
14. **SHAPES** — the factory curves and your own; drag a tile to move it, its x deletes it
15. **+ SAVE** — keeps the current curve as your own shape
16. **DEPTH** — how far the curve closes; 100 % = exactly silent
17. **CLICK** — the fade before the kick that keeps the cut from clicking
18. **DUCK** — FULL, SUB or BAND - where in the spectrum the duck works
19. **LOAD KICK / DROP** — load a kick sample, or drop one here or anywhere on the plugin
20. **Resize grip** — drag to resize the window

5 The SIDECHAIN page


How the curve works

The curve is the bass's level over one cycle: at the bottom the bass is silent, at the top it plays at full level. **Every kick restarts the curve** from its left edge, so the duck always lines up with the real kick - whatever pattern you program, fills and offbeat kicks included. The first point, the diamond on the left, is **the kick's point**: it always sits at silence, and it is the kick's first sample.

That is the promise of the plugin: at the kick's first sample the bass is **exactly silent** (at DEPTH 100 %). To get there without a click, the bass fades out just *before* the kick. That fade is **CLICK**, and it is complete at the kick's first sample. Because the plugin works a little ahead of time (the latency below), it knows the kick is coming before it arrives.


> **NOTHING LEFT UNDER THE KICK**
> A point within 5 % of silence snaps to silence, and one within 5 % of full snaps to full - a floor that looks like silence but is not is how a bass leaks under a kick. The readout UNDER THE KICK shows what really remains there; it turns red when the bass is louder than -50 dB under the kick.

Drawing the curve



The STEP shape: the kick's 16th closed, the first bass note at half, full from the second.

1. **Kick's point** — fixed at silence on the kick's first sample
2. **Step** — a vertical line: drag it to move it in time, or up and down with the levels either side
3. **Level** — a flat line: drag it up or down (and its ends in time) as one piece
4. **Point** — drag it anywhere between its neighbours; the tooltip shows its time in ms and its level in dB
5. **Playhead** — where the cycle is now while the host plays



The CLASSIC shape: a slope with its bend circle.

1 **Bend circle** — the circle in the middle of every slope - drag it up or down to bend the line

2 **Point** — the end of the slope

GESTURE	WHAT IT DOES
Drag a point	Moves it, in time and level. The last point always stays at the end of the cycle.
Drag a flat level or a vertical step	Moves the whole line. A step carries the flat levels on either side with it, so nothing tilts.
Drag the circle in the middle of a slope	Bends the slope - from a fast rise to a slow one.
Double-click the bass lane	Adds a point there.
Double-click a point	Removes it.
FREE / QUANTIZE	QUANTIZE snaps points, moved lines and new points to the grid: 16ths of the cycle and 5 % levels. FREE puts them exactly where you drag.
Hold `Shift`	Does the opposite of FREE / QUANTIZE for that one drag or double-click.
GRID	On by default and remembered. Draws the musical lines of the RATE clearly, so you see where you draw: 16ths at 1/4 and longer, with the beats stronger from 1/2; 32nds at 1/8 and 64ths at 1/16. QUANTIZE snaps to a finer grid that holds every one of these lines.

The tag in the top-left corner of the view shows the current RATE and the host tempo (for example `1/4 · 140 BPM`). Along the bottom of the view the grid is marked in milliseconds, and a white playhead runs along the cycle while the host plays.

The kick lane above is for looking only. In **OVERLAY** view the kick is drawn in grey on the bass's row and the whole box is yours to draw in.



OVERLAY: the kick and the bass on one row, the curve over both.

Shapes

The **SHAPES** row starts with thirteen factory curves - STEP, ROLL, CLASSIC, TIGHT, HOLD, SNAP, PUMP, SOFT, LATE, SWELL, DOUBLE, BOUNCE and GENTLE (hover a tile to read its name). Click one to load it, then edit it freely.



The SHAPES row with the mouse over a tile: its x appears at the top-right corner.

- **+ SAVE** adds the current curve to the end of the row as *MY 1*, *MY 2* and so on - up to 16 of your own; the oldest goes when you save a 17th.
- **Drag a tile** left or right to move it in the row; a click still just loads it.
- **The x** that appears when you hover a tile deletes it.
- **Right-click the row → RESTORE FACTORY SHAPES** brings back any factory shape you deleted, so none is ever lost for good.

The row is remembered on this computer, for every instance of RONE Sidechain and every project. Changes to it can be undone like any other edit.

The controls

RATE

`1/16, 1/8, 1/4, 1/2, 1 BAR`
`default 1/4`
`automatable`

How long one cycle of the curve is, synced to the host tempo. 1/4 = one beat, the usual four-on-the-floor kick. A kick that comes before the cycle is over restarts it there.

DEPTH

`0 to 100 %`
`default 100 %`
`automatable`

How far the curve closes. At 100 % the bottom of the curve is silence; at 50 % the bass never drops below half its level.

CLICK

`0.5 to 20 ms`
`default 2.0 ms`
`automatable`

The fade *before* the kick that keeps the cut from clicking. It is complete at the kick's first sample, so the bass is silent when the kick starts however long you set it. Shorter = a tighter cut; longer = softer on low, sustained basses.

DUCK

`FULL / SUB / BAND`
`default FULL`
`automatable`

Where in the spectrum the duck works - **the rest passes untouched**.

FULL ducks the whole bass. **SUB** ducks only its sub, below SPLIT (set on the PHASE page). **BAND** ducks only between the two handles of the strip under the switch: drag a handle and the switch goes to BAND; double-click the strip for FULL. The bands are split linear-phase, so the part that is not ducked passes exactly as it came. With PHASE turned, SUB and BAND duck the turned bass, so nothing of the band is left under the kick.

Tip: BAND's handles run from 20 Hz to 20 kHz (default 20 Hz - 200 Hz); the view's readout shows the range you set.



DUCK in BAND: the strip shows the range the duck works in.


6 The kick: routed, dropped or the grid

The **KICK chip** in the header always shows what the curve is following:

CHIP	WHAT IT MEANS
KICK IN · ROUTED	A kick arrives on the sidechain input. Every hit restarts the curve, whatever the pattern - quieter ghost kicks between the main ones too.
SAMPLE · *name*	You dropped or loaded a kick sample. It plays silently on the host's beat and restarts the curve there.
LAST KICK · ON THE BEAT	The routed kick stopped arriving. The last clean kick heard plays on, silently, on every beat.
GRID · NO KICK	No kick at all. The curve restarts on its own at every RATE. PHASE and SPACE wait for a kick.

Routing the kick (sidechain input)

Click the KICK chip to open **SEND THE KICK TO RONE SIDECHAIN**. It shows the steps for the DAW you are in, and two meters: **IN** (the bass on the plugin's input) and **SC** (the kick on the sidechain input). When the routing is right, the SC meter moves on every kick. **OTHER DAWS** lists the steps for the others.



The SETUP popover, opened from the KICK chip.

1. **KICK chip** — click to open and close the popover
2. **IN / SC meters** — the bass on the input, the kick on the sidechain
3. **Your DAW** — the routing steps for the host the plugin is running in
4. **OTHER DAWS** — the steps for FL Studio, Ableton, Cubase, Logic, Studio One, Bitwig and REAPER

FL STUDIO

1. In the Mixer, select the **kick** track, then right-click the arrow at the bottom of the **bass** track → **Sidechain to this track**.
2. In RONE Sidechain's wrapper: ⚙ → **Processing** → **Connections** - set the **sidechain input** to the kick track.
3. The SC meter in the popover now moves on every kick.

DAW	ROUTING
Ableton Live	Open the RONE Sidechain device I/O (▸) → **Sidechain** on → **Audio From** = the kick track.
Cubase	Turn on **Side-Chain** in the RONE Sidechain header; kick track → Sends → **RONE Sidechain - Side-Chain**.
Logic Pro	RONE Sidechain header → **Side Chain** = the kick track.
Studio One	RONE Sidechain header → **Side-Chain** on; kick track → Sends → RONE Sidechain.
Bitwig	RONE Sidechain device → **Sidechain input** = the kick track.
REAPER	Kick track → Route: send to the bass track on channels **3/4**; RONE Sidechain pin connector: sidechain = 3/4.

GHOST KICKS RESTART THE CURVE, OTHER DRUMS DO NOT

A kick down to 24 dB quieter than your main kick still restarts the curve, as long as it sounds like your kick: the plugin compares every quieter hit with the kick it remembers. Snares, claps and hats on the same bus, and bass bleeding onto the sidechain, do not restart it.

A SIDECHAIN THAT CARRIES THE BASS IS IGNORED

FL Studio, before a sidechain route is made, feeds the bass's own signal onto the plugin's sidechain bus. RONE Sidechain recognises that - even when it arrives at another level or a few milliseconds late - and does not treat the bass as a kick: the curve follows the beat until you route the real kick.

Dropping a kick sample

No routing at all? Drag a kick file (WAV, AIFF, MP3 or FLAC) from your browser or the desktop and drop it anywhere on the plugin - the page shows *DROP YOUR KICK* - or press **LOAD KICK…**. The sample plays **silently** on the host's beat: the curve follows the beat, and PHASE and SPACE know your kick's sound. It is saved with the project.

A dropped kick **always wins over the routing**. The button turns into ✕ **CLEAR KICK**; press it to hand control back to the routed kick.

Rendering the bass alone


When the kick stops arriving - you solo the bass, or render the bass track on its own - the **last kick heard plays on every beat, silently**. The curve, PHASE and SPACE stay exactly as they were, so a render of the bass sounds like the bass in the mix. The remembered kick is saved with the project, at its real level.

The standalone

The standalone app has no sidechain input: the curve follows its own clock (GRID). Drop a kick sample to give PHASE and SPACE a kick.

7 The PHASE page

Where the kick's tail hands over to the bass, the two low ends overlap. If they are out of phase they cancel, and the low end gets thinner exactly where it should be strongest. PHASE turns **only the bass's sub** (below SPLIT) so the two add up. The turn is a linear-phase rotation: the bass's attack is not smeared and nothing above SPLIT moves. It also keeps the level: the turn slides smoothly across SPLIT, so a note or a harmonic right at SPLIT stays as loud as it was (within half a dB) at any angle.



The PHASE page: the kick's low band (grey) and the bass's sub as you hear it (periwinkle) at the handover.

1. **Handover scope** — the first 160 ms of the cycle: the kick's low band in grey, the bass's sub as heard in periwinkle - locked, they read as one continuous wave
2. **ON / OFF** — switch PHASE off to hear what the turn does; the duck and SPACE stay
3. **PHASE** — the angle the sub is turned by, -180° to +180°
4. **SPLIT** — where the sub ends: what PHASE turns and what DUCK SUB ducks
5. **MODE / Ø FLIP** — AUTO or MANUAL for PHASE; Ø FLIP turns the sub's polarity (+180°)
6. **SPLIT AUTO / MANUAL** — AUTO sets SPLIT to 1.5 x the bass's note and follows it
7. **Status** — LOCKED, TURNING TO …, HOLDING …, NOTHING TO TURN, PHASE OFF
8. **Readout** — the bass's note, kick + bass together in dB, and what they would be turned

ON / OFF

```
default ON
automatable
```

Off = the sub as it came. Use it to compare.

MODE

```
AUTO / MANUAL
default AUTO
automatable
```

AUTO measures where the kick's tail and the bass add up and turns the sub there by itself. It turns **only while the duck is closed**, so you never hear it moving. In AUTO the PHASE knob shows the angle and is not yours to turn. AUTO settles on **one angle for the bass** from the last eight kicks. When the bass meets the kick at a different angle on every hit (a free-running oscillator, for example), no single angle fits: AUTO then holds where it is and the status reads HOLDING. **MANUAL** leaves PHASE to you; the status line tells you where AUTO would turn it and how much louder the low end would be.

PHASE

`-180° to +180°`
`default 0°`
`automatable`

How far the sub is turned against the kick. Set by AUTO, or by hand in MANUAL.

SPLIT

`50 to 200 Hz`
`default 90 Hz`
`automatable`

Where the sub ends. Everything below it is what PHASE turns and what DUCK = SUB ducks; everything above passes as it was.

SPLIT AUTO / MANUAL

`default AUTO`

AUTO sets SPLIT by itself to 1.5 x the note your bass plays - the point that turns the sub and its first harmonic and leaves the bass's body alone - and follows the bass when it moves to another note. The same bass always gives the same SPLIT. **MANUAL** keeps the value AUTO found and gives you the knob. A SPLIT change glides in over about 40 ms, so it never clicks. Projects made before 1.2.2 open in MANUAL on their own SPLIT.

Ø FLIP

`on / off`
`automatable`

Turns the sub's polarity around (+180° on top of PHASE). It stays in AUTO too: AUTO turns to its angle plus 180°.

PHASE NEEDS A KICK

With GRID · NO KICK the page reads ROUTE THE KICK OR DROP A SAMPLE - there is nothing to turn towards. If the kick and the bass never overlap, the status says NOTHING TO TURN.

8 The SPACE page

A static EQ cut on the bass takes the low end away all the time. SPACE works like a dynamic EQ instead: one sharp **bell** (a second one only for a second, separate collision) that cuts the bass **exactly where the kick is loud and the bass has a note at the same frequency, at the same moment**. The bell sits on the bass's own note, so it takes the clash and leaves the rest of the bass alone. Between kicks, and at frequencies where they do not meet, the bass is untouched.



The SPACE page: the bells as a live dynamic EQ on the bass, and when they work in the cycle.

1. **The bell** — a live dynamic EQ on the bass: the kick (grey) and the bass (blue) faint behind; outside LOW .. HIGH the display is shaded
2. **Cut now** — the bells' response in red, dipping where they cut and coming back; the dot names the deepest point. The dashed line = the deepest they went this cycle
3. **LOW / HIGH** — drag the two handles on the display: the range the bells may work in
4. **dB scale** — the EQ's own scale: 0 dB at the top line, down to -24 dB
5. **WHEN THEY WORK** — one cycle: the kick, the bass as it leaves, and in red the moments the bells cut
6. **SPACE ON / OFF** — off = no bells; the duck and PHASE stay
7. **AMOUNT** — how deep the bells go where kick and bass meet (up to 24 dB)
8. **RELEASE** — how long a bell follows the kick after its hit

WHAT YOU SEE AND WHAT YOU HEAR

The red dip drops at once and returns over about 150 ms, so the eye can follow it. That is only the display: the bells in the audio are as fast as before, set by RELEASE.

SPACE ON / OFF

default ON
automatable (Space on)

Off = no bells at all, so you hear the bass without them. The duck and PHASE stay as they are. The display then reads SPACE IS OFF.

AMOUNT

```
0 to 100 %
default 30 %
automatable
```

How deep the bells cut where the kick and the bass collide - 100 % is up to 24 dB. At 0 SPACE does nothing. The bell cuts only while the bass is heard: where the duck has already closed the bass, there is nothing to cut.

RELEASE

```
15 to 125 ms
default 29 ms
automatable
```

How long a bell keeps following the kick after its hit. Short leaves the next bass note alone; longer keeps the room open through a long kick tail.

LOW / HIGH

```
20 Hz to 20 kHz
default 20 Hz - 250
Hz
automatable
```

The range the bells may work in. Click or drag on the display and the nearer handle follows.

WHEN SPACE CUTS

Mostly under the first bass note after the kick, where the kick's tail is still ringing. With a curve that keeps the kick's 16th closed, there is nothing to cut under the kick itself - by design. SPACE needs a kick: with GRID · NO KICK it waits.

9 Presets, undo, bypass and latency

Presets



The PRESET popup with one preset of your own, starred as the default, and the SAVE AS row open.

1. **Genre presets** — full settings by genre
2. **Star** — click to make that preset the default
3. **MY PRESETS** — the presets you saved; the x deletes one
4. **Name + SAVE** — type a name, then SAVE (or Enter)
5. **+ SAVE PRESET AS** — opens the name row

Click **PRESET** in the header. A **genre preset** sets the curve, RATE, DEPTH, CLICK, DUCK, AUTO and SPACE; **PHASE stays yours.** Change anything and the header shows CUSTOM.

PRESET	RATE · SHAPE
PSYTRANCE · ROLLING	1/4 · STEP
PSYTRANCE · FULL-ON	1/4 · TIGHT
TECHNO · DEEP	1/4 · CLASSIC
TECHNO · PEAK	1/4 · HOLD
HOUSE · PUMP	1/4 · PUMP
EDM · BIG ROOM	1/4 · CLASSIC
DNB · HALF-TIME	1/2 · HOLD
TRAP · 808	1/2 · SWELL

+ SAVE PRESET AS... opens a name field: type a name and press **SAVE**. Your preset keeps everything except BYPASS - every control on all three pages, plus the curve - and appears under **MY PRESETS**; saving under an existing name updates it. The **x** next to one of your presets deletes it.

The star marks the default: the preset every new RONE Sidechain opens with. Click a star to make that preset the default; click the filled star again to go back to the factory default.

Undo and redo

The two arrows at the right of the tab row, on every page, step back and forward through your edits: `Ctrl` + `Z` undoes, `Ctrl` + `Shift` + `Z` or `Ctrl` + `Y` redoes. They cover the parameters, the curve and the SHAPES row. One drag is one step, however long it is. BYPASS, host automation and loading or clearing a kick sample are not undo steps.

BYPASS

Takes the whole plugin out of the path. The bypassed signal is delayed by the same latency as the processed one, so the host's compensation still lines up and nothing jumps in time when you switch.

Latency

RONE Sidechain works about **29 ms** ahead: it is what lets the duck be silent at the kick's very first sample and what makes PHASE's linear-phase turn exact. The latency is constant and reported to the host, which compensates for it automatically. On a live input with monitoring you will hear it as a small delay.

10 Step-by-step workflows

The rolling psytrance bass

RATE 1/4, STEP

1. Preset PSYTRANCE · ROLLING (STEP, DEPTH 100 %, CLICK 2 ms).
2. Route the kick, or drop it on the plugin.
3. Check UNDER THE KICK reads -∞ dB, then drag the middle level so the first bass note sits where you want it.
4. PHASE on AUTO; SPACE around 30 %.

A house pump

the whole beat breathes

1. Preset HOUSE · PUMP.
2. Lower DEPTH until the pump sits in the groove (60-80 %).
3. Bend the slope with its circle - a later rise pumps harder.

Duck only the sub

keep the bass's top over the kick

1. DUCK = SUB, or BAND with the handles at 20 Hz and 120-200 Hz.
2. Set SPLIT on the PHASE page to where your bass's sub ends.
3. The top of the bass now plays straight through the kick.

Render the bass alone

stems and bounces

1. Play the project once with the kick going in, so the plugin hears it.
2. Solo or render the bass: the chip shows LAST KICK · ON THE BEAT and the duck stays on the beat.
3. Or drop the kick sample - it wins over the routing and is saved with the project.

11 Interface conventions

All RONE plugins share the same graphite interface language, so once you know one, you know them all.

GESTURE	WHAT IT DOES
Drag a knob up/down	Changes the value. The lit arc shows where you are in the range; the value is printed inside the knob.
Hold `Shift` while dragging	Fine adjustment.
Double-click a knob	Resets it to the default value.
Right-click a control (VST3)	Opens your DAW's automation / parameter menu for that control (for example FL Studio's *Create automation clip*, *Link to controller*). RONE never shows a browser context menu.
Mouse wheel	Steps through segmented switches and lists where the plugin offers them.
Drag the triangle in the bottom-right corner	Resizes the window. The interface scales proportionally and keeps its aspect ratio.
Click the R logo / plugin name in the header	Flips the plugin over to its **back panel**: version, format, licence holder, a link to roneaudio.com and a DEACTIVATE button for this device.



The back panel. Click the header brand to open it; click CLOSE (or the panel edge) to flip back.

AUTOMATION

Every knob and switch is a host parameter. Automate it from the DAW's automation lane or by right-clicking the control inside the plugin (VST3). Values shown in the plugin always match the DAW's.

PRESETS AND STATE

The plugin's full state is saved with your DAW project, so a project reopens exactly as you left it. Where the plugin has its own preset browser (the name field with ◀ ▶ arrows), factory presets are built in and your own presets are stored in your user folder.

STANDALONE VERSION

The standalone app is the same plugin in its own window, useful for auditioning and exporting without a DAW. It uses your system's default audio device; when there is no DAW clock, tempo-synced controls follow the plugin's own BPM setting.

PAGES AND VIEWS

The page (SIDECHAIN, PHASE, SPACE), LANES / OVERLAY, FREE / QUANTIZE and GRID are remembered between sessions; they are view settings, not part of the sound.

12 Troubleshooting, specifications and support

Troubleshooting

SYMPTOM	WHAT TO DO
The chip says GRID · NO KICK	No kick reaches the sidechain input. Click the chip and follow your DAW's steps until the SC meter moves on every kick - or drop a kick sample.
The SC meter moves but the curve only follows the beat (FL Studio)	Before a route is made FL feeds the bass itself onto the sidechain bus; the plugin ignores it and follows the beat. Set the sidechain input to the kick under ⚙ → Processing → Connections.
Bass still audible under the kick	Check UNDER THE KICK: raise DEPTH to 100 % and pull the curve's first level down to silence.
A click at the kick	Raise CLICK a little, especially on low sustained basses.
A dropped kick does not follow my routed kick	A dropped sample always wins. Press ✕ CLEAR KICK to go back to the routed kick.
A factory shape is gone	Right-click the SHAPES row → RESTORE FACTORY SHAPES.
PHASE or SPACE do nothing	They need a kick (routed or dropped). SPACE must be ON; PHASE also needs the kick and the bass to overlap.
The plugin does not appear in the DAW	Rescan plugins. On Windows the VST3 lives in `C:\Program Files\Common Files\VST3\RONE`; make sure that folder (or its parent) is in the DAW's VST3 search path. On macOS restart the DAW after installing; Logic and GarageBand may need a full AU rescan.
The window is blank or shows an error page (Windows)	The Microsoft WebView2 runtime is missing or damaged. Reinstall the RONE Plugins Center; it repairs WebView2. Also check that `WebView2Loader.dll` sits next to the standalone executable.
The window is white in Ableton Live but the standalone works (Windows)	Turn off Live's auto-scaling for this plugin: in Live's browser open **Plug-Ins**, right-click the plugin and untick **Auto-Scale Plug-In Window**, then delete the plugin from the track and insert it again. Seen with Windows display scaling at values such as 110 %.
A licence screen appears	Open the RONE Plugins Center, sign in, confirm your plan is active, then reopen the

SYMPTOM	WHAT TO DO
	plugin. Check that you have not exceeded your device limit.
The plugin shows an older version than the Center	Close every DAW and standalone RONE app, then press UPDATE again. A running standalone keeps the old executable locked.
Crash	RONE plugins write a crash report to your user folder; the Center uploads it the next time it runs. Please also tell us what you did right before the crash.

Specifications

Product	RONE Sidechain
Version	1.2.3 `(manual revised November 2026)`
Formats	VST3 · AU · Standalone (Windows: VST3 + Standalone; macOS: VST3 + AU + Standalone)
Systems	Windows 10 / 11 (64-bit) · macOS 11 or newer (Intel and Apple silicon, universal)
Channels	Mono or stereo in / out, plus a mono or stereo sidechain input for the kick
Sample rates	44.1 kHz to 192 kHz
Latency	About 29 ms, constant, reported to the host (compensated automatically)
Engine	JUCE 8, WebView interface (WebView2 on Windows, WebKit on macOS)

Support

Website, presets, updates and support: roneaudio.com. When writing to us, include the plugin version (shown on the back panel), your DAW and operating system, and the steps to reproduce.

RONE Sidechain is designed and coded in Israel by Liran “RONE” Kalifa. © 2024–2026 RONE PLUGINS. All rights reserved. All product names are trademarks of their respective owners.