
RONE PLUGINS

USER MANUAL

MIDI NOTE GATE

RONE Gater

Write notes, hear chops. The sound on the track passes only while a note is held - your DAW's piano roll is the sequencer.



VERSION 1.0 · VST3 · AU · STANDALONE

RONEAUDIO.COM

Contents

1 Welcome to RONE Gater — write notes, hear chops

2 Installation with the RONE Plugins Center — Center, account, file locations

3 Quick start — your first chop

4 Interface tour — every element on screen

5 Controls reference — what every control does, its range and default

6 Routing - SETUP — getting the notes to the gate

7 Step-by-step workflows — recipes

8 Tips, tricks and troubleshooting

1 Welcome to RONE Gater

RONE Gater is a MIDI note gate. Put it on a pad, a vocal, a bass or a whole bus, send it notes, and the sound only passes while a note is held: *note on opens, note off closes, the note's length is how long it stays open.* There is no internal sequencer and no pattern grid - the notes you already know how to write are the pattern, with every tool your piano roll has: copy, quantize, swing, velocity, slide a note off the grid.

The three rules

- **No note = closed, playing or not.** Insert it and the track goes silent until a note arrives; BYPASS to hear the source while you design it.
- **A new note in the middle of a release continues from where the envelope is** - never a jump, never a click.
- **Any key, any channel.** The gate ignores pitch; write the notes on whatever key is comfortable.


The 10-second version

1. Insert Gater on the track with the sound.
2. Send it the notes of a MIDI track (SETUP shows how in your DAW).
3. Write a 1/16 pattern and press play.
4. Shape the chop with ATTACK and RELEASE.

> **WHEN THE MIDI LAMP LIGHTS, THE ROUTING WORKS**
> The lamp in the header lights on every note the gate receives. If the transport plays and no note has ever arrived, the gate is shut, the display says PLAYING · NO NOTES · GATE CLOSED and SETUP pulses.

2 Installation with the RONE Plugins Center

Every RONE product is installed, updated and licensed through one application: the **RONE Plugins Center**. You never download individual installers by hand, and you never enter serial numbers into the plugin itself.



RONE Plugins Center. 1 Navigation · 2 Your account and licence · 3 Sync status · 4 Search · 5 Refresh · 6 Settings · 7 Updates summary · 8 UPDATE ALL · 9 Filters · 10 Sort · 11 A plugin card · 12 Card menu (Details, Open, Manual) · 13 OPEN the standalone app · 14 INSTALL · 15 Your plan

Step by step

1. Download the Center from roneaudio.com and run the installer (Windows: `RONE_Plugins_Center_Installer.exe`, macOS: `RONE_Plugins_Center.dmg`). On Windows the installer also adds the Microsoft WebView2 runtime if your PC does not have it yet; it is required for the plugin interfaces. On macOS (10.15 Catalina or later, Intel and Apple Silicon) the first launch may be blocked because the installer is not yet Apple-notarized: open **System Settings** → **Privacy & Security**, scroll to the message about the blocked app and press **Open Anyway**, then confirm. If macOS calls the file *damaged*, run `xattr -cr "/Applications/RONE Plugins Center.app"` in Terminal once.
2. Open the Center and sign in with your **roneaudio.com account** (the same e-mail and password you used on the website). Your licences and device slots are checked automatically: an active **ALL ACCESS** plan unlocks every plugin, and a **lifetime licence** unlocks the plugin it was bought for — so RONE Gater opens either way.
3. Find **RONE Gater** in the list and press **INSTALL**. The Center downloads the signed installer, verifies its checksum, installs it silently and registers the version.

4. When the card shows **INSTALLED**, start (or restart) your DAW and rescan plugins if it does not pick up new plugins automatically. All RONE plugins appear next to each other in your plugin list because every name starts with **RONE**.

5. Updates appear on the same card. Press **UPDATE** on one plugin or **UPDATE ALL** at the top. Close the standalone version of a plugin before updating it.

Where the files go

WINDOWS

FILE	LOCATION
VST3	`C:\Program Files\Common Files\VST3\RONE\RONE Gater.vst3`
Standalone app	`C:\Program Files\RONE Plugins\RONE Gater.exe`
This manual	`C:\Program Files\RONE Plugins\Manuals\`

MACOS

FILE	LOCATION
VST3	`/Library/Audio/Plug-Ins/VST3/RONE Gater.vst3`
Audio Unit	`/Library/Audio/Plug-Ins/Components/RONE Gater.component`
Standalone app	`/Applications/RONE Gater.app`
This manual	`/Users/Shared/RONE Plugins/Manuals/`

MANUAL INSIDE THE CENTER

Every installed plugin has a **Manual** entry in its card menu (the three dots on the card). It opens this PDF from the install folder, or from roneaudio.com if the local copy is missing.

Licence and activation

Licensing is tied to your account, not to a key. The plugin checks the licence file that the Center writes when you sign in. There are two ways to own it: an **ALL ACCESS** plan, which unlocks every RONE plugin for as long as it is active, or a **lifetime licence** for this plugin alone, which never expires. Either one opens RONE Gater, and buying the lifetime licence later does not disturb a plan you already have.

If a plugin ever shows a *RONE Bundle License Required* screen, open the Center, make sure you are signed in and the plugin shows as licensed, then reopen it. Two devices can be signed in at the same time on either kind of licence; sign out on an old machine from the Center's Account page to free a slot. A lifetime licence keeps working offline for far longer than a plan does — there is nothing for it to expire against — but the Center still needs to reach the internet occasionally to confirm it.

Uninstalling

Windows: Settings → Apps → *RONE Gater (RONE)*. macOS: delete the bundles listed above. Presets and settings in your user folder are kept.

3 Quick start



RONE Gater. The last two bars on top - input in grey, what passes in chartreuse, the envelope line - and the three knobs below.

1. **Insert** RONE Gater on the track you want to chop - a held pad is the classic.
2. **Route notes to it.** Click SETUP: the plugin knows which DAW it runs in and shows that host's steps first.
3. **Write notes** on that MIDI track - a 1/16 pattern with a few gaps is a good start. Pitch does not matter.
4. **Press play.** The MIDI lamp lights on every note and the display tag reads GATE FOLLOWS THE NOTES.
5. Turn RELEASE to set the groove: short = tight chops, longer = the gaps fill in.
6. Lower DEPTH if the gaps should breathe instead of going silent.

4 Interface tour




A pad chopped by a 1/16 groove at 140 BPM, the last note still held.

1. **Display** — the last two bars: input in grey, what passes in chartreuse, the envelope as a line; bar and beat lines while the host plays
2. **MIDI lamp** — lights on every note the gate receives - WAITING FOR MIDI until the first one
3. **SETUP** — the routing steps for this DAW; the other DAWs fold out beneath
4. **BYPASS** — the envelope rides to fully open - no switch, no click
5. **ATTACK** — how fast a note opens the gate, 0.2 to 100 ms
6. **RELEASE** — how fast it closes after the note ends, 1 to 1000 ms
7. **DEPTH** — how far it closes; 100 % = silence between notes
8. **VELOCITY** — IGNORE, or → LEVEL: the note's velocity sets how far the gate opens

Click the R logo in the header to flip the unit to its back panel (About, version, licence).

5 Controls reference



ATTACK, RELEASE, DEPTH and VELOCITY.

ATTACK

`0.2 to 100 ms`
`default 1.5 ms`
`automatable`

How fast a note opens the gate. Short values give a hard chop without a click; long values fade every note in, a swell instead of a cut.

Tip: The envelope is a one-pole that reaches 95 % of the way in the knob's time.

RELEASE

`1 to 1000 ms`
`default 30 ms`
`automatable`

How fast the gate closes after the note ends. This is the groove: 10-30 ms is a tight stutter, 80-200 ms lets each chop ring into the next gap, several hundred ms turns the pattern into a pulse.

Tip: A note that arrives during a release opens from wherever the envelope is.

DEPTH

`0 to 100 %`
`default 100 %`
`automatable`

How far the gate closes between notes. 100 % is silence; 50 % leaves the sound 12 dB down (breathing); 0 % does nothing. The value under the knob shows the level between notes in dB. Closed level = $(1 - \text{depth})^2$.

VELOCITY

`IGNORE / → LEVEL`
`default IGNORE`
`automatable`

With → LEVEL the note's velocity sets how far the gate opens, between the closed level and full. Accent the pattern in the piano roll's velocity lane.

BYPASS

`on / off`

The envelope rides up to fully open, so switching it never clicks.

EVERY KNOB

Drag (Shift = fine), mouse wheel (2 % a notch), double-click = default, right-click = the host's parameter menu (automation, link to controller).

The display

The last two bars, sized from the host tempo. Grey is the input's peak history, chartreuse is what passes, the bright line is the gate envelope (top = open, bottom = closed). While the host plays, bar lines are drawn strong and beat lines faint. The tag in the corner tells you the state: **STOPPED · GATE OPEN**, **NOTE · GATE OPEN**, **GATE FOLLOWS THE NOTES**, **PLAYING · NO NOTES · GATE CLOSED** or **BYPASS**.

6 Routing – SETUP



SETUP open. This DAW's steps first; OTHER DAWS folds out the rest.

RONE Gater is an audio effect that accepts MIDI. Every DAW routes a MIDI track into an effect differently; the SETUP chip shows the steps for the host it is running in.

DAW	STEPS
FL Studio	Add a **MIDI Out** channel and set its **Port** to 1 · open RONE Gater's wrapper ⚙ and set **Input port** to 1 · write the notes in MIDI Out's piano roll
Cubase / Nuendo	MIDI track → **Output Routing** → RONE Gater · write the notes on that track
Ableton Live	MIDI track → **MIDI To** → the audio track → RONE Gater · write the clip there
Logic Pro	Instrument track → **MIDI-controlled Effects** → RONE Gater · **Side Chain** = the track with the sound
Studio One	Instrument track → **Output** → RONE Gater
Bitwig	Route the note track into RONE Gater (**Note Receiver** / MIDI routing)
Reaper	Send MIDI from the note track to the audio track (**Route** → MIDI) · RONE Gater is on the audio track
Standalone	Play any key on your MIDI keyboard - the gate follows your notes

7 Step-by-step workflows

Trance gate on a pad

The classic 1/16 chop

1. Insert Gater on a sustained pad, route a MIDI track to it.
2. Write sixteenths with a few gaps; leave ATTACK at 1.5 ms and RELEASE around 30 ms.
3. Vary note lengths: a longer note is a longer open - the groove is in the piano roll.

Breathing bus

Movement without holes

1. Set DEPTH to about 50 % (-12 dB between notes).
2. RELEASE 100-200 ms so each chop leans into the next.
3. Switch VELOCITY to → LEVEL and accent the off-beats.

8 Tips, tricks and troubleshooting

Tips

- **Short attack = hard chop.** 0.2-2 ms cuts in on the note without a click; above 10 ms the chops start to swell.
- **Release is the groove.** The same notes with 15 ms and with 150 ms are two different patterns.
- **DEPTH 50 %** keeps the sound alive between notes - a pulse instead of silence.
- **Before or after a reverb.** Gate before the reverb and the tails ring through the gaps; gate after it and the reverb is chopped too, for the hard trance-gate sound.

Troubleshooting

SYMPTOM	CAUSE	FIX
Silence while playing, SETUP pulses	No note has reached the gate	Follow SETUP for your DAW; the MIDI lamp must light
The track is silent as soon as the plugin is inserted	Rule one: no note = closed	Intended - the sound passes only while a note is held; press BYPASS to hear the source
The gate ignores which key I play	Rule three: any key, any channel	Intended - use velocity with → LEVEL for accents
Clicks on the chops	ATTACK or RELEASE at the very minimum on a low sound	Raise ATTACK to 1-2 ms and RELEASE to 10 ms or more
The window is white in Ableton Live, the standalone works (Windows)	Live's **Auto-Scale Plug-In Window** (seen with Windows display scaling such as 110 %)	In Live's browser open Plug-Ins, right-click the plugin and untick Auto-Scale Plug-In Window, then delete the plugin from the track and insert it again