RONE PLUGINS

USER MANUAL

ONE KNOB. THE WHOLE BUILD-UP.

RONE Rise

Turn one knob up over the phrase and the mix becomes a build-up - the lows leave, the reverb opens, the echoes climb. Snap it to zero and the drop hits, with the tail still spilling into it. Or press GO and let it land on the bar by itself.



VERSION **1.0.1** · VST3 · AU · STANDALONE

RONEAUDIO.COM

Contents

1 Welcome to RONE Rise — a build-up on one knob

2 Installation with the RONE Plugins Center — Center, account, file locations

3 Quick start — your first rise

4 Interface tour — every element on screen

5 Controls reference — what every control does, its range and default

6 Step-by-step workflows — recipes

7 Tips, tricks and troubleshooting

1 Welcome to RONE Rise

RONE Rise turns whatever you put through it into a build-up. One knob, **INTENSITY**, drives a whole chain the way you would automate it by hand over eight bars: a steep high-pass takes the low end away, a big reverb opens up, echoes and noise climb in, and in the bigger presets a gate speeds up, the pitch rides upward and a barber-pole shimmer climbs forever. Pull the knob back to zero on the downbeat and the drop lands - with the reverb and the echoes still ringing under it instead of dying on the one.

The sun on the right is the knob made visible: it sleeps below the horizon at zero, rises and grins as you turn it up, and pulses on every beat while the host plays.

Where it shines

- **The last 8 bars before a drop** - on the mix bus, the drum bus or a music group.
- **Transitions** - a four-bar lift between two sections without touching a single filter.
- **Live and in the DJ set** - LAND ON BAR runs the rise for you and lands it on the bar.
- **The drop that breathes** - TAIL keeps the wash under the first bar of the drop.


The 10-second version

1. Insert Rise on your mix or drum bus.
2. Pick SUNRISE.
3. Automate INTENSITY from 0 to 100 over the last 8 bars.
4. Snap it back to 0 on the drop.

> **WHY IT GETS QUIETER AT THE TOP**
> A build-up has to leave room for the drop. As INTENSITY rises the dry signal sinks (about -7 dB at 100 %, set by SINK in ADVANCED) while the reverb and echoes rise, so the moment you pull the knob down the full mix comes back louder than it left. That jump is the drop.

2 Installation with the RONE Plugins Center

Every RONE product is installed, updated and licensed through one application: the **RONE Plugins Center**. You never download individual installers by hand, and you never enter serial numbers into the plugin itself.



RONE Plugins Center. 1 Navigation · 2 Your account and licence · 3 Sync status · 4 Search · 5 Refresh · 6 Settings · 7 Updates summary · 8 UPDATE ALL · 9 Filters · 10 Sort · 11 A plugin card · 12 Card menu (Details, Open, Manual) · 13 OPEN the standalone app · 14 INSTALL · 15 Your plan

Step by step

1. Download the Center from roneaudio.com and run the installer (Windows: `RONE_Plugins_Center_Installer.exe`, macOS: `RONE_Plugins_Center.dmg`). On Windows the installer also adds the Microsoft WebView2 runtime if your PC does not have it yet; it is required for the plugin interfaces. On macOS (10.15 Catalina or later, Intel and Apple Silicon) the first launch may be blocked because the installer is not yet Apple-notarized: open **System Settings → Privacy & Security**, scroll to the message about the blocked app and press **Open Anyway**, then confirm. If macOS calls the file *damaged*, run `xattr -cr "/Applications/RONE Plugins Center.app"` in Terminal once.

2. Open the Center and sign in with your **roneaudio.com account** (the same e-mail and password you used on the website). Your licences and device slots are checked automatically: an active **ALL ACCESS** plan unlocks every plugin, and a **lifetime licence** unlocks the plugin it was bought for — so RONE Rise opens either way.

3. Find **RONE Rise** in the list and press **INSTALL**. The Center downloads the signed installer, verifies its checksum, installs it silently and registers the version.

4. When the card shows **INSTALLED**, start (or restart) your DAW and rescan plugins if it does not pick up new plugins automatically. All RONE plugins appear next to each other in your plugin list because every name starts with **RONE**.
5. Updates appear on the same card. Press **UPDATE** on one plugin or **UPDATE ALL** at the top. Close the standalone version of a plugin before updating it.

Where the files go

WINDOWS

FILE	LOCATION
VST3	`C:\Program Files\Common Files\VST3\RONE\RONE Rise.vst3`
Standalone app	`C:\Program Files\RONE Plugins\RONE Rise.exe`
This manual	`C:\Program Files\RONE Plugins\Manuals\`

MACOS

FILE	LOCATION
VST3	`/Library/Audio/Plug-Ins/VST3/RONE Rise.vst3`
Audio Unit	`/Library/Audio/Plug-Ins/Components/RONE Rise.component`
Standalone app	`/Applications/RONE Rise.app`
This manual	`/Users/Shared/RONE Plugins/Manuals/`

> **MANUAL INSIDE THE CENTER**
> Every installed plugin has a **Manual** entry in its card menu (the three dots on the card). It opens this PDF from the install folder, or from roneaudio.com if the local copy is missing.

Licence and activation

Licensing is tied to your account, not to a key. The plugin checks the licence file that the Center writes when you sign in. There are two ways to own it: an **ALL ACCESS** plan, which unlocks every RONE plugin for as long as it is active, or a **lifetime licence** for this plugin alone, which never expires. Either one opens RONE Rise, and buying the lifetime licence later does not disturb a plan you already have.

If a plugin ever shows a *RONE Bundle License Required* screen, open the Center, make sure you are signed in and the plugin shows as licensed, then reopen it. Two devices can be signed in at the same time on either kind of licence; sign out on an old machine from the Center's Account page to free a slot. A lifetime licence keeps working offline for far longer than a plan does — there is nothing for it to expire against — but the Center still needs to reach the internet occasionally to confirm it.

Uninstalling

Windows: Settings → Apps → *RONE Rise (RONE)*. macOS: delete the bundles listed above. Presets and settings in your user folder are kept.

3 Quick start




RONE Rise. INTENSITY on the left, the sun on the right, the presets along the bottom.

1. **Insert** Rise on the mix bus or a group bus. At 0 % it does nothing at all.
2. **Pick a preset** along the bottom. SUNRISE is the clean, classic lift.
3. **Automate** INTENSITY from 0 to 100 % over the bars before the drop. A curve that stays low and rises late sounds most natural.
4. **Pull it back to 0 on the drop.** The reverb and echoes keep ringing for a bar (TAIL) and then let go.
5. **Or let it run itself:** open ADVANCED, set LAND ON BAR to 8 and press GO. The rise starts from the bar you pressed it in and lands exactly eight bars later.


> **RIGHT-CLICK THE KNOB**
> Right-click any control for the host's own menu - in FL Studio that is where you create the automation clip or link it to a controller.

4 Interface tour



A LAND ON BAR run in progress: bar 5 of 8, the outer ring counting the bars.

1. **Header logo** — click to flip to the back panel (About, version, licence)
2. **BYPASS** — the untouched input, 10 ms crossfade
3. **INTENSITY** — the one knob, 0 to 100 %; the outer ring counts the bars of a LAND run
4. **GO** — appears when LAND ON BAR is set: runs the rise and lands it
5. **Bar counter** — which bar of the run you are in, and the beat
6. **Mood** — what the sun is feeling - NIGHT to HIGH NOON
7. **Presets** — five chains: SUNRISE, HORIZON, UPLIFT, DEEP DIVE, SUPERNOVA
8. **ADVANCED** — slides up LAND ON BAR, TAIL, the macros and the chain strip
9. **Resize grip** — drag to resize the window



ADVANCED open over the lower half of the window.

1. **LAND ON BAR** — MANUAL, or 4 / 8 / 16 / 32 bars for GO
2. **CURVE** — how a LAND run climbs: LIN, SOFT, EXP, S
3. **TAIL** — how long reverb and echoes ring after the knob falls
4. **Macros** — RISE, NOISE, REVERB, DELAY, KILL LOW, DIVE, GATE, SINK, PITCH
5. **Chain strip** — every stage with its live value

5 Controls reference



INTENSITY. The pink arc is where the knob is; during a LAND run the white outer ring fills bar by bar.

INTENSITY

`0 to 100 %`
`default 0`
`automatable`

The whole build-up on one knob. At 0 % the plugin passes the signal untouched (it nulls). As it rises every stage of the chain follows its own curve: the high-pass sweeps up faster near the top, the reverb and echoes open steadily, the noise comes in late. A fast pull back to zero is a drop: the tail keeps ringing (see TAIL).

Tip: Drag, or use the mouse wheel (Shift = fine). Double-click = 0. During a LAND run the knob shows the run; touching it cancels the run.

Presets

`SUNRISE / HORIZON / UPLIFT / DEEP DIVE / SUPERNOVA`
`default SUNRISE`
`automatable`

A preset chooses the fixed parts of the chain and loads the nine macros. **SUNRISE**: a 24 dB/oct high-pass up to about 340 Hz and a 45 % reverb - the clean lift. **HORIZON**: SUNRISE with a dotted-8th ping-pong echo and a breath of noise. **UPLIFT**: the full high-pass sweep to 3 kHz, a tempo gate that speeds up, noise, a hint of the Shepard climb and the pitch rising 100 Hz. **DEEP DIVE**: the opposite build-up - a low-pass closes the mix down to about 500 Hz under a huge reverb, and the drop opens the sky. **SUPERNOVA**: everything at once, the pitch rising 200 Hz and the Shepard climb racing with the knob.

Tip: Move a macro and a dot appears on the preset chip. Automating the preset from the host loads its macros too.

BYPASS

`on / off`

The untouched input with a 10 ms crossfade. While bypassed nothing runs, so the next un-bypass starts clean.

ADVANCED



LAND ON BAR, CURVE, TAIL, the nine macros and the chain strip.

LAND ON BAR

`MANUAL / 4 / 8 / 16 / 32 bars`
`default MANUAL`

MANUAL: you move or automate INTENSITY yourself. With a bar count set, a **GO** button appears under the knob. GO starts the rise from the beginning of the bar you pressed it in and runs it to 100 % so that it lands exactly on the downbeat that many bars later; the outer ring of the knob counts the bars. After the landing the plugin stays at zero until you touch the knob again. GO while running cancels, and so does moving the knob.

Tip: MIDI note C1 is GO too, and so is the Go parameter - automate a single step on it in the arrangement.

CURVE

`LIN / SOFT / EXP / S`
`default SOFT`

How a LAND run climbs. LIN is a straight line; SOFT (default) stays a little lower and speeds up; EXP stays almost silent for the first half and puts everything in the last bars; S pushes once more at the very end.

TAIL

`CUT / 1 / 2 / 3 / 4 bars`
`default 1 bar`

What the reverb and echoes do when the knob falls. They are fed by the knob, but their level only follows it down slowly; once the knob reaches zero they hold for the first third of the TAIL, then fade out over the rest, in the room they had at the top. So a snap to zero and a quick fade both leave a real tail under the drop. **CUT** stops them dead on the drop.

RISE

`0 to 100 %`

The Shepard climb: a barber-pole frequency shifter that seems to rise forever, cycling every two bars (faster with the knob in SUPERNOVA).

NOISE

`0 to 100 %`

White noise through a resonant high-pass that sweeps from 150 Hz to about 5 kHz as the knob rises. It also feeds the reverb, so it arrives as a washed riser, not as hiss.

REVERB

`0 to 100 %`

How much reverb the chain adds. **0 turns the reverb off** - for a plain filter sweep on a kick or a bass that should stay dry.

DELAY

`0 to 100 %`

How much of the dotted-8th ping-pong echo the chain adds. **0 turns it off.** SUNRISE starts with no echo; HORIZON, DEEP DIVE and SUPERNOVA bring it in.

KILL LOW `0 to 100 %`	How far the high-pass goes. Combined with the preset: in SUNRISE 100 % reaches about 340 Hz, in UPLIFT and SUPERNOVA about 3 kHz.
DIVE `0 to 100 %`	A 24 dB/oct low-pass that closes the top down to about 500 Hz as the knob rises - the underwater build.
GATE `0 to 100 %`	A tempo-synced gate on the dry signal. Its division halves as the knob rises: quarter notes, eighths, sixteenths, thirty-seconds. The amount sets how deep it chops.

SINK
`0 to 100 %`
`default 55 %`
	How far the dry signal sinks at 100 %: 55 % is about -7 dB. At 0 the dry never gets quieter and the plugin only adds.

PITCH `0 to +200 Hz`	Frequency-shifts the dry signal up as the knob rises, up to +200 Hz at 100 %. Every partial moves by the same number of hertz, so it reads as a tape-like lift with a metallic edge rather than a clean transposition.
Chain strip `read-only`	Every stage with what it is doing right now: HPF and DIVE in hertz, the GATE division, the PITCH shift, REVERB and DELAY levels, the NOISE level, the SHEPARD range and DRIVE.

Double-click a macro to return it to the preset's value.

6 Step-by-step workflows

The classic 8-bar build

SUNRISE, automated

1. Insert Rise on the mix bus (or on everything except the kick if you want the kick to keep pumping).
2. SUNRISE, TAIL 1 bar.
3. Draw INTENSITY from 0 at the start of the 8 bars to 100 % at the end, with a curve that stays low and rises late.
4. Draw it straight back to 0 on the drop. The reverb rings under the first bar of the drop.

Hands-free: LAND ON BAR

Let the plugin do the automation

1. ADVANCED: LAND ON BAR 8, CURVE SOFT.
2. Press GO (or send MIDI C1, or step the Go parameter) anywhere in the bar where the build starts.
3. The rise runs from that bar and lands exactly eight bars later. The plugin stays at zero until you touch the knob.

The underwater drop

DEEP DIVE

1. DEEP DIVE, TAIL 2 bars.
2. Rise over 8 bars: the mix closes down under a huge reverb.
3. On the drop the full-range mix comes back all at once, with the wash still fading behind it.

Festival build

UPLIFT or SUPERNOVA

1. UPLIFT: the gate speeds up bar by bar, the pitch rises 100 Hz, noise sweeps in.
2. For more, SUPERNOVA: +200 Hz, the Shepard climb racing, full noise.
3. Turn PITCH down in ADVANCED if the lift sounds too metallic on your material.

7 Tips, tricks and troubleshooting

Tips

- **Late is better.** Most of the change should happen in the last two or three bars - use CURVE EXP for LAND runs, or draw the automation that way.
- **Keep the kick out** of the bus Rise sits on if you want the groove to keep driving through the build.
- **SINK 0** turns Rise into a pure add-on: nothing ever gets quieter.
- **Stop means quiet.** When the song stops, Rise lets its tail go and rests at zero until you press play or touch the knob, so a build left half-way never colours what you audition next.
- **Presets are starting points.** Every macro works in every preset: add DIVE to HORIZON, a GATE to SUNRISE.

Troubleshooting

SYMPTOM	CAUSE	FIX
Nothing happens	INTENSITY is at 0 (the plugin nulls there)	Turn it up, or press GO with LAND ON BAR set
No GO button	LAND ON BAR is MANUAL	Set 4, 8, 16 or 32 bars in ADVANCED
The knob went back to 0 after a GO run	That is the landing - the plugin stays at zero until the knob moves	Move the knob to take over again
The build gets quieter	SINK lowers the dry so the drop can jump	Lower SINK in ADVANCED, 0 = never quieter
The tail stops dead on the drop	TAIL is CUT	Set TAIL to 1-4 bars
The effect switched off when I stopped the song	REST ON STOP: when the host stops, Rise fades its tail and rests at zero, whatever the automation left INTENSITY at - it never keeps building or ringing into a stopped project	Press play again, or touch the knob
The lift sounds metallic	PITCH is a frequency shift, not a transposition	Lower PITCH in ADVANCED