RONE PLUGINS

USER MANUAL

THE SIMPLE DELAY

RONE Delay

One TIME dial with every note value written on it, a filter inside the loop, four knobs - and a screen that shows the sound going in and every echo coming out.



VERSION 1.1.1 · VST3 · AU · STANDALONE

RONEAUDIO.COM

Contents

1	Welcome to RONE Delay	the delay you understand at a glance
2	Installation with the RONE Plugins Center	Center, account, file locations
3	Quick start	your first echo
4	Interface tour	every element on screen
5	TIME	one dial, every note value
6	Stereo modes	MONO, SPREAD, PING-PONG, DUAL
7	The loop filter	every echo a little thinner, a little darker
8	FEEDBACK, SEND, WET, DUCK	the four knobs
9	The screens	LIVE and ONE HIT
10	Footer: KILL, HOLD, lamps, BYPASS	the performance controls
11	Presets and MACRO	30 factory presets and four slots of your own
12	Step-by-step workflows	recipes
13	Interface conventions	knobs, right-click, resize, back panel
14	Troubleshooting, specifications and support	when something is off

1 Welcome to RONE Delay

RONE Delay is a feedback delay built to be read, not studied. Turn one dial for the time, pick how the echoes sit in the stereo field, set how many come back and how they darken - and watch them on screen while the track plays.

- **One TIME dial** - straight, dotted and triplet note values in one turn, sorted by length, from 1/64 to a dotted bar. The value is written out in the middle of the dial, never a bare dot.
- **Four stereo modes** - MONO, SPREAD, PING-PONG and DUAL (two delays, left and right, each with its own TIME).
- **A filter inside the loop** - every echo passes the high-pass and the low-pass once more, so each repeat is a little thinner and darker than the last.
- **SEND and WET** - close SEND and the tail rings on (the throw); close WET and the echoes are gone at once.
- **Safe by design** - FEEDBACK at 100 % holds the echoes forever instead of building up, and no echo ever passes 0 dBFS.

The dry signal is never touched. What you hear is your sound plus the echoes - closing every knob gives you back exactly what came in.

Where it shines


- **Vocal throws** - hold one word into the delay with HOLD and let it ring.
- **Rhythmic leads and plucks** - dotted and triplet echoes that sit on the groove.
- **Slapback and doubling** - short MS times for width without a tail.
- **Dub** - high feedback, a dark loop filter and KILL to stop it on cue.

The 10-second version

1. Insert RONE Delay on the track.
2. Pick a preset - the list is sorted by use.
3. Turn TIME to the note value you want.
4. Set FEEDBACK for how many echoes, WET for how loud.

2 Installation with the RONE Plugins Center

Every RONE product is installed, updated and licensed through one application: the **RONE Plugins Center**. You never download individual installers by hand, and you never enter serial numbers into the plugin itself.



RONE Plugins Center. 1 Navigation · 2 Your account and licence · 3 Sync status · 4 Search · 5 Refresh · 6 Settings · 7 Updates summary · 8 UPDATE ALL · 9 Filters · 10 Sort · 11 A plugin card · 12 Card menu (Details, Open, Manual) · 13 OPEN the standalone app · 14 INSTALL · 15 Your plan

Step by step

1. Download the Center from roneaudio.com and run the installer (Windows: `RONE_Plugins_Center_Installer.exe`, macOS: `RONE_Plugins_Center.dmg`). On Windows the installer also adds the Microsoft WebView2 runtime if your PC does not have it yet; it is required for the plugin interfaces. On macOS (10.15 Catalina or later, Intel and Apple Silicon) the first launch may be blocked because the installer is not yet Apple-notarized: open **System Settings → Privacy & Security**, scroll to the message about the blocked app and press **Open Anyway**, then confirm. If macOS calls the file *damaged*, run `xattr -cr "/Applications/RONE Plugins Center.app"` in Terminal once.

2. Open the Center and sign in with your **roneaudio.com account** (the same e-mail and password you used on the website). Your licences and device slots are checked automatically: an active **ALL ACCESS** plan unlocks every plugin, and a **lifetime licence** unlocks the plugin it was bought for — so RONE Delay opens either way.

3. Find **RONE Delay** in the list and press **INSTALL**. The Center downloads the signed installer, verifies its checksum, installs it silently and registers the version.

4. When the card shows **INSTALLED**, start (or restart) your DAW and rescan plugins if it does not pick up new plugins automatically. All RONE plugins appear next to each other in your plugin list because every name starts with **RONE**.

5. Updates appear on the same card. Press **UPDATE** on one plugin or **UPDATE ALL** at the top. Close the standalone version of a plugin before updating it.

Where the files go

WINDOWS

FILE	LOCATION
VST3	`C:\Program Files\Common Files\VST3\RONE\RONE Delay.vst3`
Standalone app	`C:\Program Files\RONE Plugins\RONE Delay.exe`
This manual	`C:\Program Files\RONE Plugins\Manuals\`

MACOS

FILE	LOCATION
VST3	`/Library/Audio/Plug-Ins/VST3/RONE Delay.vst3`
Audio Unit	`/Library/Audio/Plug-Ins/Components/RONE Delay.component`
Standalone app	`/Applications/RONE Delay.app`
This manual	`/Users/Shared/RONE Plugins/Manuals/`

> **MANUAL INSIDE THE CENTER**
> Every installed plugin has a **Manual** entry in its card menu (the three dots on the card). It opens this PDF from the install folder, or from roneaudio.com if the local copy is missing.

Licence and activation

Licensing is tied to your account, not to a key. The plugin checks the licence file that the Center writes when you sign in. There are two ways to own it: an **ALL ACCESS** plan, which unlocks every RONE plugin for as long as it is active, or a **lifetime licence** for this plugin alone, which never expires. Either one opens RONE Delay, and buying the lifetime licence later does not disturb a plan you already have.

If a plugin ever shows the *A RONE Delay licence or RONE ALL ACCESS is required* screen, open the Center, make sure you are signed in and the plugin shows as licensed, then reopen it. Two devices can be signed in at the same time on either kind of licence; sign out on an old machine from the Center's Account page to free a slot. A lifetime licence keeps working offline for far longer than a plan does — there is nothing for it to expire against — but the Center still needs to reach the internet occasionally to confirm it.

Uninstalling

Windows: Settings → Apps → *RONE Delay (RONE)*. macOS: delete the bundles listed above. Presets and settings in your user folder are kept.

3 Quick start



RONE Delay on its opening preset, HOOK DOTTED: a vocal hook on top, its ping-pong echoes jumping left and right below it.

1. **Insert** RONE Delay on a vocal, a lead or a pluck. Use it as an insert: there is no dry control - your sound always passes - so on an FX return the sent signal would be heard twice.
2. **Press play.** The LIVE screen draws the sound going in (IN, white) and the echoes coming out (L and R, champagne) over the last two bars.
3. **Pick a preset** - click the name for the list, or step with the arrows. `HOOK DOTTED` is the opening setting: a dotted 8th, ping-pong, a band-passed loop.
4. **Turn TIME.** Every step is a note value on the host tempo; the readout under the dial writes it out (*DOTTED 8TH · 317 ms @ 142 BPM*).
5. **Set FEEDBACK** for how many echoes come back, **WET** for how loud they are. The ONE HIT map shows where every echo lands and how loud it is before you play a note.
6. **Shape the loop** - drag the HP and LP handles on the filter strip. Every repeat goes through them again.

> **NO TEMPO IN THE STANDALONE**
> Without a host the plugin runs at 120 BPM, so SYNC values are worked out at that tempo.


4 Interface tour



The main page in PING-PONG with the opening preset.

1. **Header logo** — click to flip to the back panel (About, version, licence)
2. **PRESET** — the name opens the factory list by category; the arrows step through it
3. **Stereo mode** — MONO, SPREAD, PING-PONG or DUAL
4. **BYPASS** — the echoes go, the dry stays
5. **SYNC / MS** — note values on the host tempo, or free time in milliseconds
6. **TIME dial** — the delay time; in DUAL two small dials, LEFT and RIGHT, take its place
7. **Time readout** — the value written out (DOTTED 8TH) and its length in ms at the host tempo
8. **STRAIGHT / DOTTED / TRIPLET** — which family the current step belongs to - a readout, not a switch
9. **LIVE scope** — the last two bars: IN (the dry) and the echoes on L and R
10. **ONE HIT map** — one hit and every echo it makes: when, which side, how loud
11. **Loop filter** — the HP and LP handles inside the feedback loop; the wheel sets each slope
12. **FEEDBACK** — how many echoes; 100 % = infinite hold
13. **SEND** — how much goes into the delay; closing it lets the tail ring
14. **WET** — how loud the echoes are; closing it cuts them
15. **DUCK** — the echoes dip while the sound plays and come back in the gaps
16. **KILL** — the tail is gone in 20 ms
17. **HOLD** — SEND at 100 % for as long as you hold the button
18. **Lamps** — REST ON STOP, SAFE and DUCKING light when the engine does that
19. **MACRO** — four slots for your own settings, saved with the project
20. **Resize grip** — drag to resize the window

5 TIME



SYNC: the dial, the readout and the family of the step.

SYNC – note values


The dial holds **19 note values in one turn**, sorted by length - straight, dotted and triplet mixed in the order you hear them get longer:

```
1/64 · 1/32T · 1/32 · 1/16T · 1/32. · 1/16 · 1/8T · 1/16. · 1/8 · 1/4T · 1/8. · 1/4 · 1/2T · 1/4. · 1/2 · 1/1T · 1/2. · 1/1 · 1/1.
```

Around the dial, **white dots** with a label are the straight values, **champagne dots** the dotted ones and **rings** the triplets. The middle of the dial always writes the current value out (*1/8.*), the line under it names it (*DOTTED 8TH*) and gives its length at the host tempo (*317 ms @ 142 BPM*). The **STRAIGHT / DOTTED / TRIPLET** row lights the family of that step.

GESTURE	WHAT IT DOES
Drag the dial up / down	One step every 16 pixels; hold `Shift` for finer travel (40 pixels a step).
Mouse wheel / arrow keys	One step per notch or key press.
Click a dot or a label	Jumps straight to that value.
Right-click the dial (VST3)	The host's automation menu for TIME.

MS – free time



MS: 110 ms, with the nearest note value under it.

Switch to **MS** for a time that is not tied to the tempo: **5 ms to 2 s**, on a log scale marked 5, 10, 25, 50, 100, 250, 500 ms, 1 s and 2 s (click a number to jump to it). The readout shows the nearest note value at the host tempo (*≈ 1/16 @ 142 BPM*), so you know where a free time sits against the beat. Drag, the wheel and the arrow keys work as in SYNC; `Shift` is fine.

Switching between SYNC and MS keeps the time you hear: SYNC → MS takes the note's length in milliseconds, MS → SYNC takes the nearest note value.

A CLEAN JUMP, NO PITCH GLIDE

When TIME changes, a second read head starts at the new time and the two crossfade over 30 ms. The echoes already in the delay stay where they are - no tape-style pitch bend, no click.

TIME

```
SYNC: 1/64 to 1/1. (19 steps)
MS: 5 ms to 2 s
automatable
```

The delay time. In SYNC it follows the host tempo; in MS it is fixed. The opening preset is 1/8. (dotted 8th).

SYNC / MS

```
default SYNC
automatable
```

Which of the two the dial sets. Both values are kept, so switching back and forth never loses your setting.

6 Stereo modes

The switch in the header decides how the echoes sit in the stereo field. In MONO, SPREAD and PING-PONG the delay is fed with your sound summed to mono; in DUAL each side feeds its own delay.

MODE	WHAT YOU HEAR
MONO	One delay line, the echoes in the middle.
SPREAD	Two lines, the right one 17 ms longer: the same echoes, but wide.
PING-PONG	The echoes jump from side to side: the first on the left, then right, left, right.
DUAL	Two separate delays: left in → left out, right in → right out, each with its own TIME.

Changing the mode rewires the loop, so the echoes in it fade out in 20 ms and the delay starts clean in the new mode.

DUAL – two TIME dials



DUAL (the DUAL DOTTED preset): a dotted 8th on the left against a quarter on the right.

1. **DUAL** — the fourth stereo mode
2. **LEFT** — the left delay's TIME, with its name and length under it
3. **RIGHT** — the right delay's TIME

In DUAL the big dial gives way to **two small dials side by side, LEFT and RIGHT**. Each sets its own side directly: drag, wheel and arrow keys as on the big dial, `Shift` for fine. The value is written inside each dial, and the name and length under it. SYNC / MS applies to both. FEEDBACK, SEND, WET, DUCK and the loop filter are shared by the two sides.

The right side opens as a quarter note (375 ms in MS). The ONE HIT map draws the left echoes above the line and the right ones below, so you see the two rhythms against each other.

7 The loop filter



The filter strip with the pointer on it (RADIO TAIL): each handle shows its frequency, and its slope underneath.

The strip under the screens is a **high-pass and a low-pass inside the feedback loop**. The first echo passes them once, the second twice, the third three times - so every repeat is thinner and darker than the one before, the way old tape and analogue delays faded out. The curve on the strip is the filter's real response.

GESTURE	WHAT IT DOES
Drag on the strip	The nearer handle follows. HP always stays a little below LP.
Mouse wheel on the strip	The nearer handle's slope: 6, 12, 18, 24, 36 or 48 dB/oct (wheel up = steeper).
Double-click near a handle	Turns that filter off: HP to 20 Hz (OFF), LP to 20 kHz (OFF).
Right-click near a handle (VST3)	The host's automation menu for that frequency.

At rest each handle shows only its frequency (*HP 450*, *LP 2.5k*). While the pointer is on the strip the slope appears as a second line under it.

HP / LP

```
20 Hz to 20 kHz
HP at 20 Hz = OFF,
LP at 20 kHz = OFF
automatable
```

Where the loop cuts the lows and the highs. The opening preset is HP 450 Hz, LP 2.5 kHz - a band that keeps the echoes out of the way of the dry.

Tip: Both cuts are Butterworth (maximally flat): no resonant bump and never above 0 dB, so a steep slope is safe inside the loop even at high feedback.

Slopes

```
6 / 12 / 18 / 24 /
36 / 48 dB/oct
default 12 dB/oct
automatable
```

How steep each cut is, set separately for HP and LP. 6 dB/oct darkens gently over many repeats; 36 and 48 dB/oct give the hard band-passed sound of a telephone or radio.

8 FEEDBACK, SEND, WET, DUCK



FEEDBACK, SEND, WET and DUCK.

FEEDBACK

`0 to 100 %`
`100 % = ∞ hold`
`automatable`

How much of each echo goes back into the delay - how many echoes you hear. Hover the knob: its tooltip tells you how long the tail lives now and how many repeats it has (*Now: … s, … repeats*, or ∞ *HOLD*).

At **100 %** the knob shows **∞**, its arc turns white and the echoes hold forever - an infinite loop you can play over. SAFE keeps it from building up.



The ONE HIT map at FEEDBACK 100 % (INFINITE HOLD): every echo as loud as the first.

SEND

`0 to 100 %`
`automatable`

How much of your sound goes *into* the delay. Close it and what is already inside keeps ringing - the classic **throw**: open SEND for one word, close it, and the word repeats on its own.

WET

`0 to 100 %`
`automatable`

How loud the echoes are. Close it and they are gone at once. The dry is never touched by WET (or by any other control).

DUCK

`0 to 100 %`
`0 = OFF`
`automatable`

The echoes dip while your sound plays and come back up in the gaps, so a busy vocal stays clear and the tail fills the pauses. Ducking starts when the dry reaches -40 dBFS and is full at -10 dBFS; after the dry stops the echoes come back over about 150 ms. DUCK sets how deep they go - at 100 % they disappear under a loud phrase.

SEND OR WET?

Both make the echoes quieter, but not the same way. **SEND** changes what goes in: lower it and the echoes already in the delay ring on at full level. **WET** changes what comes out: lower it and every echo, old and new, drops at once. For a throw, automate SEND; to mute the delay, close WET.

EVERY KNOB

Drag (Shift = fine), mouse wheel (2 % a notch, Shift 0.5 %), right-click = the host's parameter menu. Double-click resets a knob: FEEDBACK to 45 %, SEND to 100 %, WET to 55 %, DUCK to OFF.

9 The screens

LIVE · 2 BARS

The big screen shows the last **two bars** at the host tempo, scrolling to the left, with the newest moment at the right edge. Three lanes: **IN** is your sound going in (white), **L** and **R** are the echoes coming out of each side (champagne). Heights are peak levels in dB, so quiet late echoes stay visible. While the host plays, bar lines are drawn strong and beat lines faint.

Use it to see what the settings do: in PING-PONG the echoes alternate between the L and R lanes, in SPREAD they sit on both a little apart, in DUAL each lane follows its own TIME. With DUCK up you see the echoes shrink under the phrase and swell in the gap after it.


ONE HIT → WHAT YOU HEAR

The narrow screen is a prediction you can read before you play: the white bar on the left is one hit, and every champagne bar after it is an echo - **where it lands in time, on which side and how loud**. Left echoes point up from the centre line, right echoes down; in MONO each echo is drawn on both. The heights come from the real loop filter, FEEDBACK, SEND and WET, so the map changes as you turn them. Faint lines mark the beats, stronger ones the bars.



VOCAL SLAP: MONO, 110 ms, FEEDBACK 12 %. The map shows three short echoes and nothing more; LIVE shows them right behind the phrase.

10 Footer: KILL, HOLD, lamps, BYPASS



The footer: KILL, HOLD, the three lamps and the MACRO slots.

KILL

`button`

Ends the tail now: the echoes fade out in 20 ms and the delay is emptied. Your settings do not change, and the next sound you send starts a fresh set of echoes.

HOLD = SEND 100%

`hold the button automatable (Hold Send)`

While you hold it, SEND is at 100 % whatever the knob says; let go and SEND is back to the knob. Set SEND to 0 and HOLD becomes a throw button: hold it over one word, release, and the word repeats on its own. As a host parameter it can be automated for exact throws.

BYPASS

`on / off automatable`

The echoes fade out and your sound passes untouched. Switching it never clicks.

The lamps

The three lamps are read-outs, not switches: the engine always does these things, and the lamp lights when it happens.

LAMP	LIGHTS WHEN
REST ON STOP	The host has just started or stopped playing. On both edges the echoes fade out in 20 ms and the delay is emptied, so a stopped project is silent and every play starts clean - no old tail from where you were before. The standalone has no transport, so it never rests.
SAFE	The loop is riding its safety knee. What goes into the delay is clean up to -3 dBFS and runs into a soft knee above it, so a loud input or FEEDBACK at 100 % holds instead of building up, and no echo ever passes 0 dBFS.
DUCKING	DUCK is up and the echoes are being pulled down under your sound.

11 Presets and MACRO



The preset list, opened from the name: grouped by category, the live preset marked, its time on the right.

Presets

Click the **preset name** to open the list. The 30 factory presets are grouped by use - **VOCAL, RHYTHM, SLAP, DUB, SPACE, DUAL** and **FX** - and each row shows its time on the right (a note value, a time in ms, or DUAL). The ◀ ▶ arrows step through the whole list.

A preset sets TIME (both sides for the DUAL presets), the stereo mode, FEEDBACK, SEND, WET, DUCK and the loop filter with its slopes. Change anything and a * appears after the name. The preset name is saved with the project.

CATEGORY	PRESETS
VOCAL	HOOK DOTTED · VOCAL SLAP · VOCAL QUARTER · WIDE VOCAL · HOLD THROW · RADIO TAIL
RHYTHM	CLEAN QUARTER · EIGHTH PING · DOTTED LEAD · TRIPLET SPREAD · TRIPLET PING · 16TH SHIMMER · DRUM GROOVE
SLAP	SLAP · DOUBLER · ROOM SLAP · FLAM
DUB	DUB THROW · DUB SPACE · DARK DUB · STEPPER
SPACE	BIG SPACE · WASH · INFINITE HOLD
DUAL	DUAL DOTTED · DUAL SLAP · DUAL POLY · DUAL DRIFT
FX	TELEPHONE · RISER FEED

MACRO 1-4



Slots 1 and 2 hold a setting (the small dot); you are on slot 2.

Four slots in the footer for **your own settings**, saved with the project.

GESTURE	WHAT IT DOES
Click an empty slot	Saves the current settings there.
Click a full slot	Recalls it.
Hold a slot (about 0.6 s)	Saves over it.
Right-click a slot	Clears it.

A full slot shows a small dot; the slot you are on is lit, and it goes dark again as soon as you change something. A slot keeps TIME (SYNC / MS and both sides), the stereo mode, FEEDBACK, SEND, WET, DUCK and the loop filter with its slopes - not BYPASS or HOLD.

12 Step-by-step workflows

The vocal throw

one word repeats, the rest stays dry

1. Preset HOLD THROW (SEND 0, a dotted quarter, ping-pong).
2. Play the vocal and hold **HOLD** over the word you want thrown; let go after it.
3. Set FEEDBACK for how long it rings; darken it with LP.
4. To print it, automate *Hold Send* in your DAW instead of holding the button.

The dotted lead

echoes that answer the groove

1. Preset DOTTED LEAD, or TIME on 1/8. in PING-PONG.
2. FEEDBACK 40-60 %, HP around 300 Hz so the echoes stay out of the bass.
3. DUCK 30-50 % keeps the lead's notes clear and lets the echoes fill the gaps.

Slapback and doubling

width without a tail

1. Preset VOCAL SLAP or DOUBLER - TIME in MS (20-120 ms).
2. FEEDBACK low (0-15 %), SPREAD for width.
3. Close WET until the double sits behind the voice.

A dub spin

high feedback under control

1. Preset DUB THROW or DARK DUB.
2. Ride FEEDBACK up towards 100 % - SAFE keeps the loop from running away.
3. Pull LP down while it spins, then press **KILL** on the downbeat.

Two rhythms at once

DUAL

1. Preset DUAL POLY (a triplet against a dotted 8th) or DUAL DOTTED.
2. Set LEFT and RIGHT to two values that cross - the ONE HIT map shows the pattern they make.
3. Keep FEEDBACK moderate; two lines fill up twice as fast.

13 Interface conventions

All RONE plugins share the same graphite interface language, so once you know one, you know them all.

GESTURE	WHAT IT DOES
Drag a knob up/down	Changes the value. The lit arc shows where you are in the range; the value is printed inside the knob.
Hold `Shift` while dragging	Fine adjustment.
Double-click a knob	Resets it: FEEDBACK 45 %, SEND 100 %, WET 55 %, DUCK OFF.
Right-click a control (VST3)	Opens your DAW's automation / parameter menu for that control (for example FL Studio's *Create automation clip*, *Link to controller*). RONE never shows a browser context menu.
Mouse wheel	Steps the TIME dials and the knobs; on the filter strip it sets the slope.
Drag the triangle in the bottom-right corner	Resizes the window. The interface scales proportionally and keeps its aspect ratio.
Click the R logo / plugin name in the header	Flips the plugin over to its **back panel**: version, format, licence holder, a link to roneaudio.com and a DEACTIVATE button for this device.



The back panel. Click the header brand to open it; click CLOSE (or the panel edge) to flip back.

AUTOMATION

Every knob and switch is a host parameter. Automate it from the DAW's automation lane or by right-clicking the control inside the plugin (VST3). Values shown in the plugin always match the DAW's.

PRESETS AND STATE

The plugin's full state is saved with your DAW project, so a project reopens exactly as you left it. Where the plugin has its own preset browser (the name field with ◀ ▶ arrows), factory presets are built in and your own presets are stored in your user folder.

STANDALONE VERSION

The standalone app is the same plugin in its own window, useful for auditioning and exporting without a DAW. It uses your system's default audio device; with no DAW clock RONE Delay runs at 120 BPM.

14 Troubleshooting, specifications and support

Troubleshooting

SYMPTOM	WHAT TO DO
The echoes keep going after I stop the song	They should not: REST ON STOP empties the delay when the host stops. In the standalone there is no transport - press KILL.
SYNC times are wrong in the standalone	The standalone has no host tempo and runs at 120 BPM. Use MS for exact times there.
The tail builds up and gets loud	SAFE stops it at its knee, but very high FEEDBACK with an open filter is dense by nature: lower FEEDBACK, raise HP or lower LP.
Closing SEND does not stop the echoes	That is SEND's job - it lets the tail ring. Close WET (or press KILL) to stop them.
DUAL sounds like one delay	DUAL keeps left and right apart, so a mono source feeds both sides the same sound - set LEFT and RIGHT to different times to hear two delays. On a mono track only the LEFT delay is heard.
A preset name has a * after it	You changed something since loading it. Load it again to go back, or save your version in a MACRO slot.
The plugin does not appear in the DAW	Rescan plugins. On Windows the VST3 lives in `C:\Program Files\Common Files\VST3\RONE`; make sure that folder (or its parent) is in the DAW's VST3 search path. On macOS restart the DAW after installing; Logic and GarageBand may need a full AU rescan.
The window is blank or shows an error page (Windows)	The Microsoft WebView2 runtime is missing or damaged. Reinstall the RONE Plugins Center; it repairs WebView2. Also check that `WebView2Loader.dll` sits next to the standalone executable.
The window is white in Ableton Live but the standalone works (Windows)	Turn off Live's auto-scaling for this plugin: in Live's browser open **Plug-Ins**, right-click the plugin and untick **Auto-Scale Plug-In Window**, then delete the plugin from the track and insert it again. Seen with Windows display scaling at values such as 110 %.
A licence screen appears	Open the RONE Plugins Center, sign in, confirm your plan is active, then reopen the plugin. Check that you have not exceeded your device limit.
The plugin shows an older version than the Center	Close every DAW and standalone RONE app, then press UPDATE again. A running

SYMPTOM	WHAT TO DO
	standalone keeps the old executable locked.
Crash	RONE plugins write a crash report to your user folder; the Center uploads it the next time it runs. Please also tell us what you did right before the crash.

Specifications

Product	RONE Delay
Version	1.1.1 `(manual revised November 2026)`
Formats	VST3 · AU · Standalone (Windows: VST3 + Standalone; macOS: VST3 + AU + Standalone)
Systems	Windows 10 / 11 (64-bit) · macOS 11 or newer (Intel and Apple silicon, universal)
Channels	Mono or stereo in / out (DUAL works on stereo: left and right are two separate delays)
Sample rates	44.1 kHz to 192 kHz
Latency	None added by the plugin
Engine	JUCE 8, WebView interface (WebView2 on Windows, WebKit on macOS)

Support

Website, presets, updates and support: roneaudio.com. When writing to us, include the plugin version (shown on the back panel), your DAW and operating system, and the steps to reproduce.

RONE Delay is designed and coded in Israel by Liran “RONE” Kalifa. © 2024–2026 RONE PLUGINS. All rights reserved. All product names are trademarks of their respective owners.