"一切皆文件" linux 中的至理名言。对于 linux 网络子系统,依然适用。sockfs 就是最直接的证明。接下来我们分析 linux 网络子系统的基石--sockfs。后续我们会基于 sockfs 来对 linux 网络子系统做全面深入的分析。

分析任何东西,都要先找到他的入口。net/socket.c--sock_init()就是我们需要分析的网络子系统的入口。

```
static int __init sock_init(void)
{
```

skb_init(); //初始化 skbuff 的 slab cache 名为 skbuff_head_cache skb_init 定义与 net/core/skbuff.c 中

//对 slab cache 不了解的同学可以参考下深入 linux 内核

架构中内存管理的相关章节

init_inodecache();// 初始化 socket_alloc 类型的 slab cache cache 名为 sock_inode_cache

// 返回地址存储在全局变量 sock_inode_cachep

指针中

重点讨论

}

};

err = register_filesystem(&sock_fs_type); //注册 sockfs 文件系统 注册原理同其他文件系统注册一直,都是将

//对应的

file_system_type 变量插入全局变量 file_systems 指向的链表中

sock_mnt = kern_mount(&sock_fs_type); //执行文件系统挂在操作, 接下来

```
ptp_classifier_init();//后续再分析
```

以上是 sockfs 初始化并挂载的关键步骤,省略部分代码。也是网络子系统的初始化。在 sockfs 注册过程用到了 sock_fs_type 变量。那么我们看下其定义及其结构的定义:

.mount = sockfs_mount, .kill_sb = kill_anon_super,

struct file_system_type {

const char *name;

int fs_flags;

#define FS REQUIRES DEV 1

#define FS_BINARY_MOUNTDATA 2

#define FS_HAS_SUBTYPE 4

#define FS_USERNS_MOUNT 8 /* Can be mounted by userns root */

#define FS_RENAME_DOES_D_MOVE 32768 /* FS will handle d_move()

during rename() internally. */

struct dentry *(*mount) (struct file_system_type *, int, const char *, void *);
void (*kill_sb) (struct super_block *);

```
struct module *owner;
                 struct file_system_type * next;
                 struct hlist_head fs_supers;
         }
         注册过程比较简单,就是向 file_systems 链表中插入 file_system_type 变量。接下
来分析 kern mount 挂载过程。
         include/linux/fs.h
         #define kern_mount(type) kern_mount_data(type, NULL) //宏定义
         fs/namespace.c
         最终实现:
         struct vfsmount *kern_mount_data(struct file_system_type *type, void *data)
         {
             struct vfsmount *mnt;
             mnt = vfs_kern_mount(type, MS_KERNMOUNT, type->name, data);
             if (!IS_ERR(mnt)) {
               * it is a longterm mount, don't release mnt until
               * we unmount before file sys is unregistered
               */
                  real_mount(mnt)->mnt_ns = MNT_NS_INTERNAL;
             return mnt;
         }
         调用 vfs_kern_mount()
          在 fs/namespace.c 文件中定义
         实现:
            struct vfsmount *
            vfs_kern_mount(struct file_system_type *type, int flags, const char *name, void
*data)
            {
                   struct mount *mnt;
                   struct dentry *root;
                   if (!type)
                       return ERR_PTR(-ENODEV);
                   mnt = alloc_vfsmnt(name); //分配 mount 结构, 并初始化
                   if (!mnt)
                      return ERR_PTR(-ENOMEM);
```

```
if (flags & MS_KERNMOUNT)
                       mnt->mnt.mnt_flags = MNT_INTERNAL; //设置内部挂载标志
                   root = mount_fs(type, flags, name, data);
                   if (IS_ERR(root)) {
                          mnt_free_id(mnt);
                          free_vfsmnt(mnt);
                          return ERR_CAST(root);
                     }
                   mnt->mnt.mnt root = root;
                   mnt->mnt.mnt_sb = root->d_sb;
                   mnt->mnt_mountpoint = mnt->mnt.mnt_root;
                   mnt->mnt_parent = mnt;
                   lock_mount_hash();
                   list_add_tail(&mnt->mnt_instance, &root->d_sb->s_mounts);
                   unlock_mount_hash();
                   return &mnt->mnt;
           }
             这一部分代码比较简单, 就是分配 mount(挂载点)结构, 同时调用 mount_fs
执行挂载操作, 如下
             // fs/super.c 中定义
             struct dentry *
             mount_fs(struct file_system_type *type, int flags, const char *name, void *data)
             {
                    struct dentry *root;
                    struct super_block *sb;
                    char *secdata = NULL;
                    int error = -ENOMEM;
                    if (data && !(type->fs_flags & FS_BINARY_MOUNTDATA)) {
                        secdata = alloc_secdata();
                        if (!secdata)
                         goto out;
                        error = security_sb_copy_data(data, secdata);
                        if (error)
                            goto out_free_secdata;
                    }
                    root = type->mount(type, flags, name, data);// 调用 sock_fs_type 成
员 mount 即 sockfs_mount () 函数
                    if (IS_ERR(root)) {
```

```
error = PTR_ERR(root);
                         goto out_free_secdata;
                    }
                    sb = root->d_sb;
                    BUG_ON(!sb);
                    WARN_ON(!sb->s_bdi);
                    sb->s_flags |= MS_BORN;
                    error = security_sb_kern_mount(sb, flags, secdata);
                    if (error)
                    goto out sb;
 * filesystems should never set s_maxbytes larger than MAX_LFS_FILESIZE
 * but s_maxbytes was an unsigned long long for many releases. Throw
 * this warning for a little while to try and catch filesystems that
 * violate this rule.
 */
                    WARN((sb->s_maxbytes < 0), "%s set sb->s_maxbytes to "
                         "negative value (%lld)\n", type->name, sb->s_maxbytes);
                    up_write(&sb->s_umount);
                    free_secdata(secdata);
                    return root;
                 out_sb:
                    dput(root);
                    deactivate_locked_super(sb);
                 out_free_secdata:
                    free_secdata(secdata);
                 out:
                       return ERR_PTR(error);
             }
           该函数调用 type->mount() 执行挂载操作, 返回 sockfs 根目录 root。
type->mount()指向 sockfs_mount()函数。如下:
         net/socket.c
         static struct dentry *sockfs_mount(struct file_system_type *fs_type,
                int flags, const char *dev_name, void *data)
         {
             return mount_pseudo_xattr(fs_type, "socket:", &sockfs_ops,
                     sockfs_xattr_handlers,
                     &sockfs_dentry_operations, SOCKFS_MAGIC);
         }该函数简单封装 mount_pseudo_xattr()函数,该函数主要创建 super_block 同时
创建根节点 inode, dentry 等相关关系。完成 sockfs 的初始化
```

最终 sockfs 形成如下框架:

