


(editable in Settings > System > About) can also be used to access Device Portal on the local network (for example, <http://Phone360>), which is useful for devices that may change networks or IP addresses frequently, or need to be shared.

2. Press the Pair button on your phone to generate and display the required security code
3. Enter the 6 character security code into the Device Portal password box in your browser.
4. (Optional) Check the Remember my computer box in your browser to remember this pairing in the future.

Here's the Device Portal section of the developer settings page on Windows Phone.



If you are using Device Portal in a protected environment, like a test lab, where you trust everyone on your local network, have no personal information on the device, and have unique requirements, you can disable authentication. This enables unencrypted communication, and allows anyone with the IP address of your phone to control it.

Tool Notes

Device Portal pages

Processes

The ability to terminate arbitrary processes is not included in the Windows Mobile Device Portal.

Device Portal on mobile devices provides the standard set of pages. For detailed descriptions, see [Windows Device Portal overview](#).

- App Manager
- App File Explorer (Isolated Storage Explorer)
- Processes
- Performance charts
- Event Tracing for Windows (ETW)
- Performance tracing (WPR)
- Devices
- Networking

See also

- [Windows Device Portal overview](#)
- [Device Portal core API reference](#)

Windows Device Portal core REST API reference

Article • 11/30/2022

All Windows Device Portal (WDP) functionality is built on REST APIs that developers can call directly to access resources and control their devices programmatically.

App deployment

Install an app

Request

You can install an app by using the following request format.

Method	Request URI
POST	/api/app/packagemanager/package

URI parameters

You can specify the following additional parameters on the request URI:

URI parameter	Description
package	(required) The file name of the package to be installed.

Request headers

- None

Request body

- The .appx or .appxbundle file, as well as any dependencies the app requires.
- The certificate used to sign the app, if the device is IoT or Windows Desktop. Other platforms do not require the certificate.

Response

Status code

This API has the following expected status codes.

HTTP status code	Description
200	Deploy request accepted and being processed
4XX	Error codes
5XX	Error codes

Available device families

- Windows Mobile
- Windows Desktop
- Xbox
- HoloLens
- IoT

Note

Windows Mixed Reality runs on regular desktop, so it's the same portal as Desktop.

Install a related set

Request

You can install a [related set](#) by using the following request format.

Method	Request URI
POST	/api/app/packagemanager/package

URI parameters

You can specify the following additional parameters on the request URI:

URI parameter	Description
package	(required) The file names of the packages to be installed.

Request headers

- None

Request body

- Add ".opt" to the optional package file names when specifying them as a parameter, like so: "foo.appx.opt" or "bar.appxbundle.opt".
- The .appx or .appxbundle file, as well as any dependencies the app requires.
- The certificate used to sign the app, if the device is IoT or Windows Desktop. Other platforms do not require the certificate.

Response

Status code

This API has the following expected status codes.

HTTP status code	Description
200	Deploy request accepted and being processed
4XX	Error codes
5XX	Error codes

Available device families

- Windows Mobile
 - Windows Desktop
 - Xbox
 - HoloLens
 - IoT
-

Register an app in a loose folder

Request

You can register an app in a loose folder by using the following request format.

Method	Request URI
POST	/api/app/packagemanager/networkapp

URI parameters

- None

Request headers

- None

Request body

JSON

```
{
  "mainpackage" :
  {
    "networkshare" : "\\some\share\path",
    "username" : "optional_username",
    "password" : "optional_password"
  }
}
```

Response

Status code

This API has the following expected status codes.

HTTP status code	Description
200	Deploy request accepted and being processed
4XX	Error codes
5XX	Error codes

Available device families

- Windows Desktop
- Xbox
- HoloLens
- IoT

Register a related set in loose file folders

Request

You can register a [related set](#) in loose folders by using the following request format.

Method	Request URI
POST	/api/app/packagemanager/networkapp

URI parameters

- None

Request headers

- None

Request body

JSON

```
{
  "mainpackage" :
  {
    "networkshare" : "\\some\\share\\path",
    "username" : "optional_username",
    "password" : "optional_password"
  },
  "optionalpackages" :
  [
    {
      "networkshare" : "\\some\\share\\path2",
      "username" : "optional_username2",
      "password" : "optional_password2"
    },
    ...
  ]
}
```

Response

Status code

This API has the following expected status codes.

HTTP status code	Description
200	Deploy request accepted and being processed
4XX	Error codes
5XX	Error codes

Available device families

- Windows Desktop
 - Xbox
 - HoloLens
 - IoT
-

Get app installation status

Request

You can get the status of an app installation that is currently in progress by using the following request format.

Method	Request URI
GET	/api/app/packagemanager/state

URI parameters

- None

Request headers

- None

Request body

- None

Response

Status code

This API has the following expected status codes.

HTTP status code	Description
200	The result of the last deployment
204	The installation is running
404	No installation action was found

Available device families

- Windows Mobile
- Windows Desktop
- Xbox
- HoloLens
- IoT

Uninstall an app

Request

You can uninstall an app by using the following request format.

Method	Request URI
DELETE	/api/app/packagemanager/package

URI parameters

URI parameter	Description
package	(required) The PackageFullName (from GET /api/app/packagemanager/packages) of the target app

Request headers

- None

Request body

- None

Response

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Mobile
 - Windows Desktop
 - Xbox
 - HoloLens
 - IoT
-

Get installed apps

Request

You can get a list of apps installed on the system by using the following request format.

Method	Request URI
GET	/api/app/packagemanager/packages

URI parameters

- None

Request headers

- None

Request body

- None

Response

The response includes a list of installed packages with associated details. The template for this response is as follows.

JSON

```
{
  "InstalledPackages": [
    {
      "Name": string,
      "PackageFamilyName": string,
      "PackageFullName": string,
      "PackageOrigin": int,
      (https://msdn.microsoft.com/library/windows/desktop/dn313167(v=vs.85).aspx)
      "PackageRelativeId": string,
      "Publisher": string,
      "Version": {
        "Build": int,
        "Major": int,
        "Minor": int,
        "Revision": int
      },
      "RegisteredUsers": [
        {
          "UserDisplayName": string,
          "UserSID": string
        }, ...
      ]
    }
  ]
}
```

```
} , ...  
}] }
```

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Mobile
- Windows Desktop
- Xbox
- HoloLens
- IoT

Bluetooth

Get the Bluetooth radios on the machine

Request

You can get a list of the Bluetooth radios that are installed on the machine by using the following request format. This can be upgraded to a WebSocket connection as well, with the same JSON data.

Method	Request URI
GET	/api/bt/getradios
GET/WebSocket	/api/bt/getradios

URI parameters

- None

Request headers

- None

Request body

- None

Response

The response includes a JSON array of Bluetooth radios attached to the device.

JSON

```
{ "BluetoothRadios" : [  
  {  
    "BluetoothAddress" : int64,  
    "DisplayName" : string,  
    "HasUnknownUsbDevice" : boolean,  
    "HasProblem" : boolean,  
    "ID" : string,  
    "ProblemCode" : int,  
    "State" : string  
  }, ...  
]}
```

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Desktop
- HoloLens
- IoT

Turn the Bluetooth radio on or off

Request

Sets a specific Bluetooth radio to On or Off.

Method	Request URI
POST	/api/bt/setradio

URI parameters

You can specify the following additional parameters on the request URI:

URI parameter	Description
ID	(required) The device ID for the Bluetooth radio and must be base 64 encoded.
State	(required) This can be "On" or "Off".

Request headers

- None

Request body

- None

Response

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Desktop
- HoloLens
- IoT

Get a list of paired Bluetooth devices

Request

You can get a list of the currently paired Bluetooth devices by using the following request format. This can be upgraded to a WebSocket connection with the same JSON data. During the lifetime of the WebSocket connection, the device list can change. A complete list of devices will be sent over the WebSocket connection each time there is an update.

Method	Request URI
GET	/api/bt/getpaired
GET/WebSocket	/api/bt/getpaired

URI parameters

- None

Request headers

- None

Request body

- None

Response

The response includes a JSON array of Bluetooth devices that are currently paired.

JSON

```
{ "PairedDevices": [
  {
    "Name" : string,
    "ID" : string,
    "AudioConnectionStatus" : string
  }, ...
]}
```

The *AudioConnectionStatus* field will be present if the device can be used for audio on this system. (Policies and optional components may affect this.) *AudioConnectionStatus* will be either "Connected" or "Disconnected".

Get a list of available Bluetooth devices

Request

You can get a list of the Bluetooth devices available for pairing by using the following request format. This can be upgraded to a WebSocket connection with the same JSON data. During the lifetime of the WebSocket connection, the device list can change. A complete list of devices will be sent over the WebSocket connection each time there is an update.

Method	Request URI
GET	/api/bt/getavailable
GET/WebSocket	/api/bt/getavailable

URI parameters

- None

Request headers

- None

Request body

- None

Response

The response includes a JSON array of Bluetooth devices that are currently available for pairing.

JSON

```
{  
  "AvailableDevices": [  
    {  
      "Name" : string,  
      "ID" : string  
    }, ...  
  ]  
}
```

Connect a Bluetooth device

Request

Will connect to the device if the device can be used for audio on this system. (Policies and optional components may affect this.)

Method	Request URI
--------	-------------

Method	Request URI
POST	/api/bt/connectdevice

URI parameters

URI parameter	Description
ID	(required) The Association Endpoint ID for the Bluetooth device and must be Base64-encoded.

Request headers

- None

Request body

- None

Response

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Desktop
- HoloLens
- IoT

Disconnect a Bluetooth device

Request

Will disconnect the device if the device can be used for audio on this system. (Policies and optional components may affect this.)

Method	Request URI
POST	/api/bt/disconnectdevice

URI parameters

URI parameter	Description
ID	(required) The Association Endpoint ID for the Bluetooth device and must be Base64-encoded.

Request headers

- None

Request body

- None

Response

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Desktop
- HoloLens
- IoT

Device manager

Get the installed devices on the machine

Request

You can get a list of devices that are installed on the machine by using the following request format.

Method	Request URI
GET	/api/devicemanager/devices

URI parameters

- None

Request headers

- None

Request body

- None

Response

The response includes a JSON array of devices attached to the device.

JSON

```
{ "DeviceList": [
  {
    "Class": string,
    "Description": string,
    "ID": string,
    "Manufacturer": string,
    "ParentID": string,
    "ProblemCode": int,
    "StatusCode": int
  }, ...
]}
```

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes

HTTP status code	Description
5XX	Error codes

Available device families

- Windows Mobile
- Windows Desktop
- IoT

Get data on connected USB Devices/Hubs

Request

You can get a list of USB descriptors for connected USB devices and Hubs by using the following request format.

Method	Request URI
GET	/ext/devices/usbdevices

URI parameters

- None

Request headers

- None

Request body

- None

Response

The response is JSON that includes DeviceID for the USB Device along with the USB Descriptors and port information for hubs.

JSON

```
{
  "DeviceList": [
    {
      "ID": string,
      "ParentID": string, // Will equal an "ID" within the list, or be
blank
```

```

        "Description": string, // optional
        "Manufacturer": string, // optional
        "ProblemCode": int, // optional
        "StatusCode": int // optional
    },
    ...
]
}

```

Sample return data

JSON

```

{
  "DeviceList": [{
    "ID": "System",
    "ParentID": ""
  }, {
    "Class": "USB",
    "Description": "Texas Instruments USB 3.0 xHCI Host Controller",
    "ID":
"PCI\\VEN_104C&DEV_8241&SUBSYS_1589103C&REV_02\\4&37085792&0&00E7",
    "Manufacturer": "Texas Instruments",
    "ParentID": "System",
    "ProblemCode": 0,
    "StatusCode": 25174026
  }, {
    "Class": "USB",
    "Description": "USB Composite Device",
    "DeviceDriverKey": "{36fc9e60-c465-11cf-8056-444553540000}\\0016",
    "ID": "USB\\VID_045E&PID_00DB\\8&2994096B&0&1",
    "Manufacturer": "(Standard USB Host Controller)",
    "ParentID": "USB\\VID_0557&PID_8021\\7&2E9A8711&0&4",
    "ProblemCode": 0,
    "StatusCode": 25182218
  }
  ]
}

```

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
5XX	Error codes

Available device families

- Windows Desktop

- IoT

Dump collection

Get the list of all crash dumps for apps

Request

You can get the list of all the available crash dumps for all sideloaded apps by using the following request format.

Method	Request URI
GET	/api/debug/dump/usermode/dumps

URI parameters

- None

Request headers

- None

Request body

- None

Response

The response includes a list of crash dumps for each sideloaded application.

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Window Mobile (in Windows Insider Program)
- Windows Desktop
- HoloLens
- IoT

Get the crash dump collection settings for an app

Request

You can get the crash dump collection settings for a sideloaded app by using the following request format.

Method	Request URI
GET	/api/debug/dump/usermode/crashcontrol

URI parameters

You can specify the following additional parameters on the request URI:

URI parameter	Description
packageFullName	(required) The full name of the package for the sideloaded app.

Request headers

- None

Request body

- None

Response

The response has the following format.

JSON

```
{"CrashDumpEnabled": bool}
```

Status code

This API has the following expected status codes.

HTTP status code	Description
------------------	-------------

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Window Mobile (in Windows Insider Program)
- Windows Desktop
- HoloLens
- IoT

Delete a crash dump for a sideloaded app

Request

You can delete a sideloaded app's crash dump by using the following request format.

Method	Request URI
DELETE	/api/debug/dump/usermode/crashdump

URI parameters

You can specify the following additional parameters on the request URI:

URI parameter	Description
packageFullName	(required) The full name of the package for the sideloaded app.
fileName	(required) The name of the dump file that should be deleted.

Request headers

- None

Request body

- None

Response

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Window Mobile (in Windows Insider Program)
- Windows Desktop
- HoloLens
- IoT

Disable crash dumps for a sideloaded app

Request

You can disable crash dumps for a sideloaded app by using the following request format.

Method	Request URI
DELETE	/api/debug/dump/usermode/crashcontrol

URI parameters

You can specify the following additional parameters on the request URI:

URI parameter	Description
packageFullName	(required) The full name of the package for the sideloaded app.

Request headers

- None

Request body

- None

Response

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Window Mobile (in Windows Insider Program)
- Windows Desktop
- HoloLens
- IoT

Download the crash dump for a sideloaded app

Request

You can download a sideloaded app's crash dump by using the following request format.

Method	Request URI
GET	/api/debug/dump/usermode/crashdump

URI parameters

You can specify the following additional parameters on the request URI:

URI parameter	Description
packageFullName	(required) The full name of the package for the sideloaded app.
fileName	(required) The name of the dump file that you want to download.

Request headers

- None

Request body

- None

Response

The response includes a dump file. You can use WinDbg or Visual Studio to examine the dump file.

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Window Mobile (in Windows Insider Program)
- Windows Desktop
- HoloLens
- IoT

Enable crash dumps for a sideloaded app

Request

You can enable crash dumps for a sideloaded app by using the following request format.

Method	Request URI
POST	/api/debug/dump/usermode/crashcontrol

URI parameters

You can specify the following additional parameters on the request URI:

URI parameter	Description
packageFullName	(required) The full name of the package for the sideloaded app.

Request headers

- None

Request body

- None

Response

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK

Available device families

- Window Mobile (in Windows Insider Program)
 - Windows Desktop
 - HoloLens
 - IoT
-

Get the list of bugcheck files

Request

You can get the list of bugcheck minidump files by using the following request format.

Method	Request URI
GET	/api/debug/dump/kernel/dumplist

URI parameters

- None

Request headers

- None

Request body

- None

Response

The response includes a list of dump file names and the sizes of these files. This list will be in the following format.

JSON

```
{
  "DumpFiles": [
    {
      "FileName": string,
      "FileSize": int
    }, ...
  ]
}
```

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK

Available device families

- Windows Desktop
- IoT

Download a bugcheck dump file

Request

You can download a bugcheck dump file by using the following request format.

Method	Request URI
GET	/api/debug/dump/kernel/dump

URI parameters

You can specify the following additional parameters on the request URI:

URI parameter	Description
filename	(required) The file name of the dump file. You can find this by using the API to get the dump list.

Request headers

- None

Request body

- None

Response

The response includes the dump file. You can inspect this file using WinDbg.

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Desktop
 - IoT
-

Get the bugcheck crash control settings

Request

You can get the bugcheck crash control settings by using the following request format.

Method	Request URI
GET	/api/debug/dump/kernel/crashcontrol

URI parameters

- None

Request headers

- None

Request body

- None

Response

The response includes the crash control settings. For more information about CrashControl, see the [CrashControl](#) article. The template for the response is as follows.

JSON

```
{
  "autoreboot": bool (0 or 1),
  "dumptype": int (0 to 4),
  "maxdumpcount": int,
  "overwrite": bool (0 or 1)
}
```

Dump types

0: Disabled

1: Complete memory dump (collects all in-use memory)

2: Kernel memory dump (ignores user mode memory)

3: Limited kernel minidump

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Desktop
- IoT

Get a live kernel dump

Request

You can get a live kernel dump by using the following request format.

Method	Request URI
GET	/api/debug/dump/livekernel

URI parameters

- None

Request headers

- None

Request body

- None

Response

The response includes the full kernel mode dump. You can inspect this file using WinDbg.

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Desktop
- IoT

Get a dump from a live user process

Request

You can get the dump for live user process by using the following request format.

Method	Request URI
GET	/api/debug/dump/usermode/live

URI parameters

You can specify the following additional parameters on the request URI:

URI parameter	Description
pid	(required) The unique process id for the process you are interested in.

Request headers

- None

Request body

- None

Response

The response includes the process dump. You can inspect this file using WinDbg or Visual Studio.

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Desktop
- IoT

Set the bugcheck crash control settings

Request

You can set the settings for collecting bugcheck data by using the following request format.

Method	Request URI
POST	/api/debug/dump/kernel/crashcontrol

URI parameters

You can specify the following additional parameters on the request URI:

URI parameter	Description
autoreboot	(optional) True or false. This indicates whether the system restarts automatically after it fails or locks.
dumptype	(optional) The dump type. For the supported values, see the CrashDumpType Enumeration .
maxdumpcount	(optional) The maximum number of dumps to save.
overwrite	(optional) True or false. This indicates whether or not to overwrite old dumps when the dump counter limit specified by <i>maxdumpcount</i> has been reached.

Request headers

- None

Request body

- None

Response

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Desktop

- IoT

ETW

Create a realtime ETW session over a websocket

Request

You can create a realtime ETW session by using the following request format. This will be managed over a websocket. ETW events are batched on the server and sent to the client once per second.

Method	Request URI
GET/WebSocket	/api/etw/session/realtime

URI parameters

- None

Request headers

- None

Request body

- None

Response

The response includes the ETW events from the enabled providers. See ETW WebSocket commands below.

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Mobile
- Windows Desktop
- HoloLens
- IoT

ETW WebSocket commands

These commands are sent from the client to the server.

Command	Description
provider { <i>guid</i> } enable { <i>level</i> }	Enable the provider marked by { <i>guid</i> } (without brackets) at the specified level. { <i>level</i> } is an <code>int</code> from 1 (least detail) to 5 (verbose).
provider { <i>guid</i> } disable	Disable the provider marked by { <i>guid</i> } (without brackets).

This responses is sent from the server to the client. This is sent as text and you get the following format by parsing the JSON.

JSON

```
{
  "Events": [
    {
      "Timestamp": int,
      "ProviderName": string,
      "ID": int,
      "TaskName": string,
      "Keyword": int,
      "Level": int,
      payload objects...
    }, ...
  ],
  "Frequency": int
}
```

Payload objects are extra key-value pairs (string:string) that are provided in the original ETW event.

Example:

JSON

```
{
  "ID" : 42,
  "Keyword" : 9223372036854775824,
  "Level" : 4,
  "Message" : "UDPv4: 412 bytes transmitted from 10.81.128.148:510 to 132.215.243.34:510. ",
  "PID" : "1218",
  "ProviderName" : "Microsoft-Windows-Kernel-Network",
  "TaskName" : "KERNEL_NETWORK_TASK_UDPIP",
  "Timestamp" : 131039401761757686,
  "connid" : "0",
  "daddr" : "132.245.243.34",
  "dport" : "500",
  "saddr" : "10.82.128.118",
  "seqnum" : "0",
  "size" : "412",
  "sport" : "500"
}
```

Enumerate the registered ETW providers

Request

You can enumerate through the registered providers by using the following request format.

Method	Request URI
GET	/api/etw/providers

URI parameters

- None

Request headers

- None

Request body

- None

Response

The response includes the list of ETW providers. The list will include the friendly name and GUID for each provider in the following format.

JSON

```
{  
  "Providers": [  
    {  
      "GUID": string, (GUID)  
      "Name": string  
    }, ...  
  ]  
}
```

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK

Available device families

- Windows Mobile
- Windows Desktop
- HoloLens
- IoT

Enumerate the custom ETW providers exposed by the platform.

Request

You can enumerate through the registered providers by using the following request format.

Method	Request URI
GET	/api/etw/customproviders

URI parameters

- None

Request headers

- None

Request body

- None

Response

200 OK. The response includes the list of ETW providers. The list will include the friendly name and GUID for each provider.

JSON

```
{"Providers": [  
  {  
    "GUID": string, (GUID)  
    "Name": string  
  },...  
]}
```

Status code

- Standard status codes.

Available device families

- Windows Mobile
- Windows Desktop
- HoloLens
- IoT

Location

Get location override mode

Request

You can get the device's location stack override status by using the following request format. Developer mode must be on for this call to succeed.

Method	Request URI
GET	/ext/location/override

URI parameters

- None

Request headers

- None

Request body

- None

Response

The response includes the override state of the device in the following format.

JSON

```
{"Override" : bool}
```

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Mobile
- Windows Desktop
- Xbox
- HoloLens
- IoT

Set location override mode

Request

You can set the device's location stack override status by using the following request format. When enabled, the location stack allows position injection. Developer mode must be on for this call to succeed.

Method	Request URI
PUT	/ext/location/override

URI parameters

- None

Request headers

- None

Request body

JSON

```
{"Override" : bool}
```

Response

The response includes the override state that the device has been set to in the following format.

JSON

```
{"Override" : bool}
```

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Mobile
- Windows Desktop
- Xbox
- HoloLens
- IoT

Get the injected position

Request

You can get the device's injected (spoofed) location by using the following request format. An injected location must be set, or an error will be thrown.

Method	Request URI
GET	/ext/location/position

URI parameters

- None

Request headers

- None

Request body

- None

Response

The response includes the current injected latitude and longitude values in the following format.

JSON

```
{
  "Latitude" : double,
  "Longitude" : double
}
```

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Mobile
- Windows Desktop
- Xbox

- HoloLens
- IoT

Set the injected position

Request

You can set the device's injected (spoofed) location by using the following request format. Location override mode must first be enabled on the device, and the set location must be a valid location or an error will be thrown.

Method	Request URI
PUT	/ext/location/override

URI parameters

- None

Request headers

- None

Request body

JSON

```
{
  "Latitude" : double,
  "Longitude" : double
}
```

Response

The response includes the location that has been set in the following format.

JSON

```
{
  "Latitude" : double,
  "Longitude" : double
}
```

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Mobile
- Windows Desktop
- Xbox
- HoloLens
- IoT

OS information

Get the machine name

Request

You can get the name of a machine by using the following request format.

Method	Request URI
GET	/api/os/machinename

URI parameters

- None

Request headers


- None

Request body

- None

Response

The response includes the computer name in the following format.



JSON

```
{"ComputerName": string}
```

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Mobile
- Windows Desktop
- Xbox
- HoloLens
- IoT

Get the operating system information

Request

You can get the OS information for a machine by using the following request format.

Method	Request URI
GET	/api/os/info

URI parameters

- None

Request headers

- None

Request body

- None

Response

The response includes the OS information in the following format.

JSON

```
{
  "ComputerName": string,
  "OsEdition": string,
  "OsEditionId": int,
  "OsVersion": string,
  "Platform": string
}
```

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Mobile
- Windows Desktop
- Xbox
- HoloLens
- IoT

Get the device family

Request

You can get the device family (Xbox, phone, desktop, etc) using the following request format.

Method	Request URI
GET	/api/os/devicefamily

URI parameters

- None

Request headers

- None

Request body

- None

Response

The response includes the device family (SKU - Desktop, Xbox, etc).

JSON

```
{
  "DeviceType" : string
}
```

DeviceType will look like "Windows.Xbox", "Windows.Desktop", etc.

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Mobile
- Windows Desktop
- Xbox
- HoloLens
- IoT

Set the machine name

Request

You can set the name of a machine by using the following request format.

Method	Request URI
POST	/api/os/machinename

URI parameters

You can specify the following additional parameters on the request URI:

URI parameter	Description
name	(required) The new name for the machine. This should be base64 encoded.

Request headers

- None

Request body

- None

Response

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK

Available device families

- Windows Mobile
- Windows Desktop
- Xbox
- HoloLens
- IoT

User information

Get the active user

Request

You can get the name of the active user on the device by using the following request format.

Method	Request URI
GET	/api/users/activeuser

URI parameters

- None

Request headers

- None

Request body

- None

Response

The response includes user information in the following format.

On success:

JSON

```
{
  "UserDisplayName" : string,
  "UserSID" : string
}
```

On failure:

JSON

```
{
  "Code" : int,
  "CodeText" : string,
  "Reason" : string,
  "Success" : bool
}
```

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Desktop
- HoloLens
- IoT

Performance data

Get the list of running processes

Request

You can get the list of currently running processes by using the following request format. this can be upgraded to a WebSocket connection as well, with the same JSON data being pushed to the client once per second.

Method	Request URI
GET	/api/resourcemanager/processes
GET/WebSocket	/api/resourcemanager/processes

URI parameters

- None

Request headers

- None

Request body

- None

Response

The response includes a list of processes with details for each process. The information is in JSON format and has the following template.

JSON

```
{
  "Processes": [
    {
      "CPUUsage": float,
      "ImageName": string,
      "PageFileUsage": long,
      "PrivateWorkingSet": long,
      "ProcessId": int,
      "SessionId": int,
      "UserName": string,
      "VirtualSize": long,
      "WorkingSetSize": long
    }, ...
  ]
}
```

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Mobile
- Windows Desktop
- HoloLens
- IoT

Get the system performance statistics

Request

You can get the system performance statistics by using the following request format. This includes information such as read and write cycles and how much memory has been used.

Method	Request URI
GET	/api/resourcemanager/systemperf
GET/WebSocket	/api/resourcemanager/systemperf

This can also be upgraded to a WebSocket connection. It provides the same JSON data below once every second.

URI parameters

- None

Request headers

- None

Request body

- None

Response

The response includes the performance statistics for the system such as CPU and GPU usage, memory access, and network access. This information is in JSON format and has the following template.

JSON

```
{
  "AvailablePages": int,
  "CommitLimit": int,
  "CommittedPages": int,
  "CpuLoad": int,
  "IOOtherSpeed": int,
  "IOReadSpeed": int,
  "IOWriteSpeed": int,
  "NonPagedPoolPages": int,
  "PageSize": int,
  "PagedPoolPages": int,
  "TotalInstalledInKb": int,
  "TotalPages": int,
  "GPUData":
  {
    "AvailableAdapters": [{ (One per detected adapter)
      "DedicatedMemory": int,
      "DedicatedMemoryUsed": int,
      "Description": string,
      "SystemMemory": int,
      "SystemMemoryUsed": int,
```

```
        "EnginesUtilization": [ float,... (One per detected engine)]
    },...
}],
"NetworkingData": {
    "NetworkInBytes": int,
    "NetworkOutBytes": int
}
}
```

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Mobile
- Windows Desktop
- Xbox
- HoloLens
- IoT

Power

Get the current battery state

Request

You can get the current state of the battery by using the following request format.

Method	Request URI
GET	/api/power/battery

URI parameters

- None

Request headers

- None

Request body

- None

Response

The current battery state information is returned using the following format.

JSON

```
{
  "AcOnline": int (0 | 1),
  "BatteryPresent": int (0 | 1),
  "Charging": int (0 | 1),
  "DefaultAlert1": int,
  "DefaultAlert2": int,
  "EstimatedTime": int,
  "MaximumCapacity": int,
  "RemainingCapacity": int
}
```

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Mobile
- Windows Desktop
- HoloLens
- IoT

Get the active power scheme

Request

You can get the active power scheme by using the following request format.

Method	Request URI
GET	/api/power/activecfg

URI parameters

- None

Request headers

- None

Request body

- None

Response

The active power scheme has the following format.

JSON
<pre>{"ActivePowerScheme": string (guid of scheme)}</pre>

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Desktop
- IoT

Get the sub-value for a power scheme

Request

You can get the sub-value for a power scheme by using the following request format.

Method	Request URI
GET	/api/power/cfg/<power scheme path>

Options:

- SCHEME_CURRENT

URI parameters

- None

Request headers

- None

Request body

A full listing of power states available is on a per-application basis and the settings for flagging various power states like low and critical battery.

Response

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Desktop
- IoT

Get the power state of the system

Request

You can check the power state of the system by using the following request format. This will let you check to see if it is in a low power state.

Method	Request URI
GET	/api/power/state

URI parameters

- None

Request headers

- None

Request body

- None

Response

The power state information has the following template.

JSON

```
{"LowPowerState" : false, "LowPowerStateAvailable" : true }
```

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Desktop
- HoloLens
- IoT

Set the active power scheme

Request

You can set the active power scheme by using the following request format.

Method	Request URI
POST	/api/power/activecfg

URI parameters

You can specify the following additional parameters on the request URI:

URI parameter	Description
scheme	(required) The GUID of the scheme you want to set as the active power scheme for the system.

Request headers

- None

Request body

- None

Response

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Desktop
- IoT

Set the sub-value for a power scheme

Request

You can set the sub-value for a power scheme by using the following request format.

Method	Request URI
POST	/api/power/cfg/<power scheme path>

URI parameters

You can specify the following additional parameters on the request URI:

URI parameter	Description
valueAC	(required) The value to use for A/C power.
valueDC	(required) The value to use for battery power.

Request headers

- None

Request body

- None

Response

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK

Available device families

- Windows Desktop
- IoT

Get a sleep study report

Request

Method	Request URI
--------	-------------

Method	Request URI
GET	/api/power/sleepstudy/report

You can get a sleep study report by using the following request format.

URI parameters | URI parameter | Description | | :----- | :----- | | FileName | **(required)**

The full name for the file you want to download. This value should be hex64 encoded. |

Request headers

- None

Request body

- None

Response

The response is a file containing the sleep study.

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Desktop
- IoT

Enumerate the available sleep study reports

Request

You can enumerate the available sleep study reports by using the following request format.

Method	Request URI
--------	-------------

Method	Request URI
GET	/api/power/sleepstudy/reports

URI parameters

- None

Request headers

- None

Request body

- None

Response

The list of available reports has the following template.

JSON

```
{"Reports": [  
  {  
    "FileName": string  
  },...  
]}
```

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Desktop
- IoT

Get the sleep study transform

Request

You can get the sleep study transform by using the following request format. This transform is an XSLT that converts the sleep study report into an XML format that can be read by a person.

Method	Request URI
GET	/api/power/sleepstudy/transform

URI parameters

- None

Request headers

- None

Request body

- None

Response

The response contains the sleep study transform.

Status code

This API has the following expected status codes.

HTTP status code	Description
200	OK
4XX	Error codes
5XX	Error codes

Available device families

- Windows Desktop
- IoT

Remote control
