

2026Q3.1 RELEASE

LOQATE VERIFY ENGINE/LOCAL API WITH AI PARSER

Date: 16 August 2026

Version: 1.1

Prepared by: New Teong Chuan

Contents

2026Q3.1 Local API Notice	3
Locate Local API Installer	3
64-bit Linux Installer	3
64-bit Windows Installer	4
Getting “InstallManager.jar” To Run	5
Download JRE	5
Execute Install Manager.....	6
Using AI Parser in Verify	7
Enable License Key Verification Using Product Codes for AI Parser Model File Downloads	7
Enable the Server Option “AIParser=YES”	8
Batch Verify	10

2026Q3.1 Local API Notice

In the 2026Q3.1 release, Local API is officially introduced, featuring two new installation options enhanced with AI Parser capability:

Platform	Installer
64-bit Linux (x86_64)	loqate_installer_mt_linux_x86_64-gcc13_lfs64
64-bit Windows (x86_64)	loqate_installer_mt_win_x64_vs2022_lfs64

Loqate Local API Installer

64-bit Linux Installer

The 64-bit Linux installer with AI Parser is:

- `loqate_installer_mt_linux_x86_64-gcc13_lfs64`

Dependency: The installer contains Verify Engine shared objects (.so) compiled with **GCC13.3.0** (GLIBC 2.39, GLIBCXX_3.4.33) or later, which is required on the **target Linux system for runtime compatibility**.

Running the installer will unpack the binaries as the following:

Command: `$ ./loqate_installer_mt_linux_x86_64-gcc13_lfs64`

```
/c/Loqate/Releases/2026Q3.0-2.60.0.20019-280f427-Lin64_LFS64_GCC13$ ls -lh
591K Jul 14 13:11 InstallManager.jar
214 Jul 14 13:11 InstallManager.sh
92K Jul 14 13:13 _pyloqate.so
45 Jul 14 13:11 buildc++.sh
45 Jul 14 13:11 buildjava.sh
4.0K Jul 18 21:46 data
4.0K Jul 18 11:10 lib
6.2M Jul 14 13:13 liblqtcr.so
29K Jul 14 13:13 liblqtjava.so
316M Jul 14 13:13 libtensorflow.so.2
35M Jul 14 13:13 libtensorflow_framework.so.2
14K Jul 14 13:13 loqate.jar
2.7K Jul 14 13:11 lqtSample.java
3.7K Jul 14 13:11 lqtSample.py
194K Jul 14 13:13 lqtbatch
5.3K Jul 14 13:11 lqtcr.h
100K Jul 14 13:13 lqtinter
15K Jul 14 13:11 lqtquerysample.cpp
1.7K Jul 14 13:11 lqtsample.cpp
9.9K Jul 14 13:13 pyloqate.py
426 Jul 14 13:11 runbatch.sh
94 Jul 14 13:11 runc++.sh
327 Jul 14 13:11 runjava.sh
44K Jul 14 13:11 sample.txt
21 Jul 14 13:11 version.txt
/c/Loqate/Releases/2026Q3.0-2.60.0.20019-280f427-Lin64_LFS64_GCC13$
```

64-bit Windows Installer


The 64-bit Windows installer with AI Parser is:

- `loqate_installer_mt_win_x64_vs2022_lfs64.exe`

Dependency: The installer contains Verify Engine dynamic library (.dll) compiled with Microsoft Visual Studio 2022¹, which is required on the **target Windows system for runtime compatibility**.

Running the installer will unpack the binaries as the following:

Double-click: `loqate_installer_mt_win_x64_vs2022_lfs64.exe`



Name	Date modified	Type	Size
data	22/7/2026 5:39 PM	File folder	
lib	22/7/2026 5:39 PM	File folder	
_pyloqate.pyd	14/7/2026 11:23 AM	Python Extension Module	88 KB
debug.txt	22/7/2026 6:00 PM	TXT File	486 KB
InstallManager.bat	14/7/2026 11:18 AM	Windows Batch File	1 KB
InstallManager.jar	14/7/2026 11:18 AM	Eclipse Adoptium.jarfile	591 KB
loqate.ico	14/7/2026 11:18 AM	ICO File	15 KB
loqate.jar	14/7/2026 11:23 AM	Eclipse Adoptium.jarfile	14 KB
lqtBatch.exe	14/7/2026 11:23 AM	Application	235 KB
lqtcr.dll	14/7/2026 11:23 AM	Application extension	3,393 KB
lqtcr.exp	14/7/2026 11:22 AM	Exports Library File	7 KB
lqtcr.h	14/7/2026 11:17 AM	H File	6 KB
lqtcr.lib	14/7/2026 11:22 AM	Object File Library	11 KB
lqtDemo.exe	14/7/2026 11:27 AM	Application	162 KB
lqtDemoCore.dll	14/7/2026 11:27 AM	Application extension	131 KB
lqtDemoCore.runtimeconfig.json	14/7/2026 11:27 AM	JSON File	1 KB
lqtjava.dll	14/7/2026 11:23 AM	Application extension	22 KB
lqtnet.dll	14/7/2026 11:23 AM	Application extension	19 KB
lqtnetcore.deps.json	14/7/2026 11:27 AM	JSON File	2 KB
lqtnetcore.dll	14/7/2026 11:27 AM	Application extension	21 KB
lqtquerysample.cpp	14/7/2026 11:18 AM	CPP File	15 KB
lqtsample.cpp	14/7/2026 11:18 AM	CPP File	2 KB
lqtSample.cs	14/7/2026 11:18 AM	CS File	4 KB
lqtSample.java	14/7/2026 11:18 AM	IntelliJidea2025.3	3 KB
lqtSample.py	14/7/2026 11:18 AM	Python.File	4 KB
Microsoft.Windows.SDK.NET.dll	12/11/2024 1:23 AM	Application extension	25,725 KB
pyloqate.py	14/7/2026 11:23 AM	Python.File	11 KB
runbatch.bat	14/7/2026 11:18 AM	Windows Batch File	1 KB
sample.txt	14/7/2026 11:18 AM	TXT File	45 KB
tensorflow.dll	15/11/2022 2:30 PM	Application extension	195,295 KB
version.txt	14/7/2026 11:27 AM	TXT File	1 KB
WinRT.Runtime.dll	12/11/2024 1:23 AM	Application extension	517 KB

¹ Microsoft Visual C++ Redistributable latest supported downloads. Available at: <https://learn.microsoft.com/en-us/cpp/windows/latest-supported-vc-redist?view=msvc-170#visual-studio-2015-2017-2019-and-2022>

Getting “InstallManager.jar” To Run

InstallManager.jar is a Java tool used to download all GKR/reference data subscribed to by users. Install Manager is compiled using Java 8. Thus, Java/JRE 8 (preferred) with the latest update version is required for Install Manager to execute. However, Install Manager has also been tested on Java/JRE 11, 17, 21, and 25.

Download JRE

Java consists of JDK and JRE. Different versions of Java are available at:

Website	URL
Azul	https://www.azul.com/downloads/?package=jdk#zulu
Adoptium	https://adoptium.net/temurin/releases/
Openlogic	https://www.openlogic.com/openjdk-downloads
Corretto	https://github.com/corretto/corretto-8

Please choose one of the above URLs to download JRE.

For example, to download JRE 8 using the “Adoptium” website:

The screenshot shows the Adoptium website interface. The navigation bar includes links for 'Join Us', 'Latest Releases', 'Marketplace', 'Projects', 'Resources', 'Community', and a language selector. Below the navigation bar, there are tabs for 'All Versions', 'JDK 25 - LTS', 'JDK 21 - LTS', 'JDK 17 - LTS', and 'JDK 8 - LTS'. The 'JDK 8 - LTS' tab is selected. Below the tabs, there are links for 'Release notes', 'Installation guide', 'Supported Platforms', and 'Source Code'. The main content area shows download options for macOS, Windows, and Linux. For Linux, the 'JRE' button is highlighted. The 'TAR.GZ, 41 MB' download option is also highlighted. The 'Down Arrow' icon is highlighted. Red arrows point from the instructions to these elements.

1. Click “JDK 8 - LTS”
2. Click “JRE”
3. Click “Down Arrow”

Execute Install Manager

If the Java version installed on the operating system (OS) is not compatible with Install Manager, users are required to download a JRE (e.g., JRE 8) with the latest update version, rename the entire folder to “jre”, and place it in the installation folder, e.g.:

```
/c/Loqate/Releases/2026Q3.0-2.60.0.20019-280f427-Lin64_LFS64_GCC13$ ls -l
604312 Jul 14 13:11 InstallManager.jar
214 Jul 14 13:11 InstallManager.sh
93688 Jul 14 13:13 _pyloqate.so
45 Jul 14 13:11 buildc++.sh
45 Jul 14 13:11 buildjava.sh
4096 Jul 18 21:46 data
4096 Aug 12 22:36 jre
4096 Jul 18 11:10 lib
6496992 Jul 14 13:13 liblqtcr.so
28792 Jul 14 13:13 liblqtjava.so
331125864 Jul 14 13:13 libtensorflow.so.2
36280872 Jul 14 13:13 libtensorflow_framework.so.2
13438 Jul 14 13:13 loqate.jar
2760 Jul 14 13:11 lqtSample.java
3745 Jul 14 13:11 lqtSample.py
197840 Jul 14 13:13 lqtbatch
5333 Jul 14 13:11 lqtcr.h
101496 Jul 14 13:13 lqtinter
14816 Jul 14 13:11 lqtquerysample.cpp
1716 Jul 14 13:11 lqtsample.cpp
10137 Jul 14 13:13 pyloqate.py
426 Jul 14 13:11 runbatch.sh
94 Jul 14 13:11 runc++.sh
327 Jul 14 13:11 runjava.sh
44539 Jul 14 13:11 sample.txt
21 Jul 14 13:11 version.txt
/c/Loqate/Releases/2026Q3.0-2.60.0.20019-280f427-Lin64_LFS64_GCC13$
```

Please ensure that the “jre” folder contains “bin”, “lib”, and all relevant JRE contents, such as:

```
/c/Loqate/Releases/2026Q3.0-2.60.0.20019-280f427-Lin64_LFS64_GCC13/jre$ ls -l
1522 Oct 22 2024 ASSEMBLY_EXCEPTION
19274 Oct 22 2024 LICENSE
149631 Oct 22 2024 THIRD_PARTY_README
4096 Aug 12 22:41 bin
4096 Aug 12 22:41 lib
/c/Loqate/Releases/2026Q3.0-2.60.0.20019-280f427-Lin64_LFS64_GCC13/jre$
```

This ensures that “InstallManager.sh” or “InstallManager.bat” will run “InstallManager.jar” using the “jre” in the installation folder.

Below is the command to run “InstallManager.jar”:

Linux Command: `$ ./InstallManager.sh`

Windows Command: `$ ./InstallManager.bat`

Note: For further details on how to run Install Manager, please refer to

<https://docs.loqate.com/installers/data-installation-and-update-process#command-line-interface-mode>

Using AI Parser in Verify

Enable License Key Verification Using Product Codes for AI Parser Model File Downloads

GBG Internal Users

To use AI Parser, GBG internal users must submit a request to LogateSupport@gbgplc.com to enable their license key with the AI Parser model product codes listed by country in the table below. If all countries are required, users may request to enable the worldwide AI Parser model product code “DSVWWAP” for the license key (currently limited to the 16 countries listed below). Note: if “DSVWWAP” has been enabled for a license key, do not also add any of the product codes listed in the table below.

Customers

Any customer interested in using AI Parser must explicitly request that their account manager enable their license key with the AI Parser product codes listed in the table below.

No	Product Code	Product Name	Country (ISO 3166-1 alpha-2)
1	DSVAUSAP	Australia AI Parser Model File	AU
2	DSVBELAP	Belgium AI Parser Model File	BE
3	DSVCANAP	Canada AI Parser Model File	CA
4	DSVDEUAP	Germany AI Parser Model File	DE
5	DSVDNKAP	Denmark AI Parser Model File	DK
6	DSVFINAP	Finland AI Parser Model File	FI
7	DSVGBRAP	United Kingdom AI Parser Model File	GB
8	DSVIDNAP	Indonesia AI Parser Model File	ID
9	DSVLUXAP	Luxembourg AI Parser Model File	LU
10	DSVMEXAP	Mexico AI Parser Model File	MX
11	DSVMYSAP	Malaysia AI Parser Model File	MY
12	DSVNLDAP	Netherlands AI Parser Model File	NL
13	DSVNORAP	Norway AI Parser Model File	NO
14	DSVNZLAP	New Zealand AI Parser Model File	NZ
15	DSVSWEAP	Sweden AI Parser Model File	SE
16	DSVUSAAP	USA AI Parser Model File	US

Once a license key is enabled with the above product codes, users will be able to download AI Parser model files via Install Manager.

Enable the Server Option “AIParser=YES”

A new server option, “**AIParser**”, has been introduced to invoke the AI Parser feature. This option specifies whether the address verification process uses AI Parser. The default value of “**AIParser**” is empty; users must explicitly set “**AIParser=YES**” to use AI Parser.

Windows: IqtDemo.exe

In “**IqtDemo.exe**”, users can set “**AIParser=YES**”. Acceptable boolean values are “YES/TRUE/ON/1”.

Below is an example result for **AVC=V44-I45-P6-100** when the server option is set to “**AIParser=1**”.

The screenshot displays the Logate Demonstration UI v2.60.0.20019-280f427 LFS64. The interface is divided into several sections:

- Input Data:** Fields for ID, Organization, Address (Level 3A, Wisma Miramas, 1. Jalan 2/109e, Taman Desa Business Park, 58100 Kuala Lumpur, Wilayah Persekutuan Kuala Lumpur), Locality, AdministrativeArea, PostalCode, Country (MY), AIParser (1), OutputCasing, MaxResults, and checkboxes for Parse, Verify, Match, Search, Format, Geocode, and Enhance. Buttons for Clear Options, Clear Input, Clear Output, and Process are present.
- Output:** A table showing the results of the address verification process. The table has two columns: the field name and the result. The results are as follows:

Field	Result
Address Quality Index	A
Address Verification Code	V44-I45-P6-100
Organization	Empty
SubBuilding	Level 3A
Premise	1
Building	Wisma Miramas
PostBox	Empty
DependentThoroughfare	Empty
Thoroughfare	Jalan 2/109E
DoubleDependentLocality	Empty
DependentLocality	Taman Desa Business Park
Locality	Kuala Lumpur
SubAdministrativeArea	Empty
AdministrativeArea	Wilayah Persekutuan Kuala Lumpur
SuperAdministrativeArea	Empty
PostalCode	58100
Country	Malaysia
ISO2	MY
ISO3	MYS
Unmatched	
Processed Time	00:00:00.10
- Server Status:** ssOK
- Process Status:** psOK

Below is an example result for **AVC=V22-I25-P0-100** when the server option “**AIParser**” is left empty. Note that setting “**AIParser**” to one of the values among “YES/TRUE/ON/1”, will produce the same effect.

Loqate Demonstration UI v2.60.0.20019-280f427 LFS64

GKR Verify Autocomplete Query Log Analysis ReverseGeocode

Input Data

ID

Organization

Address Level 3A, Wisma Miramas, 1, Jalan 2/109e, Taman Desa Business Park, 58100 Kuala Lumpur, Wilayah Persekutuan Kuala Lumpur

Locality

AdministrativeArea

PostalCode

Country MY

AIParser ☐ Parse ☒ Verify

OutputCasing ☐ Match ☐ Search

MaxResults ☐ Format ☐ Geocode

☐ Enhance

Clear Options Clear Input Clear Output Process

Output

Address 2/109E
3A, Wisma Miramas, 1, Jalan
Level Taman Desa Business Park
Kuala Lumpur
Wilayah Persekutuan Kuala Lumpur

Latitude

Longitude

Accuracy

Distance

Map This Location

Output

Address Quality Index 1 Result Count 1

Address Verification Code A22-I25-P0-100

Organization Empty

SubBuilding 2/109E Identified no change

Premise 3A Identified no change

Building Empty

PostBox Empty

DependentThoroughfare Empty

Thoroughfare Wisma Miramas, 1 Jalan Identified context

DoubleDependentLocality Empty

DependentLocality Level Taman Desa Business Park Identified no change

Locality Kuala Lumpur Verified no change

SubAdministrativeArea Empty

AdministrativeArea Wilayah Persekutuan Kuala Lumpur Verified no change

SuperAdministrativeArea Empty

PostalCode Empty

Country Malaysia

ISO2 MY ISO3 MYS

Unmatched 58100

Processed Time 00:00:00.11

Cache Stats

Shortcuts

View All

To Clipboard

Server Status: ssOK Process Status: psOK

Batch Verify

The batch tool “**lqtBatch.exe**” (Windows) or “**lqtbatch**” (Linux) is available in the installation folder once installation is complete.

The following illustrates how to check the batch tool and engine version:

1. Open a terminal, navigate to the installation folder, and execute the following command:

Linux:

```
/opt/loqate$ ./lqtbatch -v
```

Windows:

```
C:\Loqate>lqtBatch.exe -v
```

2. The example output is:

```
LqtBatch: 2.60.0.20019-280f427 LFS64
Version Information: 2.60.0.20019-280f427 LFS64
Threading Model: Multi
```

- The first line displays lqtbatch’s version.
- The second line displays the liblqtcr.so (engine) version.
- The third line shows the threading model, which should always be “Multi”.

To run the batch tool with a batch input file using AI Parser:

Description	Value
Input file	test.txt
Output file	test.out
Data	/opt/loqate/data
Output to include value	-oi
Output to include header	-oh
Assigns unique identifier	-uid
Thread count	-tc 8
Server option	-opt AIParser=1

Linux:

```
/opt/loqate$ ./lqtbatch -i test.txt -o test.out -d /opt/loqate/data -oi -oh -uid -tc 8 -opt AIParser=yes
```

Windows:

```
C:\Loqate>lqtBatch.exe -i test.txt -o test.out -d C:\Loqate\data -oi -oh -uid -tc 8 -opt AIParser=yes
```