How do I resolve an unauthorized server error when I connect to the Amazon EKS API server?

Last updated: 2020-01-20

I get the message "error: You must be logged in to the server (Unauthorized)" when I use kubectl commands to connect to the Amazon Elastic Kubernetes Service (Amazon EKS) API server. How can I resolve this error?

Short Description

Before you connect to the Amazon EKS API server, install and configure the latest version of the AWS Command Line Interface (AWS CLI).

Then, the cluster admin must complete the steps in one of the following sections:

- You're the cluster creator
- You're not the cluster creator

Finally, the person who received the error must complete the steps in the You're the user or role that received the error section.

Resolution

You're the cluster creator

If you create the cluster, then complete the following steps:

1. To see the configuration of your AWS CLI user or role, run the following command:

```
$ aws sts get-caller-identity
```

The output returns the Amazon Resource Name (ARN) of the AWS Identity and Access Management (IAM) user or role. See the following example:

```
{
   "UserId": "XXXXXXXXXXXXXXXXX",
   "Account": "XXXXXXXXXXXXX",
   "Arn": "arn:aws:iam::XXXXXXXXXXXX:user/testuser"
}
```

- 2. Confirm that the ARN matches the cluster creator.
- 3. Update or generate the **kubeconfig** file using one of the following commands.

As the IAM user, run the following command:

```
$ aws eks update-kubeconfig --name eks-cluster-name --region aws-region
```

Note: Replace eks-cluster-name with your cluster name. Replace aws-region with your AWS Region.

As the IAM role, run the following command:

```
$ aws eks update-kubeconfig --name eks-cluster-name --region aws-region --role-arn arn:aws:iam::XXXXXXXXXXXXX:role/test
```

Note: Replace eks-cluster-name with your cluster name. Replace aws-region with your AWS Region.

4. To confirm that the **kubeconfig** file is updated, run the following command:

```
$ kubectl config view --minify
```

5. To confirm that your IAM user or role is authenticated, run the following command:

```
$ kubectl get svc
```

You should see output similar to the following:

NAME	TYPE	CLUSTER-IP	EXTERNAL-IP	PORT(S)	AGE
kubernetes	ClusterIP	10.100.0.1	<none></none>	443/TCP	77d

You're not the cluster creator

If you didn't create the cluster, then complete the following steps:

1. To see the configuration of your AWS CLI user or role, run the following command:

```
$ aws sts get-caller-identity
```

The output returns the ARN of the IAM user or role.

- 2. Ask the cluster owner or admin to add your IAM user or role to aws-auth ConfigMap.
- 3. To edit aws-auth ConfigMap in a text editor, the cluster owner or admin must run the following command:

```
$ kubectl edit configmap aws-auth -n kube-system
```

4. To add an IAM user or IAM role, complete either of the following steps.

Add the IAM user to **mapUsers**. See the following example:

```
mapUsers: |
    - userarn: arn:aws:iam::XXXXXXXXXXX:user/testuser
    username: testuser
    groups:
     - system:masters
```

Add the IAM role to **mapRoles**. See the following example:

```
mapRoles: |
    rolearn: arn:aws:iam::XXXXXXXXXXXX:role/testrole
    username: testrole
    groups:
        - system:masters
```

Note: The **system:masters** group allows superuser access to perform any action on any resource. For more information, see Default Roles and Role Bindings.

You're the user or role that received the error

If you received the error, complete the following steps:

1. To update or generate the **kubeconfig** file after **aws-auth** ConfigMap is updated, run either of the following commands.

As the IAM user, run the following command:

```
$ aws eks update-kubeconfig --name eks-cluster-name --region aws-region
```

Note: Replace **eks-cluster-name** with your cluster name. Replace **aws-region** with your AWS Region.

2. As the IAM role, run the following command:

Note: Replace eks-cluster-name with your cluster name. Replace aws-region with your AWS Region.

3. To confirm that the **kubeconfig** file is updated, run the following command:

```
$ kubectl config view --minify
```

4. To confirm that your IAM user or role is authenticated, run the following command:

```
$ kubectl get svc
```

You should see output similar to the following:

```
NAME TYPE CLUSTER-IP EXTERNAL-IP PORT(S) AGE kubernetes ClusterIP 10.100.0.1 <none> 443/TCP 77d
```

Note: If you continue to receive errors, then see Using RBAC Authorization for troubleshooting guidelines.

Related Information

Amazon EKS Troubleshooting

Managing Users or IAM Roles for your Cluster

Why can't I connect to my Amazon EKS cluster?

this article help you?
Yes
No
Anything we could improve?
Let us know
ed more help?
Contact AWS Support

Sign In to the Console	Sign	In t	o the	Cons	ole
------------------------	------	------	-------	------	-----

What Is Cloud Computing?

Resources for AWS

Developers on AWS Help

SDKs & Tools

Python on AWS

Java on AWS

PHP on AWS

Javascript on AWS

Learn About AWS

Training and Certification

AWS Solutions Portfolio

.NET on AWS

Architecture Center

Product and Technical FAQs

Analyst Reports

Getting Started

AWS Partner Network

Developer Center Contact Us

AWS Careers

File a Support Ticket

Knowledge Center

AWS Support Overview

Legal

AWS Cloud Security

What Is a Container?

What Is a Data Lake?

What's New

What Is AWS?

What Is DevOps?

Blogs

Press Releases

Create an AWS Account











Amazon is an Equal Opportunity Employer: Minority / Women / Disability / Veteran / Gender Identity / Sexual Orientation / Age.

https://aws.amazon.com/premiumsupport/knowledge-center/eks-api-server-unauthorized-error/

```
Language
عربي
Bahasa Indonesia
Deutsch
English |
Español |
Français |
Italiano |
Português |
Tiếng Việt |
Türkçe |
Русский |
ไทย |
日本語 |
한국어 [
中文 (简体) |
中文 (繁體)
Privacy
Site Terms
© 2020, Amazon Web Services, Inc. or its affiliates. All rights reserved.
```