

HyperRAW 2026

User Guide

BRAW conversion for Windows x64

Version 2026.10.1
Publisher: Winrich-Louis Tränkner
louis-0hrs.github.io/HyperRAW

Quick start

From BRAW clip to finished output in eight steps.


1	**Start and choose licensing** Activate your key, or select **Try for free**.
2	**Add BRAW media** Drag files or folders onto the window, or select **Add files**.
3	**Wait for probing** A clip is ready when its state changes to **Ready**.
4	**Choose the output** Select a codec. Automatic encoder and decoder settings are recommended.
5	**Set size and depth** Choose Scale, Max. width, and the available bit depth.
6	**Set immersive handling** For stereo media, select separate eyes, dual-track MOV, one eye, or side-by-side.
7	**Choose a destination** Leave Output empty to save beside each source, or browse to a shared folder.
8	**Convert** Select **Convert** and monitor both per-file and overall progress.

Recommended first conversion

Use a short clip, leave Decoder and Encoder on Auto, choose H.265 for compact 10-bit video or ProRes/CineForm for editing, and save to a new empty folder.

Completed items remain visible for review and will not be processed again unless they are retryable.

Main window at a glance



1 **File queue**
Thumbnail, dimensions, frames, state, and per-file progress.

2 **Queue actions**
Add, remove, clear, skip the current job, or cancel the run.

3 **Export settings**
One configuration is applied to every pending job.

4 **Format / encoder**
Select the output and a tested encoder or Auto.

5 **Size / depth**
Scale, long-edge limit, and codec-compatible bit depth.

6 **Decode / stereo / output**
Hardware backend, immersive layout, and destination.

7 **Convert**
Starts all Ready or retryable jobs.

8 **Overall state**
Run progress, latest status, and remaining free exports.

Choosing an output format

Use this table as a starting point. HyperRAW only offers bit depths that the selected codec supports.

Format	Depth	Best suited to
H.264	8-bit	Broad playback and web compatibility
H.265 (HEVC)	8/10-bit	Efficient high-resolution delivery
AV1 / VP9	8/10-bit	Modern distribution workflows
ProRes / CineForm	10-bit	Responsive editing intermediates
FFV1	16-bit	Lossless archival video
JPEG frames	8-bit	Compact review image sequences
PNG / TIFF / JPEG-XR	16-bit	High-quality image sequences
OpenEXR	16-bit	HDR and VFX image sequences
DPX	10-bit	Post-production image sequences
Linear-DNG	16-bit	Linear image-sequence workflows
Audio: WAV	16-bit	Audio-only extraction

Encoder and decoder

Auto is recommended. HyperRAW tests encoders on the current computer and lists detected CPU, CUDA, and OpenCL BRAW decoders. Select an explicit backend only when you need predictable hardware routing or are troubleshooting.

If a selected video codec has no usable encoder, Convert remains disabled. A hardware decode failure can often be retried with Decoder set to CPU.

Resolution, immersive media, and destination

Resolution controls

Scale proportionally reduces both dimensions to Full, Half, Quarter, or Eighth. Max. width adds a limit to the long output edge. The controls are combined without stretching or changing the aspect ratio.

Playback compatibility	For unusually large H.264 or H.265 output, HyperRAW may offer a compatible downscale. Your answer is remembered for the current run, so the question is not repeated for every clip.

Immersive / stereo choices

- **Both eyes (separate):** Creates separate left- and right-eye outputs.
- **Dual-track MOV:** Stores both views as separate tracks in one MOV container.
- **Left eye / Right eye:** Exports only the selected view.
- **Side-by-side:** Combines both views horizontally into one frame.

Output location

Leave Output empty to save beside each source file. Select Browse to use one shared output directory. Existing outputs may require confirmation before replacement.

Tip: use a new empty folder for the first test of an unfamiliar codec or immersive layout.

Queue, progress, and control

Understanding job states

State	Meaning
Probing	HyperRAW is reading clip dimensions, frames, tracks, and thumbnail.
Ready	The file can be included in the next run.
Processing	The file is currently being decoded and exported.
Done	The export completed successfully and is retained for review.
Failed	The current attempt stopped; inspect the status/log and retry.
Skipped	The current job was stopped and the queue continued.

Two progress values

The progress shown in a file row belongs to that file. The bottom bar reports the overall progress of all jobs started in the current run. They normally differ while processing a batch.

Skip versus Cancel

- **Skip** stops only the current job and continues with the next queued item.
- **Cancel** stops the complete conversion run cleanly.
- Completed items remain visible and are not processed again.

License, language, and legal information

License activation

Open Help > License, enter the Gumroad key, and select Activate license. Online access is required for activation. The verified entitlement is stored using Windows secure storage.

Free test mode

Without a license, each application start permits two successful exports. Output up to 4096 x 2304 - or 2304 x 4096 in portrait orientation - is not watermarked. Larger output receives a watermark. The remaining allowance appears in the lower-right corner.

Removing a local activation does not reset Gumroad's device-use counter. Contact support if a device activation must be reset.

Language

Use Help > Language to select English, German, or French. The preference is remembered across restarts.

About and license notices

Help > About HyperRAW 2026 shows the installed version and dependency credits. It also opens the EULA, third-party notices, and full bundled license texts. View > System information lists detected processing hardware.

Product notice

HyperRAW uses the Blackmagic RAW SDK. Blackmagic RAW is a registered trademark of Blackmagic Design Pty. Ltd. HyperRAW is not affiliated with or endorsed by Blackmagic Design.

Troubleshooting and support

Convert is disabled	Wait for encoder detection, add a Ready or retryable file, check encoder availability, and verify that the free allowance is not exhausted.
Hardware decode fails	Set Decoder to CPU and retry the affected item.
Playback warning appears	Accept the compatible size, or cancel and choose a smaller Scale or Max. width.
Output already exists	Confirm replacement, choose another folder, or rename/remove the existing output.
Unexpected image sequence frame	Keep the source and affected frame, note the frame number and all settings, and contact support before overwriting evidence.
Application fails on another PC	Install with the official setup package so Qt and Microsoft runtime files are deployed together.

What to include in a support request

Include the HyperRAW version, Windows version, GPU, codec, encoder, decoder, the exact point of failure, and the HyperRAW debug log. Never include a license key in a screenshot or public report.

Website and support

https://louis-0hrs.github.io/HyperRAW/

Command-line automation

The Windows package includes bin\hyperraw_cli.exe. It uses the same conversion runtime as the desktop application.

```
hyperraw_cli.exe --input clip.braw --output C:\output --codec ffv1 --overwrite
```

Options

`--input`	Source BRAW clip.
`--output`	Existing output directory.
`--codec`	h264, h265, av1, vp9, prores, cineform, or ffv1.
`--encoder`	Explicit FFmpeg encoder, for example libx265.
`--bit-depth <8|10|16>`	Requested output bit depth.
`--overwrite`	Accepts all conversion confirmations, including replacement.
`--version`	Prints HyperRAW 2026 2026.10.1.
`--help`	Shows the complete CLI help.

Publication information

This guide applies to HyperRAW 2026 version 2026.10.1 on Windows x64. The current application and installer are unsigned; Windows SmartScreen may show an unknown-publisher warning. Verify downloads using the published SHA-256 checksums.

Copyright (c) 2026 Winrich-Louis Tränkner. All rights reserved.