KB86687

版权所有 © 2025，Oracle。保留所有权利。Oracle 机密。

适用于

All Users OCI Compute - Version N/A to Version N/A

概要

How to add a secondary VNIC that is persistent through reboots in Ubuntu

解决方案

Here you may find how to add a secondary VNIC in OCI Console, please see To create and attach a secondary VNIC

Below you may find how to configure the OS for Secondary VNIC to persist through a reboot:

1. Create a directory and download the secondary_vnic_all_configure.sh script.

```
# mkdir /opt/secondary_vnic
# cd /opt/secondary_vnic
# wget
https://docs.cloud.oracle.com/iaas/Content/Reso
urces/Assets/secondary_vnic_all_configure.sh
# chmod +x secondary_vnic_all_configure.sh
```

2. Run the script.

```
./secondary_vnic_all_configure.sh -c
/opt/secondary_vnic/
```

3. Then you can verify that the IP has been configured.

```
ip addr
```

4. Enable the cron service.

```
systemctl enable cron
```

5. Add the below entry in crontab.

```
#crontab -e
```

```
@reboot /usr/sbin/ip addr add <IP>/24
<phys_dev> label <phys_dev>:<addr_seq_num>
```

where:

<IP>: The secondary private IP address.

<phys_dev>: The interface to add the address to (for example, ens2f0).

<addr_seq_num>: The sequential number in the stack of addresses on the device (for example, 0).

For example:

```
@reboot /usr/sbin/ip addr add <IP>/24 dev
enp0s5 label enp0s5:0
```

6. Reboot the virtual machine. After reboot the IP persists

Product Versions

Product: OCI Compute - min_version: N/A - max_version: N/A

Internal Only

3-36646697901

文章反馈

☆☆☆☆☆ 对此文章评级

© 2026 Oracle | 使用条款 | 隐私