


Traffic Redirection & Capture Methods:

- Installation of Cisco WSA requires planning of how traffic will be redirected to WSA.
- Cisco Web Security Appliance WSA is not deployed in the network in inline in Network.
- It becomes the most challenging step of integration of WSA in web security deployment.
- To lie in between user and requested web servers for scanning the requests and traffic.
- There are two Main possible solutions to redirect the web traffic to Cisco Ironport WSA.
- One is Explicit Proxy Deployment and second method is Transparent Proxy Deployment.

Explicit Mode:

- In Cisco WSA in Explicit Forward Mode the client does have a Proxy configuration etc.
- Configure every client workstation in the network to direct their web requests to Proxy.
- After a client is configured for explicit proxy, all user requests are sent to the appliance.
- Appliance then determines whether to allow or deny request based on web access policy.
- There is no configuration needed on network infrastructure such as routers or switches.
- Authentication is easy & there are three different methods for providing proxy information.
- Automatic Proxy script enter proxy IP address & Automatic detect settings using WPAD.
- This option is combined solution with firewall which blocks traffic not generating from WSA.
- Web request in Explicit proxy deployed scenario will contain destination address of Proxy.




Go to **Security Services** tab, and Click **Proxy Settings**, Click **Edit Settings**, Select Transparent or Forward Proxy Mode

Edit Web Proxy Settings

Web Proxy Settings	
☒ Enable Proxy	
Basic Settings	
HTTP Ports to Proxy: 80, 3128	
Caching: ☒ Enable	
Proxy Mode:	
☐ Transparent	
☒ Forward	
When in Transparent mode, the proxy can accept both transparent and explicit forward connections. Transparent connections require a transparent redirection device (see Network > Transparent Redirection). When in Forward mode, only explicit forward connections are supported.	
IP Spoofing: ☐ Enable IP Spoofing	
When enabling IP spoofing in forward mode, you should ensure that you have appropriate network de	

Cisco WSA Lab Time:



R Configuration

```
R(config)#hostname R
R(config)#interface FastEthernet0/0
R(config-if)#ip address 192.168.1.1 255.255.255.0
R(config-if)#no shut
R(config-if)#interface FastEthernet1/0
R(config-if)#ip address 192.168.2.1 255.255.255.0
R(config-if)#no shut
R(config)#ip route 0.0.0.0 0.0.0.0 192.168.2.2
R(config)#ip name-server 8.8.8.8
R(config)#ip domain-lookup
```

EDG Router Configuration

```
EDG(config)#hostname EDG
EDG(config)#interface FastEthernet0/0
EDG(config-if)#ip address 192.168.2.2 255.255.255.0
EDG(config-if)#no shutdown
EDG(config)#interface FastEthernet0/1
EDG(config-if)#ip address dhcp
EDG(config-if)#no shutdown

EDG(config)#ip route 192.168.1.0 255.255.255.0 192.168.2.1
EDG(config)#ip name-server 8.8.8.8
EDG(config)#ip domain-lookup

EDG(config)#access-list 100 permit ip any any
EDG(config)#ip nat inside source list 100 interface FastEthernet0/1 overload
EDG(config)#interface FastEthernet0/1
EDG(config-if)#ip nat outside
EDG(config)#interface FastEthernet0/0
EDG(config-if)#ip nat inside
```

LAN PC IP and Proxy Configuration

