

# SEEKER DUAL DSR

DUAL-ANTENNA TRAFFIC RADAR SYSTEM

## Operator's Manual



This manual covers operation of the **seeker\_dual** radar system for FiveM: the display unit, the hand remote, the plate reader, and the settings available to the operator. Sections marked *server owner* describe values that are set in the resource configuration and cannot be changed from inside the game.

**Resource:** seeker\_dual • **Version:** 1.0.0 • **Author:** lwkjacob • **Requires:** ox\_lib

# TABLE OF CONTENTS

---

|                                             |           |
|---------------------------------------------|-----------|
| <b>1. INTRODUCTION</b>                      | <b>3</b>  |
| 1.1 How the radar system works . . . . .    | 3         |
| 1.2 Target zones . . . . .                  | 3         |
| <b>2. CONTROLS AND COMMANDS</b>             | <b>3</b>  |
| 2.1 Default key binds . . . . .             | 3         |
| 2.2 Commands . . . . .                      | 4         |
| 2.3 Starting the system . . . . .           | 4         |
| <b>3. DISPLAY OPERATION</b>                 | <b>5</b>  |
| 3.1 Radar display panel . . . . .           | 5         |
| 3.2 Functions of the display unit . . . . . | 6         |
| 3.3 Icon definitions . . . . .              | 6         |
| 3.4 Arrow direction definitions . . . . .   | 6         |
| 3.5 Patrol window legends . . . . .         | 7         |
| <b>4. REMOTE CONTROL</b>                    | <b>8</b>  |
| 4.1 Remote button functions . . . . .       | 9         |
| 4.2 MOV STA operating modes . . . . .       | 10        |
| <b>5. SELF-TEST SEQUENCE</b>                | <b>11</b> |
| <b>6. DOPPLER AUDIO</b>                     | <b>11</b> |
| 6.1 Doppler modes . . . . .                 | 11        |
| <b>7. PLATE READER AND ALPR</b>             | <b>12</b> |
| 7.1 Manual plate locks . . . . .            | 12        |
| 7.2 Continuous ALPR . . . . .               | 12        |
| <b>8. OPERATOR MENU</b>                     | <b>12</b> |
| <b>9. MOVING AND SCALING THE INTERFACE</b>  | <b>13</b> |
| <b>10. CONFIGURATION (server owner)</b>     | <b>13</b> |
| <b>11. TROUBLESHOOTING</b>                  | <b>14</b> |
| <b>12. INTEGRATION AND CREDITS</b>          | <b>14</b> |
| 12.1 Exports . . . . .                      | 14        |
| 12.2 Credits . . . . .                      | 15        |

# 1. INTRODUCTION

The Seeker Dual DSR is a police traffic radar modelled on the real **STALKER DUAL DSR**, a dual-antenna Doppler radar used by law enforcement. It reproduces the hardware workflow of the real unit rather than simplifying it: a display head with three speed windows, a separate hand remote carrying every operating control, front and rear antennas that transmit one at a time, audible Doppler, a spoken lock enunciator, and an integrated plate reader.

The system only operates from inside an authorised patrol vehicle. Everything the operator does — power, transmit, lane mode, locking, sensitivity, volume — is done from the remote or from the operator menu, and every setting is remembered between sessions.

## 1.1 How the radar system works

While the unit is powered and an antenna is transmitting, the radar casts a spread of rays out of the selected antenna. Every vehicle a ray strikes is recorded together with four values: its speed, its distance from the patrol car, how far it sits off the beam centreline, and its **range rate** — whether the gap between it and the patrol car is opening or closing.

Those returns are then ranked and the winner is placed in the TARGET window. If a second vehicle in the beam is travelling faster than the one in TARGET, that vehicle is placed in the FAST window, so a small fast car hidden behind a large slow one is still reported. The direction arrows beside each window are driven by range rate, not by which antenna produced the reading — the antenna is already shown by the FRONT and REAR indicators.

**Only one antenna transmits at a time.** The real DUAL DSR has no “both” position, and neither does this unit; the ANT button swaps which antenna is live.

## 1.2 Target zones

A *target zone* is one antenna combined with one lane mode. There are four in total:

| Zone           | Description                                                       |
|----------------|-------------------------------------------------------------------|
| Front Same     | Traffic ahead of the patrol car travelling in the same direction. |
| Front Opposite | Traffic ahead of the patrol car travelling towards you.           |
| Rear Same      | Traffic behind the patrol car travelling in the same direction.   |
| Rear Opposite  | Traffic behind the patrol car travelling towards you.             |

Because only one antenna transmits at a time, at most **two zones** can be watched simultaneously — that is what the **Both** position of the SAME/OPP button does for the live antenna. Switching antennas with ANT moves the pair of zones to the other end of the car.

# 2. CONTROLS AND COMMANDS

## 2.1 Default key binds

Key binds can be changed in **Pause menu** → **Settings** → **Key Bindings** → **FiveM**.

| Action                  | Key |
|-------------------------|-----|
| Open / close the remote | F5  |
| Close the remote        | ESC |

| Action                   | Key                                                        |
|--------------------------|------------------------------------------------------------|
| Lock front antenna speed | NUMPAD 8                                                   |
| Lock rear antenna speed  | NUMPAD 2                                                   |
| Lock front plate         | NUMPAD 7                                                   |
| Lock rear plate          | NUMPAD 1                                                   |
| Power toggle             | unbound by default (server owner sets Config.keybindPower) |

## 2.2 Commands

| Command             | Description                                                          |
|---------------------|----------------------------------------------------------------------|
| /seeker_settings    | Open the operator menu.                                              |
| /seeker_power       | Toggle radar power. Works with the remote closed.                    |
| /toggledoppler      | Cycle Doppler audio: On → On (Stationary Only) → Off.                |
| /togglepr           | Show or hide the plate reader. The ALPR only runs while it is shown. |
| /seeker_move        | Move and scale the radar display.                                    |
| /prmove             | Move and scale the plate reader.                                     |
| /alprlog            | Print the last 20 flagged ALPR hits from this session.               |
| /seeker_radar_debug | Draw the ray geometry in the world (diagnostic).                     |

## 2.3 Starting the system


The unit does not come on with the vehicle and must be powered up by hand.

|   |                                                                                                                                                     |
|---|-----------------------------------------------------------------------------------------------------------------------------------------------------|
| 1 | Get into an authorised patrol vehicle. By default only the emergency vehicle class is accepted; outside one, the radar will not display or respond. |
| 2 | Press <b>F5</b> to open the remote.                                                                                                                 |
| 3 | Click the round <b>PWR</b> pad on the right-hand end of the radar face. The unit runs its self-test, then comes up ready.                           |
| 4 | Press <b>ANT</b> to choose the front or rear antenna. This also brings the antenna into transmit, so the XMT indicator lights.                      |
| 5 | Press <b>SAME/OPP</b> until the lane mode you want is shown. If the mode is left on OFF the antenna will not report anything.                       |
| 6 | Targets now appear in the TARGET window. Press <b>PWR</b> again to shut down; all locks clear on power-off.                                         |

**Note:** the remote has no power button. Power is on the radar face, on /seeker\_power, and on the optional power key bind. With the remote closed the mouse cursor is released, so the radar face cannot be clicked — use the command or the key bind instead.

## 3. DISPLAY OPERATION

### 3.1 Radar display panel



The display unit and its callouts.

| # | Item                    | Description                                        |
|---|-------------------------|----------------------------------------------------|
| 1 | TARGET window (amber)   | Speed of the primary tracked vehicle.              |
| 2 | TARGET direction arrows | Direction of travel of the vehicle in TARGET.      |
| 3 | FAST indicator          | Lit whenever the FAST window is enabled.           |
| 4 | FAST window (red)       | Speed of a faster second vehicle in the beam.      |
| 5 | FAST direction arrows   | Direction of travel of the vehicle in FAST.        |
| 6 | PATROL window (green)   | Your own speed, and the operating-mode legends.    |
| 7 | PWR pad                 | Power on / off. Click it while the remote is open. |
| 8 | Status indicators       | XMT, FRONT, REAR, FORK, SAME, LOCK.                |

## 3.2 Functions of the display unit

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|-------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>PWR PAD</b>          | The power pad is a toggle. The unit does not come on with the patrol vehicle and must be switched on by hand. Powering on runs the self-test and restores the operating defaults; powering off clears every speed lock and plate lock.                                                                                                                                                                                                                |
| <b>TARGET WINDOW</b>    | The amber window on the left shows the speed of the primary tracked vehicle. Which vehicle wins is decided by the ranking method chosen by the server owner — strongest echo by default. The arrows immediately to its right show which way that vehicle is travelling. This window also carries the brief confirmations flashed by SAME/OPP, ANT, SEN, VOL, FAST LOCK and BLANK.                                                                     |
| <b>FAST WINDOW</b>      | The red window in the middle shows the fastest vehicle in the beam that is travelling faster than the vehicle in TARGET — the small fast car behind the large slow one. It is only active while FAST LOCK is on, and it is blank whenever no such vehicle is present. When a speed lock is applied, this window freezes on the vehicle it was holding; if only one vehicle was in the beam it mirrors TARGET so the window is never blank under lock. |
| <b>PATROL WINDOW</b>    | The green window on the right shows the patrol vehicle's own speed. It stays blank below the PS threshold, and can be blanked entirely while a lock is held using PS BLANK. It also carries the MOV STA operating-mode legends and the PS threshold confirmation.                                                                                                                                                                                     |
| <b>VOICE ENUNCIATOR</b> | Every successful speed lock is announced with the antenna followed by the direction of travel: FRONT/CLOSING, FRONT/AWAY, REAR/CLOSING, REAR/AWAY. If the target is pacing you, the direction word is omitted, because closing speed is inside the deadband and no direction can be resolved.                                                                                                                                                         |

## 3.3 Icon definitions

|              |                                                                                                                           |
|--------------|---------------------------------------------------------------------------------------------------------------------------|
| <b>XMT</b>   | The selected antenna is transmitting. When it is off, nothing is detected.                                                |
| <b>FRONT</b> | The front antenna is the live antenna.                                                                                    |
| <b>REAR</b>  | The rear antenna is the live antenna.                                                                                     |
| <b>SAME</b>  | The live antenna is watching the same-lane target zone. It is also lit in Both mode.                                      |
| <b>FAST</b>  | The FAST window is enabled. Turn it on and off with FAST LOCK.                                                            |
| <b>LOCK</b>  | A speed lock is being held on an antenna. Release it with LOCK/REL, with the antenna key bind, or from the operator menu. |
| <b>FORK</b>  | Printed on the panel of the real unit. It is not used in this version and never lights.                                   |

## 3.4 Arrow direction definitions

There are two pairs of arrows: one beside TARGET, one beside FAST. **Each pair reports the vehicle in its own window**, and goes dark whenever that window is blank. The arrows describe how the vehicle is moving relative to you along the beam — not which antenna saw it, and not which way the car is pointing.

| Arrow   | Meaning                                                           | Typical situation                                                                           |
|---------|-------------------------------------------------------------------|---------------------------------------------------------------------------------------------|
| Down    | <b>Closing</b> — the gap between you and the target is shrinking. | An oncoming car in opposite mode, or a slower car ahead that you are catching in same mode. |
| Up      | <b>Away</b> — the gap is growing.                                 | A car pulling away ahead of you, or a car you have already passed.                          |
| Neither | The target is pacing you, so no direction can be resolved.        | Closing speed is inside the deadband set by the server owner (1.5 mph by default).          |

When a speed lock is applied, the FAST pair freezes with the FAST reading, while the TARGET pair keeps tracking live.


### 3.5 Patrol window legends

Besides your own speed, the patrol window carries the operating-mode legends:

| Legend     | Meaning                                                                                                                                                             |
|------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| [ ]        | Moving mode, with no patrol speed to show yet — you are stopped, below the PS threshold, or blanked by PS BLANK. It gives way to the speed as soon as there is one. |
| SC         | Stationary Closing mode. Held for as long as the mode is selected.                                                                                                  |
| SA         | Stationary Away mode. Held for as long as the mode is selected.                                                                                                     |
| S_         | Bi-Directional Stationary mode. Held for as long as the mode is selected. The bar sits on the bottom segment.                                                       |
| 1 / 5 / 20 | Brief confirmation of the PS threshold after pressing PS.                                                                                                           |

## 4. REMOTE CONTROL

The remote carries every operating control except power. Open it with **F5** and close it with **F5** or **ESC**. Buttons only respond while the unit is powered.



The hand remote. Button 8 is printed on the case but is not wired in this version.



## 4.1 Remote button functions

|                        |                                                                                                                                                                                                                                                                                                                                |
|------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>LOCK / REL</b>      | Locks a speed, or releases one that is already held. The front antenna is tried first, then the rear. A successful lock plays the lock tone and the spoken enunciator, lights the LOCK indicator, and freezes the FAST window. TARGET keeps updating live while the lock is held, so you can still see what the beam is doing. |
| <b>ANT</b>             | Swaps the live antenna between front and rear — there is no both position. The window flashes Fnt or rEA and the unit beeps once for front, twice for rear. ANT also brings the antenna into transmit, so switching antennas never leaves the radar silent.                                                                    |
| <b>XMIT / HLD</b>      | Puts the selected antenna into transmit or into hold. The antenna selection is remembered while in hold, so returning to transmit comes back to the same antenna. In hold, no targets are processed at all.                                                                                                                    |
| <b>MOV STA</b>         | Steps through the four operating modes. See section 4.2.                                                                                                                                                                                                                                                                       |
| <b>SAME   OPP</b>      | Steps the lane mode of the live antenna: OFF → Same → Opposite → Both, confirmed in the TARGET window as OFF, SAn, OPP or bot. In OFF the antenna reports nothing even while transmitting.                                                                                                                                     |
| <b>FAST LOCK / REL</b> | Turns the FAST window on and off, confirmed as On or OFF. This is not a speed lock — use LOCK/REL or the antenna key binds to lock a speed.                                                                                                                                                                                    |
| <b>SEN</b>             | Steps the detection range: 100, 200, 300, 400, 500, then back to 100. The new value is shown in the TARGET window for three seconds. Lower values keep the unit on nearby traffic; higher values reach further down a long road.                                                                                               |
| <b>PS</b>              | Steps the patrol speed threshold: 1, 5, 20. The patrol window stays blank below this speed, which stops the display flickering while you creep or idle. The new value is confirmed in the patrol window.                                                                                                                       |
| <b>SELF TEST</b>       | Runs the self-test on demand. Pressing it during a run restarts the sequence. See section 5.                                                                                                                                                                                                                                   |
| <b>VOL (speaker)</b>   | Steps master volume for beeps, the enunciator and the Doppler tone: 25%, 50%, 75%, 100%. The new value is shown in the TARGET window as a percentage.                                                                                                                                                                          |
| <b>PS BLANK</b>        | When on, the patrol window is blanked for as long as a speed lock is held. Confirmed as On or OFF.                                                                                                                                                                                                                             |
| <b>LIGHT</b>           | Steps display brightness: Normal, Dim, Bright.                                                                                                                                                                                                                                                                                 |

## 4.2 MOV STA operating modes

MOV STA selects which kind of enforcement the unit is set up for. Moving mode is the only one that reads while the patrol car is rolling; the three stationary modes require the patrol car to be parked and differ in which direction of travel they will report. Pressing the button flashes the new legend in the patrol window for two seconds.

| Mode                      | Legend | Behaviour                                                                                                                      |
|---------------------------|--------|--------------------------------------------------------------------------------------------------------------------------------|
| Moving                    | [ ]    | Normal patrol operation — reads targets while you drive. The bracket sits in the patrol window until there is a speed to show. |
| Stationary Closing        | SC     | Reports only vehicles closing on you. Vehicles moving away are discarded.                                                      |
| Stationary Away           | SA     | Reports only vehicles moving away from you. Closing vehicles are discarded.                                                    |
| Bi-Directional Stationary | S_     | Reports traffic travelling in either direction.                                                                                |

The direction filter works on closing speed, so a vehicle pacing you has no resolvable direction and is ignored by SC and SA; S\_ still reports it. Filtering happens where targets are captured, so TARGET, FAST and the plate reader all see the same filtered traffic. In the three stationary modes, detection stops once the patrol car exceeds roughly 2 mph, and the legend is held in place of a patrol speed the whole time.

## 5. SELF-TEST SEQUENCE

The self-test runs automatically at power-up, on demand from the SELF TEST button or the operator menu, and on a timer if the server owner has enabled automatic testing. The whole run takes about six and a half seconds and finishes with the pass chime. The values shown are fixed — the sequence is a display and audio check, not live telemetry.

| Stage         | TARGET       | FAST | PATROL       | Meaning                                            |
|---------------|--------------|------|--------------|----------------------------------------------------|
| Lamp test     | 888          | 888  | 888          | Every segment and every indicator lit.             |
| Battery       | bAt          | 139  | —            | Supply voltage, 13.9 V.                            |
| Temperature   | 107          | °F   | —            | Internal temperature, 107 °F.                      |
| Display check | 10 / 35 / 65 | —    | 10 / 35 / 65 | Test speeds stepped through both speed windows.    |
| Result        | PAS          | S    | —            | Reads PASS across the two windows, then the chime. |

Pressing SELF TEST while a sequence is already running restarts it. The automatic timer only counts while the unit is powered, and it resets whenever power or the antenna is switched.

## 6. DOPPLER AUDIO

The Doppler tone rises and falls continuously with the speed of the vehicle being watched — there are no stepped bands. It is driven by the **difference** between the target's speed and your own, not by the number on the display, which is how the tone behaves on real Doppler hardware: how fast you are going changes what you hear.

| Situation                 | Difference  | Tone                                         |
|---------------------------|-------------|----------------------------------------------|
| Parked, target doing 75   | 75 mph      | High — the same as the displayed speed.      |
| Doing 65, target doing 75 | 10 mph      | Low.                                         |
| Target pacing you         | about 0 mph | Bottoms out at the minimum pitch and volume. |

It is a plain subtraction and only the size of the difference matters: an oncoming car doing 75 while you do 65 reads the same 10 mph difference as one ahead of you doing 75.

The tone follows the **FAST** window whenever that window holds a reading, and falls back to **TARGET** otherwise. Because FAST only fills with a vehicle faster than TARGET, this keeps the audio on the car being chased. While a speed lock is held the FAST reading is frozen, so the tone uses the frozen speed — but your own speed is still read live, so slowing down raises the pitch.

### 6.1 Doppler modes

`/toggledoppler`, or the Doppler Sound entry in the operator menu, steps three states:

| State                | Behaviour                                                                                                                                         |
|----------------------|---------------------------------------------------------------------------------------------------------------------------------------------------|
| On                   | The tone plays whenever there is a target, moving or parked.                                                                                      |
| On (Stationary Only) | The tone plays only while the patrol car is stopped and cuts out as soon as you roll. A small threshold keeps idle creep from chopping the audio. |
| Off                  | No Doppler tone. This is the default.                                                                                                             |

## 7. PLATE READER AND ALPR

The plate reader is independent of the radar: it does not need the unit powered, only the reader itself shown. Toggle it with `/togglepr`.

### 7.1 Manual plate locks

**NUMPAD 7** and **NUMPAD 1** snapshot the plate currently seen by the front and rear antenna. A locked plate is held on the reader until it is released, so a plate can be recorded before the vehicle leaves the beam.

### 7.2 Continuous ALPR

Where the server owner has enabled CAD integration, the reader also runs continuously against vehicles around the patrol car, in the manner of a real four-camera ALPR install — no manual lock is needed. **Only flagged vehicles raise an alert**; plates that come back clear are ignored silently.

| Alert                | Condition                               |
|----------------------|-----------------------------------------|
| Stolen Vehicle       | The vehicle is recorded as stolen.      |
| Impounded Vehicle    | The vehicle is recorded as impounded.   |
| Expired Registration | Registration is invalid or not active.  |
| No Insurance         | Insurance is missing or marked invalid. |

Each alert raises two notifications — plate, vehicle and direction, then owner, statuses and flags — along with an audible cue. `/alprlog` prints the last 20 flagged hits from the current session.

## 8. OPERATOR MENU

`/seeker_settings` opens the operator menu, which reaches every setting on the remote plus a few that are not on it. Each entry shows its current value.

| Entry                         | Values / effect                                                 |
|-------------------------------|-----------------------------------------------------------------|
| Power                         | On, Off.                                                        |
| Display                       | Show or hide the radar display.                                 |
| Fast Lock                     | On, Off. Same as the FAST LOCK button.                          |
| Speed Unit                    | MPH or KM/H.                                                    |
| XMIT                          | Transmit or hold, showing which antenna is selected.            |
| Front Antenna - Mode          | Off, Same, Opposite, Both. Sets the front antenna directly.     |
| Rear Antenna - Mode           | Off, Same, Opposite, Both. Sets the rear antenna directly.      |
| Unlock Front / Unlock Rear    | Release a speed lock on one antenna without touching the other. |
| Switch Antenna (ANT)          | Same as the ANT button.                                         |
| Moving / Stationary (MOV STA) | Steps the four operating modes.                                 |
| Radar Range (SEN)             | Type an exact range rather than stepping in hundreds.           |

| Entry                       | Values / effect                                         |
|-----------------------------|---------------------------------------------------------|
| Patrol Speed Threshold (PS) | 1, 5, 20.                                               |
| Self Test                   | Runs the self-test.                                     |
| Beep Volume                 | Type an exact percentage from 0 to 100.                 |
| Doppler Sound               | On, On (Stationary Only), Off.                          |
| Blank Patrol When Locked    | On, Off. Same as PS BLANK.                              |
| Display Brightness (LIGHT)  | Dim, Normal, Bright.                                    |
| Adjust Display Position     | Enter move and scale mode for the radar display.        |
| Reset Display Position      | Return the radar display to its default place and size. |
| Reset Remote Position       | Re-centre the remote at its default size.               |

## 9. MOVING AND SCALING THE INTERFACE

The radar display, the plate reader and the remote can each be placed and sized to taste. Layout is saved automatically and comes back next session.

### Radar display and plate reader

|               |                           |
|---------------|---------------------------|
| Drag          | Move the panel.           |
| Scroll wheel  | Scale it.                 |
| Corner handle | Resize the radar display. |
| ESC           | Finish and save.          |

**/seeker\_move** and **/prmove** enter the same mode without opening the menu.

### The remote

**Double-click the body of the remote** — anywhere that is not a button — to start moving it. A dashed outline appears and the buttons go inert, so a drag cannot fire a radar action by accident. Drag to move, scroll to scale between half and double size, then **double-click again** or press **ESC** to finish and save. Because buttons are excluded from the double-click that starts adjust mode, ordinary button presses are unaffected.

## 10. CONFIGURATION (server owner)

The following are set in the resource configuration and cannot be changed from inside the game. They are listed here because they change how the unit behaves for the operator.

| Setting                 | Default           | Effect                                                 |
|-------------------------|-------------------|--------------------------------------------------------|
| Speed unit              | mph               | Unit used for all display and calculation.             |
| Allowed vehicle classes | 18<br>(emergency) | Which vehicles the radar will run in.                  |
| Remote key              | F5                | Opens and closes the remote.                           |
| Power key               | unbound           | Optional key for power, useful with the remote closed. |

| Setting                     | Default     | Effect                                                                            |
|-----------------------------|-------------|-----------------------------------------------------------------------------------|
| Target ranking              | echo        | How TARGET picks a winner: echo, hybrid, boresight or strongest.                  |
| SEN range bounds            | 100 to 500  | The values the SEN button steps through.                                          |
| Same / opposite sensitivity | 0.6         | How far each lane mode reaches.                                                   |
| Closing deadband            | 1.5 mph     | Below this closing speed no direction arrow lights and SC / SA ignore the target. |
| FAST must be faster         | on          | FAST only fills with a vehicle faster than TARGET.                                |
| FAST distance window        | 70 m        | How far beyond TARGET a FAST vehicle may be.                                      |
| Doppler stationary limit    | 2.0 mph     | Speed counted as stopped in stationary-only Doppler.                              |
| Automatic self-test         | off / 600 s | Re-runs the self-test on a timer while powered.                                   |
| CAD ALPR                    | off         | Enables continuous plate lookups and the alert flags.                             |

## 11. TROUBLESHOOTING

| Symptom                                            | What to check                                                                                                                                                                      |
|----------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| The radar or remote will not open                  | You must be in an allowed vehicle class, and ox_lib must be running and started before this resource.                                                                              |
| TARGET stays blank                                 | XMT must be lit — in hold, nothing is processed. Check that the lane mode is not OFF, and that the live antenna faces the traffic you want (front reads ahead, rear reads behind). |
| Nothing reads while driving                        | MOV STA is in one of the three stationary modes. They stop reading once the patrol car moves. Step back to Moving.                                                                 |
| A car is in the beam but never reports             | In SC or SA it is travelling the wrong way, or it is pacing you and sits inside the closing deadband. Bi-Directional Stationary or Moving will show it.                            |
| No Doppler audio                                   | Doppler is off by default; cycle it with /toggledoppler. If it plays parked but stops when you drive, it is in On (Stationary Only).                                               |
| Power does nothing with the remote closed          | Expected — the cursor is released, so the radar face cannot be clicked. Use /seeker_power or the power key bind.                                                                   |
| The display position keeps resetting               | Leave adjust mode with ESC so the layout is saved.                                                                                                                                 |
| The mouse cursor is stuck after closing the remote | Restart the resource, and check that no other resource is holding NUI focus.                                                                                                       |

## 12. INTEGRATION AND CREDITS

### 12.1 Exports

Other resources can read the radar's state:

| Client                                                    |                                        |
|-----------------------------------------------------------|----------------------------------------|
| <code>exports.seeker_dual:GetRadarState()</code>          | Full state table.                      |
| <code>exports.seeker_dual:IsRadarActive()</code>          | Powered and transmitting.              |
| <code>exports.seeker_dual:IsRadarDisplayed()</code>       | The display is visible.                |
| <code>exports.seeker_dual:CanControlRadar()</code>        | In a valid patrol vehicle.             |
| Server                                                    |                                        |
| <code>exports.seeker_dual:GetPlayerRadarState(src)</code> | Power and transmit flags for a player. |
| <code>exports.seeker_dual:IsPlayerRadarActive(src)</code> | Whether their radar is active.         |

## 12.2 Credits

**WolfKnight98 (Dan)** Creator of Wraith ARS 2X, which laid much of the technical foundation for FiveM radar resources.

**Opus49** Developed an LSPDFR version of this concept and provided significant inspiration and features.

Released under the MIT License. If you redistribute a modified version, keep the credits above. Support:  
<https://discord.gg/XHrPvWVHRW>