ROBOLACYTECH

Industrial Conveyor Belt System

Modular physics-based conveyor belts for Unity 6+ · Namespace: `RoboLacyTech.Conveyors`

INCLUDED PREFABS

Straight Belts

Conveyor belt x1 LinearConveyor	**Conveyor belt x2** LinearConveyor	**Conveyor belt x3** LinearConveyor
Conveyor belt x4 LinearConveyor	**Small conveyor belt x1** LinearConveyor	**Small conveyor belt x2** LinearConveyor
Small conveyor belt x3 LinearConveyor	**Small conveyor belt x4** LinearConveyor	

Roller Conveyors

Roller conveyor x1 LinearConveyor	**Roller conveyor x2** LinearConveyor	**Roller conveyor x3** LinearConveyor
Roller conveyor x4 LinearConveyor		

Curved Sections

Curved conveyor belt CurvedConveyor	**Curved roller conveyor** CurvedConveyor	**Small curved conveyor belt** CurvedConveyor

SCRIPTING API

LinearConveyor MonoBehaviour — straight belt segments	
`SetSpeed(float)`	Set belt speed in m/s. Negative value automatically switches to Backward direction.
`SetDirection(dir)`	Set direction explicitly: `ConveyorDirection.Forward` or `.Backward`.
`Reverse()`	Flip the current direction. Fires `onDirectionChanged`.
`Play()`	Start the belt. Fires `onStarted`.
`Stop()`	Stop the belt (decelerates if acceleration is on). Fires `onStopped`.
`Toggle()`	Toggle between running and stopped.
`IsRunning`	Read-only. True if the motor is in running state.
`Direction`	Read-only. Current `ConveyorDirection`.
`CurrentSpeed`	Read-only. Actual speed this frame (negative when going Backward).
`Motor`	Reference to the inner `ConveyorMotor` for advanced control.

CurvedConveyor MonoBehaviour — curved belt segments	
`SetSpeed(float)`	Set belt speed in m/s. Negative value switches to Backward direction.
`SetDirection(dir)`	Set direction explicitly.
`Reverse()`	Flip the current direction. Fires `onDirectionChanged`.
`Play()`	Start the belt. Fires `onStarted`.
`Stop()`	Stop the belt. Fires `onStopped`.
`Toggle()`	Toggle between running and stopped.
`IsRunning`	Read-only. True if the motor is in running state.
`Direction`	Read-only. Current `ConveyorDirection`.
`CurrentSpeed`	Read-only. Actual speed this frame.
`Motor`	Reference to the inner `ConveyorMotor`.

ConveyorMotor Serializable — accessed via conveyor.Motor	
`BaseSpeed`	Speed magnitude in m/s (always ≥ 0). Get/set.
`Direction`	`ConveyorDirection` — Forward or Backward. Get/set.
`CurrentSpeed`	Actual speed this frame including ramp-up/down.
`IsRunning`	Whether the motor is active.
`IsReversed`	Shortcut for `Direction == Backward`.
`Play() / Stop()`	Start or stop the motor.
`Toggle()`	Toggle running state.
`Reverse()`	Flip direction enum.
`Reset()`	Zero current speed and re-initialize.

Events — both conveyor types expose three assignable UnityEvents in the Inspector: `onStarted`, `onStopped`, `onDirectionChanged`.