



Red Hat AMQ Broker 7.14

Managing AMQ Broker

For Use with AMQ Broker 7.14

Red Hat AMQ Broker 7.14 Managing AMQ Broker

For Use with AMQ Broker 7.14

Legal Notice

Copyright © Red Hat.

Except as otherwise noted below, the text of and illustrations in this documentation are licensed by Red Hat under the Creative Commons Attribution–Share Alike 3.0 Unported license . If you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, the Red Hat logo, JBoss, Hibernate, and RHCE are trademarks or registered trademarks of Red Hat, LLC. or its subsidiaries in the United States and other countries.

Linux[®] is the registered trademark of Linus Torvalds in the United States and other countries.

XFS is a trademark or registered trademark of Hewlett Packard Enterprise Development LP or its subsidiaries in the United States and other countries.

The OpenStack[®] Word Mark and OpenStack logo are trademarks or registered trademarks of the Linux Foundation, used under license.

All other trademarks are the property of their respective owners.

Abstract

This guide describes how to monitor, manage, and upgrade AMQ Broker.

Table of Contents

MAKING OPEN SOURCE MORE INCLUSIVE	5
CHAPTER 1. OVERVIEW	6
1.1. SUPPORTED CONFIGURATIONS	6
1.2. DOCUMENT CONVENTIONS	6
1.2.1. The sudo command	6
1.2.2. About the use of file paths in this document	6
1.2.3. Replaceable values	6
CHAPTER 2. UPGRADING YOUR BROKER	8
2.1. UPGRADING OLDER 7.X VERSIONS	8
2.1.1. Upgrading a broker instance from 7.0.x to 7.0.y	8
2.1.1.1. Upgrading from 7.0.x to 7.0.y on Linux	8
2.1.1.2. Upgrading from 7.0.x to 7.0.y on Windows	9
2.1.2. Upgrading a broker instance from 7.0.x to 7.1.0	11
2.1.2.1. Upgrading from 7.0.x to 7.1.0 on Linux	11
2.1.2.2. Upgrading from 7.0.x to 7.1.0 on Windows	12
2.1.3. Upgrading a broker instance from 7.1.x to 7.2.0	14
2.1.3.1. Upgrading from 7.1.x to 7.2.0 on Linux	14
2.1.3.2. Upgrading from 7.1.x to 7.2.0 on Windows	16
2.1.4. Upgrading a broker instance from 7.2.x to 7.3.0	17
2.1.4.1. Resolve exception due to deprecated dispatch console	17
2.1.4.2. Upgrading from 7.2.x to 7.3.0 on Linux	18
2.1.4.3. Upgrading from 7.2.x to 7.3.0 on Windows	19
2.1.5. Upgrading a broker instance from 7.3.0 to 7.4.0	21
2.1.5.1. Upgrading from 7.3.0 to 7.4.0 on Linux	21
2.1.5.2. Upgrading from 7.3.0 to 7.4.0 on Windows	22
2.2. UPGRADING A BROKER INSTANCE FROM 7.4.0 TO 7.4.X	24
2.2.1. Upgrading from 7.4.0 to 7.4.x on Linux	24
2.2.2. Upgrading from 7.4.0 to 7.4.x on Windows	26
2.3. UPGRADING A BROKER INSTANCE FROM 7.4.X TO 7.5.0	27
2.3.1. Upgrading from 7.4.x to 7.5.0 on Linux	27
2.3.2. Upgrading from 7.4.x to 7.5.0 on Windows	29
2.4. UPGRADING A BROKER INSTANCE FROM 7.5.0 TO 7.6.0	30
2.4.1. Upgrading from 7.5.0 to 7.6.0 on Linux	30
2.4.2. Upgrading from 7.5.0 to 7.6.0 on Windows	32
2.5. UPGRADING A BROKER INSTANCE FROM 7.6.0 TO 7.7.0	34
2.5.1. Upgrading from 7.6.0 to 7.7.0 on Linux	34
2.5.2. Upgrading from 7.6.0 to 7.7.0 on Windows	36
2.6. UPGRADING A BROKER INSTANCE FROM 7.7.0 TO 7.8.0	38
2.6.1. Upgrading from 7.7.0 to 7.8.0 on Linux	38
2.6.2. Upgrading from 7.7.0 to 7.8.0 on Windows	40
2.7. UPGRADING A BROKER INSTANCE FROM 7.8.X TO 7.9.X	41
2.7.1. Upgrading from 7.8.x to 7.9.x on Linux	42
2.7.2. Upgrading from 7.8.x to 7.9.x on Windows	43
2.8. UPGRADING A BROKER INSTANCE FROM 7.9.X TO 7.10.X	45
2.8.1. Upgrading from 7.9.x to 7.10.x on Linux	45
2.8.2. Upgrading from 7.9.x to 7.10.x on Windows	48
2.9. UPGRADING A BROKER INSTANCE FROM 7.10.X TO 7.11.X	50
2.9.1. Upgrading from 7.10.x to 7.11.x on Linux	50
2.9.2. Upgrading from 7.10.x to 7.11.x on Windows	53

2.10. UPGRADING A BROKER INSTANCE FROM 7.11.X TO 7.12.X	55
2.10.1. Upgrading from 7.11.x to 7.12.x on Linux	55
2.10.2. Upgrading from 7.11.x to 7.12.x on Windows	57
2.11. UPGRADING A BROKER INSTANCE FROM 7.12.X TO 7.13.X	59
2.11.1. Upgrading from 7.12.x to 7.13.x on Linux	59
2.11.2. Upgrading from 7.12.x to 7.13.x on Windows	61
2.12. UPGRADING A BROKER INSTANCE FROM 7.13.X TO 7.14.X	62
2.12.1. Upgrading from 7.13.x to 7.14.x on Linux	63
2.12.2. Upgrading from 7.13.x to 7.14.x on Windows	65
CHAPTER 3. USING THE COMMAND LINE INTERFACE	67
3.1. USING THE CLI IN AN ARTEMIS SHELL	67
3.2. ENABLING AUTO-COMPLETION IN A BASH OR ZSH SHELL	67
3.3. STARTING BROKER INSTANCES	68
3.3.1. Starting the broker instance	68
3.3.2. Starting a broker as a Linux service	69
3.3.3. Starting a broker as a Windows service	70
3.4. STOPPING BROKER INSTANCES	70
3.4.1. Stopping the broker instance	70
3.4.2. Stopping a broker instance gracefully	71
3.5. AUDITING MESSAGES BY INTERCEPTING PACKETS	71
3.5.1. Creating interceptors	72
3.5.2. Configuring the broker to use interceptors	74
3.5.3. Interceptors on the client side	75
3.6. CHECKING THE HEALTH OF BROKERS, QUEUES AND THE CLUSTER	75
3.7. COMMAND LINE TOOLS	79
CHAPTER 4. USING AMQ MANAGEMENT CONSOLE	82
4.1. OVERVIEW	82
4.2. CONFIGURING LOCAL AND REMOTE ACCESS TO AMQ MANAGEMENT CONSOLE	82
4.3. ACCESSING AMQ MANAGEMENT CONSOLE	84
4.4. CONFIGURING AMQ MANAGEMENT CONSOLE	85
4.4.1. Securing AMQ Management Console using Red Hat Single Sign-On	86
4.4.2. Setting up user access to AMQ Management Console	87
4.4.3. Securing network access to AMQ Management Console	88
4.4.4. Configuring AMQ Management Console to use certificate-based authentication	89
4.4.5. Configuring AMQ Management Console to handle X-forwarded headers	92
4.5. MANAGING BROKERS USING AMQ MANAGEMENT CONSOLE	93
4.5.1. Viewing details about the broker	93
4.5.2. Viewing the broker diagram	94
4.5.3. Viewing acceptors	95
4.5.4. Managing addresses and queues	96
4.5.4.1. Creating addresses	96
4.5.4.2. Sending messages to an address	97
4.5.4.3. Creating queues	99
4.5.4.4. Checking the status of a queue	101
4.5.4.5. Browsing queues	102
4.5.4.6. Sending messages to a queue	102
4.5.4.7. Resending messages to a queue	104
4.5.4.8. Moving messages to a different queue	104
4.5.4.9. Deleting messages or queues	104
CHAPTER 5. MONITORING BROKER RUNTIME METRICS	105
5.1. METRICS OVERVIEW	105

5.1.1. Broker metrics	105
5.1.2. Address metrics	106
5.1.3. Queue metrics	106
5.2. ENABLING THE PROMETHEUS METRICS PLUGIN FOR AMQ BROKER	107
5.3. CONFIGURING THE BROKER TO COLLECT JVM METRICS	108
5.4. DISABLING METRICS COLLECTION FOR SPECIFIC ADDRESSES	108
5.5. ACCESSING BROKER RUNTIME DATA USING PROMETHEUS	109
CHAPTER 6. USING THE MANAGEMENT API	111
6.1. METHODS FOR MANAGING AMQ BROKER USING THE MANAGEMENT API	111
6.2. MANAGING AMQ BROKER BY USING JMX	111
6.2.1. Configuring JMX management	112
6.2.2. Configuring JMX management access	112
6.2.3. MBeanServer configuration	114
6.2.4. How JMX is exposed with Jolokia	114
6.2.5. Subscribing to JMX management notifications	116
6.3. MANAGING AMQ BROKER USING THE JMS API	116
6.3.1. Configuring broker management using JMS messages and the Red Hat build of Apache Qpid JMS Client	116
6.3.2. Managing brokers using the JMS API and Red Hat build of Apache Qpid JMS Client	116
6.4. MANAGEMENT OPERATIONS	117
6.4.1. Broker management operations	117
6.4.2. Address management operations	118
6.4.3. Queue management operations	119
6.4.4. Remote resource management operations	120
6.5. MANAGEMENT NOTIFICATIONS	121
6.6. USING MESSAGE COUNTERS	124
6.6.1. Types of message counters	124
6.6.2. Enabling message counters	125
6.6.3. Retrieving message counters	125
CHAPTER 7. MONITORING BROKERS FOR PROBLEMS	127
7.1. CONFIGURING THE CRITICAL ANALYZER	127

MAKING OPEN SOURCE MORE INCLUSIVE

Red Hat is committed to replacing problematic language in our code, documentation, and web properties. We are beginning with these four terms: master, slave, blacklist, and whitelist. Because of the enormity of this endeavor, these changes will be implemented gradually over several upcoming releases. For more details, see [our CTO Chris Wright's message](#).

CHAPTER 1. OVERVIEW

AMQ Broker is a high-performance messaging system based on Apache Artemis. It supports fast message persistence and multiple protocols, languages, and platforms.

AMQ Broker provides multiple interfaces for managing and interacting with your broker instances, such as a management console, management APIs, and a command-line interface. In addition, you can monitor broker performance by collecting runtime metrics, configure brokers to proactively monitor for problems such as deadlock conditions, and interactively check the health of brokers and queues.

This guide provides detailed information about typical broker management tasks such as:

- Upgrading your broker instances
- Using the command-line interface and management API
- Checking the health of brokers and queues
- Collecting broker runtime metrics
- Proactively monitoring critical broker operations

1.1. SUPPORTED CONFIGURATIONS

Refer to the article "[Red Hat AMQ 7 Supported Configurations](#)" on the Red Hat Customer Portal to view the latest supported configurations for AMQ Broker.

1.2. DOCUMENT CONVENTIONS

This document uses the following conventions for the **sudo** command, file paths, and replaceable values.

1.2.1. The **sudo** command

In this document, **sudo** is used for any command that requires root privileges. You should always exercise caution when using **sudo**, as any changes can affect the entire system.

For more information about using **sudo**, see [Managing sudo access](#).

1.2.2. About the use of file paths in this document

In this document, all file paths are valid for Linux, UNIX, and similar operating systems (for example, **/home/...**). If you are using Microsoft Windows, you should use the equivalent Microsoft Windows paths (for example, **C:\Users\...**).

1.2.3. Replaceable values

This document sometimes uses replaceable values that you must replace with values specific to your environment. Replaceable values are lowercase, enclosed by angle brackets (**< >**), and are styled using italics and **monospace** font. Multiple words are separated by underscores (**_**).

For example, in the following command, replace **<install_dir>** with your own directory name.

```
$ <install_dir>/bin/artemis create mybroker
```

CHAPTER 2. UPGRADING YOUR BROKER

Red Hat releases new versions of AMQ Broker to the [Customer Portal](#). Learn how to upgrade your AMQ Broker instances to the latest version to access new features and security fixes.

In general, Red Hat releases a new version of AMQ Broker in one of three ways:

Major Release

A major upgrade or migration is required when an application is transitioned from one major release to the next, for example, from AMQ Broker 6 to AMQ Broker 7. This type of upgrade is not addressed in this guide.

Minor Release

AMQ Broker periodically provides minor releases, which are updates that include new features, bug fixes and security fixes. If you plan to upgrade from one AMQ Broker minor release to another, for example, from AMQ Broker 7.0 to AMQ Broker 7.1, code changes should not be required for applications that do not use private, unsupported, or tech preview components.

Micro Release

AMQ Broker also periodically provides micro releases that contain minor enhancements and fixes. Micro releases increment the minor release version by the last digit, for example from 7.0.1 to 7.0.2. A micro release should not require code changes, however, some releases may require configuration changes.

2.1. UPGRADING OLDER 7.X VERSIONS

Learn how to upgrade older 7.x versions of AMQ Broker.

2.1.1. Upgrading a broker instance from 7.0.x to 7.0.y

Learn how to upgrade from one 7.0 version to another for different operating systems.

2.1.1.1. Upgrading from 7.0.x to 7.0.y on Linux

Download the new archive to upgrade from one 7.0 version to another on Linux.

Prerequisites

- Before upgrading AMQ Broker, review the release notes for the target release. The release notes describe important enhancements, known issues, and changes to behavior in the target release.

For more information, see the [AMQ Broker 7.0 Release Notes](#).

Procedure

1. Download the required archive from the Red Hat Customer Portal by following the instructions provided in [Downloading the AMQ Broker archive](#).
2. Change the owner of the archive to the same user that owns the AMQ Broker installation to be upgraded.

```
sudo chown amq-broker:amq-broker jboss-amq-7.x.x.redhat-1.zip
```

3. Move the archive to the directory created during the original installation of AMQ Broker. In the following example, the directory **/opt/redhat** is used.

```
sudo mv jboss-amq-7.x.x.redhat-1.zip /opt/redhat
```

4. As the directory owner, extract the contents of the compressed archive. The archive is kept in a compressed format. In the following example, the user **amq-broker** extracts the archive by using the **unzip** command.

```
su - amq-broker
cd /opt/redhat
unzip jboss-amq-7.x.x.redhat-1.zip
```

5. Stop the broker if it is running.

```
<broker_instance_dir>/bin/artemis stop
```

6. Back up the instance directory of the broker by copying it to the home directory of the current user.

```
cp -r <broker_instance_dir> ~/
```

7. (Optional) Note the current version of the broker. After the broker stops, a line similar to the one below is displayed at the end of its log file, which can be found at **<broker_instance_dir>/log/artemis.log**.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221002: Apache ActiveMQ Artemis
Message Broker version 2.0.0.amq-700005-redhat-1 [4782d50d-47a2-11e7-a160-
9801a793ea45] stopped, uptime 28 minutes
```

8. Edit the **<broker_instance_dir>/etc/artemis.profile** configuration file to set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted.

```
ARTEMIS_HOME='/opt/redhat/jboss-amq-7.x.x-redhat-1'
```

9. Start the upgraded broker.

```
<broker_instance_dir>/bin/artemis run
```

10. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the log file **<broker_instance_dir>/log/artemis.log** and find two lines similar to the ones below. Note the new version number that appears in the log after the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live
...
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.1.0.amq-700005-redhat-1 [0.0.0.0, nodeID=4782d50d-47a2-11e7-
a160-9801a793ea45]
```

2.1.1.2. Upgrading from 7.0.x to 7.0.y on Windows

Download the new archive to upgrade from one 7.0 version to another on Windows.

Prerequisites

- Before upgrading AMQ Broker, review the release notes for the target release. The release notes describe important enhancements, known issues, and changes to behavior in the target release.

For more information, see the [AMQ Broker 7.0 Release Notes](#).

Procedure

1. Download the required archive from the Red Hat Customer Portal by following the instructions provided in [Downloading the AMQ Broker archive](#).
2. Use a file manager to move the archive to the folder you created during the last installation of AMQ Broker.
3. Extract the contents of the archive. Right-click the .zip file and select **Extract All**.
4. Stop the broker if it is running by entering the following command.

```
<broker_instance_dir>\bin\artemis-service.exe stop
```

5. Back up the broker by using a file manager.
 - a. Right-click the **<broker_instance_dir>** folder and select **Copy**.
 - b. Right-click in the same window and select **Paste**.
6. (Optional) Note the current version of the broker. After the broker stops, a line similar to the one below is displayed at the end of its log file, which can be found at **<broker_instance_dir>\log\artemis.log**.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221002: Apache ActiveMQ Artemis  
Message Broker version 2.0.0.amq-700005-redhat-1 [4782d50d-47a2-11e7-a160-  
9801a793ea45] stopped, uptime 28 minutes
```

7. Edit the **<broker_instance_dir>\etc\artemis.profile** configuration file to set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted.

```
ARTEMIS_HOME=<install_dir>
```

8. Start the upgraded broker.

```
<broker_instance_dir>\bin\artemis-service.exe start
```

9. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the log file **<broker_instance_dir>\log\artemis.log** and find two lines similar to the ones below. Note the new version number that appears in the log after the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live  
...  
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis  
Message Broker version 2.1.0.amq-700005-redhat-1 [0.0.0.0, nodeID=4782d50d-47a2-11e7-  
a160-9801a793ea45]
```

2.1.2. Upgrading a broker instance from 7.0.x to 7.1.0

Learn how to upgrade a 7.0.x broker instance to 7.1.0 for different operating systems.

AMQ Broker 7.1.0 includes configuration files and settings that were not included with previous versions. Upgrading a broker instance from 7.0.x to 7.1.0 requires adding these new files and settings to your existing 7.0.x broker instances.



IMPORTANT

Starting with AMQ Broker 7.1.0, you can access AMQ Management Console only from the local host by default. To learn about configuring remote access to the console, see [link:https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing](https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing)[Configuring local and remote access to AMQ Management Console].

2.1.2.1. Upgrading from 7.0.x to 7.1.0 on Linux

Before you can upgrade a 7.0.x broker, you need to install Red Hat AMQ Broker 7.1.0 and create a temporary broker instance. This will generate the 7.1.0 configuration files required to upgrade a 7.0.x broker.

Prerequisites

- Before upgrading AMQ Broker, review the release notes for the target release. The release notes describe important enhancements, known issues, and changes to behavior in the target release.

For more information, see the [AMQ Broker 7.1 Release Notes](#).

- Before upgrading your 7.0.x brokers, you must first install version 7.1.

Procedure

1. If it is running, stop the 7.0.x broker you want to upgrade.

```
$ <broker_instance_dir>/bin/artemis stop
```

2. Back up the instance directory of the broker by copying it to the home directory of the current user.

```
cp -r <broker_instance_dir> ~/
```

3. Open the file **artemis.profile** in the **<broker_instance_dir>/etc/** directory of the 7.0.x broker.
 - a. Update the **ARTEMIS_HOME** property so that its value refers to the installation directory for AMQ Broker 7.1.0:

```
ARTEMIS_HOME="<7.1.0_install_dir>"
```

- b. On the line below the one you updated, add the property **ARTEMIS_INSTANCE_URI** and assign it a value that refers to the 7.0.x broker instance directory:

```
ARTEMIS_INSTANCE_URI="file://<7.0.x_broker_instance_dir>"
```

- c. Update the **JAVA_ARGS** property by adding the **jolokia.policyLocation** parameter and assigning it the following value:

```
-Djolokia.policyLocation=${ARTEMIS_INSTANCE_URI}/etc/jolokia-access.xml
```

4. Create a 7.1.0 broker instance. The creation procedure generates the configuration files required to upgrade from 7.0.x to 7.1.0. In the following example, note that the instance is created in the directory **upgrade_tmp**:

```
$ <7.1.0_install_dir>/bin/artemis create --allow-anonymous --user admin --password admin upgrade_tmp
```

5. Copy configuration files from the **etc** directory of the temporary 7.1.0 instance into the **<broker_instance_dir>/etc/** directory of the 7.0.x broker.

- a. Copy the **management.xml** file:

```
$ cp <temporary_7.1.0_broker_instance_dir>/etc/management.xml <7.0_broker_instance_dir>/etc/
```

- b. Copy the **jolokia-access.xml** file:

```
$ cp <temporary_7.1.0_broker_instance_dir>/etc/jolokia-access.xml <7.0_broker_instance_dir>/etc/
```

6. Open up the **bootstrap.xml** file in the **<broker_instance_dir>/etc/** directory of the 7.0.x broker.

- a. Comment out or delete the following two lines:

```
<app url="jolokia" war="jolokia.war"/>
<app url="hawtio" war="hawtio-no-slf4j.war"/>
```

- b. Add the following to replace the two lines removed in the previous step:

```
<app url="console" war="console.war"/>
```

7. Start the broker that you upgraded:

```
$ <broker_instance_dir>/bin/artemis run
```

Additional resources

- [Creating a broker instance](#)

2.1.2.2. Upgrading from 7.0.x to 7.1.0 on Windows

Before you can upgrade a 7.0.x broker, you need to install Red Hat AMQ Broker 7.1.0 and create a temporary broker instance. This will generate the 7.1.0 configuration files required to upgrade a 7.0.x broker.

Prerequisites

- Before upgrading AMQ Broker, review the release notes for the target release. The release notes describe important enhancements, known issues, and changes to behavior in the target release.

For more information, see the [AMQ Broker 7.1 Release Notes](#).

- Before upgrading your 7.0.x brokers, you must first install version 7.1. For steps on installing 7.1 on Windows, see [Installing AMQ Broker](#).

Procedure

1. If it is running, stop the 7.0.x broker you want to upgrade:

```
> <broker_instance_dir>\bin\artemis-service.exe stop
```

2. Back up the instance directory of the broker by using a file manager.
 - a. Right-click the **<broker_instance_dir>** folder and select **Copy**.
 - b. Right-click in the same window and select **Paste**.
3. Open the file **artemis.profile** in the **<broker_instance_dir>/etc/** directory of the 7.0.x broker.
 - a. Update the **ARTEMIS_HOME** property so that its value refers to the installation directory for AMQ Broker 7.1.0:

```
ARTEMIS_HOME="<7.1.0_install_dir>"
```

- b. On the line below the one you updated, add the property **ARTEMIS_INSTANCE_URI** and assign it a value that refers to the 7.0.x broker instance directory:

```
ARTEMIS_INSTANCE_URI="file://<7.0.x_broker_instance_dir>"
```

- c. Update the **JAVA_ARGS** property by adding the **jolokia.policyLocation** parameter and assigning it the following value:

```
-Djolokia.policyLocation=${ARTEMIS_INSTANCE_URI}/etc/jolokia-access.xml
```

4. Create a 7.1.0 broker instance. The creation procedure generates the configuration files required to upgrade from 7.0.x to 7.1.0. In the following example, note that the instance is created in the directory **upgrade_tmp**:

```
> <7.1.0_install_dir>/bin/artemis create --allow-anonymous --user admin --password admin  
upgrade_tmp
```

5. Copy configuration files from the **etc** directory of the temporary 7.1.0 instance into the **<broker_instance_dir>/etc/** directory of the 7.0.x broker.
 - a. Copy the **management.xml** file:

```
> cp <temporary_7.1.0_broker_instance_dir>/etc/management.xml  
<7.0_broker_instance_dir>/etc/
```

- b. Copy the **jolokia-access.xml** file:

```
> cp <temporary_7.1.0_broker_instance_dir>/etc/jolokia-access.xml
<7.0_broker_instance_dir>/etc/
```

6. Open up the **bootstrap.xml** file in the **<broker_instance_dir>/etc/** directory of the 7.0.x broker.

- a. Comment out or delete the following two lines:

```
<app url="jolokia" war="jolokia.war"/>
<app url="hawtio" war="hawtio-no-slf4j.war"/>
```

- b. Add the following to replace the two lines removed in the previous step:

```
<app url="console" war="console.war"/>
```

7. Start the broker that you upgraded:

```
> <broker_instance_dir>\bin\artemis-service.exe start
```

Additional resources

- [Creating a broker instance](#)

2.1.3. Upgrading a broker instance from 7.1.x to 7.2.0

Learn how to upgrade a 7.1.x broker instance to 7.2.0 for different operating systems.

AMQ Broker 7.2.0 includes configuration files and settings that were not included with 7.0.x versions. If you are running 7.0.x instances, you must first upgrade those broker instances from [7.0.x to 7.1.0](#) before upgrading to 7.2.0.



IMPORTANT

Starting with AMQ Broker 7.1.0, you can access AMQ Management Console only from the local host by default. To learn about configuring remote access to the console, see [link:https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing](https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing)[Configuring local and remote access to AMQ Management Console].

2.1.3.1. Upgrading from 7.1.x to 7.2.0 on Linux

Download the new archive to upgrade from 7.1.x to 7.2.0 on Linux.

Procedure

1. Download the required archive from the Red Hat Customer Portal by following the instructions provided in [Downloading the AMQ Broker archive](#).
2. Change the owner of the archive to the same user that owns the AMQ Broker installation to be upgraded.

```
sudo chown amq-broker:amq-broker amq-7.x.x.redhat-1.zip
```

3. Move the archive to the directory created during the original installation of AMQ Broker. In the following example, the directory **/opt/redhat** is used.

```
sudo mv amq-7.x.x.redhat-1.zip /opt/redhat
```

4. As the directory owner, extract the contents of the compressed archive. In the following example, the user **amq-broker** extracts the archive by using the **unzip** command.

```
su - amq-broker
cd /opt/redhat
unzip jboss-amq-7.x.x.redhat-1.zip
```

5. Stop the broker if it is running.

```
<broker_instance_dir>/bin/artemis stop
```

6. Back up the instance directory of the broker by copying it to the home directory of the current user.

```
cp -r <broker_instance_dir> ~/
```

7. (Optional) Note the current version of the broker. After the broker stops, a line similar to the one below is displayed at the end of its log file, which can be found at **<broker_instance_dir>/log/artemis.log**.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.5.0.amq-720001-redhat-1 [0.0.0.0, nodeID=554cce00-63d9-11e8-
9808-54ee759954c4]
```

8. Edit the **<broker_instance_dir>/etc/artemis.profile** configuration file to set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted.

```
ARTEMIS_HOME='/opt/redhat/amq-7.x.x-redhat-1'
```

9. Start the upgraded broker.

```
<broker_instance_dir>/bin/artemis run
```

10. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the log file **<broker_instance_dir>/log/artemis.log** and find two lines similar to the ones below. Note the new version number that appears in the log after the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live
...
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.5.0.amq-720001-redhat-1 [0.0.0.0, nodeID=554cce00-63d9-11e8-
9808-54ee759954c4]
```



NOTE

You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker_instance_dir>/etc/artemis.profile** file, update the **ARTEMIS_INSTANCE_ETC_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **etc/** and **data/** directories within the broker instance's directory.

- [Creating a broker instance](#)

2.1.3.2. Upgrading from 7.1.x to 7.2.0 on Windows

Download the new archive to upgrade from 7.1.x to 7.2.0 on Windows.

Procedure

1. Download the required archive from the Red Hat Customer Portal by following the instructions provided in [Downloading the AMQ Broker archive](#).
2. Use a file manager to move the archive to the folder you created during the last installation of AMQ Broker.
3. Extract the contents of the archive. Right-click the .zip file and select **Extract All**.
4. Stop the broker if it is running by entering the following command.

```
<broker_instance_dir>\bin\artemis-service.exe stop
```

5. Back up the broker by using a file manager.
 - a. Right-click the **<broker_instance_dir>** folder and select **Copy**.
 - b. Right-click in the same window and select **Paste**.
6. (Optional) Note the current version of the broker. After the broker stops, a line similar to the one below is displayed at the end of its log file, which can be found at **<broker_instance_dir>\log\artemis.log**.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221002: Apache ActiveMQ Artemis
Message Broker version 2.0.0.amq-700005-redhat-1 [4782d50d-47a2-11e7-a160-
9801a793ea45] stopped, uptime 28 minutes
```

7. Edit the **<broker_instance_dir>\etc\artemis.profile.cmd** and **<broker_instance_dir>\bin\artemis-service.xml** configuration files to set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted.

```
ARTEMIS_HOME=<install_dir>
```

8. Start the upgraded broker.

```
<broker_instance_dir>\bin\artemis-service.exe start
```

9. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the log file `<broker_instance_dir>\log\artemis.log` and find two lines similar to the ones below. Note the new version number that appears in the log after the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live
...
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.5.0.amq-720001-redhat-1 [0.0.0.0, nodeID=554cce00-63d9-11e8-
9808-54ee759954c4]
```



NOTE

You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the `<broker_instance_dir>\etc\artemis.profile` file, update the **ARTEMIS_INSTANCE_ETC_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the `\etc` and `\data` directories within the broker instance's directory.

Additional resources

- [Creating a broker instance](#)

2.1.4. Upgrading a broker instance from 7.2.x to 7.3.0

Learn how to upgrade a 7.2.x broker instance to 7.3.0 for different operating systems.

2.1.4.1. Resolve exception due to deprecated dispatch console

Starting in version 7.3.0, AMQ Broker no longer includes the Hawtio dispatch console plugin **dispatch-hawtio-console.war**. Previously, the dispatch console was used to manage AMQ Interconnect. However, AMQ Interconnect now uses its own, standalone web console. This change affects the upgrade procedures in the sections that follow.

If you take no further action before upgrading your broker instance to 7.3.0, the upgrade process produces an exception that looks like the following:

```
2019-04-11 18:00:41,334 WARN [org.eclipse.jetty.webapp.WebAppContext] Failed startup of context
o.e.j.w.WebAppContext@1ef3efa8{/dispatch-hawtio-console,null,null}/{/opt/amqbroker/amq-broker-
7.3.0/web/dispatch-hawtio-console.war}: java.io.FileNotFoundException: /opt/amqbroker/amq-broker-
7.3.0/web/dispatch-hawtio-console.war.
```


You can safely ignore the preceding exception without affecting the success of your upgrade.

However, if you would prefer not to see this exception during your upgrade, you must first remove a reference to the Hawtio dispatch console plugin in the **bootstrap.xml** file of your existing broker instance. The **bootstrap.xml** file is in the `{instance_directory}/etc/` directory of your broker instance. The following example shows some of the contents of the **bootstrap.xml** file for a AMQ Broker 7.2.4 instance:

```
<broker xmlns="http://activemq.org/schema">
....
```

```
<!-- The web server is only bound to localhost by default -->
<web bind="http://localhost:8161" path="web">
  <app url="redhat-branding" war="redhat-branding.war"/>
  <app url="artemis-plugin" war="artemis-plugin.war"/>
  <app url="dispatch-hawtio-console" war="dispatch-hawtio-console.war"/>
  <app url="console" war="console.war"/>
</web>
</broker>
```

To avoid an exception when upgrading AMQ Broker to version 7.3.0, delete the line **<app url="dispatch-hawtio-console" war="dispatch-hawtio-console.war"/>**, as shown in the preceding example. Then, save the modified bootstrap file and start the upgrade process, as described in the sections that follow.



IMPORTANT

Starting with AMQ Broker 7.1.0, you can access AMQ Management Console only from the local host by default. To learn about configuring remote access to the console, see [link:https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing\[Configuring local and remote access to AMQ Management Console\]](https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing[Configuring local and remote access to AMQ Management Console]).

2.1.4.2. Upgrading from 7.2.x to 7.3.0 on Linux

Download the new archive to upgrade from 7.2.x to 7.3.0 on Linux.

Procedure

1. Download the required archive from the Red Hat Customer Portal by following the instructions provided in [Downloading the AMQ Broker archive](#).
2. Change the owner of the archive to the same user that owns the AMQ Broker installation to be upgraded.

```
sudo chown amq-broker:amq-broker amq-7.x.x.redhat-1.zip
```

3. Move the archive to the directory created during the original installation of AMQ Broker. In the following example, the directory **/opt/redhat** is used.

```
sudo mv amq-7.x.x.redhat-1.zip /opt/redhat
```

4. As the directory owner, extract the contents of the compressed archive. In the following example, the user **amq-broker** extracts the archive by using the `unzip` command.

```
su - amq-broker
cd /opt/redhat
unzip jboss-amq-7.x.x.redhat-1.zip
```

5. Stop the broker if it is running.

```
<broker_instance_dir>/bin/artemis stop
```

6. Back up the instance directory of the broker by copying it to the home directory of the current user.

```
cp -r <broker_instance_dir> ~/
```

7. (Optional) Note the current version of the broker. After the broker stops, a line similar to the one below is displayed at the end of its log file, which can be found at

<broker_instance_dir>/log/artemis.log.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.6.3.amq-720001-redhat-1 [0.0.0.0, nodeID=554cce00-63d9-11e8-
9808-54ee759954c4]
```

8. Edit the **<broker_instance_dir>/etc/artemis.profile** configuration file to set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted.

```
ARTEMIS_HOME='/opt/redhat/amq-7.x.x-redhat-1'
```

9. Start the upgraded broker.

```
<broker_instance_dir>/bin/artemis run
```

10. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the log file **<broker_instance_dir>/log/artemis.log** and find two lines similar to the ones below. Note the new version number that appears in the log after the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live
...
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.7.0.redhat-00054 [0.0.0.0, nodeID=554cce00-63d9-11e8-9808-
54ee759954c4]
```



NOTE

* You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker_instance_dir>/etc/artemis.profile** file, update the **ARTEMIS_INSTANCE_ETC_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **etc/** and **data/** directories within the broker instance's directory.

- [Creating a broker instance](#)

2.1.4.3. Upgrading from 7.2.x to 7.3.0 on Windows

Download the new archive to upgrade from 7.2.x to 7.3.0 on Windows.

Procedure

1. Download the required archive from the Red Hat Customer Portal by following the instructions provided in [Downloading the AMQ Broker archive](#).

2. Use a file manager to move the archive to the folder you created during the last installation of AMQ Broker.
3. Extract the contents of the archive. Right-click the .zip file and select **Extract All**.
4. Stop the broker if it is running by entering the following command.

```
<broker_instance_dir>\bin\artemis-service.exe stop
```

5. Back up the broker by using a file manager.
 - a. Right-click the **<broker_instance_dir>** folder and select **Copy**.
 - b. Right-click in the same window and select **Paste**.
6. (Optional) Note the current version of the broker. After the broker stops, a line similar to the one below is displayed at the end of its log file, which can be found at **<broker_instance_dir>\log\artemis.log**.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221002: Apache ActiveMQ Artemis  
Message Broker version 2.6.3.amq-720001-redhat-1 [4782d50d-47a2-11e7-a160-  
9801a793ea45] stopped, uptime 28 minutes
```

7. Edit the **<broker_instance_dir>\etc\artemis.profile.cmd** and **<broker_instance_dir>\bin\artemis-service.xml** configuration files to set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted.

```
ARTEMIS_HOME=<install_dir>
```

8. Edit the **<broker_instance_dir>\etc\artemis.profile.cmd** configuration file to set the **JAVA_ARGS** environment variable to reference the correct log manager version.

```
JAVA_ARGS=<install_dir>\lib\jboss-logmanager-2.0.3.Final-redhat-1.jar
```

9. Edit the **<broker_instance_dir>\bin\artemis-service.xml** configuration file to set the bootstrap class path start argument to reference the correct log manager version.

```
<startargument>Xbootclasspath/a:%ARTEMIS_HOME%\lib\jboss-logmanager-2.0.3.Final-  
redhat-1.jar</startargument>
```

10. Start the upgraded broker.

```
<broker_instance_dir>\bin\artemis-service.exe start
```

11. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the log file **<broker_instance_dir>\log\artemis.log** and find two lines similar to the ones below. Note the new version number that appears in the log after the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live  
...  
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis  
Message Broker version 2.7.0.redhat-00054 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-  
54ee759954c4]
```


You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the `<broker_instance_dir>\etc\artemis.profile` file, update the `ARTEMIS_INSTANCE_ETC_URI` property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the `\etc` and `\data` directories within the broker instance's directory.

Additional resources

- [Creating a broker instance](#)

2.1.5. Upgrading a broker instance from 7.3.0 to 7.4.0

Learn how to upgrade a 7.3.0 broker instance to 7.4.0 for different operating systems.



IMPORTANT

Starting with AMQ Broker 7.1.0, you can access AMQ Management Console only from the local host by default. To learn about configuring remote access to the console, see [link:https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing](https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing) [Configuring local and remote access to AMQ Management Console].

2.1.5.1. Upgrading from 7.3.0 to 7.4.0 on Linux

Download the new archive to upgrade from 7.3.0 to 7.4.0 on Linux.

Procedure

1. Download the required archive from the Red Hat Customer Portal. Follow the instructions provided in [Downloading the AMQ Broker archive](#).
2. Change the owner of the archive to the same user that owns the AMQ Broker installation to be upgraded. The following example shows a user called **amq-broker**.

```
sudo chown amq-broker:amq-broker amq-broker-7.x.x.redhat-1.zip
```

3. Move the archive to the directory created during the original installation of AMQ Broker. The following example uses `/opt/redhat`.

```
sudo mv amq-broker-7.x.x.redhat-1.zip /opt/redhat
```

4. As the directory owner, extract the contents of the compressed archive. In the following example, the user **amq-broker** extracts the archive using the **unzip** command.

```
su - amq-broker
cd /opt/redhat
unzip amq-broker-7.x.x.redhat-1.zip
```

5. If the broker is running, stop it.

```
<broker_instance_dir>/bin/artemis stop
```

6. Back up the instance directory of the broker by copying it to the home directory of the current user.

```
cp -r <broker_instance_dir> ~/
```

7. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker_instance_dir>/log/artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.7.0.redhat-00054 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```

8. Edit the **<broker_instance_dir>/etc/artemis.profile** configuration file.
 - a. Set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted.

```
ARTEMIS_HOME='/opt/redhat/amq-broker-7.x.x-redhat-1'
```

- b. Edit the **JAVA_ARGS** property. Add the bootstrap class path argument, which references a dependent file for the log manager.

```
-Xbootclasspath/a:$ARTEMIS_HOME/lib/wildfly-common-1.5.1.Final-redhat-00001.jar
```

9. Edit the **<broker_instance_dir>/etc/bootstrap.xml** configuration file. In the **<web>** configuration element, add a reference to the metrics plugin file for AMQ Broker.

```
<app url="metrics" war="metrics.war"/>
```

10. Start the upgraded broker.

```
<broker_instance_dir>/bin/artemis run
```

11. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker_instance_dir>/log/artemis.log** file. Find two lines similar to the ones below. Note the new version number that appears in the log when the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live
...
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.9.0.redhat-00001 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```

Additional resources

- [Creating a broker instance](#)

2.1.5.2. Upgrading from 7.3.0 to 7.4.0 on Windows

Download the new archive to upgrade from 7.3.0 to 7.4.0 on Windows.

Procedure

1. Download the required archive from the Red Hat Customer Portal by following the instructions provided in [Downloading the AMQ Broker archive](#).
2. Use a file manager to move the archive to the folder you created during the last installation of AMQ Broker.
3. Extract the contents of the archive. Right-click the .zip file and select **Extract All**.
4. If the broker is running, stop it.

```
<broker_instance_dir>\bin\artemis-service.exe stop
```

5. Back up the broker using a file manager.
 - a. Right-click the **<broker_instance_dir>** folder and select **Copy**.
 - b. Right-click in the same window and select **Paste**.
6. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker_instance_dir>\log\artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221002: Apache ActiveMQ Artemis
Message Broker version 2.7.0.redhat-00054 [4782d50d-47a2-11e7-a160-9801a793ea45]
stopped, uptime 28 minutes
```

7. Edit the **<broker_instance_dir>\etc\artemis.profile.cmd** and **<broker_instance_dir>\bin\artemis-service.xml** configuration files. Set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted.

```
ARTEMIS_HOME=<install_dir>
```

8. Edit the **<broker_instance_dir>\etc\artemis.profile.cmd** configuration file. Set the **JAVA_ARGS** environment variable to reference the correct log manager version and dependent file.

```
JAVA_ARGS=-Xbootclasspath/%ARTEMIS_HOME%\lib\jboss-logmanager-2.1.10.Final-
redhat-00001.jar;%ARTEMIS_HOME%\lib\wildfly-common-1.5.1.Final-redhat-00001.jar
```

9. Edit the **<broker_instance_dir>\bin\artemis-service.xml** configuration file. Set the bootstrap class path start argument to reference the correct log manager version and dependent file.

```
<startargument>-Xbootclasspath/a:%ARTEMIS_HOME%\lib\jboss-logmanager-2.1.10.Final-
redhat-00001.jar;%ARTEMIS_HOME%\lib\wildfly-common-1.5.1.Final-redhat-
00001.jar</startargument>
```

10. Edit the **<broker_instance_dir>\etc\bootstrap.xml** configuration file. In the **<web>** configuration element, add a reference to the metrics plugin file for AMQ Broker.

```
<app url="metrics" war="metrics.war"/>
```

11. Start the upgraded broker.

```
<broker_instance_dir>\bin\artemis-service.exe start
```

12. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the `<broker_instance_dir>\log\artemis.log` file. Find two lines similar to the ones below. Note the new version number that appears in the log when the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live
...
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.9.0.redhat-00001 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```


You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the `<broker_instance_dir>\etc\artemis.profile` file, update the `ARTEMIS_INSTANCE_ETC_URI` property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the `\etc` and `\data` directories within the broker instance's directory.

Additional resources

- [Creating a broker instance](#)


2.2. UPGRADING A BROKER INSTANCE FROM 7.4.0 TO 7.4.X

Learn how to upgrade a 7.4.0 broker instance to 7.4.x for different operating systems.



IMPORTANT

AMQ Broker 7.4 has been designated as a Long Term Support (LTS) release version. Bug fixes and security advisories will be made available for AMQ Broker 7.4 in a series of micro releases (7.4.1, 7.4.2, and so on) for a period of at least 12 months. This means that you will be able to get recent bug fixes and security advisories for AMQ Broker without having to upgrade to a new minor release. For more information, see [Long Term Support for AMQ Broker](#).



IMPORTANT

Starting with AMQ Broker 7.1.0, you can access AMQ Management Console only from the local host by default. To learn about configuring remote access to the console, see link:[https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing\[Configuring local and remote access to AMQ Management Console\]](https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing[Configuring local and remote access to AMQ Management Console]).

2.2.1. Upgrading from 7.4.0 to 7.4.x on Linux

Download the new archive to upgrade from 7.4.0 to 7.4.x on Linux.

Procedure

1. Download the required archive from the Red Hat Customer Portal. Follow the instructions provided in [Downloading the AMQ Broker archive](#).
2. Change the owner of the archive to the same user that owns the AMQ Broker installation to be upgraded. The following example shows a user called **amq-broker**.

■

```
sudo chown amq-broker:amq-broker amq-broker-7.4.x.redhat-1.zip
```

3. Move the archive to the directory created during the original installation of AMQ Broker. The following example uses **/opt/redhat**.

```
sudo mv amq-broker-7.4.x.redhat-1.zip /opt/redhat
```

4. As the directory owner, extract the contents of the compressed archive. In the following example, the user **amq-broker** extracts the archive using the **unzip** command.

```
su - amq-broker
cd /opt/redhat
unzip amq-broker-7.4.x.redhat-1.zip
```

5. If the broker is running, stop it.

```
<broker_instance_dir>/bin/artemis stop
```

6. Back up the instance directory of the broker by copying it to the home directory of the current user.

```
cp -r <broker_instance_dir> ~/
```

7. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker_instance_dir>/log/artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.7.0.redhat-00054 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```

8. Edit the **<broker_instance_dir>/etc/artemis.profile** configuration file. Set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted.

```
ARTEMIS_HOME='/opt/redhat/amq-broker-7.4.x-redhat-1'
```

9. Start the upgraded broker.

```
<broker_instance_dir>/bin/artemis run
```

10. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker_instance_dir>/log/artemis.log** file. Find two lines similar to the ones below. Note the new version number that appears in the log when the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live
...
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.9.0.redhat-00001 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```



NOTE

You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker_instance_dir>/etc/artemis.profile** file, update the **ARTEMIS_INSTANCE_ETC_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **etc/** and **data/** directories within the broker instance's directory.

Additional resources

- [Creating a broker instance](#)

2.2.2. Upgrading from 7.4.0 to 7.4.x on Windows

Download the new archive to upgrade from 7.4.0 to 7.4.x on Windows.

Procedure

1. Download the required archive from the Red Hat Customer Portal by following the instructions provided in [Downloading the AMQ Broker archive](#).
2. Use a file manager to move the archive to the folder you created during the last installation of AMQ Broker.
3. Extract the contents of the archive. Right-click the .zip file and select **Extract All**.
4. If the broker is running, stop it.

```
<broker_instance_dir>\bin\artemis-service.exe stop
```

5. Back up the broker using a file manager.
 - a. Right-click the **<broker_instance_dir>** folder and select **Copy**.
 - b. Right-click in the same window and select **Paste**.
6. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker_instance_dir>\log\artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221002: Apache ActiveMQ Artemis
Message Broker version 2.7.0.redhat-00054 [4782d50d-47a2-11e7-a160-9801a793ea45]
stopped, uptime 28 minutes
```

7. Edit the **<broker_instance_dir>\etc\artemis.profile.cmd** and **<broker_instance_dir>\bin\artemis-service.xml** configuration files. Set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted.

```
ARTEMIS_HOME=<install_dir>
```

8. Start the upgraded broker.

```
<broker_instance_dir>\bin\artemis-service.exe start
```

9. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the `<broker_instance_dir>\log\artemis.log` file. Find two lines similar to the ones below. Note the new version number that appears in the log when the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live
...
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.9.0.redhat-00001 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```



NOTE

You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the `<broker_instance_dir>\etc\artemis.profile` file, update the **ARTEMIS_INSTANCE_ETC_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the `\etc` and `\data` directories within the broker instance's directory.

Additional resources

- [Creating a broker instance](#)

2.3. UPGRADING A BROKER INSTANCE FROM 7.4.X TO 7.5.0

Learn how to upgrade a 7.4.x broker instance to 7.5.0 for different operating systems.



IMPORTANT

Starting with AMQ Broker 7.1.0, you can access AMQ Management Console only from the local host by default. To learn about configuring remote access to the console, see link:https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing[Configuring local and remote access to AMQ Management Console].

2.3.1. Upgrading from 7.4.x to 7.5.0 on Linux

Download the new archive to upgrade from 7.4.x to 7.5.0 on Linux.

Procedure

1. Download the required archive from the Red Hat Customer Portal. Follow the instructions provided in [Downloading the AMQ Broker archive](#).
2. Change the owner of the archive to the same user that owns the AMQ Broker installation to be upgraded. The following example shows a user called **amq-broker**.

```
sudo chown amq-broker:amq-broker amq-broker-7.5.0.redhat-1.zip
```

3. Move the archive to the directory created during the original installation of AMQ Broker. The following example uses `/opt/redhat`.

```
sudo mv amq-broker-7.5.0.redhat-1.zip /opt/redhat
```

4. As the directory owner, extract the contents of the compressed archive. In the following example, the user **amq-broker** extracts the archive using the **unzip** command.

```
su - amq-broker
cd /opt/redhat
unzip amq-broker-7.5.0.redhat-1.zip
```

5. If the broker is running, stop it.

```
<broker_instance_dir>/bin/artemis stop
```

6. Back up the instance directory of the broker by copying it to the home directory of the current user.

```
cp -r <broker_instance_dir> ~/
```

7. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker_instance_dir>/log/artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.7.0.redhat-00054 [0.0.0.0, nodeID=554cce00-63d9-11e8-9808-
54ee759954c4]
```

8. Edit the **<broker_instance_dir>/etc/artemis.profile** configuration file.

- a. Set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted.

```
ARTEMIS_HOME='/opt/redhat/amq-broker-7.5.0-redhat-1'
```

- b. Edit the **JAVA_ARGS** property. Add the bootstrap class path argument, which references a dependent file for the log manager.


```
-Xbootclasspath/a:$ARTEMIS_HOME/lib/wildfly-common-1.5.2.Final-redhat-00001.jar
```

9. Start the upgraded broker.

```
<broker_instance_dir>/bin/artemis run
```

10. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker_instance_dir>/log/artemis.log** file. Find two lines similar to the ones below. Note the new version number that appears in the log when the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live
...
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.9.0.redhat-00001 [0.0.0.0, nodeID=554cce00-63d9-11e8-9808-
54ee759954c4]
```



NOTE

You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker_instance_dir>/etc/artemis.profile** file, update the **ARTEMIS_INSTANCE_ETC_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **etc/** and **data/** directories within the broker instance's directory.

Additional resources

- [Creating a broker instance](#)

2.3.2. Upgrading from 7.4.x to 7.5.0 on Windows

Download the new archive to upgrade from 7.4.x to 7.5.0 on Windows.

Procedure

1. Download the required archive from the Red Hat Customer Portal by following the instructions provided in [Downloading the AMQ Broker archive](#).
2. Use a file manager to move the archive to the folder you created during the last installation of AMQ Broker.
3. Extract the contents of the archive. Right-click the .zip file and select **Extract All**.
4. If the broker is running, stop it.

```
<broker_instance_dir>\bin\artemis-service.exe stop
```

5. Back up the broker using a file manager.
 - a. Right-click the **<broker_instance_dir>** folder and select **Copy**.
 - b. Right-click in the same window and select **Paste**.
6. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker_instance_dir>\log\artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221002: Apache ActiveMQ Artemis
Message Broker version 2.7.0.redhat-00054 [4782d50d-47a2-11e7-a160-9801a793ea45]
stopped, uptime 28 minutes
```

7. Edit the **<broker_instance_dir>\etc\artemis.profile.cmd** and **<broker_instance_dir>\bin\artemis-service.xml** configuration files. Set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted.

```
ARTEMIS_HOME=<install_dir>
```

8. Edit the **<broker_instance_dir>\etc\artemis.profile.cmd** configuration file. Set the **JAVA_ARGS** environment variable to reference the correct log manager version and dependent file.

```
JAVA_ARGS=-Xbootclasspath/%ARTEMIS_HOME%\lib\jboss-logmanager-2.1.10.Final-redhat-00001.jar;%ARTEMIS_HOME%\lib\wildfly-common-1.5.2.Final-redhat-00001.jar
```

9. Edit the **<broker_instance_dir>\bin\artemis-service.xml** configuration file. Set the bootstrap class path start argument to reference the correct log manager version and dependent file.

```
<startargument>-Xbootclasspath/a:%ARTEMIS_HOME%\lib\jboss-logmanager-2.1.10.Final-redhat-00001.jar;%ARTEMIS_HOME%\lib\wildfly-common-1.5.2.Final-redhat-00001.jar</startargument>
```

10. Start the upgraded broker.

```
<broker_instance_dir>\bin\artemis-service.exe start
```

11. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker_instance_dir>\log\artemis.log** file. Find two lines similar to the ones below. Note the new version number that appears in the log when the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live
...
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.9.0.redhat-00001 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```



NOTE


You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker_instance_dir>\etc\artemis.profile** file, update the **ARTEMIS_INSTANCE_ETC_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **\etc** and **\data** directories within the broker instance's directory.

Additional resources

- [Creating a broker instance](#)

2.4. UPGRADING A BROKER INSTANCE FROM 7.5.0 TO 7.6.0

Learn how to upgrade a 7.5.0 broker instance to 7.6.0 for different operating systems.



IMPORTANT

Starting with AMQ Broker 7.1.0, you can access AMQ Management Console only from the local host by default. To learn about configuring remote access to the console, see [link:https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing](https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing)[Configuring local and remote access to AMQ Management Console].

2.4.1. Upgrading from 7.5.0 to 7.6.0 on Linux

Download the new archive to upgrade from 7.5.0 to 7.6.0 on Linux.

Procedure

1. Download the required archive from the Red Hat Customer Portal by following the instructions provided in [Downloading the AMQ Broker archive](#).
2. Change the owner of the archive to the same user that owns the AMQ Broker installation to be upgraded. The following example shows a user called **amq-broker**.

```
sudo chown amq-broker:amq-broker amq-broker-7.6.0.redhat-1.zip
```

3. Move the archive to the directory created during the original installation of AMQ Broker. The following example uses **/opt/redhat**.

```
sudo mv amq-broker-7.6.0.redhat-1.zip /opt/redhat
```

4. As the directory owner, extract the contents of the compressed archive. In the following example, the user **amq-broker** extracts the archive using the **unzip** command.

```
su - amq-broker
cd /opt/redhat
unzip amq-broker-7.6.0.redhat-1.zip
```

5. If the broker is running, stop it.

```
<broker_instance_dir>/bin/artemis stop
```

6. Back up the instance directory of the broker by copying it to the home directory of the current user.

```
cp -r <broker_instance_dir> ~/
```

7. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker_instance_dir>/log/artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.9.0.redhat-00054 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```

8. Edit the **<broker_instance_dir>/etc/artemis.profile** configuration file.

- a. Set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted.

```
ARTEMIS_HOME='/opt/redhat/amq-broker-7.6.0-redhat-1'
```

- b. Edit the **JAVA_ARGS** property. Add the bootstrap class path argument, which references a dependent file for the log manager.

```
-Xbootclasspath/a:$ARTEMIS_HOME/lib/wildfly-common-1.5.2.Final-redhat-00002.jar
```

9. Start the upgraded broker.

```
<broker_instance_dir>/bin/artemis run
```

10. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker_instance_dir>/log/artemis.log** file. Find two lines similar to the ones below. Note the new version number that appears in the log when the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live
...
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.11.0.redhat-00001 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```



NOTE

You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker_instance_dir>/etc/artemis.profile** file, update the **ARTEMIS_INSTANCE_ETC_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **etc/** and **data/** directories within the broker instance's directory.

Additional resources

- [Creating a broker instance](#)

2.4.2. Upgrading from 7.5.0 to 7.6.0 on Windows

Download the new archive to upgrade from 7.5.0 to 7.6.0 on Windows.

Procedure

1. Download the required archive from the Red Hat Customer Portal by following the instructions provided in [Downloading the AMQ Broker archive](#).
2. Use a file manager to move the archive to the folder you created during the last installation of AMQ Broker.
3. Extract the contents of the archive. Right-click the .zip file and select **Extract All**.
4. If the broker is running, stop it.

```
<broker_instance_dir>\bin\artemis-service.exe stop
```

5. Back up the broker using a file manager.
 - a. Right-click the **<broker_instance_dir>** folder and select **Copy**.
 - b. Right-click in the same window and select **Paste**.
6. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker_instance_dir>\log\artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221002: Apache ActiveMQ Artemis
Message Broker version 2.9.0.redhat-00054 [4782d50d-47a2-11e7-a160-9801a793ea45]
stopped, uptime 28 minutes
```

7. Edit the **<broker_instance_dir>\etc\artemis.profile.cmd** and **<broker_instance_dir>\bin\artemis-service.xml** configuration files. Set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted.

```
ARTEMIS_HOME=<install_dir>
```

8. Edit the **<broker_instance_dir>\etc\artemis.profile.cmd** configuration file. Set the **JAVA_ARGS** environment variable to reference the correct log manager version and dependent file.

```
JAVA_ARGS=-Xbootclasspath/%ARTEMIS_HOME%\lib\jboss-logmanager-2.1.10.Final-
redhat-00001.jar;%ARTEMIS_HOME%\lib\wildfly-common-1.5.2.Final-redhat-00002.jar
```

9. Edit the **<broker_instance_dir>\bin\artemis-service.xml** configuration file. Set the bootstrap class path start argument to reference the correct log manager version and dependent file.

```
<startargument>-Xbootclasspath/a:%ARTEMIS_HOME%\lib\jboss-logmanager-2.1.10.Final-
redhat-00001.jar;%ARTEMIS_HOME%\lib\wildfly-common-1.5.2.Final-redhat-
00002.jar</startargument>
```

10. Start the upgraded broker.

```
<broker_instance_dir>\bin\artemis-service.exe start
```

11. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker_instance_dir>\log\artemis.log** file. Find two lines similar to the ones below. Note the new version number that appears in the log when the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live
...
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.11.0.redhat-00001 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```



NOTE

You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker_instance_dir>\etc\artemis.profile** file, update the **ARTEMIS_INSTANCE_ETC_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **\etc** and **\data** directories within the broker instance's directory.

Additional resources

- [Creating a broker instance](#)

2.5. UPGRADING A BROKER INSTANCE FROM 7.6.0 TO 7.7.0

Learn how to upgrade a 7.6.0 broker instance to 7.7.0 for different operating systems.



IMPORTANT

Starting with AMQ Broker 7.1.0, you can access AMQ Management Console only from the local host by default. To learn about configuring remote access to the console, see [link:https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing](https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing)[Configuring local and remote access to AMQ Management Console].

2.5.1. Upgrading from 7.6.0 to 7.7.0 on Linux

Download the new archive to upgrade from 7.6.0 to 7.7.0 on Linux.

Procedure

1. Download the required archive from the Red Hat Customer Portal by following the instructions provided in [Downloading the AMQ Broker archive](#).
2. Change the owner of the archive to the same user that owns the AMQ Broker installation to be upgraded. The following example shows a user called **amq-broker**.

```
sudo chown amq-broker:amq-broker amq-broker-7.7.0.redhat-1.zip
```

3. Move the archive to the directory created during the original installation of AMQ Broker. The following example uses **/opt/redhat**.

```
sudo mv amq-broker-7.7.0.redhat-1.zip /opt/redhat
```

4. As the directory owner, extract the contents of the compressed archive. In the following example, the user **amq-broker** extracts the archive using the **unzip** command.

```
su - amq-broker
cd /opt/redhat
unzip amq-broker-7.7.0.redhat-1.zip
```

5. If the broker is running, stop it.

```
<broker_instance_dir>/bin/artemis stop
```

6. Back up the instance directory of the broker by copying it to the home directory of the current user.

```
cp -r <broker_instance_dir> ~/
```

7. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker_instance_dir>/log/artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.11.0.redhat-00001 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```

8. Edit the **<broker_instance_dir>/etc/artemis.profile** configuration file.

- a. Set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted. For example:

```
ARTEMIS_HOME='/opt/redhat/amq-broker-7.7.0-redhat-1'
```

- b. Locate the **JAVA_ARGS** property. Ensure that the bootstrap class path argument references the required version of a dependent file for the log manager, as shown below.

```
-Xbootclasspath/a:$ARTEMIS_HOME/lib/wildfly-common-1.5.2.Final-redhat-00002.jar
```

9. Edit the **<broker_instance_dir>/etc/logging.properties** configuration file.

- a. On the list of additional loggers to be configured, include the **org.apache.activemq.audit.resource** resource logger that was added in AMQ Broker 7.7.0.

```
loggers=org.eclipse.jetty,org.jboss.logging,org.apache.activemq.artemis.core.server,org.apache.activemq.artemis.utils,org.apache.activemq.artemis.journal,org.apache.activemq.artemis.jms.server,org.apache.activemq.artemis.integration.bootstrap,org.apache.activemq.audit.base,org.apache.activemq.audit.message,org.apache.activemq.audit.resource
```

- b. Before the **Console handler configuration** section, add a default configuration for the resource logger.

```
..

logger.org.apache.activemq.audit.resource.level=ERROR
logger.org.apache.activemq.audit.resource.handlers=AUDIT_FILE
logger.org.apache.activemq.audit.resource.useParentHandlers=false

# Console handler configuration
..
```

10. Start the upgraded broker.

```
<broker_instance_dir>/bin/artemis run
```

11. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker_instance_dir>/log/artemis.log** file. Find two lines similar to the ones below. Note the new version number that appears in the log when the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live
...
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Mesq.audit.resource.handlers=AUDIT_FILE
logger.org.apache.activemq.audit.resource.useParentHandlers=false
sage Broker version 2.13.0.redhat-00003 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```



NOTE

You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker_instance_dir>/etc/artemis.profile** file, update the **ARTEMIS_INSTANCE_ETC_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **etc/** and **data/** directories within the broker instance's directory.

Additional resources

- [Creating a broker instance](#)

2.5.2. Upgrading from 7.6.0 to 7.7.0 on Windows

Download the new archive to upgrade from 7.6.0 to 7.7.0 on Windows.

Procedure

1. Download the required archive from the Red Hat Customer Portal by following the instructions provided in [Downloading the AMQ Broker archive](#).
2. Use a file manager to move the archive to the folder you created during the last installation of AMQ Broker.
3. Extract the contents of the archive. Right-click the .zip file and select **Extract All**.
4. If the broker is running, stop it.

```
<broker_instance_dir>\bin\artemis-service.exe stop
```

5. Back up the broker using a file manager.
 - a. Right-click the **<broker_instance_dir>** folder and select **Copy**.
 - b. Right-click in the same window and select **Paste**.
6. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker_instance_dir>\log\artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221002: Apache ActiveMQ Artemis
Message Broker version 2.11.0.redhat-00001 [4782d50d-47a2-11e7-a160-9801a793ea45]
stopped, uptime 28 minutes
```

7. Edit the **<broker_instance_dir>\etc\artemis.profile.cmd** and **<broker_instance_dir>\bin\artemis-service.xml** configuration files. Set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted.

```
ARTEMIS_HOME=<install_dir>
```

8. Edit the **<broker_instance_dir>\etc\artemis.profile.cmd** configuration file. Ensure that the **JAVA_ARGS** environment variable references the correct versions for the log manager and dependent file, as shown below.

```
JAVA_ARGS=-Xbootclasspath/%ARTEMIS_HOME%\lib\jboss-logmanager-2.1.10.Final-redhat-00001.jar;%ARTEMIS_HOME%\lib\wildfly-common-1.5.2.Final-redhat-00002.jar
```

9. Edit the **<broker_instance_dir>\bin\artemis-service.xml** configuration file. Ensure that the bootstrap class path start argument references the correct versions for the log manager and dependent file, as shown below.

```
<startargument>-Xbootclasspath/a:%ARTEMIS_HOME%\lib\jboss-logmanager-2.1.10.Final-redhat-00001.jar;%ARTEMIS_HOME%\lib\wildfly-common-1.5.2.Final-redhat-00002.jar</startargument>
```

10. Edit the **<broker_instance_dir>\etc\logging.properties** configuration file.
 - a. On the list of additional loggers to be configured, include the **org.apache.activemq.audit.resource** resource logger that was added in AMQ Broker 7.7.0.

```
loggers=org.eclipse.jetty,org.jboss.logging,org.apache.activemq.artemis.core.server,org.apache.activemq.artemis.utils,org.apache.activemq.artemis.journal,org.apache.activemq.artemis.jms.server,org.apache.activemq.artemis.integration.bootstrap,org.apache.activemq.audit.base,org.apache.activemq.audit.message,org.apache.activemq.audit.resource
```

- b. Before the **Console handler configuration** section, add a default configuration for the resource logger.

```
..

logger.org.apache.activemq.audit.resource.level=ERROR
logger.org.apache.activemq.audit.resource.handlers=AUDIT_FILE
logger.org.apache.activemq.audit.resource.useParentHandlers=false

# Console handler configuration
..
```

11. Start the upgraded broker.

```
<broker_instance_dir>\bin\artemis-service.exe start
```

12. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker_instance_dir>\log\artemis.log** file. Find two lines similar to the ones below. Note the new version number that appears in the log when the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live
...
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.13.0.redhat-00003 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```



NOTE


You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the `<broker_instance_dir>/etc/artemis.profile` file, update the **ARTEMIS_INSTANCE_ETC_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the `/etc` and `/data` directories within the broker instance's directory.

Additional resources

- [Creating a broker instance](#)

2.6. UPGRADING A BROKER INSTANCE FROM 7.7.0 TO 7.8.0

Learn how to upgrade a 7.7.0 broker instance to 7.8.0 for different operating systems.



IMPORTANT

Starting with AMQ Broker 7.1.0, you can access AMQ Management Console only from the local host by default. To learn about configuring remote access to the console, see [link:https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing](https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing)[Configuring local and remote access to AMQ Management Console].

2.6.1. Upgrading from 7.7.0 to 7.8.0 on Linux

Download the new archive to upgrade from 7.7.0 to 7.8.0 on Linux.

Procedure

1. Download the required archive from the Red Hat Customer Portal by following the instructions provided in [Downloading the AMQ Broker archive](#).
2. Change the owner of the archive to the same user that owns the AMQ Broker installation to be upgraded. The following example shows a user called **amq-broker**.

```
sudo chown amq-broker:amq-broker amq-broker-7.8.0.redhat-1.zip
```

3. Move the archive to the directory created during the original installation of AMQ Broker. The following example uses **/opt/redhat**.

```
sudo mv amq-broker-7.8.0.redhat-1.zip /opt/redhat
```

4. As the directory owner, extract the contents of the compressed archive. In the following example, the user **amq-broker** extracts the archive using the **unzip** command.

```
su - amq-broker
cd /opt/redhat
unzip amq-broker-7.8.0.redhat-1.zip
```

5. If the broker is running, stop it.

```
<broker_instance_dir>/bin/artemis stop
```

6. Back up the instance directory of the broker by copying it to the home directory of the current user.

```
cp -r <broker_instance_dir> ~/
```

7. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker_instance_dir>/log/artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.13.0.redhat-00003 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```

8. Edit the **<broker_instance_dir>/etc/artemis.profile** configuration file.
 - a. Set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted. For example:

```
ARTEMIS_HOME='/opt/redhat/amq-broker-7.8.0-redhat-1'
```

- b. Locate the **JAVA_ARGS** property. Ensure that the bootstrap class path argument references the required version of a dependent file for the log manager, as shown below.

```
-Xbootclasspath/a:$ARTEMIS_HOME/lib/wildfly-common-1.5.2.Final-redhat-00002.jar
```

9. Edit the **<broker_instance_dir>/etc/bootstrap.xml** configuration file. In the **web** element, update the name of the **.war** file required by AMQ Management Console in 7.8.

```
<web bind="http://localhost:8161" path="web">
...
  <app url="console" war="hawtio.war"/>
...
</web>
```

10. Start the upgraded broker.

```
<broker_instance_dir>/bin/artemis run
```

11. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker_instance_dir>/log/artemis.log** file. Find two lines similar to the ones below. Note the new version number that appears in the log when the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live
...
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Mesq.audit.resource.handlers=AUDIT_FILE
logger.org.apache.activemq.audit.resource.useParentHandlers=false
sage Broker version 2.16.0.redhat-00007 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```



NOTE

You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker_instance_dir>/etc/artemis.profile** file, update the **ARTEMIS_INSTANCE_ETC_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **etc/** and **data/** directories within the broker instance's directory.

Additional resources

- [Creating a broker instance](#)

2.6.2. Upgrading from 7.7.0 to 7.8.0 on Windows

Download the new archive to upgrade from 7.7.0 to 7.8.0 on Windows.

Procedure

1. Download the required archive from the Red Hat Customer Portal by following the instructions provided in [Downloading the AMQ Broker archive](#).
2. Use a file manager to move the archive to the folder you created during the last installation of AMQ Broker.
3. Extract the contents of the archive. Right-click the .zip file and select **Extract All**.
4. If the broker is running, stop it.

```
<broker_instance_dir>\bin\artemis-service.exe stop
```

5. Back up the broker using a file manager.
 - a. Right-click the **<broker_instance_dir>** folder and select **Copy**.
 - b. Right-click in the same window and select **Paste**.
6. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker_instance_dir>\log\artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221002: Apache ActiveMQ Artemis
Message Broker version 2.13.0.redhat-00003 [4782d50d-47a2-11e7-a160-9801a793ea45]
stopped, uptime 28 minutes
```

7. Edit the **<broker_instance_dir>\etc\artemis.profile.cmd** and **<broker_instance_dir>\bin\artemis-service.xml** configuration files. Set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted.

```
ARTEMIS_HOME=<install_dir>
```

8. Edit the **<broker_instance_dir>\etc\artemis.profile.cmd** configuration file. Ensure that the **JAVA_ARGS** environment variable references the correct versions for the log manager and dependent file, as shown below.

```
JAVA_ARGS=-Xbootclasspath/%ARTEMIS_HOME%\lib\jboss-logmanager-2.1.10.Final-redhat-00001.jar;%ARTEMIS_HOME%\lib\wildfly-common-1.5.2.Final-redhat-00002.jar
```

9. Edit the **<broker_instance_dir>\bin\artemis-service.xml** configuration file. Ensure that the bootstrap class path start argument references the correct versions for the log manager and dependent file, as shown below.

```
<startargument>-Xbootclasspath/a:%ARTEMIS_HOME%\lib\jboss-logmanager-2.1.10.Final-redhat-00001.jar;%ARTEMIS_HOME%\lib\wildfly-common-1.5.2.Final-redhat-00002.jar</startargument>
```

10. Edit the **<broker_instance_dir>\etc\bootstrap.xml** configuration file. In the **web** element, update the name of the **.war** file required by AMQ Management Console in 7.8.

```
<web bind="http://localhost:8161" path="web">
...
<app url="console" war="hawtio.war"/>
...
</web>
```

11. Start the upgraded broker.

```
<broker_instance_dir>\bin\artemis-service.exe start
```

12. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker_instance_dir>\log\artemis.log** file. Find two lines similar to the ones below. Note the new version number that appears in the log when the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live
...
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.16.0.redhat-00007 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```



NOTE

You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker_instance_dir>\etc\artemis.profile** file, update the **ARTEMIS_INSTANCE_ETC_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **\etc** and **\data** directories within the broker instance's directory.

Additional resources

- [Creating a broker instance](#)

2.7. UPGRADING A BROKER INSTANCE FROM 7.8.X TO 7.9.X

Learn how to upgrade a 7.8.x broker instance to 7.9.x for different operating systems.



IMPORTANT

Starting with AMQ Broker 7.1.0, you can access AMQ Management Console only from the local host by default. To learn about configuring remote access to the console, see [link:https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing](https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing)[Configuring local and remote access to AMQ Management Console].

2.7.1. Upgrading from 7.8.x to 7.9.x on Linux

Download the new archive to upgrade from 7.8.x to 7.9.x on Linux.

Procedure

1. Download the required archive from the Red Hat Customer Portal by following the instructions provided in [Downloading the AMQ Broker archive](#).
2. Change the owner of the archive to the same user that owns the AMQ Broker installation to be upgraded. The following example shows a user called **amq-broker**.

```
sudo chown amq-broker:amq-broker amq-broker-7.x.x-bin.zip
```

3. Move the archive to the directory created during the original installation of AMQ Broker. The following example uses **/opt/redhat**.

```
sudo mv amq-broker-7.x.x-bin.zip /opt/redhat
```

4. As the directory owner, extract the contents of the compressed archive. In the following example, the user **amq-broker** extracts the archive using the **unzip** command.

```
su - amq-broker
cd /opt/redhat
unzip amq-broker-7.x.x-bin.zip
```

5. If the broker is running, stop it.

```
<broker_instance_dir>/bin/artemis stop
```

6. Back up the instance directory of the broker by copying it to the home directory of the current user.

```
cp -r <broker_instance_dir> ~/
```

7. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker_instance_dir>/log/artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.13.0.redhat-00003 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```

8. Edit the **<broker_instance_dir>/etc/artemis.profile** configuration file.

- a. Set the **ARTEMIS_HOME** property to the new directory created when the archive was

extracted. For example:

```
ARTEMIS_HOME='/opt/redhat/amq-broker-7.x.x-bin'
```

- b. Locate the **JAVA_ARGS** property. Ensure that the bootstrap class path argument references the required version of a dependent file for the log manager, as shown below.

```
-Xbootclasspath/a:$ARTEMIS_HOME/lib/wildfly-common-1.5.2.Final-redhat-00002.jar
```

9. Edit the **<broker_instance_dir>/etc/bootstrap.xml** configuration file. In the **web** element, update the name of the **.war** file required by AMQ Management Console in 7.9.

```
<web bind="http://localhost:8161" path="web">
...
  <app url="console" war="hawtio.war"/>
...
</web>
```

10. Start the upgraded broker.

```
<broker_instance_dir>/bin/artemis run
```

11. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker_instance_dir>/log/artemis.log** file. Find two lines similar to the ones below. Note the new version number that appears in the log when the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Mes
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live
...
sage Broker version 2.18.0.redhat-00010 [0.0.0.0, nodeID=554cce00-63d9-11e8-9808-
54ee759954c4]
```



NOTE

You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker_instance_dir>/etc/artemis.profile** file, update the **ARTEMIS_INSTANCE_ETC_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **etc/** and **data/** directories within the broker instance's directory.

Additional resources

- [Creating a broker instance](#)

2.7.2. Upgrading from 7.8.x to 7.9.x on Windows

Download the new archive to upgrade from 7.8.x to 7.9.x on Windows.

Procedure

1. Follow the instructions provided in [Downloading the AMQ Broker archive](#) to download the AMQ Broker archive.
2. Use a file manager to move the archive to the folder you created during the last installation of AMQ Broker.
3. Extract the contents of the archive. Right-click the .zip file and select **Extract All**.
4. If the broker is running, stop it.

```
<broker_instance_dir>\bin\artemis-service.exe stop
```

5. Back up the broker using a file manager.
 - a. Right-click the **<broker_instance_dir>** folder and select **Copy**.
 - b. Right-click in the same window and select **Paste**.
6. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker_instance_dir>\log\artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221002: Apache ActiveMQ Artemis
Message Broker version 2.13.0.redhat-00003 [4782d50d-47a2-11e7-a160-9801a793ea45]
stopped, uptime 28 minutes
```

7. Edit the **<broker_instance_dir>\etc\artemis.profile.cmd** and **<broker_instance_dir>\bin\artemis-service.xml** configuration files. Set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted.

```
ARTEMIS_HOME=<install_dir>
```

8. Edit the **<broker_instance_dir>\etc\artemis.profile.cmd** configuration file. Ensure that the **JAVA_ARGS** environment variable references the correct versions for the log manager and dependent file, as shown below.

```
JAVA_ARGS=-Xbootclasspath/%ARTEMIS_HOME%\lib\jboss-logmanager-2.1.10.Final-
redhat-00001.jar;%ARTEMIS_HOME%\lib\wildfly-common-1.5.2.Final-redhat-00002.jar
```

9. Edit the **<broker_instance_dir>\bin\artemis-service.xml** configuration file. Ensure that the bootstrap class path start argument references the correct versions for the log manager and dependent file, as shown below.

```
<startargument>-Xbootclasspath/a:%ARTEMIS_HOME%\lib\jboss-logmanager-2.1.10.Final-
redhat-00001.jar;%ARTEMIS_HOME%\lib\wildfly-common-1.5.2.Final-redhat-
00002.jar</startargument>
```

10. Edit the **<broker_instance_dir>\etc\bootstrap.xml** configuration file. In the **web** element, update the name of the **.war** file required by AMQ Management Console in 7.9.

```
<web bind="http://localhost:8161" path="web">
...
<app url="console" war="hawtio.war"/>
...
</web>
```

11. Start the upgraded broker.

```
<broker_instance_dir>\bin\artemis-service.exe start
```

12. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker_instance_dir>\log\artemis.log** file. Find two lines similar to the ones below. Note the new version number that appears in the log when the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live
...
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.18.0.redhat-00010 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```



NOTE

You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker_instance_dir>\etc\artemis.profile** file, update the **ARTEMIS_INSTANCE_ETC_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **\etc** and **\data** directories within the broker instance's directory.

Additional resources

- [Creating a broker instance](#)

2.8. UPGRADING A BROKER INSTANCE FROM 7.9.X TO 7.10.X

Learn how to upgrade a 7.9.x broker instance to 7.10.x for different operating systems.



IMPORTANT

Starting with AMQ Broker 7.1.0, you can access AMQ Management Console only from the local host by default. To learn about configuring remote access to the console, see link: https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing [Configuring local and remote access to AMQ Management Console].

2.8.1. Upgrading from 7.9.x to 7.10.x on Linux

Download the new archive to upgrade from 7.9.x to 7.10.x on Linux.

Prerequisites

- At a minimum, AMQ Broker 7.10.x requires Java version 11 to run. Ensure that each AMQ Broker host is running Java version 11 or higher. For more information on supported configurations, see [Red Hat AMQ Broker 7 Supported Configurations](#).
- If AMQ Broker 7.9 is configured to persist message data in a database, the data type of the **HOLDER_EXPIRATION_TIME** column is **timestamp** in the node manager database table. In AMQ Broker 7.10, the data type of the column changed to **number**. Before you upgrade to AMQ

Broker 7.10.x, you must drop the node manager table, that is, remove it from the database. After you drop the table, it is recreated with the new schema when you restart the upgraded broker. In a shared store high availability (HA) configuration, the node manager table is shared between brokers. Therefore, you must ensure that all brokers that share the table are stopped before you drop the table. The following example drops a node manager table called **NODE_MANAGER_TABLE**:

```
DROP TABLE NODE_MANAGER_TABLE
```

Procedure

1. Download the required archive from the Red Hat Customer Portal by following the instructions provided in [Downloading the AMQ Broker archive](#).
2. Change the owner of the archive to the same user that owns the AMQ Broker installation to be upgraded. The following example shows a user called **amq-broker**.

```
sudo chown amq-broker:amq-broker amq-broker-7.x.x-bin.zip
```

3. Move the archive to the directory created during the original installation of AMQ Broker. The following example uses **/opt/redhat**.

```
sudo mv amq-broker-7.x.x-bin.zip /opt/redhat
```

4. As the directory owner, extract the contents of the compressed archive. In the following example, the user **amq-broker** extracts the archive using the **unzip** command.

```
su - amq-broker
cd /opt/redhat
unzip amq-broker-7.x.x-bin.zip
```

5. If the broker is running, stop it.

```
<broker_instance_dir>/bin/artemis stop
```

6. Back up the instance directory of the broker by copying it to the home directory of the current user.

```
cp -r <broker_instance_dir> ~/
```

7. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker_instance_dir>/log/artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.18.0.redhat-00010 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```

8. Edit the **<broker_instance_dir>/etc/artemis.profile** configuration file.

- a. Set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted. For example:

```
ARTEMIS_HOME='/opt/redhat/amq-broker-7.x.x-bin'
```

9. Edit the **<broker_instance_dir>/etc/bootstrap.xml** configuration file.

In the **web** element, update the name of the **.war** file required by AMQ Management Console in 7.10.x.

```
<web path="web">
  <binding uri="https://localhost:8161"
  ...
  <app url="console" war="hawtio.war"/>
  ...
</web>
```

In the **broker xmlns** element, change the schema value from **"http://activemq.org/schema"** to **"http://activemq.apache.org/schema"**.

```
<broker xmlns="http://activemq.apache.org/schema">
```

10. Edit the **<broker_instance_dir>/etc/management.xml** file.

In the **management-context xmlns** element, change the schema value from **"http://activemq.org/schema"** to **"http://activemq.apache.org/schema"**.

```
<management-context xmlns="http://activemq.apache.org/schema">
```

11. Start the upgraded broker.

```
<broker_instance_dir>/bin/artemis run
```

12. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker_instance_dir>/log/artemis.log** file. Find two lines similar to the ones below. Note the new version number that appears in the log when the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Mes
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live
...
sage Broker version 2.21.0.redhat-00025 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```



NOTE

You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker_instance_dir>/etc/artemis.profile** file, update the **ARTEMIS_INSTANCE_ETC_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **etc/** and **data/** directories within the broker instance's directory.

Additional resources

- [Creating a broker instance](#)

2.8.2. Upgrading from 7.9.x to 7.10.x on Windows

Download the new archive to upgrade from 7.9.x to 7.10.x on Windows.

Prerequisites

- At a minimum, AMQ Broker 7.10.x requires Java version 11 to run. Ensure that each AMQ Broker host is running Java version 11 or higher. For more information on supported configurations, see [Red Hat AMQ Broker 7 Supported Configurations](#).
- If AMQ Broker 7.9 is configured to persist message data in a database, the data type of the `HOLDER_EXPIRATION_TIME` column is **timestamp** in the node manager database table. In AMQ Broker 7.10, the data type of the column changed to **number**. Before you upgrade to AMQ Broker 7.10.x, you must drop the node manager table, that is, remove it from the database. After you drop the table, it is recreated with the new schema when you restart the upgraded broker. In a shared store high availability (HA) configuration, the node manager table is shared between brokers. Therefore, you must ensure that all brokers that share the table are stopped before you drop the table. The following example drops a node manager table called **NODE_MANAGER_TABLE**:

```
DROP TABLE NODE_MANAGER_TABLE
```

Procedure

1. Follow the instructions provided in [Downloading the AMQ Broker archive](#) to download the AMQ Broker archive.
2. Use a file manager to move the archive to the folder you created during the last installation of AMQ Broker.
3. Extract the contents of the archive. Right-click the .zip file and select **Extract All**.
4. If the broker is running, stop it.

```
<broker_instance_dir>\bin\artemis-service.exe stop
```

5. Back up the broker using a file manager.
 - a. Right-click the **<broker_instance_dir>** folder and select **Copy**.
 - b. Right-click in the same window and select **Paste**.
6. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker_instance_dir>\log\artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221002: Apache ActiveMQ Artemis
Message Broker version 2.18.0.redhat-00010[4782d50d-47a2-11e7-a160-9801a793ea45]
stopped, uptime 28 minutes
```

7. Edit the **<broker_instance_dir>\etc\artemis.profile.cmd** and **<broker_instance_dir>\bin\artemis-service.xml** configuration files. Set the **ARTEMIS_HOME** property to the new directory created when the archive was extracted.

```
ARTEMIS_HOME=<install_dir>
```

8. Edit the **<broker_instance_dir>\etc\artemis.profile.cmd** configuration file. Ensure that the **JAVA_ARGS** environment variable references the correct versions for the log manager and dependent file, as shown below.

```
JAVA_ARGS=-Xbootclasspath/%ARTEMIS_HOME%\lib\jboss-logmanager-2.1.10.Final-
redhat-00001.jar;%ARTEMIS_HOME%\lib\wildfly-common-1.5.2.Final-redhat-00002.jar
```

9. Edit the **<broker_instance_dir>\bin\artemis-service.xml** configuration file. Ensure that the bootstrap class path start argument references the correct versions for the log manager and dependent file, as shown below.

```
<startargument>-Xbootclasspath/a:%ARTEMIS_HOME%\lib\jboss-logmanager-2.1.10.Final-
redhat-00001.jar;%ARTEMIS_HOME%\lib\wildfly-common-1.5.2.Final-redhat-
00002.jar</startargument>
```

10. Edit the **<broker_instance_dir>\etc\bootstrap.xml** configuration file.
In the **web** element, update the name of the **.war** file required by AMQ Management Console in 7.10.x.

```
<web path="web">
  <binding uri="https://localhost:8161"
  ...
  <app url="console" war="hawtio.war"/>
  ...
</web>
```

In the **broker xmlns** element, change the schema value from **"http://activemq.org/schema"** to **"http://activemq.apache.org/schema"**.

```
<broker xmlns="http://activemq.apache.org/schema">
```

11. Edit the **<broker_instance_dir>\etc\management.xml** file.
In the **management-context xmlns** element, change the schema value from **"http://activemq.org/schema"** to **"http://activemq.apache.org/schema"**.

```
<management-context xmlns="http://activemq.apache.org/schema">
```

12. Start the upgraded broker.

```
<broker_instance_dir>\bin\artemis-service.exe start
```

13. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker_instance_dir>\log\artemis.log** file. Find two lines similar to the ones below. Note the new version number that appears in the log when the broker is live.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221007: Server is now live
...
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.21.0.redhat-00025 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```

**NOTE**


You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker_instance_dir>\etc\artemis.profile** file, update the **ARTEMIS_INSTANCE_ETC_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **\etc** and **\data** directories within the broker instance's directory.

Additional resources

- [Creating a broker instance](#)

2.9. UPGRADING A BROKER INSTANCE FROM 7.10.X TO 7.11.X

Learn how to upgrade a 7.10.x broker instance to 7.11.x for different operating systems.

**IMPORTANT**

Starting with AMQ Broker 7.1.0, you can access AMQ Management Console only from the local host by default. To learn about configuring remote access to the console, see [link:https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing](https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing)[Configuring local and remote access to AMQ Management Console].

2.9.1. Upgrading from 7.10.x to 7.11.x on Linux

Upgrade from 7.10.x to 7.11.x on Linux by downloading the new archive and running the **artemis upgrade** command.

**NOTE**

The name of the archive that you download could differ from what is used in the following examples.

Prerequisites

- At a minimum, AMQ Broker 7.11.x requires Java version 11 to run. Ensure that each AMQ Broker host is running Java version 11 or higher. For more information on supported configurations, see [Red Hat AMQ Broker 7 Supported Configurations](#).

Procedure

1. Follow the instructions provided in [Downloading the AMQ Broker archive](#) to download the AMQ Broker archive.
2. Change the owner of the archive that you downloaded to the same user that owns the AMQ Broker installation to be upgraded. The following example shows a user called **amq-broker**.

```
sudo chown amq-broker:amq-broker amq-broker-7.x.x-bin.zip
```

3. Move the archive to the directory created during the original installation of AMQ Broker. The following example uses **/opt/redhat**.

```
sudo mv amq-broker-7.x.x-bin.zip /opt/redhat
```

4. As the directory owner, extract the contents of the compressed archive. In the following example, the user **amq-broker** extracts the archive using the **unzip** command.

```
su - amq-broker
cd /opt/redhat
unzip amq-broker-7.x.x-bin.zip
```



NOTE

The contents of the latest archive are extracted to a directory called **apache-artemis-2.28.0.redhat-00022** in your current directory.

5. If the broker is running, stop it.

```
<broker_instance_dir>/bin/artemis stop
```

6. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker_instance_dir>/log/artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.18.0.redhat-00010 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```

7. Back up the instance directory of the broker by copying it to the home directory of the current user.

```
cp -r <broker_instance_dir> ~/
```

8. Change to directory to which you extracted the contents of the compressed archive.

```
cd /opt/redhat/apache-artemis-2.28.0.redhat-00022/bin
```

9. Run the **artemis upgrade** command to upgrade your existing broker. The following example upgrades a broker instance in the **/var/opt/amq-broker/mybroker** directory.

```
./artemis upgrade /var/opt/amq-broker/mybroker
```

The **artemis upgrade** command completes the following steps to upgrade the broker.

- Makes a backup of each file it modifies in an **old-config-bkp.<n>** subdirectory of the broker instance directory for the broker that you are upgrading.
- Sets the **ARTEMIS_HOME** property in the **<broker_instance_dir>/etc/artemis.profile** file to the new directory created when you extracted the archive.

- Updates the **<broker_instance_dir>bin/artemis** script to use the Apache Log4j 2 logging utility, which is bundled with AMQ Broker 7.11.x, instead of the the JBoss Logging framework used in previous versions.
 - Deletes the existing **<broker_instance_dir>/etc/logging.properties** file used by JBoss and creates a new **<broker_instance_dir>/etc/log4j2.properties** file for the Apache Log4j 2 logging utility.
10. If the Prometheus metrics plugin included with AMQ Broker is enabled in 7.10.x, change the class name of the plugin from **org.apache.activemq.artemis.core.server.metrics.plugins.ArtemisPrometheusMetricsPlugin** in to **com.redhat.amq.broker.core.server.metrics.plugins.ArtemisPrometheusMetricsPlugin**, which is the new class name of the plugin in AMQ Broker 7.11.x.
- Open the **<broker_instance_dir>/etc/broker.xml** configuration file.
 - In the **<plugin>** sub-element of the **<metrics>** element, update the plugin class name to **com.redhat.amq.broker.core.server.metrics.plugins.ArtemisPrometheusMetricsPlugin**.

```
<metrics>
  <plugin class-
name="com.redhat.amq.broker.core.server.metrics.plugins.ArtemisPrometheusMetricsPlugi
n"/>
</metrics>
```

- Save the **broker.xml** configuration file.

11. Start the upgraded broker.

```
<broker_instance_dir>/bin/artemis run
```

12. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker_instance_dir>/log/artemis.log** file. Find lines similar to the ones below. Note the new version number that appears in the log after the broker starts.

```
2023-02-08 20:53:50,128 INFO [org.apache.activemq.artemis.integration.bootstrap]
AMQ101000: Starting ActiveMQ Artemis Server version 2.28.0.redhat-00022
2023-02-08 20:53:51,077 INFO [org.apache.activemq.artemis.core.server] AMQ221001:
Apache ActiveMQ Artemis Message Broker version 2.28.0.redhat-00022 [0.0.0.0,
nodeID=be02a2b2-3e42-11ec-9b8a-4c796e887ecb]
```



NOTE

You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker_instance_dir>/etc/artemis.profile** file, update the **ARTEMIS_INSTANCE_ETC_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **etc/** and **data/** directories within the broker instance's directory.

Additional resources

- [Creating a broker instance](#)

2.9.2. Upgrading from 7.10.x to 7.11.x on Windows

Upgrade from 7.10.x to 7.11.x on Windows by downloading the new archive and running the **artemis upgrade** command.

Prerequisites

- At a minimum, AMQ Broker 7.11.x requires Java version 11 to run. Ensure that each AMQ Broker host is running Java version 11 or higher. For more information on supported configurations, see [Red Hat AMQ Broker 7 Supported Configurations](#).

Procedure

1. Follow the instructions provided in [Downloading the AMQ Broker archive](#) to download the AMQ Broker archive.
2. Use a file manager to move the archive to the folder you created during the last installation of AMQ Broker.
3. Extract the contents of the archive. Right-click the .zip file and select **Extract All**.



NOTE

The contents of the latest archive are extracted to a folder called **apache-artemis-2.28.0.redhat-00022** in the current folder.

4. If the broker is running, stop it.

```
<broker_instance_dir>\bin\artemis-service.exe stop
```

5. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker_instance_dir>\log\artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221002: Apache ActiveMQ Artemis
Message Broker version 2.18.0.redhat-00010[4782d50d-47a2-11e7-a160-9801a793ea45]
stopped, uptime 28 minutes
```

6. Back up the broker using a file manager.
 - a. Right-click the **<broker_instance_dir>** folder and select **Copy**.
 - b. Right-click in the same window and select **Paste**.
7. Change to directory to which you extracted the contents of the compressed archive. For example:

```
cd \redhat\amq-broker\apache-artemis-2.28.0.redhat-00022\bin
```

8. Run the **artemis upgrade** command to upgrade your existing broker. The following example upgrades the broker instance in the **C:\redhat\amq-broker\mybroker** directory.

```
artemis upgrade C:\redhat\amq-broker\mybroker
```

The **artemis upgrade** command completes the following steps to upgrade the broker.

- Makes a backup of each file it modifies in an **old-config-bkp.<n>** subdirectory of the broker instance directory for the broker that you are upgrading.
 - Sets the **ARTEMIS_HOME** property in the **<broker_instance_dir>\etc\artemis.cmd.profile** file to the new directory created when you extracted the archive.
 - Updates the **<broker_instance_dir>\bin\artemis.cmd** script to use the Apache Log4j 2 logging utility, which is bundled with AMQ Broker 7.11.x, instead of the the JBoss Logging framework used in previous versions.
 - Deletes the existing **<broker_instance_dir>\etc\logging.properties** file used by JBoss and creates a new **<broker_instance_dir>\etc\log4j2.properties** file for the Apache Log4j 2 logging utility.
9. If the Prometheus metrics plugin included with AMQ Broker was enabled in 7.10.x, change the class name of the plugin from **org.apache.activemq.artemis.core.server.metrics.plugins.ArtemisPrometheusMetricsPlugin** in to **com.redhat.amq.broker.core.server.metrics.plugins.ArtemisPrometheusMetricsPlugin**, which is the new class name of the plugin in 7.11.x.
- a. Open the **<broker_instance_dir>\etc\broker.xml** configuration file.
 - b. In the **<plugin>** sub-element of the **<metrics>** element, update the plugin class name to **com.redhat.amq.broker.core.server.metrics.plugins.ArtemisPrometheusMetricsPlugin**.
- ```
<metrics>
 <plugin class-
name="com.redhat.amq.broker.core.server.metrics.plugins.ArtemisPrometheusMetricsPlugi
n"/>
</metrics>
```
- c. Save the **broker.xml** configuration file.

10. Start the upgraded broker.

```
<broker_instance_dir>\bin\artemis-service.exe start
```

11. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker\_instance\_dir>\log\artemis.log** file. Find two lines similar to the ones below. Note the new version number that appears in the log when the broker is live.

```
2023-02-08 20:53:50,128 INFO [org.apache.activemq.artemis.integration.bootstrap]
AMQ101000: Starting ActiveMQ Artemis Server version 2.28.0.redhat-00022
2023-02-08 20:53:51,077 INFO [org.apache.activemq.artemis.core.server] AMQ221001:
Apache ActiveMQ Artemis Message Broker version 2.28.0.redhat-00022 [0.0.0.0,
nodeID=be02a2b2-3e42-11ec-9b8a-4c796e887ecb]
```



## NOTE

You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the `<broker_instance_dir>\etc\artemis.profile` file, update the **ARTEMIS\_INSTANCE\_ETC\_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the `\etc` and `\data` directories within the broker instance's directory.

### Additional resources

- [Creating a broker instance](#)

## 2.10. UPGRADING A BROKER INSTANCE FROM 7.11.X TO 7.12.X

Learn how to upgrade a 7.11.x broker instance to 7.12.x for different operating systems.



## IMPORTANT

Starting with AMQ Broker 7.1.0, you can access AMQ Management Console only from the local host by default. To learn about configuring remote access to the console, see [link:https://access.redhat.com/documentation/en-us/red\\_hat\\_amq\\_broker/7.13/html-single/managing\\_amq\\_broker/#proc-br-configuring-local-and-remote-access-to-console\\_managing](https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing)[Configuring local and remote access to AMQ Management Console].

### 2.10.1. Upgrading from 7.11.x to 7.12.x on Linux

Upgrade from 7.11.x to 7.12.x on Linux by downloading the new archive and running the **artemis upgrade** command.

#### Prerequisites

- At a minimum, AMQ Broker 7.12.x requires Java version 11 to run. Ensure that each AMQ Broker host is running Java version 11 or higher. For more information on supported configurations, see [Red Hat AMQ 7 Supported Configurations](#).

#### Procedure

1. Follow the instructions provided in [Downloading the AMQ Broker archive](#) to download the AMQ Broker archive.
2. Change the owner of the archive that you downloaded to the same user that owns the AMQ Broker installation to be upgraded. The following example shows a user called **amq-broker**.

```
sudo chown amq-broker:amq-broker amq-broker-7.x.x-bin.zip
```

3. Move the AMQ Broker archive to the directory created during the original installation of AMQ Broker. The following example uses **/opt/redhat**.

```
sudo mv amq-broker-7.x.x-bin.zip /opt/redhat
```

- As the directory owner, extract the contents of the compressed archive. In the following example, the user **amq-broker** extracts the archive using the **unzip** command.

```
su - amq-broker
cd /opt/redhat
unzip amq-broker-7.x.x-bin.zip
```



#### NOTE

The contents of the latest archive are extracted to a directory called **apache-artemis-2.33.0.redhat-00013** in your current directory.

- If the broker is running, stop it.

```
<broker_instance_dir>/bin/artemis stop
```

- (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker\_instance\_dir>/log/artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.28.0.redhat-00019 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```

- Back up the instance directory of the broker by copying it to the home directory of the current user.

```
cp -r <broker_instance_dir> ~/
```

- Change to directory to which you extracted the contents of the compressed archive.

```
cd /opt/redhat/apache-artemis-2.33.0.redhat-00013/bin
```

- Run the **artemis upgrade** command to upgrade your existing broker. The following example upgrades a broker instance in the **/var/opt/amq-broker/mybroker** directory.

```
./artemis upgrade /var/opt/amq-broker/mybroker
```

The **artemis upgrade** command completes the following steps to upgrade the broker.

- Makes a backup of each file it modifies in an **old-config-bkp.<n>** subdirectory of the broker instance directory for the broker that you are upgrading.
- Sets the **ARTEMIS\_HOME** property in the **<broker\_instance\_dir>/etc/artemis.profile** file to the new directory created when you extracted the archive.

- Start the upgraded broker.

```
<broker_instance_dir>/bin/artemis run
```

- (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker\_instance\_dir>/log/artemis.log** file. Find lines similar to the ones below. Note the new version number that appears in the log after the broker starts.

```
2023-02-08 20:53:50,128 INFO [org.apache.activemq.artemis.integration.bootstrap]
AMQ101000: Starting ActiveMQ Artemis Server version 2.33.0.redhat-00013
2023-02-08 20:53:51,077 INFO [org.apache.activemq.artemis.core.server] AMQ221001:
Apache ActiveMQ Artemis Message Broker version 2.33.0.redhat-00013 [0.0.0.0,
nodeID=be02a2b2-3e42-11ec-9b8a-4c796e887ecb]
```



## NOTE

You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker\_instance\_dir>\etc\artemis.profile** file, update the **ARTEMIS\_INSTANCE\_ETC\_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **\etc** and **\data** directories within the broker instance's directory.

## Additional resources

- [Creating a broker instance](#)

## 2.10.2. Upgrading from 7.11.x to 7.12.x on Windows

Upgrade from 7.11.x to 7.12.x on Windows by downloading the new archive and running the **artemis upgrade** command.

## Prerequisites

- At a minimum, AMQ Broker 7.12.x requires Java version 11 to run. Ensure that each AMQ Broker host is running Java version 11 or higher. For more information on supported configurations, see [Red Hat AMQ 7 Supported Configurations](#).

## Procedure

1. Follow the instructions provided in [Downloading the AMQ Broker archive](#) to download the AMQ Broker archive.
2. Use a file manager to move the archive to the folder you created during the last installation of AMQ Broker.
3. Extract the contents of the archive. Right-click the .zip file and select **Extract All**.



## NOTE

The contents of the latest archive are extracted to a folder called **apache-artemis-2.33.0.redhat-00013** in the current folder.

4. If the broker is running, stop it.

```
<broker_instance_dir>\bin\artemis-service.exe stop
```

5. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker\_instance\_dir>\log\artemis.log** file.

■

```
INFO [org.apache.activemq.artemis.core.server] AMQ221002: Apache ActiveMQ Artemis
Message Broker version 2.28.0.redhat-00019[4782d50d-47a2-11e7-a160-9801a793ea45]
stopped, uptime 28 minutes
```

6. Back up the broker using a file manager.
  - a. Right-click the **<broker\_instance\_dir>** folder and select **Copy**.
  - b. Right-click in the same window and select **Paste**.
7. Change to directory to which you extracted the contents of the compressed archive. For example:

```
cd \redhat\amq-broker\apache-artemis-2.33.0.redhat-00013\bin
```

8. Run the **artemis upgrade** command to upgrade your existing broker. The following example upgrades the broker instance in the **C:\redhat\amq-broker\mybroker** directory.

```
artemis upgrade C:\redhat\amq-broker\mybroker
```

The **artemis upgrade** command completes the following steps to upgrade the broker.

- Makes a backup of each file it modifies in an **old-config-bkp.<n>** subdirectory of the broker instance directory for the broker that you are upgrading.
- Sets the **ARTEMIS\_HOME** property in the **<broker\_instance\_dir>\etc\artemis.cmd.profile** file to the new directory created when you extracted the archive.

9. Start the upgraded broker.

```
<broker_instance_dir>\bin\artemis-service.exe start
```

10. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker\_instance\_dir>\log\artemis.log** file. Find two lines similar to the ones below. Note the new version number that appears in the log when the broker is live.

```
2023-02-08 20:53:50,128 INFO [org.apache.activemq.artemis.integration.bootstrap]
AMQ101000: Starting ActiveMQ Artemis Server version 2.33.0.redhat-00013
2023-02-08 20:53:51,077 INFO [org.apache.activemq.artemis.core.server] AMQ221001:
Apache ActiveMQ Artemis Message Broker version 2.33.0.redhat-00013 [0.0.0.0,
nodeID=be02a2b2-3e42-11ec-9b8a-4c796e887ecb]
```



## NOTE

You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker\_instance\_dir>\etc\artemis.profile** file, update the **ARTEMIS\_INSTANCE\_ETC\_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **\etc** and **\data** directories within the broker instance's directory.

## Additional resources

- [Creating a broker instance](#)

## 2.11. UPGRADING A BROKER INSTANCE FROM 7.12.X TO 7.13.X

Learn how to upgrade a 7.12.x broker instance to 7.13.x for different operating systems.



### IMPORTANT

Starting with AMQ Broker 7.1.0, you can access AMQ Management Console only from the local host by default. To learn about configuring remote access to the console, see [link:https://access.redhat.com/documentation/en-us/red\\_hat\\_amq\\_broker/7.13/html-single/managing\\_amq\\_broker/#proc-br-configuring-local-and-remote-access-to-console\\_managing](https://access.redhat.com/documentation/en-us/red_hat_amq_broker/7.13/html-single/managing_amq_broker/#proc-br-configuring-local-and-remote-access-to-console_managing)[Configuring local and remote access to AMQ Management Console].

### 2.11.1. Upgrading from 7.12.x to 7.13.x on Linux

Upgrade from 7.12.x to 7.13.x on Linux by downloading the new archive and running the **artemis upgrade** command.

#### Prerequisites

- At a minimum, AMQ Broker 7.13.x requires Java version 17 to run. Ensure that each AMQ Broker host is running Java version 17 or higher. For more information on supported configurations, see [Red Hat AMQ 7 Supported Configurations](#).

#### Procedure

1. Follow the instructions provided in [Downloading the AMQ Broker archive](#) to download the AMQ Broker archive.
2. Change the owner of the archive that you downloaded to the same user that owns the AMQ Broker installation to be upgraded. The following example shows a user called **amq-broker**.

```
sudo chown amq-broker:amq-broker amq-broker-7.x.x-bin.zip
```

3. Move the archive to the directory created during the original installation of AMQ Broker. The following example uses **/opt/redhat**.

```
sudo mv amq-broker-7.x.x-bin.zip /opt/redhat
```

4. As the directory owner, extract the contents of the compressed archive. In the following example, the user **amq-broker** extracts the archive using the **unzip** command.

```
su - amq-broker
cd /opt/redhat
unzip amq-broker-7.x.x-bin.zip
```



### NOTE

The contents of the latest archive are extracted to a directory called **apache-artemis-2.40.0.redhat-00003** in your current directory.

5. If the broker is running, stop it.

```
<broker_instance_dir>/bin/artemis stop
```

6. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker\_instance\_dir>/log/artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.40.0.redhat-00003 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```

7. Back up the instance directory of the broker by copying it to the home directory of the current user.

```
cp -r <broker_instance_dir> ~/
```

8. Change to directory to which you extracted the contents of the compressed archive.

```
cd /opt/redhat/apache-artemis-2.40.0.redhat-00003/bin
```

9. Run the **artemis upgrade** command to upgrade your existing broker. The following example upgrades a broker instance in the **/var/opt/amq-broker/mybroker** directory.

```
./artemis upgrade /var/opt/amq-broker/mybroker
```

The **artemis upgrade** command completes the following steps to upgrade the broker.

- Makes a backup of each file it modifies in an **old-config-bkp.<n>** subdirectory of the broker instance directory for the broker that you are upgrading.
- Sets the **ARTEMIS\_HOME** property in the **<broker\_instance\_dir>/etc/artemis.profile** file to the new directory created when you extracted the archive.

10. Start the upgraded broker.

```
<broker_instance_dir>/bin/artemis run
```

11. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker\_instance\_dir>/log/artemis.log** file. Find lines similar to the ones below. Note the new version number that is displayed in the log after the broker starts.

```
2023-02-08 20:53:50,128 INFO [org.apache.activemq.artemis.integration.bootstrap]
AMQ101000: Starting ActiveMQ Artemis Server version 2.40.0.redhat-00003
2023-02-08 20:53:51,077 INFO [org.apache.activemq.artemis.core.server] AMQ221001:
Apache ActiveMQ Artemis Message Broker version 2.40.0.redhat-00003 [0.0.0.0,
nodeID=be02a2b2-3e42-11ec-9b8a-4c796e887ecb]
```



## NOTE

You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker\_instance\_dir>/etc/artemis.profile** file, update the **ARTEMIS\_INSTANCE\_ETC\_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **etc/** and **data/** directories within the broker instance's directory.

### Additional resources

- [Creating a broker instance](#)

## 2.11.2. Upgrading from 7.12.x to 7.13.x on Windows

Upgrade from 7.12.x to 7.13.x on Windows by downloading the new archive and running the **artemis upgrade** command.

### Prerequisites

- At a minimum, AMQ Broker 7.13.x requires Java version 17 to run. Ensure that each AMQ Broker host is running Java version 17 or higher. For more information on supported configurations, see [Red Hat AMQ Broker 7 Supported Configurations](#).

### Procedure

1. Follow the instructions provided in [Downloading the AMQ Broker archive](#) to download the AMQ Broker archive.
2. Use a file manager to move the archive to the folder you created during the last installation of AMQ Broker.
3. Extract the contents of the archive. Right-click the .zip file and select **Extract All**.



## NOTE

The contents of the latest archive are extracted to a folder called **apache-artemis-2.40.0.redhat-00003** in the current folder.

4. If the broker is running, stop it.

```
<broker_instance_dir>\bin\artemis-service.exe stop
```

5. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker\_instance\_dir>\log\artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221002: Apache ActiveMQ Artemis
Message Broker version 2.40.0.redhat-00003[4782d50d-47a2-11e7-a160-9801a793ea45]
stopped, uptime 28 minutes
```

6. Back up the broker using a file manager.

- a. Right-click the **<broker\_instance\_dir>** folder and select **Copy**.
  - b. Right-click in the same window and select **Paste**.
7. Change to directory to which you extracted the contents of the compressed archive. For example:

```
cd \redhat\amq-broker\apache-artemis-2.40.0.redhat-00003\bin
```

8. Run the **artemis upgrade** command to upgrade your existing broker. The following example upgrades the broker instance in the **C:\redhat\amq-broker\mybroker** directory.

```
artemis upgrade C:\redhat\amq-broker\mybroker
```

The **artemis upgrade** command completes the following steps to upgrade the broker.

- Makes a backup of each file it modifies in an **old-config-bkp.<n>** subdirectory of the broker instance directory for the broker that you are upgrading.
  - Sets the **ARTEMIS\_HOME** property in the **<broker\_instance\_dir>\etc\artemis.cmd.profile** file to the new directory created when you extracted the archive.
9. Start the upgraded broker.

```
<broker_instance_dir>\bin\artemis-service.exe start
```

10. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker\_instance\_dir>\log\artemis.log** file. Find two lines similar to the ones below. Note the new version number that is displayed in the log when the broker is live.

```
2023-02-08 20:53:50,128 INFO [org.apache.activemq.artemis.integration.bootstrap]
AMQ101000: Starting ActiveMQ Artemis Server version 2.40.0.redhat-00003
2023-02-08 20:53:51,077 INFO [org.apache.activemq.artemis.core.server] AMQ221001:
Apache ActiveMQ Artemis Message Broker version 2.40.0.redhat-00003 [0.0.0.0,
nodeID=be02a2b2-3e42-11ec-9b8a-4c796e887ecb]
```



## NOTE


You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker\_instance\_dir>\etc\artemis.profile** file, update the **ARTEMIS\_INSTANCE\_ETC\_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **\etc** and **\data** directories within the broker instance's directory.

## Additional resources

- [Creating a broker instance](#)

## 2.12. UPGRADING A BROKER INSTANCE FROM 7.13.X TO 7.14.X

Learn how to upgrade a 7.13.x broker instance to 7.14.x for different operating systems.



### IMPORTANT

Starting with AMQ Broker 7.1.0, you can access AMQ Management Console only from the local host by default. To learn about configuring remote access to the console, see [Configuring local and remote access to AMQ Management Console](#).

## 2.12.1. Upgrading from 7.13.x to 7.14.x on Linux

Upgrade from 7.13.x to 7.14.x on Linux by downloading the new archive and running the **artemis upgrade** command.

### Prerequisites

- At a minimum, AMQ Broker 7.14.x requires Java version 17 to run. Ensure that each AMQ Broker host is running Java version 17 or higher. For more information on supported configurations, see [Red Hat AMQ 7 Supported Configurations](#).

### Procedure

- Follow the instructions provided in [Downloading the AMQ Broker archive](#) to download the AMQ Broker archive.
- Change the owner of the archive that you downloaded to the same user that owns the AMQ Broker installation to be upgraded. The following example shows a user called **amq-broker**.

```
sudo chown amq-broker:amq-broker amq-broker-7.x.x-bin.zip
```

- Move the archive to the directory created during the original installation of AMQ Broker. The following example uses **/opt/redhat**.

```
sudo mv amq-broker-7.x.x-bin.zip /opt/redhat
```

- As the directory owner, extract the contents of the compressed archive. In the following example, the user **amq-broker** extracts the archive using the **unzip** command.

```
su - amq-broker
cd /opt/redhat
unzip amq-broker-7.x.x-bin.zip
```



### NOTE

The contents of the latest archive are extracted to a directory named **apache-artemis-2.53.0.redhat-00003** in your current directory.

- If the broker is running, stop it.

```
<broker_instance_dir>/bin/artemis stop
```

- (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker\_instance\_dir>/log/artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221001: Apache ActiveMQ Artemis
Message Broker version 2.40.0.redhat-00003 [0.0.0.0, nodeId=554cce00-63d9-11e8-9808-
54ee759954c4]
```

7. Back up the instance directory of the broker by copying it to the home directory of the current user.

```
cp -r <broker_instance_dir> ~/
```

8. Change to directory to which you extracted the contents of the compressed archive.

```
cd /opt/redhat/apache-artemis-2.53.0.redhat-00003/bin
```

9. Run the **artemis upgrade** command to upgrade your existing broker. The following example upgrades a broker instance in the **/var/opt/amq-broker/mybroker** directory.

```
./artemis upgrade /var/opt/amq-broker/mybroker
```

The **artemis upgrade** command completes the following steps to upgrade the broker.

- Makes a backup of each file it modifies in an **old-config-bkp.<n>** subdirectory of the broker instance directory for the broker that you are upgrading.
- Sets the **ARTEMIS\_HOME** property in the **<broker\_instance\_dir>/etc/artemis.profile** file to the new directory created when you extracted the archive.

10. Start the upgraded broker.

```
<broker_instance_dir>/bin/artemis run
```

11. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker\_instance\_dir>/log/artemis.log** file. Find lines similar to the ones below. Note the new version number that is displayed in the log after the broker starts.

```
2023-02-08 20:53:50,128 INFO [org.apache.activemq.artemis.integration.bootstrap]
AMQ101000: Starting Apache Artemis Server version 2.53.0.redhat-00003
2023-02-08 20:53:51,077 INFO [org.apache.activemq.artemis.core.server] AMQ221001:
Apache Artemis Message Broker version 2.53.0.redhat-00003[0.0.0.0, nodeId=be02a2b2-
3e42-11ec-9b8a-4c796e887ecb]
```



## NOTE

You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker\_instance\_dir>/etc/artemis.profile** file, update the **ARTEMIS\_INSTANCE\_ETC\_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **etc/** and **data/** directories within the broker instance's directory.

## Additional resources

- [Creating a broker instance](#)

### 2.12.2. Upgrading from 7.13.x to 7.14.x on Windows

Upgrade from 7.13.x to 7.14.x on Windows by downloading the new archive and running the **artemis upgrade** command.

#### Prerequisites

- At a minimum, AMQ Broker 7.14.x requires Java version 17 to run. Ensure that each AMQ Broker host is running Java version 17 or higher. For more information on supported configurations, see [Red Hat AMQ Broker 7 Supported Configurations](#).

#### Procedure

1. Follow the instructions provided in [Downloading the AMQ Broker archive](#) to download the AMQ Broker archive.
2. Use a file manager to move the archive to the folder you created during the last installation of AMQ Broker.
3. Extract the contents of the archive. Right-click the .zip file and select **Extract All**.



#### NOTE

The contents of the latest archive are extracted to a folder called **apache-artemis-2.53.0.redhat-00003** in the current folder.

4. If the broker is running, stop it.

```
<broker_instance_dir>\bin\artemis-service.exe stop
```

5. (Optional) Note the current version of the broker. After the broker stops, you see a line similar to the one below at the end of the **<broker\_instance\_dir>\log\artemis.log** file.

```
INFO [org.apache.activemq.artemis.core.server] AMQ221002: Apache ActiveMQ Artemis
Message Broker version 2.40.0.redhat-00003 [4782d50d-47a2-11e7-a160-9801a793ea45]
stopped, uptime 28 minutes
```

6. Back up the broker using a file manager.
  - a. Right-click the **<broker\_instance\_dir>** folder and select **Copy**.
  - b. Right-click in the same window and select **Paste**.
7. Change to directory to which you extracted the contents of the compressed archive. For example:

```
cd \redhat\amq-broker\apache-artemis-2.53.0.redhat-00003\bin
```

8. Run the **artemis upgrade** command to upgrade your existing broker. The following example upgrades the broker instance in the **C:\redhat\amq-broker\mybroker** directory.

```
artemis upgrade C:\redhat\amq-broker\mybroker
```

The **artemis upgrade** command completes the following steps to upgrade the broker.

- Makes a backup of each file it modifies in an **old-config-bkp.<n>** subdirectory of the broker instance directory for the broker that you are upgrading.
- Sets the **ARTEMIS\_HOME** property in the **<broker\_instance\_dir>\etc\artemis.cmd.profile** file to the new directory created when you extracted the archive.

9. Start the upgraded broker.

```
<broker_instance_dir>\bin\artemis-service.exe start
```

10. (Optional) Confirm that the broker is running and that the version has changed. After starting the broker, open the **<broker\_instance\_dir>\log\artemis.log** file. Find two lines similar to the ones below. Note the new version number that is displayed in the log when the broker is live.

```
2023-02-08 20:53:50,128 INFO [org.apache.activemq.artemis.integration.bootstrap]
AMQ101000: Starting Apache Artemis Server version 2.53.0.redhat-00003
2023-02-08 20:53:51,077 INFO [org.apache.activemq.artemis.core.server] AMQ221001:
Apache Artemis Message Broker version 2.53.0.redhat-00003 [0.0.0.0, nodeId=be02a2b2-
3e42-11ec-9b8a-4c796e887ecb]
```



## NOTE

You can now store a broker instance's configuration files and data in any custom directory, including locations outside of the broker instance's directory. In the **<broker\_instance\_dir>\etc\artemis.profile** file, update the **ARTEMIS\_INSTANCE\_ETC\_URI** property by specifying the location of the custom directory after creating the broker instance. Previously, these configuration files and data could only be stored in the **\etc** and **\data** directories within the broker instance's directory.

## Additional resources

- [Creating a broker instance](#)

## CHAPTER 3. USING THE COMMAND LINE INTERFACE

You can interact with the message broker by using the command line interface (CLI). You can manage broker actions, configure messages, and modify users and roles through an interactive shell.

You can use the CLI to interact with the broker in a Bash or zsh shell, or a custom **artemis** shell. The same commands are available in each shell. By default, the **artemis** shell has built-in auto-completion of commands and command parameters. You can add auto-completion of the CLI commands and command parameters to a Bash or zsh shell also.

### 3.1. USING THE CLI IN AN ARTEMIS SHELL

The **artemis** shell interface provides auto-completion of commands and parameters that are available with the **artemis** command. The shell remembers your broker URI and credentials for subsequent commands that you run in the same shell session.

#### Procedure

1. Switch to the user account you created during installation, for example:

```
$ su - amq-broker
```

2. Use the **artemis** command to start the shell, for example:

```
$ /var/opt/amq-broker/mybroker/bin/artemis
```

If you want to supply the broker connection details when you start an **artemis** shell, use the **artemis shell** command. For example:

```
$ /var/opt/amq-broker/mybroker/bin/artemis shell --user myuser --password mypassword --url tcp://localhost:61616
```

The credentials and URI provided are reused for any subsequent command run in the shell that requires authentication with a broker.

3. Press Tab to display auto-completion information anywhere in the shell. For example:
  - To display a list of commands available in the **artemis** shell, press Tab at the shell prompt.
  - To display sub-commands for a command, press Tab after the command. For example, type **check** and press Tab to display the sub-commands for the **check** command. The auto-completion information shows that the **check** command supports three sub-commands: **cluster**, **node** and **queue**.
  - To display auto-completion information for a sub-command, press Tab after the sub-command. For example, type **check node** and press Tab. If no further auto-completion information is displayed, type **--**, for example, **check node --**, and press Tab to display the parameters available for the command.

### 3.2. ENABLING AUTO-COMPLETION IN A BASH OR ZSH SHELL

You can enable auto-completion of CLI commands and command parameters in a Bash or Zsh shell.

## Procedure

1. Switch to the user account you created during installation, for example:

```
$ su - amq-broker
```

2. Use the following command to create a command auto-completion script called **auto-complete-artemis.sh**.

```
$ /var/opt/amq-broker/mybroker/bin/artemis auto-complete
```

3. To run the **auto-complete-artemis.sh**, use the following command:

```
$ source /var/opt/amq-broker/mybroker/bin/artemis/auto-complete-artemis.sh
```

4. To view auto-completion information for the **artemis** command, type **/var/opt/amq-broker/mybroker/artemis** and press Tab. A list of commands available for the **artemis** command is displayed.
5. To view auto-completion information for an available command, press Tab after the command. For example, type **/var/opt/amq-broker/mybroker/artemis check node** and press Tab. If no further auto-completion information is displayed, type **--**, for example, **check node --**, and press Tab to display the parameters available for the command.

## 3.3. STARTING BROKER INSTANCES

A broker instance is a directory that contains all the configuration and runtime data, such as logs and data files. The runtime data is associated with a unique broker process. You can start a broker in the foreground by using the **artemis** script, as a Linux service, or as a Windows service.

### 3.3.1. Starting the broker instance

After the broker instance is created, you use the **artemis run** command to start it.

## Procedure

1. Switch to the user account you created during installation.

```
$ su - amq-broker
```

2. Use the **artemis run** command to start the broker instance.

```
$ /var/opt/amq-broker/mybroker/bin/artemis run
```

```

 ^ | V | _ \ | _ \ | | |
 / \ \ / | | | | | | | | |
 / \ \ | | | | | | | | |
 / \ \ | | | | | | | | |
 / \ \ | | | | | | | | |
 / \ \ | | | | | | | | |

```

```
Red Hat JBoss AMQ 7.2.1.GA
```

```

10:53:43,959 INFO [org.apache.activemq.artemis.integration.bootstrap] AMQ101000:
Starting Apache Artemis Server
10:53:44,076 INFO [org.apache.activemq.artemis.core.server] AMQ221000: live Message
Broker is starting with configuration Broker Configuration
(clustered=false,journalDirectory=./data/journal,bindingsDirectory=./data/bindings,largeMessage
sDirectory=./data/large-messages,pagingDirectory=./data/paging)
10:53:44,099 INFO [org.apache.activemq.artemis.core.server] AMQ221012: Using AIO
Journal
...

```

The broker starts and displays log output with the following information:

- The location of the transaction logs and cluster configuration.
- The type of journal being used for message persistence (AIO in this case).
- The URI(s) that can accept client connections.  
By default, port 61616 can accept connections from any of the supported protocols (CORE, MQTT, AMQP, STOMP, HORNETQ, and OPENWIRE). There are separate, individual ports for each protocol as well.
- The web console is available at <http://localhost:8161>.
- The Jolokia service (JMX over REST) is available at <http://localhost:8161/jolokia>.

### 3.3.2. Starting a broker as a Linux service

If the broker is installed on Linux, you can run it as a service.

#### Procedure

1. Create a new **amq-broker.service** file in the **/etc/systemd/system/** directory.
2. Copy the following text into the file.  
Modify the path and user fields according to the information provided during the broker instance creation. In the example below, the user **amq-broker** starts the broker service installed under the **/var/opt/amq-broker/mybroker/** directory.

```

[Unit]
Description=AMQ Broker
After=syslog.target network.target

[Service]
ExecStart=/var/opt/amq-broker/mybroker/bin/artemis run
Restart=on-failure
User=amq-broker
Group=amq-broker

A workaround for Java signal handling
SuccessExitStatus=143

[Install]
WantedBy=multi-user.target

```

3. Open a terminal.

4. Enable the broker service using the following command:

```
sudo systemctl enable amq-broker
```

5. Run the broker service using the following command:

```
sudo systemctl start amq-broker
```

### 3.3.3. Starting a broker as a Windows service

If the broker is installed on Windows, you can run it as a service.

#### Procedure

1. Open a command prompt to enter the commands
2. Install the broker as a service with the following command:

```
<broker_instance_dir>\bin\artemis-service.exe install
```

3. Start the service by using the following command:

```
<broker_instance_dir>\bin\artemis-service.exe start
```

4. (Optional) Uninstall the service:

```
<broker_instance_dir>\bin\artemis-service.exe uninstall
```

## 3.4. STOPPING BROKER INSTANCES

You can stop a broker instance manually for immediate shutdown, or configure it to shut down gracefully to allow active connections to close.

### 3.4.1. Stopping the broker instance

You can stop the broker instance manually using the **artemis stop** command. This action forcefully closes all client connections.

In a production environment, you should configure the broker to stop gracefully so that client connections can be closed properly.

#### Procedure

- Use the **artemis stop** command to stop the broker instance:

```
$ /var/opt/amq-broker/mybroker/bin/artemis stop
2018-12-03 14:37:30,630 INFO [org.apache.activemq.artemis.core.server] AMQ221002:
Apache Artemis Message Broker version 2.6.1.amq-720004-redhat-1 [b6c244ef-f1cb-11e8-
a2d7-0800271b03bd] stopped, uptime 35 minutes
Server stopped!
```

### 3.4.2. Stopping a broker instance gracefully

Configure a graceful shutdown to allow existing clients to disconnect before the broker stops. This prevents forceful disconnection of active clients.

Configure a graceful shutdown by using the **graceful-shutdown-enabled** configuration element to allow existing clients to disconnect before the broker stops.

When **graceful-shutdown-enabled** is set to **true**, no new client connections are allowed after a **stop** command is entered. However, existing connections are allowed to close on the client-side before the shutdown process is started. The default value for **graceful-shutdown-enabled** is **false**.

Use the **graceful-shutdown-timeout** configuration element to set a length of time, in milliseconds, for clients to disconnect before connections are forcefully closed from the broker side. After all connections are closed, the shutdown process is started. One advantage of using **graceful-shutdown-timeout** is that it prevents client connections from delaying a shutdown. The default value for **graceful-shutdown-timeout** is **-1**, meaning the broker waits indefinitely for clients to disconnect.

The following procedure demonstrates how to configure a graceful shutdown that uses a timeout.

#### Procedure

1. Open the configuration file **<broker\_instance\_dir>\etc\broker.xml**.
2. Add the **graceful-shutdown-enabled** configuration element and set the value to **true**.

```
<configuration>
 <core>
 ...
 <graceful-shutdown-enabled>
 true
 </graceful-shutdown-enabled>
 ...
 </core>
</configuration>
```

3. Add the **graceful-shutdown-timeout** configuration element and set a value for the timeout in milliseconds. In the following example, client connections are forcefully closed 30 seconds (**30000** milliseconds) after the **stop** command is issued.

```
<configuration>
 <core>
 ...
 <graceful-shutdown-enabled>
 true
 </graceful-shutdown-enabled>
 <graceful-shutdown-timeout>
 30000
 </graceful-shutdown-timeout>
 ...
 </core>
</configuration>
```

## 3.5. AUDITING MESSAGES BY INTERCEPTING PACKETS

You can use interceptors to audit or filter packets entering or exiting the broker. Interceptors can modify packets, so use them carefully to avoid unintended side effects.

Develop interceptors to meet your business requirements. Interceptors are protocol specific and must implement the appropriate interface.

Interceptors must implement the **intercept()** method, which returns a boolean value. If the value is **true**, the message packet continues onward. If **false**, the process is aborted, no other interceptors are called, and the message packet is not processed further.

### 3.5.1. Creating interceptors

Create custom incoming and outgoing interceptors to audit or modify packets. You must implement the appropriate protocol-specific interface for your needs.

Interceptors and their dependencies must be placed in the Java classpath of the broker. You can use the **<broker\_instance\_dir>/lib** directory because it is part of the classpath by default.

The following examples demonstrate how to create an interceptor that checks the size of each packet passed to it.



#### NOTE

The examples implement a specific interface for each protocol.

#### Procedure

1. Implement the appropriate interface and override its **intercept()** method.
  - a. If you are using the AMQP protocol, implement the **org.apache.activemq.artemis.protocol.amqp.broker.AmqpInterceptor** interface.

```
package com.example;

import org.apache.activemq.artemis.protocol.amqp.broker.AMQPMessage;
import org.apache.activemq.artemis.protocol.amqp.broker.AmqpInterceptor;
import org.apache.activemq.artemis.spi.core.protocol.RemotingConnection;

public class MyInterceptor implements AmqpInterceptor
{
 private final int ACCEPTABLE_SIZE = 1024;

 @Override
 public boolean intercept(final AMQPMessage message, RemotingConnection
connection)
 {
 int size = message.getEncodeSize();
 if (size <= ACCEPTABLE_SIZE) {
 System.out.println("This AMQPMessage has an acceptable size.");
 return true;
 }
 return false;
 }
}
```

- b. If you are using Core Protocol, your interceptor must implement the **org.apache.artemis.activemq.api.core.Interceptor** interface.

```
package com.example;

import org.apache.artemis.activemq.api.core.Interceptor;
import org.apache.activemq.artemis.core.protocol.core.Packet;
import org.apache.activemq.artemis.spi.core.protocol.RemotingConnection;

public class MyInterceptor implements Interceptor
{
 private final int ACCEPTABLE_SIZE = 1024;

 @Override
 boolean intercept(Packet packet, RemotingConnection connection)
 throws ActiveMQException
 {
 int size = packet.getPacketSize();
 if (size <= ACCEPTABLE_SIZE) {
 System.out.println("This Packet has an acceptable size.");
 return true;
 }
 return false;
 }
}
```

- c. If you are using the MQTT protocol, implement the **org.apache.activemq.artemis.core.protocol.mqtt.MQTTInterceptor** interface.

```
package com.example;

import org.apache.activemq.artemis.core.protocol.mqtt.MQTTInterceptor;
import io.netty.handler.codec.mqtt.MqttMessage;
import org.apache.activemq.artemis.spi.core.protocol.RemotingConnection;

public class MyInterceptor implements Interceptor
{
 private final int ACCEPTABLE_SIZE = 1024;

 @Override
 boolean intercept(MqttMessage mqttMessage, RemotingConnection connection)
 throws ActiveMQException
 {
 byte[] msg = (mqttMessage.toString()).getBytes();
 int size = msg.length;
 if (size <= ACCEPTABLE_SIZE) {
 System.out.println("This MqttMessage has an acceptable size.");
 return true;
 }
 return false;
 }
}
```

- d. If you are using the STOMP protocol, implement the **org.apache.activemq.artemis.core.protocol.stomp.StompFrameInterceptor** interface.

```

package com.example;

import org.apache.activemq.artemis.core.protocol.stomp.StompFrameInterceptor;
import org.apache.activemq.artemis.core.protocol.stomp.StompFrame;
import org.apache.activemq.artemis.spi.core.protocol.RemotingConnection;

public class MyInterceptor implements Interceptor
{
 private final int ACCEPTABLE_SIZE = 1024;

 @Override
 boolean intercept(StompFrame stompFrame, RemotingConnection connection)
 throws ActiveMQException
 {
 int size = stompFrame.getEncodedSize();
 if (size <= ACCEPTABLE_SIZE) {
 System.out.println("This StompFrame has an acceptable size.");
 return true;
 }
 return false;
 }
}

```

### 3.5.2. Configuring the broker to use interceptors

Register your custom interceptor classes in the **broker.xml** configuration file to enable them for incoming or outgoing traffic.

#### Prerequisites

- Create an interceptor class and add it (and its dependencies) to the Java classpath of the broker. You can use the **<broker\_instance\_dir>/lib** directory since it is part of the classpath by default.

#### Procedure

1. Open **<broker\_instance\_dir>/etc/broker.xml**
2. Configure the broker to use an interceptor by adding configuration to **<broker\_instance\_dir>/etc/broker.xml**
  - a. If the interceptor is intended for incoming messages, add its **class-name** to the list of **remoting-incoming-interceptors**.

```

<configuration>
 <core>
 ...
 <remoting-incoming-interceptors>
 <class-name>org.example.MyIncomingInterceptor</class-name>
 </remoting-incoming-interceptors>
 ...
 </core>
</configuration>

```

- b. If the interceptor is intended for outgoing messages, add its **class-name** to the list of **remoting-outgoing-interceptors**.

```
<configuration>
 <core>
 ...
 <remoting-outgoing-interceptors>
 <class-name>org.example.MyOutgoingInterceptor</class-name>
 </remoting-outgoing-interceptors>
 </core>
</configuration>
```

### 3.5.3. Interceptors on the client side

Implement client-side interceptors to process packets sent to or received from the server. If an interceptor returns a **false** value, processing stops.

If an an interceptor returns a **false** value, processing stops transparently unless an outgoing packet is sent in a **blocking** fashion. In this case, an **ActiveMQException** is thrown to the caller. The **ActiveMQException** thrown contains the name of the interceptor that returned the **false** value.

On the server, the client interceptor classes and their dependencies must be added to the Java classpath of the client, to be properly instantiated and invoked.

## 3.6. CHECKING THE HEALTH OF BROKERS, QUEUES AND THE CLUSTER

Use the command-line utility to perform health checks on brokers, queues, and cluster topologies to ensure your system is operating correctly.

### Procedure

1. See the list of checks that you can run for a particular broker (that is, *node*) in your broker topology.

```
$ <broker_instance_dir>/bin/artemis help check node
```

You see output that describes the set of options that you can use with the **artemis check node** command.

```
NAME
 artemis check node - Check a node

SYNOPSIS
 artemis check node [--backup] [--clientID <clientID>]
 [--diskUsage <diskUsage>] [--fail-at-end] [--live]
 [--memoryUsage <memoryUsage>] [--name <name>] [--password <password>]
 [--peers <peers>] [--protocol <protocol>] [--silent]
 [--timeout <timeout>] [--up] [--url <brokerURL>] [--user <user>]
 [--verbose]

OPTIONS
 --backup
```

Check that the node has a backup

--clientID <clientID>

ClientID to be associated with connection

--diskUsage <diskUsage>

Disk usage percentage to check or -1 to use the max-disk-usage

--fail-at-end

If a particular module check fails, continue the rest of the checks

--live

Check that the node has a live

--memoryUsage <memoryUsage>

Memory usage percentage to check

--name <name>

Name of the target to check

--password <password>

Password used to connect

--peers <peers>

Number of peers to check

--protocol <protocol>

Protocol used. Valid values are amqp or core. Default=core.

--silent

It will disable all the inputs, and it would make a best guess **for** any required input

--timeout <timeout>

Time to wait **for** the check execution, **in** milliseconds

--up

Check that the node is started, it is executed by default **if** there are no other checks

--url <brokerURL>

URL towards the broker. (default: tcp://localhost:61616)

--user <user>

User used to connect

--verbose

Adds more information on the execution

- For example, check that the disk usage of the local broker is below the maximum disk usage configured for the broker.

```
$ <broker_instance_dir>/bin/artemis check node --url tcp://localhost:61616 --diskUsage -1
```

Connection brokerURL = tcp://localhost:61616

Running NodeCheck

Checking that the disk usage is less **than** the max-disk-usage ... success

Checks run: 1, Failures: 0, Errors: 0, Skipped: 0, Time elapsed: 0.065 sec - NodeCheck

In the preceding example, specifying a value of **-1** for the **--diskUsage** option means that the utility checks disk usage against the **maximum** disk usage configured for the broker. The maximum disk usage of a broker is configured using the **max-disk-usage** parameter in the **broker.xml** configuration file. The value specified for **max-disk-usage** represents the percentage of available physical disk space that the broker is allowed to consume.

3. See the list of checks that you can run for a particular queue in your broker topology.

```
$ <broker_instance_dir>/bin/artemis help check queue
```

You see output that describes the set of options that you can use with the **artemis check queue** command.

#### NAME

artemis check queue - Check a queue

#### SYNOPSIS

```
artemis check queue [--browse <browse>] [--clientID <clientID>]
 [--consume <consume>] [--fail-at-end] [--name <name>]
 [--password <password>] [--produce <produce>] [--protocol <protocol>]
 [--silent] [--timeout <timeout>] [--up] [--url <brokerURL>]
 [--user <user>] [--verbose]
```

#### OPTIONS

```
--browse <browse>
 Number of the messages to browse or -1 to check that the queue is
 browsable

--clientID <clientID>
 ClientID to be associated with connection

--consume <consume>
 Number of the messages to consume or -1 to check that the queue is consumable

--fail-at-end
 If a particular module check fails, continue the rest of the checks

--name <name>
 Name of the target to check

--password <password>
 Password used to connect

--produce <produce>
 Number of the messages to produce

--protocol <protocol>
 Protocol used. Valid values are amqp or core. Default=core.

--silent
 It will disable all the inputs, and it would make a best guess for any required input

--timeout <timeout>
 Time to wait for the check execution, in milliseconds
```

**--up**

Check that the queue exists and is not paused, it is executed by default **if** there are no other checks

**--url <brokerURL>**

URL towards the broker. (default: tcp://localhost:61616)

**--user <user>**

User used to connect

**--verbose**

Adds more information on the execution

4. The utility can execute multiple options with a single command. For example, to check production, browsing, and consumption of 1000 messages on the default **helloworld** queue on the local broker, use the following command:

```
$ <broker_instance_dir>/bin/artemis check queue --name helloworld --produce 1000 --
browse 1000 --consume 1000
```

Connection brokerURL = tcp://localhost:61616

Running QueueCheck

Checking that a producer can send 1000 messages to the queue helloworld ... success

Checking that a consumer can browse 1000 messages from the queue helloworld ... success

Checking that a consumer can consume 1000 messages from the queue helloworld ...

success

Checks run: 3, Failures: 0, Errors: 0, Skipped: 0, Time elapsed: 2.882 sec - QueueCheck

In the preceding example, observe that you did not specify a broker URL when running the queue check. If you do not explicitly specify a URL, the utility uses a default value of **tcp://localhost:61616**.

5. If your brokers are clustered, see the list of checks that you can run for the cluster topology.

```
$ <broker_instance_dir>/bin/artemis help check cluster
```

You see output that describes the set of options that you can use with the **artemis check cluster** command.

## NAME

artemis check cluster - Verify **if** all the nodes on the cluster match the same topology and time configuration.

## SYNOPSIS

```
artemis check cluster [--acceptor=<acceptor>]
 [--clientID=<clientID>] [--password=<password>]
 [--protocol=<protocol>] [--silent] [--url=<brokerURL>]
 [--user=<user>] [--variance=<variance>] [--verbose]
```

## OPTIONS

**--acceptor=<acceptor>**

Name used to find the default connection URL on the acceptor list. If an acceptor with that name cannot be found, the command looks **for** a connector with the same name.

```

--clientID <clientID>
 ClientID to be associated with connection.

--password <password>
 Password used to connect.

--protocol <protocol>
 Protocol used. Valid values are amqp or core. Default=core.

--silent
 Disables all the input options and make a best guess for any required input.

--url <brokerURL>
 URL of the broker (default: tcp://localhost:61616).

--user <user>
 User used to connect.

--variance <variance>
 Allowed time variance in milliseconds after which check is deemed to have failed
 (default=1000).

--verbose
 Adds more information on the execution.

```

## 3.7. COMMAND LINE TOOLS

Use the provided command-line interface (CLI) tools to manage your messaging journal, including data export, import, and maintenance tasks.

The following table describes the purpose of each tool.

**Table 3.1. Command line tools**

Tool	Description
address	Addresses tool groups (create/delete/update/show) (example <b>./artemis address create</b> ).
browser	Browses messages on an instance.
consumer	Consumes messages on an instance.
data	Prints reports about journal records and compacts the data.
decode	Imports the internal journal format from encode.
encode	Shows an internal format of the journal encoded to String.
exp	Exports the message data using a special and independent XML format.

Tool	Description
help	Displays help information.
imp	Imports the journal to a running broker using the output provided by <b>exp</b> .
kill	Kills a broker instance started with <code>--allow-kill</code> .
mask	Masks a password and prints it out.
perf-journal	Calculates the journal-buffer timeout you should use with the current data folder.
queue	Queues tool groups (create/delete/update/stat) (example <code>./artemis queue create</code> ).
run	Runs the broker instance.
stop	Stops the broker instance.
user	Default file-based user managment (add/rm/list/reset) (example <code>./artemis user list</code> )

For a full list of commands available for each tool, use the **help** parameter followed by the tool's name. For instance, in the example below, the CLI output lists all the commands available to the **data** tool after the user enters the command `./artemis help data`.

```
$./artemis help data
```

## NAME

```
artemis data - data tools group
(print|imp|exp|encode|decode|compact) (example ./artemis data print)
```

## SYNOPSIS

```
artemis data
artemis data compact [--broker <brokerConfig>] [--verbose]
 [--paging <paging>] [--journal <journal>]
 [--large-messages <largeMessges>] [--bindings <binding>]
artemis data decode [--broker <brokerConfig>] [--suffix <suffix>]
 [--verbose] [--paging <paging>] [--prefix <prefix>] [--file-size <size>]
 [--directory <directory>] --input <input> [--journal <journal>]
 [--large-messages <largeMessges>] [--bindings <binding>]
artemis data encode [--directory <directory>] [--broker <brokerConfig>]
 [--suffix <suffix>] [--verbose] [--paging <paging>] [--prefix <prefix>]
 [--file-size <size>] [--journal <journal>]
 [--large-messages <largeMessges>] [--bindings <binding>]
artemis data exp [--broker <brokerConfig>] [--verbose]
 [--paging <paging>] [--journal <journal>]
 [--large-messages <largeMessges>] [--bindings <binding>]
artemis data imp [--host <host>] [--verbose] [--port <port>]
 [--password <password>] [--transaction] --input <input> [--user <user>]
artemis data print [--broker <brokerConfig>] [--verbose]
 [--paging <paging>] [--journal <journal>]
 [--large-messages <largeMessges>] [--bindings <binding>]
```

**COMMANDS**

With no arguments, Display help information

**print**

Print data records information (WARNING: don't use while a production server is running)

...

You can use the **help** parameter for more information on how to execute each of the commands. For example, the CLI lists more information about the **data print** command after the user enters the **./artemis help data print**.

```
$./artemis help data print
```

**NAME**

artemis data print - Print data records information (WARNING: don't use while a production server is running)

**SYNOPSIS**

```
artemis data print [--bindings <binding>] [--journal <journal>]
 [--paging <paging>]
```

**OPTIONS**

**--bindings <binding>**

The folder used for bindings (default ../data/bindings)

**--journal <journal>**

The folder used for messages journal (default ../data/journal)

**--paging <paging>**

The folder used for paging (default ../data/paging)

## CHAPTER 4. USING AMQ MANAGEMENT CONSOLE

You can manage your AMQ Broker installation in a web browser by using AMQ Management Console, which is included in the AMQ Broker installation.

AMQ Management Console is based on [hawtio](#).

### 4.1. OVERVIEW

AMQ Broker is a full-featured, message-oriented middleware broker. It offers specialized queuing behaviors, message persistence, and manageability. It supports multiple protocols and client languages, freeing you to use many of your application assets.

AMQ Broker's key features allow you to:

- monitor your AMQ brokers and clients
  - view the topology
  - view network health at a glance
- manage AMQ brokers using:
  - AMQ Management Console
  - Command-line Interface (CLI)
  - Management API

The supported web browsers for AMQ Management Console are Firefox and Chrome. For more information on supported browser versions, see [AMQ 7 Supported Configurations](#).

### 4.2. CONFIGURING LOCAL AND REMOTE ACCESS TO AMQ MANAGEMENT CONSOLE

Configure the broker to allow access to the AMQ Management Console from local or remote hosts.

Remote access to the console can take one of two forms:

- Within a console session on a local broker, you use the **Connect** tab to connect to another, remote broker
- From a remote host, you connect to the console for the local broker, using an externally-reachable IP address for the local broker

#### Prerequisites

- You must upgrade to at least AMQ Broker 7.1.0. As part of this upgrade, an access-management configuration file named **jolokia-access.xml** is added to the broker instance. For more information about upgrading, see [Upgrading a Broker instance from 7.0.x to 7.1.0](#).

#### Procedure

1. Open the **<broker\_instance\_dir>/etc/bootstrap.xml** file.

2. Within the **web** element, observe that the web port is bound only to **localhost** by default.

```
<web path="web">
 <binding uri="http://localhost:8161">
 <app url="redhat-branding" war="redhat-branding.war"/>
 <app url="artemis-plugin" war="artemis-plugin.war"/>
 <app url="dispatch-hawtio-console" war="dispatch-hawtio-console.war"/>
 <app url="console" war="console.war"/>
 </binding>
</web>
```

3. To enable connection to the console for the local broker from a remote host, change the web port binding to a network-reachable interface. For example:

```
<web path="web">
 <binding uri="http://0.0.0.0:8161">
```

In the preceding example, by specifying **0.0.0.0**, you bind the web port to **all** interfaces on the local broker.

4. Save the **bootstrap.xml** file.
5. Open the **<broker\_instance\_dir>/etc/jolokia-access.xml** file.
6. Within the **<cors>** (that is, *Cross-Origin Resource Sharing*) element, add an **allow-origin** entry for each HTTP origin request header that you want to allow to access the console. For example:

```
<cors>
 <allow-origin>*://localhost*</allow-origin>
 <allow-origin>*://192.168.0.49*</allow-origin>
 <allow-origin>*://192.168.0.51*</allow-origin>
 <!-- Check for the proper origin on the server side, too -->
 <strict-checking/>
</cors>
```


In the preceding configuration, you specify that the following connections are allowed:

- Connection from the local host (that is, the host machine for your local broker instance) to the console.
  - The first asterisk (\*) wildcard character allows either the **http** or **https** scheme to be specified in the connection request, based on whether you have configured the console for secure connections.
  - The second asterisk wildcard character allows any port on the host machine to be used for the connection.
- Connection from a remote host to the console for the local broker, using the externally-reachable IP address of the local broker. In this case, the externally-reachable IP address of the local broker is **192.168.0.49**.
- Connection from within a console session opened on another, remote broker to the local broker. In this case, the IP address of the remote broker is **192.168.0.51**.

7. Save the **jolokia-access.xml** file.

8. Open the `<broker_instance_dir>/etc/artemis.profile` file.
9. To enable the **Connect** tab in the console, set the value of the **Dhawtio.disableProxy** argument to **false**.

```
-Dhawtio.disableProxy=false
```



#### IMPORTANT

It is recommended that you enable remote connections from the console (that is, set the value of the **Dhawtio.disableProxy** argument to **false**) **only** if the console is exposed to a secure network.

10. Add a new argument, **Dhawtio.proxyWhitelist**, to the **JAVA\_ARGS** list of Java system arguments. As a comma-separated list, specify IP addresses for any remote brokers that you want to connect to from the local broker (that is, by using the **Connect** tab within a console session running on the local broker). For example:

```
-Dhawtio.proxyWhitelist=192.168.0.51
```

Based on the preceding configuration, you can use the **Connect** tab within a console session on the local broker to connect to another, remote broker with an IP address of **192.168.0.51**.

11. Save the **artemis.profile** file.

#### Additional resources

- [Section 4.3, “Accessing AMQ Management Console”](#)
- [W3C Recommendations](#)
- [Jolokia Protocols](#)
- [Section 4.4.3, “Securing network access to AMQ Management Console”](#)

## 4.3. ACCESSING AMQ MANAGEMENT CONSOLE

You can access the console from a local or remote host, and connect to other brokers within the console session.

- Open a console instance for the local broker from a remote host using the externally-reachable IP address of the local broker

#### Prerequisites

- You must have already configured local and remote access to the console. For more information, see [Section 4.2, “Configuring local and remote access to AMQ Management Console”](#).

#### Procedure

1. In your web browser, navigate to the console address for the local broker.  
The console address is **http://<host:port>/console/login**. If you are using the default address,

navigate to <http://localhost:8161/console/login>. Otherwise, use the values of host and port that are defined for the **bind** attribute of the **web** element in the **<broker\_instance\_dir>/etc/bootstrap.xml** configuration file.

2. Log in to AMQ Management Console using the default user name and password that you created when you created the broker.
3. To connect to another, remote broker from the console session of the local broker:

- a. In the left menu, click the **Connect** tab.
- b. In the main pane, on the **Remote** tab, click the **Add connection** button.
- c. In the **Add Connection** dialog box, specify the following details:

**Name**

Name for the remote connection, for example, **my\_other\_broker**.

**Scheme**

Protocol to use for the remote connection. Select **http** for a non-secured connection, or **https** for a secured connection.

**Host**

IP address of a remote broker. You must have already configured console access for this remote broker.

**Port**

Port on the local broker to use for the remote connection. Specify the port value that is defined for the **bind** attribute of the **web** element in the **<broker\_instance\_dir>/etc/bootstrap.xml** configuration file. The default value is **8161**.

**Path**

Path to use for console access. Specify **console/jolokia**.

- d. To test the connection, click the **Test Connection** button.  
If the connection test is successful, click the **Add** button. If the connection test fails, review and modify the connection details as needed. Test the connection again.
  - e. On the **Remote** page, for a connection that you have added, click the **Connect** button.  
A new web browser tab opens for the console instance on the remote broker.
  - f. In the **Log In** dialog box, enter the user name and password for the remote broker. Click **Log In**.  
The console instance for the remote broker opens.
4. To connect to the console for the local broker from a remote host, specify the Jolokia endpoint for the local broker in a web browser. This endpoint includes the externally-reachable IP address that you specified for the local broker when configuring remote console access. For example:

**|** <http://192.168.0.49/console/jolokia>

## 4.4. CONFIGURING AMQ MANAGEMENT CONSOLE

Configure authentication and authorization settings for the AMQ Management Console to control user access to broker resources.

#### 4.4.1. Securing AMQ Management Console using Red Hat Single Sign-On

You can configure Hawtio to use an OpenID Connect provider, such as Red Hat Single Sign-On, to manage authentication for AMQ Management Console.

##### Prerequisites

- Red Hat Single Sign-On

##### Procedure

1. Configure Red Hat Single Sign-On:
  - a. Navigate to the realm in Red Hat Single Sign-On that you want to use for securing AMQ Management Console. Each realm in Red Hat Single Sign-On includes a client named **Broker**. This client is not related to AMQ.
  - b. Create a new client in Red Hat Single Sign-On, for example **amq-console**.
  - c. Navigate to the client settings page and set:
    - **Valid Redirect URIs** to the AMQ Management Console URL followed by `*`, for example:  
`https://broker.example.com:8161/console/*`
    - **Web Origins** to the same value as **Valid Redirect URIs**. Red Hat Single Sign-On allows you enter `+`, indicating that allowed CORS origins includes the value for **Valid Redirect URIs**.
  - d. Create a role for the client, for example **amq**.
  - e. Make sure all users who require access to AMQ Management Console are assigned the above role, for example, using Red Hat Single Sign-On groups.
2. Configure the AMQ Broker instance to integrate with Red Hat Single Sign-On by using the generic OpenID Connect support in Hawtio.
  - a. Create a `<broker-instance-dir>/etc/hawtio-oidc.properties` file and specify the details required by the broker to use Red Hat Single Sign-On for authentication. For example:

```
name = RHSSO
provider = https://rhssso-host:18080/realms/amq-console
client_id = amq
redirect_uri = https://broker.example.com:8161/console
response_mode = fragment
scope = openid email profile
code_challenge_method = S256
prompt = login
oidc.cacheConfig = true
jwks.cacheTime = 60
oidc.userPath = preferred_username
oidc.rolesPath = realm_access.roles
http.connectionTimeout = 5000
http.readTimeout = 10000
```

For more information about the supported configuration options in the **hawtio-oidc.properties** file, see the [Hawtio documentation](#).

- b. If you specify role names for the client in the Red Hat Single Sign-On realm that do not match roles configured in (brokername) security settings, create a mapping between the roles in the **hawtio-oidc.properties** file.

The following example creates a mapping between an **ssoadmin** role configured in the Red Hat Single Sign-On realm and the **amq** role on the broker.

```
roleMapping.ssoadmin = amq
```



#### NOTE

Ensure that all roles that require permission to log in to AMQ Management Console are added to the HAWTIO\_ROLES variable in the **<broker-instance-dir>/etc/artemis.profile** file. You can replace the list of role names in the **HAWTIO\_ROLES** variable with a wildcard asterisk (\*) to grant all roles permission to log in to the console.

3. Edit the **<broker-instance-dir>/etc/broker.xml** file and assign permissions to a role configured on the broker. For example:

```
<security-setting match="Info">
 <permission roles="amq" type="createDurableQueue"/>
 <permission roles="amq" type="deleteDurableQueue"/>
 <permission roles="amq" type="createNonDurableQueue"/>
 <permission roles="amq" type="deleteNonDurableQueue"/>
 <permission roles="amq" type="send"/>
 <permission roles="amq" type="consume"/>
</security-setting>
```

4. Run the AMQ Broker instance and validate AMQ Management Console configuration.

### 4.4.2. Setting up user access to AMQ Management Console

You can configure user access to the AMQ Management Console by using guest, basic, or LDAP authentication methods.

The following table describes the different methods you can use to grant users access to the AMQ Management Console:

**Table 4.1. Methods to grant users access to AMQ Management Console**

Authentication Method	Description
Guest authentication	Enables anonymous access. In this configuration, any user who connects without credentials or with the wrong credentials will be authenticated automatically and assigned a specific user and role.   For more information, see <a href="#">Configuring guest access</a> in <i>Configuring AMQ Broker</i>.

Authentication Method	Description
Basic user and password authentication	For each user, you must define a username and password and assign a security role. Users can only log into AMQ Management Console using these credentials.   For more information, see <a href="#">Configuring basic user and password authentication</a> in <i>Configuring AMQ Broker</i>.
LDAP authentication	Users are authenticated and authorized by checking the credentials against user data stored in a central X.500 directory server.   For more information, see <a href="#">Configuring LDAP to authenticate clients</a> in <i>Configuring AMQ Broker</i>.

### 4.4.3. Securing network access to AMQ Management Console

You can secure network access to the AMQ Management Console by using SSL/TLS to encrypt traffic over a WAN or the internet.

#### Prerequisites

The following should be located in the `<broker_instance_dir>/etc/` directory:

- Java key store
- Java trust store (needed only if you require client authentication)

#### Procedure

1. Open the `<broker_instance_dir>/etc/bootstrap.xml` file.
2. In the `<web>` element, add the following attributes:

```
<web path="web">
 <binding uri="https://0.0.0.0:8161" keyStorePath="<path_to_keystore>"
keyStorePassword="<password>"
 clientAuth="<true/false>" trustStorePath="<path_to_truststore>" trustStorePassword="
<password>">
 </binding>
</web>
```

#### bind

For secure connections to the console, change the URI scheme to **https**.

#### keyStorePath

Path of the keystore file. For example:

```
keyStorePath="<broker_instance_dir>/etc/keystore.jks"
```

#### keyStorePassword

Key store password. This password can be encrypted.

#### **clientAuth**

Specifies whether client authentication is required. The default value is **false**.

#### **trustStorePath**

Path of the trust store file. You need to define this attribute only if **clientAuth** is set to **true**.

#### **trustStorePassword**

Trust store password. This password can be encrypted.

### **Additional resources**

- [Encrypting Passwords in Configuration Files](#)

## **4.4.4. Configuring AMQ Management Console to use certificate-based authentication**

You can configure AMQ Management Console to authenticate users by using SSL certificates, eliminating the need for passwords.

### **Procedure**

1. Obtain certificates for the broker and clients from a trusted certificate authority or generate self-signed certificates. If you want to generate self-signed certificates, complete the following steps:

- a. Generate a self-signed certificate for the broker.

```
$ keytool -storetype pkcs12 -keystore broker-keystore.p12 -storepass securepass -
keypass securepass -alias client -genkey -keyalg "RSA" -keysize 2048 -dname
"CN=ActiveMQ Broker, OU=Artemis, O=ActiveMQ, L=AMQ, S=AMQ, C=AMQ" -ext
bc=ca:false -ext eku=cA
```

- b. Export the certificate from the broker keystore, so that it can be shared with clients.

```
$ keytool -storetype pkcs12 -keystore broker-keystore.p12 -storepass securepass -alias
client -exportcert -rfc > broker.crt
```

- c. On the client, import the broker certificate into the client truststore.

```
$ keytool -storetype pkcs12 -keystore client-truststore.p12 -storepass securepass -
keypass securepass -importcert -alias client-ca -file broker.crt -noprompt
```

- d. On the client, generate a self-signed certificate for the client.

```
$ keytool -storetype pkcs12 -keystore client-keystore.p12 -storepass securepass -
keypass securepass -alias client -genkey -keyalg "RSA" -keysize 2048 -dname
"CN=ActiveMQ Client, OU=Artemis, O=ActiveMQ, L=AMQ, S=AMQ, C=AMQ" -ext
bc=ca:false -ext eku=cA
```

- e. Export the client certificate from the client keystore to a file so that it can be added to the broker truststore.

```
$ keytool -storetype pkcs12 -keystore client-keystore.p12 -storepass securepass -alias
client -exportcert -rfc > client.crt
```

- f. Import the client certificate into the broker truststore.

```
$ keytool -storetype pkcs12 -keystore client-truststore.p12 -storepass securepass -
keypass securepass -importcert -alias client-ca -file client.crt -noprompt
```



#### NOTE

On the broker machine, ensure that the keystore and truststore files are in a location that is accessible to the broker.

2. In the **<broker\_instance\_dir>/etc/bootstrap.xml** file, update the web configuration to enable the HTTPS protocol and client authentication for the broker console. For example:

```
...
<web path="web">
 <binding uri="https://localhost:8161" keyStorePath="${artemis.instance}/etc/server-
keystore.p12" keyStorePassword="password"
 clientAuth="true" trustStorePath="${artemis.instance}/etc/client-truststore.p12"
 trustStorePassword="password">
 ...
 </binding>
</web>
...
```

#### binding uri

Specify the https protocol to enable SSL and add a host name and port.

#### keyStorePath

The path to the keystore where the broker certificate is installed.

#### keyStorePassword

The password of the keystore where the broker certificate is installed.

#### ClientAuth

Set to true to configure the broker to require that each client presents a certificate when a client tries to connect to the broker console.

#### trustStorePath

If clients are using self-signed certificates, specify the path to the truststore where client certificates are installed.

#### trustStorePassword

If clients are using self-signed certificates, specify the password of the truststore where client certificates are installed .

NOTE. You need to configure the **trustStorePath** and **trustStorePassword** properties only if clients are using self-signed certificates.

3. Obtain the Subject *Distinguished Names* (DNs) from each client certificate so you can create a mapping between each client certificate and a broker user.

- a. Export each client certificate from the client's keystore file into a temporary file. For example:

```
keytool -export -file <file_name> -alias broker-localhost -keystore broker.ks -storepass <password>
```

- b. Print the contents of the exported certificate:

```
keytool -printcert -file <file_name>
```

The output is similar to that shown below:

```
Owner: CN=AMQ Client, OU=Artemis, O=AMQ, L=AMQ, ST=AMQ, C=AMQ
Issuer: CN=AMQ Client, OU=Artemis, O=AMQ, L=AMQ, ST=AMQ, C=AMQ
Serial number: 51461f5d
Valid from: Sun Apr 17 12:20:14 IST 2022 until: Sat Jul 16 12:20:14 IST 2022
Certificate fingerprints:
 SHA1: EC:94:13:16:04:93:57:4F:FD:CA:AD:D8:32:68:A4:13:CC:EA:7A:67
 SHA256:
85:7F:D5:4A:69:80:3B:5B:86:27:99:A7:97:B8:E4:E8:7D:6F:D1:53:08:D8:7A:BA:A7:0A:7A:
96:F3:6B:98:81
```

The **Owner** entry is the Subject DN. The format used to enter the Subject DN depends on your platform. The string above could also be represented as;

```
Owner: `CN=localhost,\ OU=broker,\ O=Unknown,\ L=Unknown,\ ST=Unknown,\
C=Unknown`
```

4. Enable certificate-based authentication for the broker's console.

- a. Open the **<broker\_instance\_dir>/etc/login.config** configuration file. Add the certificate login module and reference the user and roles properties files. For example:

```
activemq {
 org.apache.activemq.artemis.spi.core.security.jaas.TextFileCertificateLoginModule
 debug=true
 org.apache.activemq.jaas.textfiledn.user="artemis-users.properties"
 org.apache.activemq.jaas.textfiledn.role="artemis-roles.properties";
};
```

#### **org.apache.activemq.artemis.spi.core.security.jaas.TextFileCertificateLoginModule**

The implementation class.

#### **org.apache.activemq.jaas.textfiledn.user**

Specifies the location of the user properties file relative to the directory that contains the login configuration file.

#### **org.apache.activemq.jaas.textfiledn.role**

Specifies the properties file that maps users to defined roles for the login module implementation.

**NOTE**

If you change the default name of the certificate login module configuration in the **<broker\_instance\_dir>/etc/login.config** file, you must update the value of the **-dhawtio.realm** argument in the **<broker\_instance\_dir>/etc/artemis.profile** file to match the new name. The default name is **activemq**.

- b. Open the **<broker\_instance\_dir>/etc/artemis-users.properties** file. Create a mapping between client certificates and broker users by adding the Subject DNS that you obtained from each client certificate to a broker user. For example:

```
user1=CN=user1,O=Progress,C=US
user2=CN=user2,O=Progress,C=US
```

In this example, the user1 broker user is mapped to the client certificate that has a Subject Distinguished Name of CN=user1,O=Progress,C=US Subject DN. After you create a mapping between a client certificate and a broker user, the broker can authenticate the user by using the certificate.

- c. Open the **<broker\_instance\_dir>/etc/artemis-roles.properties** file. Grant users permission to log in to the console by adding them to the role that is specified for the HAWTIO\_ROLE variable in the **<broker\_instance\_dir>/etc/artemis.profile** file. The default value of the HAWTIO\_ROLE variable is **amq**. For example:

```
amq=user1, user2
```

5. Configure the following recommended security properties for the HTTPS protocol.

- a. Open the **<broker\_instance\_dir>/etc/artemis.profile** file.
- b. Set the **hawtio.http.strictTransportSecurity** property to allow only HTTPS requests to the AMQ Management Console and to convert any HTTP requests to HTTPS. For example:

```
hawtio.http.strictTransportSecurity = max-age=31536000; includeSubDomains; preload
```

- c. Set the **hawtio.http.publicKeyPins** property to instruct the web browser to associate a specific cryptographic public key with the AMQ Management Console to decrease the risk of “man-in-the-middle” attacks using forged certificates. For example:

```
hawtio.http.publicKeyPins = pin-sha256="..."; max-age=5184000; includeSubDomains
```

#### 4.4.5. Configuring AMQ Management Console to handle X-forwarded headers

If requests to the AMQ Management Console go through a proxy server, you can configure the AMQ Broker embedded web server, which hosts AMQ Management Console, to handle X-Forwarded headers. This allows the AMQ Management Console to correctly identify the protocols in use when it is accessed behind a proxy server.

For example, the proxy can expose AMQ Management Console using HTTPS, and the AMQ Management Console, which uses HTTP, can identify from the X-Forwarded header that the connection between the browser and the proxy uses HTTPS and switch to HTTPS to serve browser requests.

## Procedure

1. Open the `<broker_instance_dir>/etc/bootstrap.xml` file.
2. In the `<web>` element, add the `customizer` attribute with a value of `org.eclipse.jetty.server.ForwardedRequestCustomizer`. For example:

```
<web path="web" customizer="org.eclipse.jetty.server.ForwardedRequestCustomizer">
..
</web>
```

3. Save the `bootstrap.xml` file.
4. Start or restart the broker by entering the following command:
  - On Linux: `<broker_instance_dir>/bin/artemis run`
  - On Windows: `<broker_instance_dir>\bin\artemis-service.exe start`

## 4.5. MANAGING BROKERS USING AMQ MANAGEMENT CONSOLE

View broker status and manage resources like connections, addresses, and queues using the AMQ Management Console.

### 4.5.1. Viewing details about the broker

You can view configuration details, status, connections, and runtime metrics for your broker from the **Artemis** menu in the console.


To see how the broker is configured, in the left menu, click **Artemis**.

In the main pane, the following tabs are available:

#### Status

Displays information about the current status of the broker, such as version information, uptime and the high availability policy deployed. Also displays the amount of address memory that the broker is currently using. The graph shows this value as a proportion of the **global-max-size** configuration parameter.

Figure 4.1. Status tab



### Connections

Displays information about broker connections, including client, cluster, and bridge connections.

### Sessions

Displays information about all sessions currently open on the broker.

### Consumers

Displays information about all consumers currently open on the broker.

### Producers

Displays information about producers currently open on the broker.

### Addresses

Displays information about addresses on the broker. This includes internal addresses, such as store-and-forward addresses.

### Queues

Displays information about queues on the broker. This includes internal queues, such as store-and-forward queues.

### Broker diagram

Displays a diagram of the cluster topology. This includes all brokers in the cluster and any addresses and queues on the local broker.

## 4.5.2. Viewing the broker diagram


You can visualize your cluster topology, including brokers, addresses, queues, and clients, by using the broker diagram.

### Procedure

1. In the left menu, click **Artemis**.
2. In the main pane, click the **Broker Diagram** tab.


The console displays a diagram of the cluster topology. This includes all brokers in the cluster and any addresses and queues on the local broker, as shown in the figure.

Figure 4.2. Broker diagram tab



3. To change the items displayed in the diagram, in the **Node options** list, select the checkboxes for the items you want to display.
4. To show attributes for the local broker or an address or queue that is connected to it, click that node in the diagram. For example, the following figure shows a diagram that also includes attributes for the local broker.

Figure 4.3. Broker diagram tab, including attributes



### 4.5.3. Viewing acceptors


Inspect the attributes and operations of configured acceptors to understand how the broker listens for connections.

#### Procedure

1. In the left menu, click **Artemis JMX**.
2. In the folder tree, click **acceptors**.
3. To view details about how an acceptor is configured, click the acceptor.  
The console shows the acceptor attributes on the **Attributes** tab and the operations you can execute for the acceptor on the **Operations** tab.

The following examples shows the attributes for the **amqp** acceptor.

**Figure 4.4. AMQP acceptor attributes**



4. To see complete details for an attribute, click the attribute. An additional pane opens to show the details.
5. To execute an operation on the acceptor, click the **Operations** tab, expand the operation and click the **Execute** button.

#### 4.5.4. Managing addresses and queues

You can create, configure, and delete addresses and queues to manage messaging endpoints within the broker configuration.

An address represents a messaging endpoint. Within the configuration, a typical address is given a unique name.

A queue is associated with an address. There can be multiple queues per address. Once an incoming message is matched to an address, the message is sent on to one or more of its queues, depending on the routing type configured. Queues can be automatically created and deleted.

##### 4.5.4.1. Creating addresses

You create new addresses by specifying a unique name and a routing type. A routing type determines how messages are sent to the queues associated with an address.

Addresses can be configured with two different routing types.


If you want your messages routed to...	Use this routing type...
A single queue within the matching address, in a point-to-point manner.	Anycast
Every queue within the matching address, in a publish-subscribe manner.	Multicast

You can create and configure addresses and queues, and then delete them when they are no longer in use.

### Procedure

1. In the left menu, click **Artemis**.
2. In the main pane, click the **Addresses** tab.
3. Click **Create Address**.  
The Create Address dialog is displayed.

Figure 4.5. Create Address dialog



The screenshot shows a 'Create Address' dialog box. At the top, there's a title bar with the text 'Create Address ?' and a close button 'x'. Below the title bar, there's a label 'Address Name' followed by a text input field. Underneath that, there's a label 'Routing Type' followed by two radio buttons: 'Anycast' and 'Multicast'. At the bottom of the dialog, there are two buttons: 'Create Address' and 'Close'.

4. Complete the following fields:

#### Address Name

The routing name of the address.

#### Routing type

Select one of the following options:

- **Multicast:** Messages sent to the address are distributed to all subscribers in a publish-subscribe manner.
- **Anycast:** Messages sent to this address are distributed to only one subscriber in a point-to-point manner.

5. Click **Create Address**.

### 4.5.4.2. Sending messages to an address

You can use the AMQ Management Console to send messages to an address.

### Procedure

1. In the left menu, click **Artemis**.
2. In the main pane, click the **Addresses** tab.

3. Click the three-dot icon for the selected address.
4. Click **Send Message**.  
The Send Message to Address <address name> dialog is displayed.

Figure 4.6. Send Message to Address

Send Message to Address TEST ?

Durable i  
☒

Create Message ID i  
☐

Use Current Logged in User i  
☒

[Add Headers](#)

Message

1

xml ▼ Format

Send

Cancel

5. By default messages are sent using the credentials that you used to log in to AMQ Management Console. If you want to use different credentials, clear the **Use Current Logged in User** checkbox and specify values in the **Username** and **Password** fields, which are displayed after you clear the checkbox.
6. If necessary, click the **Add Header** button to add message header information.
7. Enter the message body.

8. In the **Format** drop-down menu, select an option for the format of the message body, and then click **Format**. The message body is formatted in a human-readable style for the format you selected.
9. Click **Send**.  
The message is sent.
10. To send additional messages, change any of the information you entered, and then click **Send**.

#### 4.5.4.3. Creating queues

Create queues bound to specific addresses to enable message delivery to consumers.

##### Prerequisites

- The address to which you want to bind the queue must exist. To learn how to use the console to create an address, see [Section 4.5.4.1, "Creating addresses"](#).

##### Procedure

1. In the left menu, click **Artemis**.
2. In the main pane, click the **Addresses** tab.
3. Click the three-dot icon for the address to which you want to bind the queue.
4. Click **Create Queue**.  
The Create Queue on Address <address name> dialog is displayed

Figure 4.7. Create Queue on Address dialog

**Create Queue on Address TEST ?** ✕

**Queue Name** ⓘ

**Routing Type** ⓘ

☐ Anycast ☐ Multicast

**Durable** ⓘ

☒

**Filter** ⓘ

**Max Consumers** ⓘ

ⓘ

**Purge when no Consumers** ⓘ

☐ ⓘ

**Extra configuration** ⓘ

[Add Configuration](#)

5. Complete the following fields:

### Queue name

A unique name for the queue.

### Routing Type

Select one of the following options:

- **Multicast:** Messages sent to the parent address will be distributed to all queues bound to the address.
- **Anycast:** Only one queue bound to the parent address will receive a copy of the message. Messages will be distributed evenly among all of the queues bound to the address.

### Durable

If you select this option, the queue and its messages are persistent.

### Filter

The username to be used when connecting to the broker.

## Max Consumers

The maximum number of consumers that can access the queue at a given time.

## Purge when no Consumers

If selected, the queue will be purged when no consumers are connected.

6. Click **Create Queue**.


### 4.5.4.4. Checking the status of a queue

Charts provide a real-time view of the status of a queue on a broker.

## Procedure

1. In the left menu, click **Artemis JMX**.
2. In the folder tree, navigate to a queue.
3. Click the **Chart** tab.  
The console displays a chart that shows real-time data for the queue attributes.

Figure 4.8. Chart tab for a queue



## NOTE

To view a chart for multiple queues on an address, select the **anycast** or **multicast** folder that contains the queues.

4. By default, all attributes for a queue are displayed on the chart. If necessary, change the list of attributes displayed on the chart:
  - a. Click **Edit watches**.
  - b. On the **Watched attributes** list, select the checkbox beside each attribute that you do not want to include in the chart.
  - c. Click the right arrow icon to remove the selected attributes from the chart.
  - d. Click **Close**.

### 4.5.4.5. Browsing queues

Browsing a queue displays all of the messages in the queue. You can also filter and sort the list of messages to find specific messages.

#### Procedure

1. In the left menu, click **Artemis**.
2. In the main pane, click the **Queues** tab.
3. Click the three-dot icon for the queue that you want to browse.
4. Click **Browse Messages**.  
The messages in the queue are displayed. By default, the first 200 messages are displayed.

Figure 4.9. Browse Queue dialog

Message ID	Type	Durable	Priority	Timestamp	Expires	Redelivered	Large	Persistent Size
52	text	true	4	2025-02-05 12:23:38	never			392 Bytes
53	text	true	4	2025-02-05 12:23:38	never			392 Bytes
54	text	true	4	2025-02-05 12:23:38	never			392 Bytes
55	text	true	4	2025-02-05 12:23:38	never			392 Bytes
56	text	true	4	2025-02-05 12:23:38	never			392 Bytes
57	text	true	4	2025-02-05 12:23:38	never			392 Bytes
58	text	true	4	2025-02-05 12:23:38	never			392 Bytes
59	text	true	4	2025-02-05 12:23:38	never			392 Bytes
60	text	true	4	2025-02-05 12:23:38	never			392 Bytes
61	text	true	4	2025-02-05 12:23:38	never			392 Bytes

5. To view the content of a message, click the three-dot icon for the message and click **View**.  
You can view the message body, header and properties.

### 4.5.4.6. Sending messages to a queue

You can send messages directly to a queue in the AMQ Management Console.

#### Procedure

1. In the left menu, click **Artemis**.
2. In the main pane, click the **Queues** tab.
3. Click the three-dot icon for the queue to which you want to send a message .
4. Click **Send Message**.  
The Send Message to Queue <queue name> dialog is displayed

Figure 4.10. Send Message to Queue dialog

**Send Message to Queue TEST ?** X

**Durable** i  
☒

**Create Message ID** i  
☐

**Use Current Logged in User** i  
☒

[Add Headers](#)

**Message**

1

xml ▼ Format

Send

Cancel

5. By default messages are sent using the credentials that you used to log in to AMQ Management Console. If you want to use different credentials, clear the **Use Current Logged in User** checkbox and specify values in the **Username** and **Password** fields, which are displayed after you clear the checkbox.
6. If necessary, click the **Add Header** button to add message header information.
7. Enter the message body.
8. In the **Format** drop-down menu, select an option for the format of the message body, and then click **Format**. The message body is formatted in a human-readable style for the format you selected.
9. Click **Send**.

10. To send additional messages, change any of the information you entered, and then click **Send**.

#### 4.5.4.7. Resending messages to a queue

You can resend messages previously sent to a queue in the AMQ Management Console.

##### Procedure

1. [Browse for the message you want to resend](#) .
2. Click the three-dot icon for the message that you want to resend.
3. Click **Resend**.  
The Resend Message dialog is displayed.
4. Update the [message header and body](#) as needed, and then click **Send**.

#### 4.5.4.8. Moving messages to a different queue

You can move one or more messages in a queue to a different queue in AMQ Management Console.

##### Procedure

1. [Browse for the messages you want to move](#) .
2. Click the checkbox next to each message that you want to move.
3. Click **Move**.  
A confirmation dialog box is displayed.
4. From the drop-down menu, select the name of the queue to which you want to move the messages. Click **Confirm**.

#### 4.5.4.9. Deleting messages or queues

You can delete all of the messages in a queue and retain the queue, or you can delete the queue entirely.

##### Procedure

1. In the left menu, click **Artemis**.
2. In the main pane, click the **Queues** tab.
3. Click the three-dot icon for the queue you want to purge or delete.
  - a. To delete all the message in the selected queue without deleting the queue, click **Purge**.
  - b. To delete all the messages and the queue itself, click **Delete**.
4. In the confirmation dialog, click **Confirm**.

## CHAPTER 5. MONITORING BROKER RUNTIME METRICS

When you install AMQ Broker, a Prometheus metrics plugin is installed. You must enable the Prometheus metrics plugin in the broker configuration so it collects runtime metrics for the broker and exports these metrics in Prometheus format.

You can then use Prometheus to review the metrics. You might also use a graphical tool such as Grafana to configure more advanced visualizations of the data.



### NOTE

The Prometheus metrics plugin enables you to collect and export broker metrics in Prometheus **format**. However, Red Hat **does not** provide support for installation or configuration of Prometheus itself, nor of visualization tools such as Grafana. If you require support with installing, configuring, or running Prometheus or Grafana, visit the product websites for resources such as community support and documentation.

In addition to the broker metrics collected by the Prometheus plugin, you can modify the broker configuration to capture standard sets of metrics relating to the host Java Virtual Machine (JVM) for the broker. Specifically, you can capture JVM metrics for Garbage Collection (GC), memory, and threads.

### 5.1. METRICS OVERVIEW

You can use the Prometheus plugin for AMQ Broker to collect runtime metrics, which you can use monitor the health and performance of brokers. The AMQ Broker Prometheus plugin exports the runtime metrics in Prometheus format, enabling you to use Prometheus itself to visualize and query the data.

You can also use a graphical tool, such as Grafana, to configure more advanced visualizations and dashboards for the metrics that the Prometheus plugin collects.

The metrics that the plugin exports to Prometheus format are described below.

For higher-level broker metrics that are not listed below, you can calculate these by aggregating lower-level metrics. For example, to calculate total message count, you can aggregate the **artemis\_message\_count** metrics from all queues in your broker deployment.

For a standalone deployment of AMQ Broker on RHEL, metrics for the Java Virtual Machine (JVM) hosting the broker are also exported to Prometheus format. This does not apply to a deployment of AMQ Broker on OpenShift Container Platform.

#### 5.1.1. Broker metrics

##### **artemis\_address\_memory\_usage**

Number of bytes used by all addresses on this broker for in-memory messages.

##### **artemis\_address\_memory\_usage\_percentage**

Memory used by all the addresses on this broker as a percentage of the **global-max-size** parameter.

##### **artemis\_connection\_count**

Number of clients connected to this broker.

##### **artemis\_session\_count**

Number of sessions on this broker.

**artemis\_total\_session\_count**

Total number of sessions created on this broker since it was started.

**artemis\_total\_connection\_count**

Number of clients that have connected to this broker since it was started.

**artemis\_disk\_store\_usage**

The fraction of the total disk store used.

**artemis\_replica\_sync**

Is the initial replication synchronization process between primary and backup brokers complete.

**artemis\_active**

Is the broker active in a primary-backup group configuration.

**artemis\_authentication\_count**

Number of successful and failed authentication attempts.

**artemis\_authorization\_count**

Number of successful and failed authorization attempts.

### 5.1.2. Address metrics

**artemis\_routed\_message\_count**

Number of messages routed to one or more queue bindings.

**artemis\_unrouted\_message\_count**

Number of messages *not* routed to any queue bindings.

**artemis\_address\_size**

The size in bytes used by all queues bound to this address.

**artemis\_number\_of\_pages**

The number of page files used to store messages for this address.

**artemis\_limit\_percent**

The percentage of a configured memory limit that is used by this address. If a memory limit is set for the address by using the **max-size-bytes** attribute, the percentage reported is based on that value. If the **max-size-bytes** attribute is not set, the percentage reported is based on the value of the **global-max-size** attribute. If neither attribute is set, a value of 0 is reported.

### 5.1.3. Queue metrics

**artemis\_consumer\_count**

Number of clients consuming messages from a given queue.

**artemis\_delivering\_durable\_message\_count**

Number of durable messages that a given queue is currently delivering to consumers.

**artemis\_delivering\_durable\_persistent\_size**

Persistent size of durable messages that a given queue is currently delivering to consumers.

**artemis\_delivering\_message\_count**

Number of messages that a given queue is currently delivering to consumers.

**artemis\_delivering\_persistent\_size**

Persistent size of messages that a given queue is currently delivering to consumers.

#### **artemis\_durable\_message\_count**

Number of durable messages currently in a given queue. This includes scheduled, paged, and in-delivery messages.

#### **artemis\_durable\_persistent\_size**

Persistent size of durable messages currently in a given queue. This includes scheduled, paged, and in-delivery messages.

#### **artemis\_messages\_acknowledged**

Number of messages acknowledged from a given queue since the queue was created.

#### **artemis\_messages\_added**

Number of messages added to a given queue since the queue was created.

#### **artemis\_message\_count**

Number of messages currently in a given queue. This includes scheduled, paged, and in-delivery messages.

#### **artemis\_messages\_killed**

Number of messages removed from a given queue since the queue was created. The broker kills a message when the message exceeds the configured maximum number of delivery attempts.

#### **artemis\_messages\_expired**

Number of messages expired from a given queue since the queue was created.

#### **artemis\_persistent\_size**

Persistent size of all messages (both durable and non-durable) currently in a given queue. This includes scheduled, paged, and in-delivery messages.

#### **artemis\_scheduled\_durable\_message\_count**

Number of durable, scheduled messages in a given queue.

#### **artemis\_scheduled\_durable\_persistent\_size**

Persistent size of durable, scheduled messages in a given queue.

#### **artemis\_scheduled\_message\_count**

Number of scheduled messages in a given queue.

#### **artemis\_scheduled\_persistent\_size**

Persistent size of scheduled messages in a given queue.

## 5.2. ENABLING THE PROMETHEUS METRICS PLUGIN FOR AMQ BROKER

You must enable the Prometheus metrics plugin in the broker configuration so it collects runtime metrics for the broker and exports these metrics in Prometheus format.

### Procedure

1. Open the `<broker_instance_dir>/etc/broker.xml` configuration file.
2. Enable the Prometheus plugin in the broker configuration. Add a `<metrics>` element with a `<plugin>` sub-element, configured as shown below.

```
<metrics>
```

```
<plugin class-
name="com.redhat.amq.broker.core.server.metrics.plugins.ArtemisPrometheusMetricsPlugin"
/>
</metrics>
```

3. Save the **broker.xml** configuration file. The metrics plugin starts to gather broker runtime metrics in Prometheus format.

## 5.3. CONFIGURING THE BROKER TO COLLECT JVM METRICS

You can configure the broker to collect JVM metrics, including garbage collection, memory, and threads, for more detailed performance analysis.

### Prerequisites

- You enabled the Prometheus metrics plugin in your broker configuration. For more information, see [Section 5.2, “Enabling the Prometheus metrics plugin for AMQ Broker”](#).

### Procedure

1. Open the **<broker\_instance\_dir>/etc/broker.xml** configuration file.
2. In the **<metrics>** element that you added to the configuration when enabling the Prometheus metrics plugin, specify whether the broker collects JVM metrics for Garbage Collection (GC), memory, and threads. For example:

```
<metrics>
 <jvm-gc>true</jvm-gc>
 <jvm-memory>true</jvm-memory>
 <jvm-threads>true</jvm-threads>
 <plugin class-
name="com.redhat.amq.broker.core.server.metrics.plugins.ArtemisPrometheusMetricsPlugin"
/>
</metrics>
```



### NOTE

If you do not explicitly add the **jvm-memory** parameter to your configuration and specify a value, the broker uses a default value of **true**. This means that the broker exports JVM memory metrics by default. The default values of the **jvm-gc** and **jvm-threads** parameters are **false**.

3. Save the **broker.xml** configuration file. The broker starts to gather the JVM metrics that you have enabled. These metrics are also exported to Prometheus format.

## 5.4. DISABLING METRICS COLLECTION FOR SPECIFIC ADDRESSES

You can disable metrics collection for specific addresses in the configuration to reduce overhead or exclude irrelevant data.

### Procedure

1. Open the `<broker_instance_dir>/etc/broker.xml` configuration file.
2. In the **address-setting** element of a matching address or set of addresses, add the **enable-metrics** parameter and set the value of the parameter to **false**. For example, the following configuration disables metrics collection for an address called **orders**.

```
<configuration>
 <core>
 ...
 <address-settings>
 <address-setting match="orders">
 ...
 <enable-metrics>false</enable-metrics>
 ...
 </address-setting>
 </address-settings>
 ...
 </core>
</configuration>
```

## 5.5. ACCESSING BROKER RUNTIME DATA USING PROMETHEUS

You can use the Prometheus web console to query and visualize the broker runtime data that was collected by the Prometheus plugin.

### Prerequisites

- To query and visualize the broker runtime data collected by the Prometheus plugin, you need to install Prometheus. For more information, see [Installing Prometheus](#) in the Prometheus documentation.

### Procedure

1. From your Prometheus installation directory, open the **prometheus.yml** configuration file.
2. In the **static\_configs** section of the configuration file, change the **targets** element to **localhost:8161**. This location is where the broker runs its web server. By default, **/metrics** is appended to this host name, forming the full path to the metrics stored on the broker web server.
3. To view the broker runtime metrics collected by the Prometheus plugin, open **localhost:8161/metrics** in a web browser.  
On the resulting web page, you see the current values of the metrics collected by the plugin, based on the queues and addresses that you have configured on the broker. If you have more than one running broker instance in your JVM, you see metrics for each broker.
4. From your Prometheus installation directory, run Prometheus.

```
$./prometheus
```

When Prometheus starts, the shell output includes the following line:

```
component=web, msg="Start listening for connections" address=0.0.0.0:9090
```

The preceding line indicates that Prometheus is listening for HTTP traffic on port 9090.

5. To access the Prometheus web console, open **127.0.0.1:9090** in a web browser.
6. In the Prometheus web console, you can use the **Expression** field to create a query on your broker data. The queries you create are based on the Prometheus query language, PromQL. Broker metrics that are available to insert in your query are in the **Insert metric** drop-down list. As a simple example, suppose you want to query the message count on the DLQ queue, over time. In this case, select **artemis\_message\_count** from the metrics drop-down list. Complete your query by specifying the DLQ queue name and address. This example query is shown below.

```
artemis_message_count{address="DLQ", queue="DLQ"}
```

For more advanced visualizations, you can use regular expressions to create complex queries that overlay several metrics, for example. Or, you can perform mathematical operations on a number of metrics, such as aggregating them. For more information about creating Prometheus queries, see [Querying Prometheus](#) in the Prometheus documentation.

## CHAPTER 6. USING THE MANAGEMENT API

Use the AMQ Broker management API to configure the broker and to create and manage resources such as queues and addresses.

In addition, clients can use the management API to manage the broker and subscribe to management notifications.

### 6.1. METHODS FOR MANAGING AMQ BROKER USING THE MANAGEMENT API

You can manage the broker either by using Java Management Extensions (JMX) or the Java Message Service (JMS) API. JMX is the standard way to manage Java applications. When using the JMS API, management operations are sent to the broker in JMS messages from the Red Hat build of Apache Qpid JMS client.

Although there are two different ways to manage the broker, each API supports the same functionality. If it is possible to manage a resource using JMX it is also possible to achieve the same result by using JMS messages and the Red Hat build of Apache Qpid JMS client.

This choice depends on your particular requirements, application settings, and environment. Regardless of the way you invoke management operations, the management API is the same.

For each managed resource, there exists a Java interface describing what can be invoked for this type of resource. The broker exposes its managed resources in the **org.apache.activemq.artemis.api.core.management** package. The way to invoke management operations depends on whether JMX messages or JMS messages and the Red Hat build of Apache Qpid JMS client are used.



#### NOTE

Some management operations require a **filter** parameter to choose which messages are affected by the operation. Passing **null** or an empty string means that the management operation will be performed on *all messages*.

### 6.2. MANAGING AMQ BROKER BY USING JMX

You can use Java Management Extensions (JMX) and MBeans to manage broker resources registered under the `org.apache.activemq` domain.

For example, the **ObjectName** to manage a queue named **exampleQueue** is:

```
org.apache.activemq.artemis:broker="__BROKER_NAME__",component=addresses,address="exampleQueue",subcomponent=queues,routing-type="anycast",queue="exampleQueue"
```

The MBean is:

```
org.apache.activemq.artemis.api.management.QueueControl
```

The MBean's **ObjectName** is built by using the helper class **org.apache.activemq.artemis.api.core.management.ObjectNameBuilder**. You can also use JConsole to find the **ObjectName** of the MBeans you want to manage.

Managing the broker by using JMX is identical to management of any Java applications by using JMX. It can be done by reflection or by creating proxies of the MBeans.

### 6.2.1. Configuring JMX management

You can enable or disable JMX management by setting the **jmx-management-enabled** property in the **broker.xml** configuration file. By default, JMX is enabled to manage the broker.

#### Procedure

1. Open the **<broker\_instance\_dir>/etc/broker.xml** configuration file.
2. Set **<jmx-management-enabled>**.

```
<jmx-management-enabled>true</jmx-management-enabled>
```

If JMX is enabled, the broker can be managed locally using **jconsole**.



#### NOTE

Remote connections to JMX are not enabled by default for security reasons.

3. If you want to manage multiple brokers from the same **MBeanServer**, configure the JMX domain for each of the brokers.

By default, the broker uses the JMX domain **org.apache.activemq.artemis**.

```
<jmx-domain>my.org.apache.activemq</jmx-domain>
```



#### NOTE

If you are using AMQ Broker on a Windows system, system properties must be set in **artemis**, or **artemis.cmd**. A shell script is located under **<install\_dir>/bin**.

#### Additional resources

- [Java Management Guide](#)


### 6.2.2. Configuring JMX management access

By default, remote JMX access to a broker is disabled for security reasons. However, AMQ Broker has a JMX agent that allows remote access to JMX MBeans. You enable JMX access by configuring a connector element in the broker **management.xml** configuration file.



#### NOTE

While it is also possible to enable JMX access using the ``com.sun.management.jmxremote`` JVM system property, that method is not supported and is not secure. Modifying that JVM system property can bypass RBAC on the broker. To minimize security risks, consider limited access to localhost.



## IMPORTANT

Exposing the JMX agent of a broker for remote management has security implications.

To secure your configuration as described in this procedure:

- Use SSL for all connections.
- Explicitly define the connector host, that is, the host and port to expose the agent on.
- Explicitly define the port that the RMI (Remote Method Invocation) registry binds to.

## Prerequisites

- A working broker instance
- The Java **jconsole** utility

## Procedure

1. Open the **<broker-instance-dir>/etc/management.xml** configuration file.
2. Define a connector for the JMX agent. The connector-port setting establishes an RMI registry that clients such as jconsole query for the JMX connector server. For example, to allow remote access on port 1099:

```
<connector connector-port="1099"/>
```

3. Verify the connection to the JMX agent using **jconsole**:

```
service:jmx:rmi:///jndi/rmi://localhost:1099/jmxrmi
```

4. Define additional properties on the connector, as described below.

### connector-host

The broker server host to expose the agent on. To prevent remote access, set **connector-host** to **127.0.0.1** (localhost).

### rmi-registry-port

The port that the JMX RMI connector server binds to. If not set, the port is always random. Set this property to avoid problems with remote JMX connections tunnelled through a firewall.

### jmx-realm

JMX realm to use for authentication. The default value is **activemq** to match the JAAS configuration.

### object-name

Object name to expose the remote connector on. The default value is **connector:name=rmi**.

### secured

Specify whether the connector is secured using SSL. The default value is **false**. Set the value to **true** to ensure secure communication.

**key-store-path**

Location of the keystore. Required if you have set **secured="true"**.

**key-store-password**

Keystore password. Required if you have set **secured="true"**. The password can be encrypted.

**key-store-provider**

Keystore provider. Required if you have set **secured="true"**. The default value is **JKS**.

**trust-store-path**

Location of the truststore. Required if you have set **secured="true"**.

**trust-store-password**

Truststore password. Required if you have set **secured="true"**. The password can be encrypted.

**trust-store-provider**

Truststore provider. Required if you have set **secured="true"**. The default value is **JKS**.

**password-codec**

The fully qualified class name of the password codec to use. See the password masking documentation, linked below, for more details on how this works.

**NOTE**

The RMI registry picks an IP address to bind to. If you have multiple IP addresses/NICs present on the system, then you can choose the IP address to use by adding the following to the **artemis.profile** file: -

**Djava.rmi.server.hostname=localhost**

- Set an appropriate value for the endpoint serialization using **jdk.serialFilter** as described in the [Java Platform documentation](#).

**Additional resources**


- [Encrypting Passwords in Configuration Files](#)

**6.2.3. MBeanServer configuration**

When the broker runs in standalone mode, it uses the Java Virtual Machine's **Platform MBeanServer** to register its MBeans. By default, [Jolokia](#) is also deployed to allow access to the MBean server using REST.

**6.2.4. How JMX is exposed with Jolokia**

By default, AMQ Broker includes the [Jolokia](#) HTTP agent deployed as a web application. Jolokia is a remote JMX over HTTP bridge that exposes MBeans.

**NOTE**

To use Jolokia, the user must belong to the role defined by the **hawtio.roles** system property in the **<broker\_instance\_dir>/etc/artemis.profile** configuration file. By default, this role is **amq**.

You can send Jolokia requests to the broker as HTTP GET requests. These requests encode all their parameters within the Jolokia REST URL.

### Example Jolokia REST URLs

The following is an example of a Jolokia REST URL in a request to find the version of a broker. The **Origin** flag should specify the domain name or DNS host name for the broker server. In addition, the value you specify for **Origin** must correspond to an entry for **<allow-origin>** in your Jolokia Cross-Origin Resource Sharing (CORS) specification.

```
$ curl
http://admin:admin@localhost:8161/console/jolokia/read/org.apache.activemq.artemis:broker=\
"0.0.0.0"/Version -H "Origin: mydomain.com"
{"request":
{"mbean":"org.apache.activemq.artemis:broker=\
"0.0.0.0","attribute":"Version","type":"read"},"value":
"2.4.0.amq-710002-redhat-1","timestamp":1527105236,"status":200}
```

The following is an example of a Jolokia REST URL in a request to obtain a message count for the myQueue0 queue.

```
$ curl -u
http://admin:admin@localhost:8161/console/jolokia/read/org.apache.activemq.artemis:broker\
=\!%22a
mq-
broker\!%22,component\=addresses,address\=\!%22myAddress0\!%22,subcomponent\=queues,
routing-type\=\!%22anycast\!%22,queue\=\!%22myQueue0\!%22/MessageCount
```



### NOTE

You can find the Jolokia URL to use in a specific HTTP GET request by copying the Jolokia URL for the corresponding operation in AMQ Management Console. The following example copies the Jolokia URL for use in a HTTP GET request that browses the myQueue0 queue. After you copy the URL, you can customize it for your request.

Figure 6.1. Operations page

AMQ7 Console

Broker: broker1

org.apache.activemq.artemis

- broker1
  - acceptors
  - addresses
    - \$sys.mqtt.sessions
    - \$sys.mqtt.sessions
    - activemq.notifications
    - DLQ
    - DLQ
    - ExpiryQueue
    - ExpiryQueue
    - myQueue0
      - queues
        - anycast
          - myQueue0

Attributes Operations Chart Browse Messages Delete Queue Send Message

This MBean supports the following JMX operations. Expand an item in the list to invoke that operation.

- javax.management.openbean.CompositeData[] browse()
  - Browse Messages
  - This JMX operation requires no arguments. Click the Execute button to invoke the operation.
  - Execute
- javax.management.openbean.CompositeData[] browse(int, int, String)
  - Browse Messages
- javax.management.openbean.CompositeData[] browse(int, int)
  - Browse Messages
- javax.management.openbean.CompositeData[] browse(String)
  - Browse Messages
- boolean changeMessagePriority(long, int)
  - Change the priority of the message corresponding to the given messageID
- int changeMessagesPriority(String, int)
  - Change the priority of the messages corresponding to the given filter

Copy method name  
Copy Jolokia URL

Copied to clipboard

## Additional resources

- [Jolokia documentation](#)
- [Security](#)

### 6.2.5. Subscribing to JMX management notifications

If JMX is enabled in your broker configuration, you can subscribe to management notifications to receive alerts about broker events and state changes.

#### Procedure

- Subscribe to **ObjectName** `org.apache.activemq.artemis:broker="<broker-name>"`.

## Additional resources

- [Section 6.5, "Management notifications"](#)

## 6.3. MANAGING AMQ BROKER USING THE JMS API

You can manage brokers by sending specially formatted JMS messages to the management queue using the Red Hat build of Apache Qpid JMS client.

### 6.3.1. Configuring broker management using JMS messages and the Red Hat build of Apache Qpid JMS Client

If you want to manage the broker by using JMS messages, you must grant the broker's management address the **manage** permission.

#### Procedure

1. Open the `<broker_instance_dir>/etc/broker.xml` configuration file.
2. Add the `<management-address>` element, and specify a management address.  
By default, the management address is **activemq.management**. You only need to specify a different address if you do not want to use the default.

```
<management-address>my.management.address</management-address>
```

3. Provide the management address with the **manage** user permission type.  
This permission type enables the management address to receive and handle management messages.

```
<security-setting match="activemq.management">
 <permission-type="manage" roles="admin"/>
</security-setting>
```

### 6.3.2. Managing brokers using the JMS API and Red Hat build of Apache Qpid JMS Client

To invoke management operations by using JMS messages, the Red Hat build of Apache Qpid JMS client must instantiate the special management queue.

### Procedure

1. Create a **QueueRequestor** to send messages to the management address and receive replies.
2. Create a **Message**.
3. Use the helper class **org.apache.activemq.artemis.api.jms.management.JMSManagementHelper** to fill the message with the management properties.
4. Send the message using the **QueueRequestor**.
5. Use the helper class **org.apache.activemq.artemis.api.jms.management.JMSManagementHelper** to retrieve the operation result from the management reply.

#### Example 6.1. Viewing the number of messages in a queue

This example shows how to use the JMS API to view the number of messages in the JMS queue **exampleQueue**:

```
Queue managementQueue = ActiveMQJMSClient.createQueue("activemq.management");

QueueSession session = ...
QueueRequestor requestor = new QueueRequestor(session, managementQueue);
connection.start();
Message message = session.createMessage();
JMSManagementHelper.putAttribute(message, "queue.exampleQueue", "messageCount");
Message reply = requestor.request(message);
int count = (Integer)JMSManagementHelper.getResult(reply);
System.out.println("There are " + count + " messages in exampleQueue");
```

## 6.4. MANAGEMENT OPERATIONS

You can use the same management operations to manage brokers, addresses, and queues regardless of whether you use JMX or JMS.

### 6.4.1. Broker management operations

You can use the management API to manage your brokers.

#### Listing, creating, deploying, and destroying queues

A list of deployed queues can be retrieved using the **getQueueNames()** method. Queues can be created or destroyed using the management operations **createQueue()**, **deployQueue()**, or **destroyQueue()** on the **ActiveMQServerControl** (with the **ObjectName** **org.apache.activemq.artemis:broker="BROKER\_NAME"** or the resource name **server**).

**createQueue** will fail if the queue already exists while **deployQueue** will do nothing.

## Pausing and resuming queues

The **QueueControl** can pause and resume the underlying queue. When a queue is paused, it will receive messages but will not deliver them. When it is resumed, it will begin delivering the queued messages, if any.

## Listing and closing remote connections

Retrieve a client's remote addresses by using **listRemoteAddresses()**. It is also possible to close the connections associated with a remote address using the **closeConnectionsForAddress()** method. Alternatively, list connection IDs using **listConnectionIDs()** and list all the sessions for a given connection ID using **listSessions()**.

## Managing transactions

In case of a broker crash, when the broker restarts, some transactions might require manual intervention. Use the the following methods to help resolve issues you encounter.

List the transactions which are in the prepared states (the transactions are represented as opaque Base64 Strings) using the **listPreparedTransactions()** method lists.

Commit or rollback a given prepared transaction using **commitPreparedTransaction()** or **rollbackPreparedTransaction()** to resolve heuristic transactions.

List heuristically completed transactions using the **listHeuristicCommittedTransactions()** and **listHeuristicRolledBackTransactions** methods.

## Enabling and resetting message counters

Enable and disable message counters using the **enableMessageCounters()** or **disableMessageCounters()** method.

Reset message counters by using the **resetAllMessageCounters()** and **resetAllMessageCounterHistories()** methods.

## Retrieving broker configuration and attributes

The **ActiveMQServerControl** exposes the broker's configuration through all its attributes (for example, **getVersion()** method to retrieve the broker's version, and so on).

## Listing, creating, and destroying Core Bridge and diverts

List deployed Core Bridge and diverts using the **getBridgeNames()** and **getDivertNames()** methods respectively.

Create or destroy using bridges and diverts using **createBridge()** and **destroyBridge()** or **createDivert()** and **destroyDivert()** on the **ActiveMQServerControl** (with the **ObjectName** **org.apache.activemq.artemis:broker="BROKER\_NAME"** or the resource name **server**).

## Stopping the broker and forcing failover to occur with any currently attached clients

Use the **forceFailover()** on the **ActiveMQServerControl** (with the **ObjectName** **org.apache.activemq.artemis:broker="BROKER\_NAME"** or the resource name **server**)



### NOTE

Because this method actually stops the broker, you will likely receive an error. The exact error depends on the management service you used to call the method.

## 6.4.2. Address management operations

You can use the management API to manage addresses by using the **AddressControl** class.

Manage addresses using the **AddressControl** class with **ObjectName** **org.apache.activemq.artemis:broker="<broker-name>", component=addresses,address="<address-name>"** or the resource name **address.<address-name>**.

Modify roles and permissions for an address using the **addRole()** or **removeRole()** methods. You can list all the roles associated with the queue with the **getRoles()** method.

### 6.4.3. Queue management operations

You can use the management API to manage queues by using the **QueueControl** class.

The core management API deals with queues. The **QueueControl** class defines the queue management operations (with the **ObjectName** **org.apache.activemq.artemis:broker="<broker-name>", component=addresses,address="<bound-address>", subcomponent=queues, routing-type="<routing-type>", queue="<queue-name>"** or the resource name **queue.<queue-name>**).

Most of the management operations on queues take either a single message ID (for example, to remove a single message) or a filter (for example, to expire all messages with a given property).

#### Expiring, sending to a dead letter address, and moving messages

Expire messages from a queue using the **expireMessages()** method. If an expiry address is defined, messages are sent to this address, otherwise they are discarded. You can define the expiry address for an address or set of addresses (and hence the queues bound to those addresses) in the **address-settings** element of the **broker.xml** configuration file. For an example, see the "Default message address settings" section in [Understanding the default broker configuration](#).

Send messages to a dead letter address using the **sendMessagesToDeadLetterAddress()** method. This method returns the number of messages sent to the dead letter address. If a dead letter address is defined, messages are sent to this address, otherwise they are removed from the queue and discarded. You can define the dead letter address for an address or set of addresses (and hence the queues bound to those addresses) in the **address-settings** element of the **broker.xml** configuration file. For an example, see the "Default message address settings" section in [Understanding the default broker configuration](#).

Move messages from one queue to another using the **moveMessages()** method.

#### Listing and removing messages

List messages from a queue using the **listMessages()** method. It will return an array of **Map**, one **Map** for each message.

Remove messages from a queue using the **removeMessages()** method, which returns a **boolean** for the single message ID variant or the number of removed messages for the filter variant. This method takes a **filter** argument to remove only filtered messages. Setting the filter to an empty string will in effect remove all messages.

#### Counting messages

The number of messages in a queue is returned by the **getMessageCount()** method. Alternatively, the **countMessages()** will return the number of messages in the queue which match a given filter.

#### Changing message priority

The message priority can be changed by using the **changeMessagesPriority()** method which returns a **boolean** for the single message ID variant or the number of updated messages for the filter variant.

### Message counters

Message counters can be listed for a queue with the **listMessageCounter()** and **listMessageCounterHistory()** methods (see [Section 6.6, “Using message counters”](#)). The message counters can also be reset for a single queue using the **resetMessageCounter()** method.

### Retrieving the queue attributes

The **QueueControl** exposes queue settings through its attributes (for example, **getFilter()** to retrieve the queue’s filter if it was created with one, **isDurable()** to know whether the queue is durable, and so on).

### Pausing and resuming queues

The **QueueControl** can pause and resume the underlying queue. When a queue is paused, it will receive messages but will not deliver them. When it is resumed, it will begin delivering the queued messages, if any.

## 6.4.4. Remote resource management operations

You can use the management API to start and stop a broker’s remote resources, such as acceptors, diverts, bridges and so on, so that the broker can be taken offline for a period of time without a full shutdown.

### Acceptors

Start or stop an acceptor using the **start()** or **stop()** method on the **AcceptorControl** class (with the **ObjectName** `org.apache.activemq.artemis:broker="<broker-name>",component=acceptors,name="<acceptor-name>"` or the resource name `acceptor.<address-name>`). Acceptor parameters can be retrieved using the **AcceptorControl** attributes. See [Network Connections: Acceptors and Connectors](#) for more information about Acceptors.

### Diverts

Start or stop a divert using the **start()** or **stop()** method on the **DivertControl** class (with the **ObjectName** `org.apache.activemq.artemis:broker="<broker-name>",component=diverts,name="<divert-name>"` or the resource name `divert.<divert-name>`). Divert parameters can be retrieved using the **DivertControl** attributes.

### Bridges

Start or stop a bridge using the **start()** (resp. **stop()**) method on the **BridgeControl** class (with the **ObjectName** `org.apache.activemq.artemis:broker="<broker-name>",component=bridge,name="<bridge-name>"` or the resource name `bridge.<bridge-name>`). Bridge parameters can be retrieved using the **BridgeControl** attributes.

### Broadcast groups

Start or stop a broadcast group using the **start()** or **stop()** method on the **BroadcastGroupControl** class (with the **ObjectName** `org.apache.activemq.artemis:broker="<broker-name>",component=broadcast-group,name="<broadcast-group-name>"` or the resource name `broadcastgroup.<broadcast-group-name>`). Broadcast group parameters can be retrieved using the **BroadcastGroupControl** attributes. See [Broker discovery methods](#) for more information.

### Discovery groups

Start or stop a discovery group using the **start()** or **stop()** method on the **DiscoveryGroupControl** class (with the **ObjectName** `org.apache.activemq.artemis:broker="<broker-name>",component=discovery-group,name="<discovery-group-name>"` or the resource name

**discovery.<discovery-group-name>**). Discovery groups parameters can be retrieved using the **DiscoveryGroupControl** attributes. See [Broker discovery methods](#) for more information.

### Cluster connections

Start or stop a cluster connection using the **start()** or **stop()** method on the **ClusterConnectionControl** class (with the **ObjectName** **org.apache.activemq.artemis:broker="<broker-name>,component=cluster-connection,name="<cluster-connection-name>"** or the resource name **clusterconnection.<cluster-connection-name>**). Cluster connection parameters can be retrieved using the **ClusterConnectionControl** attributes. See [Creating a broker cluster](#) for more information.

## 6.5. MANAGEMENT NOTIFICATIONS

Review the list of available management notifications and their headers to monitor specific broker events.

Below is a list of all the different kinds of notifications as well as which headers are on the messages. Every notification has a **\_AMQ\_NotifType** (value noted in parentheses) and **\_AMQ\_NotifTimestamp** header. The time stamp is the unformatted result of a call to **java.lang.System.currentTimeMillis()**.

Table 6.1. Management notifications

Notification type	Headers
<b>BINDING_ADDED</b> (0)	<b>_AMQ_Binding_Type</b> <b>_AMQ_Address</b> <b>_AMQ_ClusterName</b> <b>_AMQ_RoutingName</b> <b>_AMQ_Binding_ID</b> <b>_AMQ_Distance</b> <b>_AMQ_FilterString</b>
<b>BINDING_REMOVED</b> (1)	<b>_AMQ_Address</b> <b>_AMQ_ClusterName</b> <b>_AMQ_RoutingName</b> <b>_AMQ_Binding_ID</b> <b>_AMQ_Distance</b> <b>_AMQ_FilterString</b>

Notification type	Headers
<b>CONSUMER_CREATED</b> (2)	_AMQ_Address _AMQ_ClusterName _AMQ_RoutingName _AMQ_Distance _AMQ_ConsumerCount _AMQ_User _AMQ_RemoteAddress _AMQ_SessionName _AMQ_FilterString
<b>CONSUMER_CLOSED</b> (3)	_AMQ_Address _AMQ_ClusterName _AMQ_RoutingName _AMQ_Distance _AMQ_ConsumerCount _AMQ_User _AMQ_RemoteAddress _AMQ_SessionName _AMQ_FilterString
<b>SECURITY_AUTHENTICATION_VIOLATION</b> (6)	_AMQ_User
<b>SECURITY_PERMISSION_VIOLATION</b> (7)	_AMQ_Address _AMQ_CheckType _AMQ_User
<b>DISCOVERY_GROUP_STARTED</b> (8)	name
<b>DISCOVERY_GROUP_STOPPED</b> (9)	name
<b>BROADCAST_GROUP_STARTED</b> (10)	name

Notification type	Headers
<b>BROADCAST_GROUP_STOPPED</b> (11)	<b>name</b>
<b>BRIDGE_STARTED</b> (12)	<b>name</b>
<b>BRIDGE_STOPPED</b> (13)	<b>name</b>
<b>CLUSTER_CONNECTION_STARTED</b> (14)	<b>name</b>
<b>CLUSTER_CONNECTION_STOPPED</b> (15)	<b>name</b>
<b>ACCEPTOR_STARTED</b> (16)	<b>factory</b> <b>id</b>
<b>ACCEPTOR_STOPPED</b> (17)	<b>factory</b> <b>id</b>
<b>PROPOSAL</b> (18)	<b>_JBM_ProposalGroupId</b> <b>_JBM_ProposalValue</b> <b>_AMQ_Binding_Type</b> <b>_AMQ_Address</b> <b>_AMQ_Distance</b>
<b>PROPOSAL_RESPONSE</b> (19)	<b>_JBM_ProposalGroupId</b> <b>_JBM_ProposalValue</b> <b>_JBM_ProposalAltValue</b> <b>_AMQ_Binding_Type</b> <b>_AMQ_Address</b> <b>_AMQ_Distance</b>

Notification type	Headers
<b>CONSUMER_SLOW</b> (21)	<b>_AMQ_Address</b> <b>_AMQ_ConsumerCount</b> <b>_AMQ_RemoteAddress</b> <b>_AMQ_ConnectionName</b> <b>_AMQ_ConsumerName</b> <b>_AMQ_SessionName</b>

## 6.6. USING MESSAGE COUNTERS

You can use message counters to track queue statistics over time and identify usage trends.

For example, you could use message counters to determine how a particular queue is being used over time. You could also attempt to obtain this information by using the management API to query the number of messages in the queue at regular intervals, but this would not show how the queue is actually being used. The number of messages in a queue can remain constant because no clients are sending or receiving messages on it, or because the number of messages sent to the queue is equal to the number of messages consumed from it. In both of these cases, the number of messages in the queue remains the same even though it is being used in very different ways.

### 6.6.1. Types of message counters

Understand the different types of message counters that are available for monitoring queue activity and history.

#### **count**

The total number of messages added to the queue since the broker was started.

#### **countDelta**

The number of messages added to the queue since the last message counter update.

#### **lastAckTimestamp**

The time stamp of the last time a message from the queue was acknowledged.

#### **lastAddTimestamp**

The time stamp of the last time a message was added to the queue.

#### **messageCount**


The current number of messages in the queue.

#### **messageCountDelta**

The overall number of messages added/removed from the queue since the last message counter update. For example, if **messageCountDelta** is **-10**, then 10 messages overall have been removed from the queue.

#### **updateTimestamp**

The time stamp of the last message counter update.



## NOTE

You can combine message counters to determine other meaningful data as well. For example, to know specifically how many messages were consumed from the queue since the last update, you would subtract the **messageCountDelta** from **countDelta**.

### 6.6.2. Enabling message counters

You must enable message counters in the broker configuration file to start collecting queue metrics. Be aware that enabling message counters can have a small impact on the broker's memory.

#### Procedure

1. Open the **<broker\_instance\_dir>/etc/broker.xml** configuration file.
2. Enable message counters.

```
<message-counter-enabled>true</message-counter-enabled>
```

3. Set the message counter history and sampling period.

```
<message-counter-max-day-history>7</message-counter-max-day-history>
<message-counter-sample-period>60000</message-counter-sample-period>
```

#### message-counter-max-day-history

The number of days the broker should store queue metrics. The default is 10 days.

#### message-counter-sample-period

How often (in milliseconds) the broker should sample its queues to collect metrics. The default is 10000 milliseconds.

### 6.6.3. Retrieving message counters

You can use the management API to retrieve message counters.

#### Prerequisites

- Message counters must be enabled on the broker.  
For more information, see [Section 6.6.2, "Enabling message counters"](#).

#### Procedure

- Use the management API to retrieve message counters.

```
// Retrieve a connection to the broker's MBeanServer.
MBeanServerConnection mbsc = ...
JMSQueueControlMBean queueControl =
(JMSQueueControl)MBeanServerInvocationHandler.newProxyInstance(mbsc,
 on,
 JMSQueueControl.class,
 false);

// Message counters are retrieved as a JSON string.
String counters = queueControl.listMessageCounter();
```

```
// Use the MessageCounterInfo helper class to manipulate message counters more easily.
MessageCounterInfo messageCounter = MessageCounterInfo.fromJSON(counters);
System.out.format("%s message(s) in the queue (since last sample: %s)\n",
messageCounter.getMessageCount(),
messageCounter.getMessageCountDelta());
```

#### Additional resources

- [Section 6.4.3, "Queue management operations"](#)

## CHAPTER 7. MONITORING BROKERS FOR PROBLEMS

AMQ Broker includes a tool called the *Critical Analyzer* that actively monitors running brokers for problems such as deadlock conditions.

A problem such as a deadlock condition can be caused by IO errors, a defective disk, memory shortage, or excess CPU usage caused by other processes.

The Critical Analyzer periodically measures the response time for critical operations such as queue delivery (that is, adding of messages to a queue on the broker) and journal operations. If the response time of a checked operation exceeds a configurable timeout value, the broker is considered unstable. In this case, you can configure the Critical Analyzer to simply log a message or take action to protect the broker, such as shutting down the broker or stopping the virtual machine (VM) that is running the broker.

### 7.1. CONFIGURING THE CRITICAL ANALYZER

You can configure the time allowed for Critical Analyzer checks to complete, the interval at which the Critical Analyzer checks run and the response to a check failure.

#### Procedure

1. Open the `<broker_instance_dir>/etc/broker.xml` configuration file.

```
<critical-analyzer>true</critical-analyzer>
<critical-analyzer-timeout>120000</critical-analyzer-timeout>
<critical-analyzer-check-period>60000</critical-analyzer-check-period>
<critical-analyzer-policy>HALT</critical-analyzer-policy>
```

2. Specify parameter values, as described below.

#### **critical-analyzer**

Specifies whether to enable or disable the Critical Analyzer tool. The default value is **true**, which means that the tool is enabled.

#### **critical-analyzer-timeout**

Timeout, in milliseconds, for the checks run by the Critical Analyzer. If the time taken by one of the checked operations exceeds this value, the broker is considered unstable.

#### **critical-analyzer-check-period**

Time period, in milliseconds, between consecutive checks by the Critical Analyzer for each operation.

#### **critical-analyzer-policy**

If the broker fails a check and is considered unstable, this parameter specifies whether the broker logs a message (**LOG**), stops the virtual machine (VM) hosting the broker (**HALT**), or shuts down the broker (**SHUTDOWN**).

Based on the policy option that you have configured, if the response time for a critical operation exceeds the configured timeout value, you see output that resembles one of the following:

**critical-analyzer-policy=LOG**

```
[Artemis Critical Analyzer] 18:11:52,145 ERROR
```

```
[org.apache.activemq.artemis.core.server] AMQ224081: The component
org.apache.activemq.artemis.tests.integration.critical.CriticalSimpleTest$2@5af97850 is
not responsive
```

### **critical-analyzer-policy=HALT**

```
[Artemis Critical Analyzer] 18:10:00,831 ERROR
[org.apache.activemq.artemis.core.server] AMQ224079: The process for the virtual
machine will be killed, as component
org.apache.activemq.artemis.tests.integration.critical.CriticalSimpleTest$2@5af97850 is
not responsive
```

### **critical-analyzer-policy=SHUTDOWN**

```
[Artemis Critical Analyzer] 18:07:53,475 ERROR
[org.apache.activemq.artemis.core.server] AMQ224080: The server process will now be
stopped, as component
org.apache.activemq.artemis.tests.integration.critical.CriticalSimpleTest$2@5af97850 is
not responsive
```

You also see a thread dump on the broker that resembles the following:

```
[Artemis Critical Analyzer] 18:10:00,836 ERROR
[org.apache.activemq.artemis.core.server] AMQ222199: Thread dump: AMQ119001:
Generating thread dump
=====
=====
AMQ119002: Thread Thread[Thread-1 (ActiveMQ-scheduled-threads),5,main] name =
Thread-1 (ActiveMQ-scheduled-threads) id = 19 group =
java.lang.ThreadGroup[name=main,maxpri=10]
sun.misc.Unsafe.park(Native Method)
java.util.concurrent.locks.LockSupport.park(LockSupport.java:175)
java.util.concurrent.locks.AbstractQueuedSynchronizer$ConditionObject.await(AbstractQue
uedSynchronizer.java:2039)
java.util.concurrent.ScheduledThreadPoolExecutor$DelayedWorkQueue.take(ScheduledThr
eadPoolExecutor.java:1088)
java.util.concurrent.ScheduledThreadPoolExecutor$DelayedWorkQueue.take(ScheduledThr
eadPoolExecutor.java:809)
java.util.concurrent.ThreadPoolExecutor.getTask(ThreadPoolExecutor.java:1067)
java.util.concurrent.ThreadPoolExecutor.runWorker(ThreadPoolExecutor.java:1127)
java.util.concurrent.ThreadPoolExecutor$Worker.run(ThreadPoolExecutor.java:617)
java.lang.Thread.run(Thread.java:745)
=====
=====
.....
=====
=====
AMQ119003: End Thread dump
```

*Revised on 2026-04-16 16:31:06 UTC*

