

Installing and Configuring WDS (Windows Deployment Services): Full Images Deployment (Part I)

9–12 minutes


I've prepared a complete guide to configure a **WDS Server on Windows Server 2008 or Windows Server 2003 to deploy complete operating systems images**, this is the first part. In this post I'll be setting the **WDS requirements, installation, first configurations and images needed**.

Introduction

Deploying operating systems it's always a hard thing to do. Annoying, uncomfortable, but necessary for every environment. Why? Because every desktop computer on every organization has their own life cycle (even servers, a longer one, but cycle at last).

Even if your organization doesn't have many desktops and even if those desktops don't seem to need an image refresh in several months; the dynamics of today's technology makes your base operating systems to change: Updates available, service packs, a new version of your organization's software, newer operating systems, etc. And don't forget the consequences of any user's intervention: overloading the hard drive, personal software installation, etc; transforming always into a need to a fresh new installation. No need to keep enumerating things that normally happens; you probably know all of them.

Common Base Image Life Cycle



The bottom line is that a **good and automated system to deploy your full operating systems images will significantly (and I do mean significantly) improve your daily tasks**: Making an awkward job of following the installations steps for maybe 2 or 3 hours and transforming it to 30mins of a complete unattended provisioning. Here's where Windows Deployment Services comes to play.

First of all I want to thank a friend of mine, [Leonardo](#), who made a great "How To", in Spanish, for WDS with Windows Server 2003 SP1, here's the [link](#) to see it. Also you can find the Microsoft document "[Deploying and Managing the Windows Deployment Services Update on Windows Server 2003](#)".

Requirements

- **Windows Server 2008** or **Windows Server 2003 SP2 *** for the WDS server .
- **Active Directory and DNS** up and working.
- **DHCP** server available and authorized by Active Directory on your network. Linux DHCP servers do not need to be authorized by AD.
- On the client side: **NICs PXE compliant**.
Almost all of Network Adapter that are available for several years now are in fact PXE compliant, so I think you don't have to worry about that.

(Optional) And if we want to create our own **unattended files**:

- **Windows Automated Installation Kit (WAIK)**.

We will use of this kit the **Windows System Image Manager** to create our Unattended Files for installation. Here's the [link](#) to download the DVD image for installation.

Hardware Requirements


- **Processor**: No special specs on processor characteristics, but of course to WDS work properly you will need a **Pentium III 800 MHz or higher**.
- **Memory**: 256mb minimum.
- **HD**: Recommended **30 GB of free space** on the disk that will be used for images storing.
It always depends on the images amount of images you will use to deploy. For example, I have over 5 full Vista images (meaning operating system, Office 2007 and several other applications) and less than 10 GB of disk space used.

Installation

To install WDS on a Windows Server 2003 SP2 you only need to add the component from "**Add or Remove Programs**"




To install it on **Windows Server 2008** it is practically the same procedure, just add the Windows Deployment Services role from the “**Add Role Wizard**“. After that, all the configurations tasks are the same, since it is the same snap-in; and you’ll get bonus options using WDS on W2K8, like **multicasting transmissions**. I’ll comment this on the next posts.



** To install Windows Deployment Services on **Windows Server 2003 SP1** first you must install the “Remote Installation Service” (RIS) component, you will not need to configure anything special with this component. After that, you have to use WAIK media: in the options you will find the Windows Deployment Services for installation.*

Configuration

Once installed, access the “**Windows Deployment Services**” snap-in.



On the console, to get started **right-click on the listed server and select “Configure Server”**.

Here are the **considerations** you need to have to configure your server properly.

Configuring the Server

– **After you selected the folder where you are going to store all the images for WDS, you need to check on the DHCP settings.** The wizard will explain you about this option.

Since in my example I have a **Microsoft-DHCP Server working on a different server from the WDS**, these two options will remain unchecked. If you have both, WDS and DHCP, on the same

If a DHCP server is running on the Windows Deployment Services server, Windows Deployment Services must be configured to not listen on port 67 and DHCP Option Tag 60 must be added to all DHCP scopes on your DHCP server. Non-Microsoft DHCP servers require manual configuration of DHCP option tag 60.


If Microsoft DHCP is running on this server click the check boxes to set the following options, if non-Microsoft DHCP is running on this server check the first box and manually configure DHCP option 60:

☐ Do not listen on port 67

☐ Configure DHCP option 60 to 'PXEClient'


server you should check both options.

– **Response Configurations:** This is where you set to which clients you will respond when you receive a PXE request.



The difference between known clients and unknown is set on if the Computer Object exists on Active Directory.

If you want to create the computer objects before running WDS on that computer, you should have the **GUID** of that computer and include that information on the computer object. When you create the object on **Active Directory**, using **“Active Directory Users and Computers”** you need to set that **“This is a managed computer”** and insert the GUID.



Selecting this option can be really annoying if you want to improve your deployment, because you have to add the object first on Active Directory every time that you want to deploy an image, but it's of course the more secure option to apply.

Or you can use the option **“For unknown clients, notify administrator and respond after approval”**. With this option, all the unknown clients that request to boot from PXE will appear to you in **“Pending Devices”** on your console, from there you can approve or decline them.



Or simply use the option **“Respond to all (unknown and known) computer clients”** and when you don't need WDS, you can just stop the service to avoid any rogue clients.

On the final step of the wizard, select to start adding images now are we are ready to go!


Adding Boot Images

Before creating a complete image to be deployed with WDS, we need to **add first a Windows Pre-Installation image (WindowsPE)**. With this image we provide the server with a pre installation environment needed for all installations. WindowsPE comes, as all the new operating systems, in a WIM format, included in the Vista or Windows 2008 installation media.


1 – To add the image, expand the server options on the console and on the “**Boot Images**” select “**Add Boot Image**”. Remember that this WindowsPE that we are adding will be the same for all the operating systems that we are going to use with WDS.



2 – Select “**Browse**” and check on the Vista or Windows 2008 installation media for the folder “**Sources**” and the file “**boot.wim**”. This is our WindowsPE.



3 – Select the name for this image and click on “**Next**”



Note: You can also use, of course, the x64 WindowsPE. Will be discussing it later.

4 – Review the summary and click on “**Next**”.

And now the Windows Pre-Installation Environment is available to boot from your network.

A clean Vista installation?

The procedure to add a clean Vista installation to WDS it's pretty simple and practically the same procedure as for the boot image. As a good practice **you should always have a clean Vista installation available on your server**, here are some reasons:

- 1 – The unattended files that you may use on full images deployment also apply to clean installations.
- 2 – WDS use a **smart storage method, which does not duplicate any installation files**. Meaning that if you save a clean installation of Vista and you add later a full Vista image with several applications included, **all the new information that is stored are the differential (delta) files between those two**.
- 3 – **Rearm activations**: If you use the command line “[*slmgr -rearm*](#)” on the Vista installations to reset back your grace period back to 30 days, you should know that Vista only allows 3 times to run this command. But when you deploy a full image, the times that you can run this command line reduces according to the time when the image was created. But using the clean WIM file extracted from the Vista media, does not have that drawback when you run the rearm command.
- 4 – Having a clean installation always available that you can deploy any time will help you when you need to make changes to the default installation image or when you need to start a new one from the scratch.

Here are the steps (again, you have to use the Vista installation media):


1 – On the WDS console, right click on “**Install Images**” and select “**Add Image Group**”




2 – Select the **name** that you are going to use for this group. For Example: VistaInstallation.




3 – Right click on “**Install Images**” again and select “**Add Install Image**”. When the wizard starts select to use the group you’ve just created and click “**Next**”.



4 – On the next window, browse the Vista media for the folder “**Sources**” and select the file “**install.wim**” and click “**Next**”



5 – Since the Vista installations always include all the versions on the same file, we should select only the one that apply for our case. In my case, **Windows Vista Ultimate**. Click “**Next**”



6 – On the summary window click “**Next**” and the image will start to upload to your server.

At this point **we have all the necessary components to deploy a clean image for Vista from the network; but the installation remains attended**. So, the disk configuration and the Vista options (language, product key, computer name, etc) still need to be manually inserted.

Ok then, after completing the first configurations made on the [Part I](#) of this guide we can perform a clean but attended network installation of Windows Vista.

There are **two main steps** to take and complete a full image and unattended deployment:

1. Creating the base image to deploy: OS, programs and other special configurations + uploading it to the WDS server.

2. Making an unattended file to be used with that image.

Creating the Base Image

Note: *On this series of posts we are only considering to deploy Windows Vista or Windows Server 2008 images. The files used on WDS Native mode as unattended files are only valid to those operating systems, if you want to make unattended deployment with Windows XP or 2003 OS; you will need to use RIS or WDS Legacy Mode.*

The first step it's pretty simple, it consists on installing the operating system with all the features, programs and configurations that you want. But there are some **considerations** first:

After you complete the image, there's a **process where you release all the specific data involving the computer where it's installed**, like the Security Identifier ([SID](#)), computer name, etc. **Here are some of the things that the image won't keep after the release process:**

- **Computer name**
- **Owner and Company name**
- [SID](#)
- **Domain or workgroup membership**
- **TCP/IP Settings**
- **Regional and keyboard settings**
- **Specific hardware drivers.** This refers to specific computer hardware, like video or audio drivers. But if you only applied drivers used on the Windows installation, the same will apply for the deployment, but any other external driver installed will be unavailable.
- **Any saved network connections** (wireless networks saved)
- **OS product key.** This is an important note, since no matter if your product has been activated; the key is reset after this process.

But here are some of the things that **are kept after this release process:**

- **Programs and features installed** (pretty obvious to say that at this moment right?)
- **Local Users and Groups created.**
- **Product Keys used for programs installed.** Meaning if you have Microsoft Office installed, the key used will remain as the same on the deployments.
- **Windows updates installed**
- **User Profiles:** Since all the profiles configuration are basically data stored on the Users folders, all that information will be uploaded within the image.
- **Printers installed.**

All the uploading process is made from the client side; but **we must first prepare the WDS server to be ready to receive images.**


First, we are going to **add a boot image that will be specially to capture operating system images.**

1. Go to WDS Console and let's upload a **second boot image**; it can be the same that we added on the first post using the **boot.wim** from a Vista or Windows Server 2008 media.



2. Instead of naming it Windows PE, use a name like **"Image Capture"**.


3. After the process completes, right click on the image you just added and select **"Create Capture Boot Image"**




Now we have set our WDS server, let's **prepare the client using the sysprep tool** and upload the image:

1. On the Vista or Windows 2008 client open a **"cmd"** as administrator and insert **"cd c:\windows\system32sysprep"**.

2. Run **"sysprep /oobe /generalize /reboot"**.



This process will require for a few second and after it completes the OS will automatically reboot.



3. Soon as the machine is rebooting, press **F12** to select different devices to boot.

4. Select to **boot from the network card connected to the LAN**


Now the client is communicating with the DHCP server to require an IP and a boot image, the DHCP will forward the request to the WDS. You will be prompted to **press F12 one more time**.

```
Network boot from AMD AM79C978A
Copyright (C) 2003-2005 VMware, Inc.
Copyright (C) 1997-2000 Intel Corporation

CLIENT MAC ADDR: 00 0C 29 F2 0C 0E  GUID: 564D826F-16B2-0FA5-8D59-409C2FF20C0E
CLIENT IP:          MASK:          DHCP IP:
GATEWAY IP:

Press F12 for network service boot
-
```

5. Since we have two boot images, let's select "**Image Capture**"




The boot image will start to load.



6. A image capture wizard will start, click on “**Next**”




7. Now let's select the volume we want to capture, in our case **C:**. And put a name for the image that will be uploaded as long with a description.




It's important to note that if the sysprep process did not completed properly no volume will be available to select.

8. On the next window you must select **where the .wim file will be temporary stored locally**. Select to keep it on the root C: (this file it's not uploaded within the image).



9. Select the option **“Load the image to a WDS server”**; put the name of the server and click on **“Connect”**



10. You will be **prompted with credentials**, use a privileged account on the domain or local administrator account of the WDS server.

11. Now select the **image group name** where you want to store the new image and click on **Finish**.

Here the process of the image compression and preparation starts, this could take several minutes (~30 mins to ~1hr) depending on the image size and the hardware involved. After this process, the image is uploaded to the WDS server.

After it completes, check on the **WDS console**, the image should be uploaded and ready to be deployed.

Still we have not configured any unattended file, so the image can be deployed but the entire OS configuration should be entered manually, like on normal OS installation but all the programs will be installed.

At this point we've already installed and properly configured Windows Deployment Server on Windows 2003/Windows 2008 ([Part I](#)); and we created a full image (programs and features installed) on our Windows Vista and uploaded it to the server ([Part II](#)); the only thing missing is creating the answer files that will be used on the images to achieve the full unattended installation of our operating system.

For those using Windows Server 2003 SP1, we reviewed that among the requirements for WDS installation there was installing **Windows Automated Installation Kit**. This kit also gives us an important tool for the unattended files creation, the **Windows System Image Manager**.

So, it's recommended for any other platform used on WDS to [download this kit](#) and install the System Image Manager. This tool it's not a requirement for creating the unattended files.


Installing WAIK



Preparing the Files Using System Image Manager

System Image Manager provides us the way to, using the .wim (or .clg) file for an installation, select the components that are necessary within the answer files. This way we can be sure that the answer options selected are used on the right place at the right time:

1. Open System Image Manager for Start Menu.



2. Click on **File** and click on **Select Windows Image**.
3. Select the .wim file that we previously created or just use the file from the installation media (install.wim).
 1. You can also select the catalog files (.clg): these are the specific files for each Windows Vista version (Home Ed, Enterprise, Ultimate, etc).
4. To start creating, on the File menu select **New answer file**.

Adding a .wim or .clg files is not a requirement, but you won't be able to validate or check the errors on unattended files that is not using an OS image as a reference.

For more information, visit the site [Windows System Image Manager Technical Reference](#).

We'll create two files that are necessary for a complete unattended image installation:
WDSClientUnattend.xml and **AutoUnattend.xml**.

Note: All of the components that we'll add here are associated to 32bit images because the installation file selected has that architecture. If we uploaded a 64bit image, you'll see an answer file with x64 components.

WDSClientUnattend


Download **WDSClientUnattend.xml** example [here](#).

(Change file extension from .doc to .xml to start using it or you can still open it as a Word file).

This is the first file used by WDS to respond to all the first configurations on the Windows PE: Disk partitions (creating, modifying) and selecting the image from WDS that we are going to install.

As you can imagine, all the components that we will add will go on **Windows PE cycle**:

- *x86_Microsoft-Windows-International-Core-WinPE_6.0.6000.16385_neutral\SetupUILanguage*
- *x86_Microsoft-Windows-Setup_6.0.6000.16385_neutral\DiskConfiguration\Disk\CreatePartitions\CreatePartition*
- *x86_Microsoft-Windows-Setup_6.0.6000.16385_neutral\DiskConfiguration\Disk\CreatePartitions\ModifyPartition*
- *x86_Microsoft-Windows-Setup_6.0.6000.16385_neutral\DiskConfiguration\ImageInstall\OSImage\InstallTo*
- *x86_Microsoft-Windows-Setup_6.0.6000.16385_neutral\DiskConfiguration\WindowsDeploymentServices\ImageSelection\InstallImage*
- *x86_Microsoft-Windows-Setup_6.0.6000.16385_neutral\DiskConfiguration\WindowsDeploymentServices\ImageSelection\InstallTo*
- *x86_Microsoft-Windows-Setup_6.0.6000.16385_neutral\DiskConfiguration\WindowsDeploymentServices\Login\Credentials*



Here's an example of all the components and values that can be inserted on the answer file. On the values I have set in here I'm doing the following:

- Setup and keyboard language: English
- Delete and create a single NTFS partition on root disk.
- The partition will take the complete size of the HD.
- Label: system.
- Installation Group: *VistaInstallation*. This is the group that we created when we uploaded the image.
- File: *Install.wim*. This is the name of the installation file that we uploaded.
- Image Name: This is the description name that we used on the installation that we uploaded.
- User and domain name that will be used to login and choose available images. No higher privileges needed on the user.

Component	Values
x86_Microsoft-Windows-International-Core-WinPE_6.0.6000.16385_neutral	InputLocale = <i>en-US</i> UILanguage = <i>en-US</i> UserLocale = <i>en-US</i>
x86_Microsoft-Windows-International-Core-WinPE_6.0.6000.16385_neutral\SetupUILanguage	UILanguage = <i>en-US</i> WillShowUI = <i>OnError</i>
x86_Microsoft-Windows-Setup_6.0.6000.16385_neutral\DiskConfiguration	WillShowUI = <i>OnError</i>
x86_Microsoft-Windows-Setup_6.0.6000.16385_neutral\DiskConfiguration\Disk\	DiskID = <i>0</i> WillWipeDisk = <i>True</i>
x86_Microsoft-Windows-Setup_6.0.6000.16385_neutral\DiskConfiguration\Disk\CreatePartitions\CreatePartition	Extend = <i>True</i> Order = <i>1</i> Type = <i>Primary</i>
x86_Microsoft-Windows-Setup_6.0.6000.16385_neutral\DiskConfiguration\Disk\CreatePartitions\ModifyPartition	Active = <i>True</i> Extend = <i>False</i> Format = <i>NTFS</i> Label = <i>system</i> Letter = <i>C</i> Order = <i>1</i> PartitionID = <i>1</i>
x86_Microsoft-Windows-Setup_6.0.6000.16385_neutral\DiskConfiguration\WindowsDeploymentServices\ImageSelection	WillShowUI = <i>OnError</i>
x86_Microsoft-Windows-Setup_6.0.6000.16385_neutral\DiskConfiguration\WindowsDeploymentServices\ImageSelection\InstallImage	FileName = <i>Install.wim</i> ImageGroup = <i>VistaInstallation</i> ImageName = <i>Windows Vista ULTIMATE</i>
x86_Microsoft-Windows-Setup_6.0.6000.16385_neutral\DiskConfiguration\WindowsDeploymentServices\ImageSelection\InstallTo	DiskID = <i>0</i> PartitionID = <i>1</i>
x86_Microsoft-Windows-Setup_6.0.6000.16385_neutral\DiskConfiguration\WindowsDeploymentServices\Login	WillShowUI = <i>OnError</i>
x86_Microsoft-Windows-Setup_6.0.6000.16385_neutral\DiskConfiguration\WindowsDeploymentServices\Login\Credentials	Domain = <i><DomainName></i> Password = <i><Password></i> UserName = <i><UserName></i>

To confirm that the answer file has no errors, click on **Tools** and **Validate Answer File**. All the errors will be displayed and explained on the lower panel.

Once the file is validated click on **Save** and use the name **WDSClientUnattend**. This file must be stored inside the folder of installation files created by default:

/RemoteInstall/WDSClientUnattend.xml

AutoUnattend

Download **AutoUnattend.xml** example [here](#).

(**Change file extension from .doc to .xml** to start using it or you can still open it as a Word file).

This is the file that we are using to answer all the Vista configurations: Product key, computer name, domain joining, local users and passwords, etc.


The components that need to be added are the following:

Cycle 4: Specialize

- *x86_Microsoft-Windows-Shell-Setup_6.0.6000.16385_Neutral*
- *x86_Microsoft-Windows-UnattendedJoin_neutral\Identification\Credentials*

Cycle 7: OobeSystem

- *x86_Microsoft-Windows-International-Core_6.0.6000.16385_Neutral*
- *x86_Microsoft-Windows-Shell-Setup_6.0.6000.16385_Neutral\OOBE*
- *x86_Microsoft-Windows-Shell-Setup_6.0.6000.16385_Neutral\Themes*
- *x86_Microsoft-Windows-Shell-Setup_6.0.6000.16385_Neutral\UserAccounts\AdministratorPassword*
- *x86_Microsoft-Windows-Shell-Setup_6.0.6000.16385_Neutral\UserAccounts\LocalAccounts\LocalAccount\Password*



Here's an example of the values selected:


- **ComputerName**: If you set the value “*” on the computer name will be selected randomly (using RegisteredOwner value).
- The user name inserted in “**Credentials**” will be the user that will join the computer to the domain. No higher privileges needed for this user, but remember a normal user can only join 10 computers to the domain.
- **ProtectYourPc**: If 1 establishes that the updates will be automatically downloaded and installed.
- **LocalAccount**: User added here will be created locally and in this example is also member of the **Administrators** group.


Component	Value
x86_Microsoft-Windows-Shell-Setup_6.0.6000.16385_Neutral	ComputerName = <ComputerName> ProductKey = <XXXXX-XXXXX-XXXXX-XXXXX-XXXXX> TimeZone = S4 Eastern Standard Time RegisteredOrganization = <CompanyName> (optional) RegisteredOwner = <OwnerName> (optional)
x86_Microsoft-Windows-UnattendedJoin_neutral\Identification	JoinDomain = <DomainName>
x86_Microsoft-Windows-UnattendedJoin_neutral\Identification\Credentials	Domain = <DomainName> Password = <Password> UserName = <UserName> PlainText = False
x86_Microsoft-Windows-International-Core_6.0.6000.16385_Neutral	InputLocale = en-US UILanguage = en-US UserLocale = en-US
x86_Microsoft-Windows-Shell-Setup_6.0.6000.16385_Neutral\OOBE	HideEULAPage = True NetworkLocation = Work ProtectYourPc = 1 SkipUserOOBE = True
x86_Microsoft-Windows-Shell-Setup_6.0.6000.16385_Neutral\Themes	DefaultThemes = Off
x86_Microsoft-Windows-Shell-Setup_6.0.6000.16385_Neutral\UserAccounts\AdministratorPassword	Value = <Password>
x86_Microsoft-Windows-Shell-Setup_6.0.6000.16385_Neutral\UserAccounts\LocalAccounts\LocalAccount	DisplayName = <UserNameToShow> Name = <UserName> Group = Administrators
x86_Microsoft-Windows-Shell-Setup_6.0.6000.16385_Neutral\UserAccounts\LocalAccounts\LocalAccount\Password	Value = <Password>

To confirm that the answer file has no errors, click on **Tools** and **Validate Answer File**. All the errors will be displayed and explained on the lower panel.

Once the file is validated click on **Save** and use the name **AutoUnattend**. You can locate this answer file on any folder.

Note: A good thing about System Image Manager is that for each component that you have here, you can access to the description of it. If you have any doubt on the values that you are placing, take a look to the help file.





Associating Unattended Files


Now that we have the both files necessary, all we need is to associate each file to the images we are going to install:

1. Associating **WDSClientUnattend**.

- a) Open the WDS console on your server.
- b) On the servers listed on the snap-in, right click on the server name and select **Properties**.
- c) Open **Client** and select **Enable Unattended Installations**.
- d) According to the architecture where you created the image, browse for the **WDSClientUnattend.xml** file.

2. Associating **AutoUnattend**

- a) On the **Installation Images**, open **VistaInstallation**.
- b) Right click on the image that you uploaded and select **Properties**.
- c) Select the option **Allow image to install in unattended mode**.



d) Click on **Select File** and browse for **AutoUnattend.xml**.

And there you go; you have the complete environment to install full and unattended images of Windows Vista.

You have to remember that at the moment of booting a client machine, once you've selected the WindowsPE image to boot, the **complete installation process will not require any user intervention**. If you have to select on clients different disk options or partitions, you can deselect the option where you choose the WDSClientUnattend file; with this you'll get to manually introduce any changes on image selection and disk management.


Common Issue on x64 images and WDS

I've encountered that there are some scenarios that the **64bits images are not available for selection on a deployment**, even though you have correctly uploaded to the WDS Server and the client supports x64 architecture.

The problem is that when the client connects to the WDS Server (soon after you pressed F12 to boot from the network) it doesn't notify that it is x64 compatible client. And for the server, the client is just x86 compatible and the rest of the images do not apply for it.

To solve it:

1. Open a **cmd** on the WDS Server
2. Insert **WDSUTIL /set-server /architecturediscovery:yes**



```
Administrator: Command Prompt
Microsoft Windows [Version 6.0.6001]
Copyright (c) 2006 Microsoft Corporation. All rights reserved.

C:\Users\Augusto>WDSUTIL /set-server /architecturediscovery:yes_
```

And the next time any client contacts the WDS Server, will first notify about if is x64 compatible.