SMB Connect User Guide

v0.5.5 (build 14) · 31 July 2026

Overview

SMB Connect is a menu bar app for connecting to SMB shares by IP address while preferring the fastest configured network path.

Typical uses:

- connect to the same storage over `10GbE` when available and `1GbE` when not
- keep several shares ready in one menu bar utility
- preload share definitions from JSON or MDM
- let each user store their own password locally in Keychain

How To Use The App

1. Open The Menu Bar App

Click the SMB Connect drive icon in the macOS menu bar.

The popover shows:

- a top banner with current active wired network information
- a `Connection Summary` section
- a `Shares` section with one status card per configured share
- `Refresh` and `Connect All` as the main actions at the bottom
- a row beneath them with `Settings`, `Help`, `Check for Updates`, and `Quit`
- the app version in that same row for a quick peek (also shown, with build number, in the bottom-left of the Settings window)

`Connect All` is highlighted as the primary action. Hover any of the smaller buttons for a description of what it does.

The top banner and the bottom action rows (including `Quit`) stay pinned in place. Only the `Connection Summary` and `Shares` sections scroll, so the title and buttons remain visible no matter how many shares you have configured.

2. Read The Connection Summary

The `Connection Summary` section gives a quick count of:

- `Mounted`
- `Preferred`
- `Fallback`
- `Attention`

Below that is a one-line summary per share so you can quickly scan which shares are connected and on what network speed.

3. Read A Share Card

Each share card is centered on one configured share alias.

A card shows:

- the share alias
- the SMB share name
- a status icon and a source badge, at the top right
- a `Connection` pill
- a `Status` pill
- a `Network` pill
- a summary line
- a detail line
- an action button such as `Connect`, `Disconnect`, `Fix Connection…`, or `Complete Setup…`

Long share names are shortened with a trailing `…`. Hover the name to see it in full.

Status Icon Legend

The icon at the top right of each card is an at-a-glance version of the same state the `Connection` and `Status` pills spell out below it. Hover any icon to see its wording.

Icon	Meaning	What to do
✅ green check	Connected — the share is mounted	Nothing
◌ blue dashed circle	Ready — a network path is reachable and credentials are saved	Press `Connect`
🚫 grey crossed-out Wi-Fi	Not connected — no configured endpoint responded on port 445	Check the server is on and reachable
🔑 yellow key	Setup needed — no credentials saved for this share	Press `Complete Setup…`
⚠️ red triangle	Mounted wrong, or a duplicate mount was found	Press `Fix Connection…`
⛔ red octagon	Blocked — a `/Volumes` name conflict is preventing the mount	See *What To Do For A Volume Name Conflict*
❌ red cross octagon	Error	Read the detail line beneath the card

Source Badge

Beside the status icon, a badge shows where the share's configuration came from:

- `User` — added by you in Settings
- `JSON` — imported from a setup file
- `MDM` — supplied by a managed configuration profile and locked

4. Understand The Main Pills

Connection

This tells you the broad connection state:

- `Connected`
- `Ready`
- `Blocked`
- `Not Connected`
- `Error`

Status

This tells you whether the share is on the expected path:

- `Preferred`
- `Fallback`
- `Fix Needed`
- `Duplicate`
- `Setup`
- `Blocked`

There may also be a second share-state pill such as:

- `Mounted`
- `Available`
- `Reconnect`
- `Setup Needed`
- `Rename /Volumes Item`

Network

This shows the current or selected network speed for that share, for

example:

- `1GbE`
- `10GbE`
- `25GbE`
- `100GbE`

5. Use Connect All

The `Connect All` button (`⌘K`) in the footer connects every share that is currently in a ready state — meaning the preferred or fallback network path is reachable and credentials are saved in Keychain.

It is disabled when no shares are connectable (for example, when all shares are already mounted or no network paths are active).

Shares with missing credentials, name conflicts, or duplicate mounts are skipped and must be resolved individually.

What The Main States Mean

Connected On Preferred Network

The share is mounted and the app believes it is using the fastest configured preferred path.

Connected On Fallback Network

The share is mounted, but the preferred path is not active or not selected.

Preferred Network Available

The share is not mounted yet, but the preferred network path appears

The share is not mounted yet, but the preferred network path appears reachable and ready.

Fallback Network Available

The share is not mounted yet, but only a slower fallback path appears available right now.

Complete Setup

The share definition is present, but the user has not yet saved credentials in Keychain.

Duplicate Mount Detected

The app has detected multiple mounted instances such as:

- `Video`
- `Video-1`

This is a warning condition and should usually be repaired before continuing work.

Mount detection only looks at genuine network shares mounted under `/Volumes`. macOS system and automounted volumes — such as the `auto_home` map that appears as a non-local volume literally named `home` at `/System/Volumes/Data/home` — are ignored, so a share whose name matches a system volume (for example a share called `Home`) no longer shows a false `Mounted Wrong` or duplicate state.

Notifications

When a share *newly* enters an attention state — a genuine duplicate, a wrong-path mount, or a `/Volumes` name conflict — SMB Connect posts a

single, quiet macOS notification so you are told without having to open the popover. macOS asks for notification permission the first time the app runs; you can change it later in System Settings → Notifications → SMB Connect.

Volume Name Conflict

The app found a local file or folder in `/Volumes` that already uses the share's mount name.

Example:

- local folder: `/Volumes/Video`
- intended share mount: `Video`

If the app mounted anyway, macOS could create `Video-1`, which is exactly what SMB Connect is trying to prevent.

Why `-1` Mount Paths Matter

If macOS mounts a share as `Video-1`, applications may record file paths using that full mounted path.

That is especially risky in Final Cut Pro because relinking later can become more difficult if media paths were recorded using a suffixed mount name.

SMB Connect tries to prevent this by:

- warning when duplicate mounts already exist
- blocking connects when a `/Volumes` name conflict would cause a `-1` mount

mount

- offering repair guidance and reconnect workflows

What To Do For A Volume Name Conflict

If the menu shows `Volume Name Conflict`:

1. Click `Open /Volumes in Finder`.
2. Inspect the conflicting item.
3. Rename or remove the local item that is occupying the intended mount name.
4. Return to SMB Connect and press `Refresh`.
5. Connect again.

If files are already open from that share, quit those apps first.

What `Refresh` Does

`Refresh` does four things:

- re-evaluates any MDM managed preferences pushed since the last refresh
- rescans the setup folder for new JSON setup files
- rechecks active local network interfaces and reachability
- refreshes mounted volume and conflict status

Use it after:

- dropping a new setup JSON into the setup folder
- an MDM policy change is pushed to the device
- changing networks

- changing networks
- renaming or removing an item in `/Volumes`
- disconnecting or reconnecting shares outside the app

In-App Help

You do not need this guide open to get going. SMB Connect has help built in.

Press the `?` button in the menu bar popup, or open **Settings** → **Help** → **Getting Started**. The Help window has two tabs:

- **Quick Start** — adding a share, saving credentials, connecting, and a visual legend for the status icons, plus how to make mounting fully automatic.
- **Advanced** — preferred and fallback network paths, shares over VPN, duplicate mounts and `-1` paths, volume name conflicts, deploying to many Macs, update checking, and what `Refresh` does.

Both tabs link back to this full guide.

Checking For Updates

SMB Connect can tell you when a newer version has been published.

On demand — press `Check for Updates…` in the footer of the menu bar popup. This always checks and always reports back, including when nothing newer exists. If your copy is newer than the published release, it says so and names both versions rather than claiming a match.

Automatically — the app also checks quietly when it launches, at most once every 24 hours. This check is silent unless a newer version is found, in which case an alert offers a `Download` button that opens the release page in your browser.

Nothing is downloaded or installed for you. The check reads only the published version number and compares it against the running app, and no information about your Mac or your share configuration is sent.

Pre-release builds are not offered. You will only be told about full releases.

Settings Window

Open `Settings…` from the menu bar popover.

The Settings window has a left sidebar and a right detail pane.

Sidebar

The sidebar contains:

- `General`
- `Shares`

The `Shares` list shows each configured share alias, source, and preferred network summary.

General Section

This contains:

- `Launch at login`
- `Connect all shares on start`

- `Connect all shares on start`
- `Auto-reconnect dropped shares`
- `Setup Folder`
- `Refresh Status`

`Launch at login` registers the app with macOS to open automatically when the user logs in.

`Connect all shares on start` automatically connects every share that is in a ready state after the app finishes its first status check on launch. This works the same as pressing `Connect All` manually — only shares with saved credentials and a reachable network path are attempted. Shares with issues are skipped.

`Auto-reconnect dropped shares` monitors connected shares and automatically reconnects any that drop while the server is still reachable. When a share transitions from mounted to unmounted and SMB Connect can still reach the server on TCP port 445, the app disconnects any stale mount points and reconnects cleanly via the best available network path. A 60-second cooldown per share prevents rapid-fire reconnect attempts if the server is flapping. This is enabled by default.

Pairing `Launch at login` with `Connect all shares on start` and `Auto-reconnect dropped shares` gives a fully automatic mount experience: the app opens at login, connects all ready shares without any user interaction, and keeps them connected if a transient network drop occurs.

`Setup Folder` is where the app looks for setup JSON files on startup and refresh:

`~/Library/Application Support/SMBConnect/Setup`

Import / Export

Import / Export

This section is for:

- `Import JSON…`
- `Export JSON…`
- `Open Setup Folder`

Use `Import JSON…` to load a setup file manually from anywhere.

Use `Export JSON…` to save the current user-editable share definitions as JSON.

Passwords are not exported.

If you need to create a valid setup JSON file and a matching MDM `.mobileconfig` from a server list, the repo includes a helper script:

- generate_smbconnect_config.sh

It accepts a comma-separated `.csv` or `.txt` file using:

```
alias,protocol,shareName,mountName,defaultUsername,note,preferredI
```

and generates both output formats for SMB Connect.

Examples and usage details are here:

- Config Generator README

Share Settings

This section defines the core share identity.

Fields:

- `Source` Admin or config origin, such as user-defined, imported JSON,

- `Source` Admin or config origin, such as user-defined, imported JSON, or MDM-managed.
- `Preferred Network` The first-choice network path for this share.
- `Alias` The display name shown in the menu bar.
- `Protocol` Currently `smb`.
- `Share Name` The SMB share path, such as `Outputs` in `smb://server/Outputs`.
- `Mount Name` The volume name expected in `/Volumes` after the share is mounted.
- `Default Username` A suggested username for the user.
- `Notes` Optional comments about the share.

Network Paths

This section defines one or more IP-based paths to the same share.

Typical use:

- one preferred `10GbE` path
- one fallback `1GbE` path

For each network path, the app shows:

- `Server IP`
- `Network Speed`
- `Priority`
- `Subnet`

- `Label`

Lower priority numbers are preferred first.

Reachability over VPN. SMB Connect prefers an endpoint whose `Server IP` is on the same subnet as one of your Mac's local interfaces (your fast local path). If none of those respond, it then tries every other configured endpoint and connects to whichever actually answers on SMB (TCP port 445). This means a share reachable only through a VPN — WireGuard, Tailscale, a corporate tunnel, or a routed/inter-VLAN path — connects normally even though your `utun` address is on a different subnet than the NAS. When a connection is made over such a routed path, the status detail tags it `(via VPN)`, for example `Current network: 1GbE · 192.168.1.50 (via VPN)`, so an over-the-tunnel connection is always visible.

Credentials

This section stores the user's login details in Keychain.

Fields:

- `Username`
- `Password`

Actions:

- `Save Credentials`
- `Delete Credentials`

Important:

- passwords are saved locally in Keychain
- passwords are not stored in JSON

- passwords are not stored in JSON
- passwords are not stored in the MDM profile

Current Status

This section shows the live status for the selected share and any repair guidance.

If the share needs repair or attention, this section explains why.

Ways To Create Configuration

There are several ways to produce share definitions, depending on what you start from. They all end in one of two artifacts: a **setup JSON** (imported per user in the app) or an **MDM `.mobileconfig` profile** (pushed by IT).

Starting point	Tool	Produces
Typing shares by hand	The app's `Settings…` window	Local config (export to JSON)
Shares	**Mount Import Assistant** app, or	Setup JSON

Shares already mounted on a Mac	**Mount Import Assistant** app, or `mount_to_smbconnect_config.sh`	Setup JSON
A spreadsheet / server list	`generate_smbconnect_config.sh`	Setup JSON **and** `.mobileconfig`
An existing setup JSON	`json_to_mobileconfig.sh`	`.mobileconfig`

- **In the app** — add and edit shares in `Settings…`, then `Export` to a JSON file for backup or to seed another Mac. See `Import / Export` above.
- **Mount Import Assistant** — a small companion app that reads the SMB shares already mounted on a Mac and writes a setup JSON, so you can bootstrap a config from a machine that is already working. The same workflow is available on the command line via

same workflow is available on the command line via `mount_to_smbconnect_config.sh`. See scripts/README-mount-import.md.

- **Generator script** — turn a `.csv` / `.txt` server list into both a setup JSON and a matching profile in one step. See scripts/README-config-generator.md.
- **JSON → profile converter** — when you already have a setup JSON and just need the deployable MDM profile. See scripts/README-json-to-mobileconfig.md.

JSON Configuration

SMB Connect can import and export JSON share definitions.

JSON is useful for:

- bootstrapping users
- copying a setup to another Mac
- keeping a backup of share definitions

JSON can define:

- alias
- protocol
- share name
- mount name
- default username
- one or more network paths

- one or more network paths
- path priority
- notes

Passwords are intentionally omitted.

See:

- Configuration Format
- SMBConnectSetup-EXAMPLE.json
- SMBConnectSetup-DEMO-SIX-SERVERS.json

MDM Profile Configuration

SMB Connect also supports an MDM profile that preloads managed share definitions.

This is useful when IT wants to push:

- share aliases
- share names
- mount names
- preferred and fallback IPs
- network speed labels
- default usernames

- default usernames

The user can still enter and store their own password locally in Keychain.

You can build the profile directly from a setup JSON with `json_to_mobileconfig.sh`:

```
./scripts/json_to_mobileconfig.sh \
  -i ./Config/SMBConnectSetup-AVNAS.json \
  -o ./Config/generated/SMBConnectSetup-AVNAS.mobileconfig \
  --organization "Your Org"
```

Two options shape how the profile behaves on the user's Mac:

- `--allow-user-defined true|false` — with `true` (the default) a deployed profile **keeps** each user's own imported shares and merges the managed ones on top, so pushing a profile does not wipe a user's existing setup. With `false`, the app shows only the managed shares.
- `--blank-username` — leave each managed share's `defaultUsername` empty so every user enters their own. Without it, the username from the JSON is baked into the profile and is identical (and locked) for all users on the device.

Passwords are never written to the profile.

Entering Credentials For A Managed Share

A managed share is preloaded read-only, but its username and password are not part of the profile. To finish setup, open `Settings…`, select the managed share, and enter the username and password in the `Credentials` section — they are saved to the user's Keychain and reused on every connect.

> **Requires app v0.5.2 or later.** Earlier builds regenerated a managed share's internal identity on every refresh (about every 20 seconds), which reset the Settings selection and blanked the credential fields as you typed, and prevented saved credentials from being reloaded. v0.5.2 gives managed shares a stable identity so credentials can be entered once and persist. If you deployed an earlier build, install v0.5.2 and re-enter the credentials once; the profile itself does not need to be redeployed.

See:

- com.matx.SMBConnect.mobileconfig
- scripts/README-json-to-mobileconfig.md

Recommended Admin Workflow

1. Create share definitions using one of the methods in Ways To Create Configuration — type them in the app, import existing mounts with the Mount Import Assistant, or generate them from a server list.
2. Preload alias, share name, mount name, and preferred/fallback IPs.
3. Optionally preload a default username, or use `--blank-username` so each user supplies their own.
4. To deploy by MDM, convert the JSON with `json_to_mobileconfig.sh` (or generate the profile directly). Keep `--` unless you want to lock users to only the

`allow-user-defined true` unless you want to lock users to only the managed shares.

5. Let the user open the app and save their password locally in Keychain.
6. Have the user connect from the menu bar app.

Recommended User Workflow

1. Open SMB Connect from the menu bar.
2. Open `Settings…` if a share shows `Complete Setup`.
3. Save your username and password in the `Credentials` section.
4. Return to the menu bar app.
5. Press `Connect All` to mount all ready shares in one action, or connect individual shares as needed.
6. If warned about duplicate mounts or `/Volumes` conflicts, resolve those before editing media.

To connect automatically on every login, enable both `Launch at login` and `Connect all shares on start` in Settings → General.

Troubleshooting

The Share Does Not Connect

Check:

- the configured IP address
- whether the preferred or fallback network is actually active
- whether credentials were saved in Keychain
- whether the target SMB server is reachable

The App Says `Volume Name Conflict`

There is already a local item in `/Volumes` using the mount name. Open `/Volumes`, inspect the item, then rename or remove it before connecting.

The App Says `Duplicate Mount Detected`

The share appears mounted more than once. Use the repair workflow or manually disconnect all matching mounts and reconnect only once.

The Share Mounted On The Wrong Network

If the app says the share is on a fallback or slower path, use the repair flow to disconnect and reconnect on the preferred network when available.

> **Fixed in v0.5.3.** Earlier builds (v0.5.1 and v0.5.2) could falsely report `Mounted Wrong` or a duplicate for a share whose name matched a macOS system/autofs volume — most commonly a share called `Home`, which collided with the built-in `auto_home` volume named `home` — even though there was no real mount and no `-1` volume in `/Volumes`. v0.5.3 restricts detection to genuine network shares under `/Volumes`. If you saw this, install v0.5.3 and press `Refresh`.

A Share Keeps Disconnecting And Reconnecting

If a share repeatedly drops and auto-reconnects, the underlying NAS or network path is unstable. SMB Connect enforces a 60-second cooldown between reconnect attempts for the same share to prevent thrashing.

between reconnect attempts for the same share to prevent thrashing. Check:

- the physical network connection to the NAS
- whether the NAS is under heavy load or restarting services
- whether a VPN or firewall is intermittently blocking SMB traffic on port 445

If the flapping continues, consider disabling `Auto-reconnect dropped shares` in Settings → General until the network issue is resolved.

Auto-Reconnect Is Not Triggering

Auto-reconnect only fires when the share transitions from mounted to unmounted while the server is still reachable. It will not trigger if:

- the server itself is down or unreachable (the share shows `Unavailable`, not `Ready`)
- the share was never mounted in the current session (the app must have seen it mounted at least once)
- the 60-second cooldown from a previous reconnect attempt has not elapsed
- `Auto-reconnect dropped shares` is turned off in Settings → General