

ISP Router

```
enable
configure terminal

hostname ISP

interface FastEthernet0/0
 ip address 100.0.0.1 255.255.255.252
 no shutdown

interface FastEthernet1/0
 ip address 100.0.0.5 255.255.255.252
 no shutdown

router bgp 65000
 neighbor 100.0.0.2 remote-as 65001
 neighbor 100.0.0.6 remote-as 65002

end
write
```

CORE-1

```
enable
configure terminal

hostname CORE-1

access-list 1 permit 192.168.0.0 0.0.255.255

ip nat inside source list 1 interface FastEthernet0/0 overload

interface FastEthernet0/0
 ip address 100.0.0.2 255.255.255.252
 ip nat outside
 no shutdown

interface FastEthernet1/0
 ip address 192.168.0.1 255.255.255.252
 ip nat inside
 no shutdown

interface FastEthernet2/0
 ip address 192.168.0.5 255.255.255.252
 ip nat inside
 no shutdown

interface FastEthernet3/0
 ip address 192.168.0.9 255.255.255.252
 ip nat inside
 no shutdown
```

```
interface FastEthernet4/0
 ip address 192.168.0.13 255.255.255.252
 ip nat inside
 no shutdown

interface FastEthernet5/0
 ip address 192.168.0.17 255.255.255.252
 ip nat inside
 no shutdown

interface FastEthernet6/0
 ip address 192.168.0.21 255.255.255.252
 ip nat inside
 no shutdown

interface FastEthernet7/0
 ip address 192.168.0.49 255.255.255.252
 ip nat inside
 no shutdown

router bgp 65001
 neighbor 100.0.0.1 remote-as 65000
 neighbor 192.168.0.2 remote-as 65011
 neighbor 192.168.0.6 remote-as 65012
 neighbor 192.168.0.10 remote-as 65013
 neighbor 192.168.0.14 remote-as 65014
 neighbor 192.168.0.18 remote-as 65015
 neighbor 192.168.0.22 remote-as 65016
 neighbor 192.168.0.50 remote-as 65002

ip route 0.0.0.0 0.0.0.0 100.0.0.1

end
write
```

CORE-2

```
enable
configure terminal

hostname CORE-2

access-list 1 permit 192.168.0.0 0.0.255.255

ip nat inside source list 1 interface FastEthernet0/0 overload

interface FastEthernet0/0
 ip address 100.0.0.6 255.255.255.252
 ip nat outside
 no shutdown

interface FastEthernet1/0
 ip address 192.168.0.25 255.255.255.252
 ip nat inside
 no shutdown
```

```
interface FastEthernet2/0
 ip address 192.168.0.29 255.255.255.252
 ip nat inside
 no shutdown

interface FastEthernet3/0
 ip address 192.168.0.33 255.255.255.252
 ip nat inside
 no shutdown

interface FastEthernet4/0
 ip address 192.168.0.37 255.255.255.252
 ip nat inside
 no shutdown

interface FastEthernet5/0
 ip address 192.168.0.41 255.255.255.252
 ip nat inside
 no shutdown

interface FastEthernet6/0
 ip address 192.168.0.45 255.255.255.252
 ip nat inside
 no shutdown

interface FastEthernet7/0
 ip address 192.168.0.50 255.255.255.252
 ip nat inside
 no shutdown

router bgp 65002
 neighbor 100.0.0.5 remote-as 65000
 neighbor 192.168.0.26 remote-as 65017
 neighbor 192.168.0.30 remote-as 65018
 neighbor 192.168.0.34 remote-as 65019
 neighbor 192.168.0.38 remote-as 65020
 neighbor 192.168.0.42 remote-as 65021
 neighbor 192.168.0.46 remote-as 65022
 neighbor 192.168.0.49 remote-as 65001

ip route 0.0.0.0 0.0.0.0 100.0.0.5

end
write
```

DR-1

```
enable
configure terminal

hostname DR-1

interface FastEthernet0/0
 ip address 192.168.0.2 255.255.255.252
```

```
no shutdown

interface FastEthernet1/0
 ip address 192.168.1.2 255.255.255.0
 standby 1 ip 192.168.1.1
 standby 1 priority 110
 standby 1 preempt
 no shutdown

router bgp 65011
 neighbor 192.168.0.1 remote-as 65001
 network 192.168.1.0 mask 255.255.255.0

ip route 0.0.0.0 0.0.0.0 192.168.0.1

end
write
```

BDR-1

```
enable
configure terminal

hostname BDR-1

interface FastEthernet0/0
 ip address 192.168.0.26 255.255.255.252
 no shutdown

interface FastEthernet1/0
 ip address 192.168.1.3 255.255.255.0
 standby 1 ip 192.168.1.1
 standby 1 priority 100
 standby 1 preempt
 no shutdown

router bgp 65017
 neighbor 192.168.0.25 remote-as 65002
 network 192.168.1.0 mask 255.255.255.0

ip route 0.0.0.0 0.0.0.0 192.168.0.25

end
write
```

DR-2

```
enable
configure terminal

hostname DR-2
```

```
interface FastEthernet0/0
 ip address 192.168.0.6 255.255.255.252
 no shutdown

interface FastEthernet1/0
 ip address 192.168.2.2 255.255.255.0
 standby 1 ip 192.168.2.1
 standby 1 priority 110
 standby 1 preempt
 no shutdown

router bgp 65012
 neighbor 192.168.0.5 remote-as 65001
 network 192.168.2.0 mask 255.255.255.0

ip route 0.0.0.0 0.0.0.0 192.168.0.5

end
write
```

BDR-2

```
enable
configure terminal

hostname BDR-2

interface FastEthernet0/0
 ip address 192.168.0.30 255.255.255.252
 no shutdown

interface FastEthernet1/0
 ip address 192.168.2.3 255.255.255.0
 standby 1 ip 192.168.2.1
 standby 1 priority 100
 standby 1 preempt
 no shutdown

router bgp 65018
 neighbor 192.168.0.29 remote-as 65002
 network 192.168.2.0 mask 255.255.255.0

ip route 0.0.0.0 0.0.0.0 192.168.0.29

end
write
```

DR-3

```
enable
configure terminal
```

```
hostname DR-3

interface FastEthernet0/0
 ip address 192.168.0.10 255.255.255.252
 no shutdown

interface FastEthernet1/0
 ip address 192.168.3.2 255.255.255.0
 standby 1 ip 192.168.3.1
 standby 1 priority 110
 standby 1 preempt
 no shutdown

router bgp 65013
 neighbor 192.168.0.9 remote-as 65001
 network 192.168.3.0 mask 255.255.255.0

ip route 0.0.0.0 0.0.0.0 192.168.0.9

end
write
```

BDR-3

```
enable
configure terminal

hostname BDR-3

interface FastEthernet0/0
 ip address 192.168.0.34 255.255.255.252
 no shutdown

interface FastEthernet1/0
 ip address 192.168.3.3 255.255.255.0
 standby 1 ip 192.168.3.1
 standby 1 priority 100
 standby 1 preempt
 no shutdown

router bgp 65019
 neighbor 192.168.0.33 remote-as 65002
 network 192.168.3.0 mask 255.255.255.0

ip route 0.0.0.0 0.0.0.0 192.168.0.33

end
write
```

DR-4

```
enable
configure terminal

hostname DR-4

interface FastEthernet0/0
 ip address 192.168.0.14 255.255.255.252
 no shutdown

interface FastEthernet1/0
 ip address 192.168.4.2 255.255.255.0
 standby 1 ip 192.168.4.1
 standby 1 priority 110
 standby 1 preempt
 no shutdown

router bgp 65014
 neighbor 192.168.0.13 remote-as 65001
 network 192.168.4.0 mask 255.255.255.0

ip route 0.0.0.0 0.0.0.0 192.168.0.13

end
write
```

BDR-4

```
enable
configure terminal

hostname BDR-4

interface FastEthernet0/0
 ip address 192.168.0.38 255.255.255.252
 no shutdown

interface FastEthernet1/0
 ip address 192.168.4.3 255.255.255.0
 standby 1 ip 192.168.4.1
 standby 1 priority 100
 standby 1 preempt
 no shutdown

router bgp 65020
 neighbor 192.168.0.37 remote-as 65002
 network 192.168.4.0 mask 255.255.255.0

ip route 0.0.0.0 0.0.0.0 192.168.0.37

end
write
```

DR-5

```
enable
configure terminal

hostname DR-5

interface FastEthernet0/0
 ip address 192.168.0.18 255.255.255.252
 no shutdown

interface FastEthernet1/0
 ip address 192.168.5.2 255.255.255.0
 standby 1 ip 192.168.5.1
 standby 1 priority 110
 standby 1 preempt
 no shutdown

router bgp 65015
 neighbor 192.168.0.17 remote-as 65001
 network 192.168.5.0 mask 255.255.255.0

ip route 0.0.0.0 0.0.0.0 192.168.0.17

end
write
```

BDR-5

```
enable
configure terminal

hostname BDR-5

interface FastEthernet0/0
 ip address 192.168.0.42 255.255.255.252
 no shutdown

interface FastEthernet1/0
 ip address 192.168.5.3 255.255.255.0
 standby 1 ip 192.168.5.1
 standby 1 priority 100
 standby 1 preempt
 no shutdown

router bgp 65021
 neighbor 192.168.0.41 remote-as 65002
 network 192.168.5.0 mask 255.255.255.0

ip route 0.0.0.0 0.0.0.0 192.168.0.41

end
write
```


DR-6

```
enable
configure terminal

hostname DR-6

interface FastEthernet0/0
 ip address 192.168.0.22 255.255.255.252
 no shutdown

interface FastEthernet1/0
 ip address 192.168.6.2 255.255.255.0
 standby 1 ip 192.168.6.1
 standby 1 priority 110
 standby 1 preempt
 no shutdown

router bgp 65016
 neighbor 192.168.0.21 remote-as 65001
 network 192.168.6.0 mask 255.255.255.0

ip route 0.0.0.0 0.0.0.0 192.168.0.21

end
write
```

BDR-6

```
enable
configure terminal

hostname BDR-6

interface FastEthernet0/0
 ip address 192.168.0.46 255.255.255.252
 no shutdown

interface FastEthernet1/0
 ip address 192.168.6.3 255.255.255.0
 standby 1 ip 192.168.6.1
 standby 1 priority 100
 standby 1 preempt
 no shutdown

router bgp 65022
 neighbor 192.168.0.45 remote-as 65002
 network 192.168.6.0 mask 255.255.255.0

ip route 0.0.0.0 0.0.0.0 192.168.0.45
```

end
write