LAB - Unique Constraint

In this lab, you will learn how to use SQL Server UNIQUE constraint to ensure the uniqueness of data contained in a column or a group of columns.

SQL Server UNIQUE constraints allow you to ensure that the data stored in a column, or a group of columns, is unique among the rows in a table.

The following statement creates a table whose data in the email column is unique among the rows in the hr.persons table:

```
CREATE SCHEMA hr;

GO

CREATE TABLE hr.persons(
    person_id INT IDENTITY PRIMARY KEY,
    first_name VARCHAR(255) NOT NULL,
    last_name VARCHAR(255) NOT NULL,
    email VARCHAR(255) UNIQUE

);
```

In this syntax, you define the UNIQUE constraint as a column constraint. You can also define the UNIQUE constraint as a table constraint, like this:

```
CREATE TABLE hr.persons(
    person_id INT IDENTITY PRIMARY KEY,
    first_name VARCHAR(255) NOT NULL,
    last_name VARCHAR(255) NOT NULL,
    email VARCHAR(255),
    UNIQUE(email)
);
```

Behind the scenes, SQL Server automatically creates a UNIQUE index to enforce the uniqueness of data stored in the columns that participate in the UNIQUE constraint. Therefore, if you attempt to insert a duplicate row, SQL Server rejects the change and returns an error message stating that the UNIQUE constraint has been violated.

The following statement inserts a new row into the hr.persons table:

```
INSERT INTO hr.persons(first_name, last_name, email)
VALUES('John','Doe','j.doe@bike.stores');
```

The statement works as expected. However, the following statement fails due to the duplicate email:

```
INSERT INTO hr.persons(first_name, last_name, email)
VALUES('Jane','Doe','j.doe@bike.stores');
```

SQL Server issued the following error message:

```
Violation of UNIQUE KEY constraint 'UQ__persons__AB6E616417240E4E'. Cannot insert duplicate key in object 'hr.persons'. The duplicate key value is (j.doe@bike.stores).
```

If you don't specify a separate name for the UNIQUE constraint, SQL Server will automatically generate a name for it. In this example, the constraint name is UQ__persons__AB6E616417240E4E , which is not quite readable.

To assign a particular name to a UNIQUE constraint, you use the CONSTRAINT keyword as follows:

```
CREATE TABLE hr.persons (

person_id INT IDENTITY PRIMARY KEY,

first_name VARCHAR(255) NOT NULL,

last_name VARCHAR(255) NOT NULL,

email VARCHAR(255),

CONSTRAINT unique_email UNIQUE(email)

);
```

The following are the benefits of assigning a UNIQUE constraint a specific name:

- It easier to classify the error message.
- You can reference the constraint name when you want to modify it.

UNIQUE constraint vs. PRIMARY KEY constraint

Although both UNIQUE and PRIMARY KEY constraints enforce the uniqueness of data, you should use the UNIQUE constraint instead of PRIMARY KEY constraint when you want to enforce the uniqueness of a column, or a group of columns, that are not the primary key columns.

UNIQUE constraint allows NULL , however a PRIMARY KEY doesn't. Moreover, UNIQUE constraint treats the NULL as a regular value, therefore, it only allows one NULL value per column.

The following statement inserts a row whose value in the email column is NULL:

```
INSERT INTO hr.persons(first_name, last_name)
VALUES('John','Smith');
```

Now, if you try to insert one more NULL into the email column, you will get an error:

```
INSERT INTO hr.persons(first_name, last_name)
VALUES('Lily','Bush');
```

Here is the output:

```
Violation of UNIQUE KEY constraint 'UQ__persons__AB6E616417240E4E'. Cannot insert duplicate key in object 'hr.persons'. The duplicate key value is (<NULL>).
```

UNIQUE constraint for a group of columns

To define a UNIQUE constraint for a group of columns, you write it as a table constraint with column names separated by commas as follows:

```
CREATE TABLE table_name (

key_column data_type PRIMARY KEY,

column1 data_type,

column2 data_type,

column3 data_type,

...,

UNIQUE (column1,column2)
);
```

The following example creates a UNIQUE constraint that consists of two columns person_id and skill_id:

```
CREATE TABLE hr.person_skills (
   id INT IDENTITY PRIMARY KEY,
   person_id int,
   skill_id int,
   updated_at DATETIME,
   UNIQUE (person_id, skill_id)
);
```

Add UNIQUE constraints to existing columns

When you add a UNIQUE constraint to an existing column or a group of columns in a table, SQL Server first examines the existing data in these columns to ensure that all values are unique. If SQL Server finds the duplicate values, then it returns an error and does not add the UNIQUE constraint.

The following shows the syntax of adding a UNIQUE constraint to a table:

```
ALTER TABLE table_name

ADD CONSTRAINT constraint_name

UNIQUE(column1, column2,...);
```

Suppose you have the following hr.persons table:

```
CREATE TABLE hr.persons (

person_id INT IDENTITY PRIMARY KEY,

first_name VARCHAR(255) NOT NULL,

last_name VARCHAR(255) NOT NULL,

email VARCHAR(255),

phone VARCHAR(20),

);
```

The following statement adds a UNIQUE constraint to the email column:

```
ALTER TABLE hr.persons

ADD CONSTRAINT unique_email UNIQUE(email);
```

Similarly, the following statement adds a UNIQUE constraint to the phone column:

```
ALTER TABLE hr.persons

ADD CONSTRAINT unique_phone UNIQUE(phone);
```

Delete UNIQUE constraints

To define a UNIQUE constraint, you use the ALTER TABLE DROP CONSTRAINT statement as follows:

```
ALTER TABLE table_name

DROP CONSTRAINT constraint_name;
```

The following statement removes the unique_phone constraint from the hr.person table:

```
ALTER TABLE hr.persons

DROP CONSTRAINT unique_phone;
```

Modify UNIQUE constraints

SQL Server does not have any direct statement to modify a UNIQUE constraint, therefore, you need to drop the constraint first and recreate it if you want to change the constraint.

In this lab, you have learned how to use the SQL Server UNIQUE constraint to make sure that the data contained in a column or a group of columns is unique.