

# integrity lifecycle manager

Server Failover Configuration

11.1

#### Copyright © 2017 PTC Inc. and/or Its Subsidiary Companies. All Rights Reserved.

User and training guides and related documentation from PTC Inc. and its subsidiary companies (collectively "PTC") are subject to the copyright laws of the United States and other countries and are provided under a license agreement that restricts copying, disclosure, and use of such documentation. PTC hereby grants to the licensed software user the right to make copies in printed form of this documentation if provided on software media, but only for internal/personal use and in accordance with the license agreement under which the applicable software is licensed. Any copy made shall include the PTC copyright notice and any other proprietary notice provided by PTC. Training materials may not be copied without the express written consent of PTC. This documentation may not be disclosed, transferred, modified, or reduced to any form, including electronic media, or transmitted or made publicly available by any means without the prior written consent of PTC and no authorization is granted to make copies for such purposes. Information described herein is furnished for general information only, is subject to change without notice, and should not be construed as a warranty or commitment by PTC. PTC assumes no responsibility or liability for any errors or inaccuracies that may appear in this document.

The software described in this document is provided under written license agreement, contains valuable trade secrets and proprietary information, and is protected by the copyright laws of the United States and other countries. It may not be copied or distributed in any form or medium, disclosed to third parties, or used in any manner not provided for in the software licenses agreement except with written prior approval from PTC.

## UNAUTHORIZED USE OF SOFTWARE OR ITS DOCUMENTATION CAN RESULT IN CIVIL DAMAGES AND CRIMINAL PROSECUTION.

PTC regards software piracy as the crime it is, and we view offenders accordingly. We do not tolerate the piracy of PTC software products, and we pursue (both civilly and criminally) those who do so using all legal means available, including public and private surveillance resources. As part of these efforts, PTC uses data monitoring and scouring technologies to obtain and transmit data on users of illegal copies of our software. This data collection is not performed on users of legally licensed software from PTC and its authorized distributors. If you are using an illegal copy of our software and do not consent to the collection and transmission of such data (including to the United States), cease using the illegal version, and contact PTC to obtain a legally licensed copy.

Important Copyright, Trademark, Patent, and Licensing Information: See the About Box, or copyright notice, of your PTC software.

#### UNITED STATES GOVERNMENT RIGHTS

PTC software products and software documentation are "commercial items" as that term is defined at 48 C.F. R. 2.101. Pursuant to Federal Acquisition Regulation (FAR) 12.212 (a)-(b) (Computer Software) (MAY 2014) for civilian agencies or the Defense Federal Acquisition Regulation Supplement (DFARS) at 227.7202-1(a) (Policy) and 227.7202-3 (a) (Rights in commercial computer software or commercial computer software documentation) (FEB 2014) for the Department of Defense, PTC software products and software documentation are provided to the U.S. Government under the PTC commercial license agreement. Use, duplication or disclosure by the U.S. Government is subject solely to the terms and conditions set forth in the applicable PTC software license agreement.

PTC Inc., 140 Kendrick Street, Needham, MA 02494 USA

# **Contents**

Integrity Lifecycle Manager Server Failover Configuration	7
Before You Start	
Overview	
Pre-requisites	
Creating a Mount Start Up Script (Windows only)	
Installation and Configuration	15
Installing a Failover Configuration	
To install a standard failover configuration (Windows and Solaris)	16
To install a Sun Failover Configuration (Solaris)	
Defining a Cluster Name	
Defining Cluster Member Names	
Defining Bind Addresses for Members	
Configuring Additional Properties Files	
Using an Oracle RAC Configuration	
Configuring the Layer 4 Switch	
Defining a Load-Balance Using a Cisco Layer 4 Switch	
Diagnostics and Troubleshooting	29
Defining Log and Temp Directories	30
Configuring the Primary Server's Heartbeat	30
Reconnecting After a Failover	31
Forcing a Failover	31
Forcing a Shutdown	
Forcing a Restart	32
mks.logfile Parent Directory Not Created	
Troubleshooting	32
Getting Help	32

# **Integrity Lifecycle Manager Server Failover Configuration**

Before You Start	8
Overview	8
Pre-requisites	9
Creating a Mount Start Up Script (Windows only)	12

For global organizations with hundreds or thousands of users working 24x7, it is imperative that key infrastructure systems support high levels of availability and not suffer from single points of failure. In the event of an unforeseen disaster, bringing mission-critical systems back online in the least amount of time is critical.

As a safeguard, PTC offers a failover configuration for the Integrity Lifecycle Manager server. In the event that your main Integrity Lifecycle Manager server fails (the server's operating system goes down, the network to the database is lost, or the network that the server is communicating over is lost), a secondary Integrity Lifecycle Manager server takes over and resumes server operations without manual intervention and minimal impact on users.



### Note

As a best practice, PTC highly recommends that you also have a disaster recovery process in place, such as backing up the Integrity Lifecycle Manager server.

### **Before You Start**

If you are upgrading from Integrity Lifecycle Manager 2009, remove the failover-service.xml file from the installdir/server/mks/ deploy directory. Failure to remove the file prevents the server from starting.

If you remove the failover-service.xml file but do not set the mksis.ha.type property in the is.properties file, multiple servers will point to the same database, unaware that they are running in a failover configuration. This can lead to serious problems. For more information, see Defining a Cluster Name on page 22


### Overview

The Integrity Lifecycle Manager server failover configuration implements a clustering framework. Clustering uses a group of servers to transparently run an application as if it were a single entity. However, the failover configuration is actually a warm failover solution, not a full clustering solution. A future release of Integrity Lifecycle Manager is expected to implement full clustering for a specific set of databases and Integrity Lifecycle Manager functionality, replacing the warm failover solution

#### Note

For licensing purposes, each node in a warm failover implementation requires its own Integrity Lifecycle Manager server license. For more information on licensing, see the Integrity Lifecycle Manager Installation and Upgrading Guide.

On initial startup, the failover configuration detects the servers that are in the cluster; each server in the cluster is defined as a *node*or *member*. For the purposes of illustration in this document, a main production server and a secondary production server are used. An election service uses the database server to vote on which server becomes the primary server (the active server used for production). The Integrity Lifecycle Manager server that wins the vote becomes the *primary* server, performing a complete start up and begins listening to client requests. The primary server then sends a *heartbeat* (specified by the mksis.heartbeatproperty) to the database server, indicating its status as the active primary server and that it is running incident free. The *secondary* server detects that it lost the vote. It suspends its start up process and does not listen to client requests. As long as the primary server sends a regular heartbeat to the database, the secondary server's start up process is suspended and continues to vote, attempting to become the primary server until the primary server fails.



A failover configuration with a primary and secondary Integrity Lifecycle Manager server

When the primary server fails, the secondary server waits two heartbeats to give the primary server a chance to win the election, for example, the database connection may have been temporarily lost. If the secondary server wins the election, it becomes the new primary server and continues its start up process. When the former primary server detects that it lost the election, it shuts down, triggering a process that performs a restart, making it the secondary server.

Connected Integrity Lifecycle Manager client systems GUI clients transparently reconnect after the failover occurs. Intensive and long running commands (create Sandbox and resynchronize) include a **Continue After Recoverable Outages** option that is enabled by default, allowing clients to automatically reconnect and resume the operation after a failover occurs. A similar option is enabled by default from the CLI for sicreatesandbox and siresync. To configure the reconnect preferences for the GUI and CLI, see Reconnecting After a Failover on page 31

For clustered staging and production servers, a failover during an admin migration triggers a rollback.

### **Pre-requisites**

To implement the Integrity Lifecycle Manager server failover configuration, the following pre-requisites are required:

Database

A shared database repository that is Oracle, or Microsoft SQL. For an Oracle database, an Oracle RAC configuration is supported (for more information, see Using an Oracle RAC Configuration on page 24). The RCS repository is not supported.

#### Integrity Lifecycle Manager server systems

At least one secondary server must exist for each primary server. The servers must also reside on separate machines and use a shared database.

Each Integrity Lifecycle Manager server must be at the same major build version (Integrity Lifecycle Manager server 2009 or greater). Service packs and HotFixes should indicate if they are incompatible. If you need to install a service pack, stop both servers, install the service pack, and then restart the servers.

Configuration of the two servers must be identical, sharing configuration files on a shared file system.



#### 💡 Tip

As a security measure, you can hide the servers behind a firewall, exposing only the single IP/Port on the switch.

#### Network Load Balancer

A *network load balancer* (balancer) is responsible for making failover transparent to clients by automatically re-directing client requests to the active node. The balancer, placed between the client and server nodes:

- Provides a single access point (IP address) to the multi-node failover configuration, where each node has a different IP address. Without the balancer, clients require manual configuration to connect to a different node in the event of failure.
- Tracks the active node by periodically checking each node to see if the configured port is turned up (in listening state).
- Transparently directs new and existing client connections to the active node.

PTC recommends using a hardware load balancer for speed and reliability. A dedicated load balancer, such as the Cisco Content Switching Module (CSM) available for the 6500 series of Cisco switches, provides all of the features and flexibility required by failover configurations.

A modern Layer-4 network switch, such as the Cisco CSS 11501, can also be configured to provide balancing between ports.

#### Shared File System

For ease of installation and maintenance of a failover configuration, a shared file system is used for the application, configuration, and data. The shared file system, such as a *Network Attached Storage* (NAS) device, requires the following:

- Since the shared network drive that the shared file system resides on contains paths that may contain drive letters, the shared file system must be mounted using the same drive letter on each of the nodes.
- All Integrity Lifecycle Manager server property files must be available to either Integrity Lifecycle Manager server.
- The drive setup between the primary and secondary machines must be the same, and the shared file system must have the same name.
  - Shared file systems implement one or more network file sharing protocols. The implemented protocol should be robust enough to protect against network outages. The following are the two most commonly used protocols (most NAS devices, such as the NetApp Filer, implement both):
- Network File System (NFS)

On UNIX, NFS is the default protocol and allows a hard mount. This means that in the case of a network outage to the file system, all file system requests are blocked until the outage is resolved and operations resume. PTC recommends implementing the NFS protocol.

On Windows, an NFS client is required to access a NAS using the NFS protocol. Windows Vista and later OS' include an NFS client; however, you must enable the Services for NFS feature in the Control Panel/ Programs and Features/Windows features.

Server Message Block (SMB) / Common Internet File System (CIFS)

On Windows, SMB is the default protocol and does not allow a hard mount. This means that in the case of a network outage to the file system, all file system requests become invalid, even if the outage is only temporary.



### Note

PTC recommends that you only use the SMB protocol if you have high confidence in the network that each Integrity Lifecycle Manager server and the NAS device reside on. In the event of a [temporary] network outage with the SMB protocol, the Integrity Lifecycle Manager server may fail.

To start the primary server from the shared drive on Windows, another service needs to map the drive for the Integrity Lifecycle Manager server. To do this, you need to create a mount startup script. For more information, see Creating a Mount Start Up Script (Windows only) on page 12

On UNIX, there is no concept of a per-session mount. From a command line, use the mount - o hard command.

Redundancy of System Components

The failover configuration enables redundancy of the Integrity Lifecycle Manager server. To avoid a single point of failure, ensure that you enable redundancy for the following system components: FlexNet license server, database, and shared drive.

## Creating a Mount Start Up Script (Windows only)



### Note

For ease of installation and maintenance of failover configuration, a shared network drive is used for the application, configuration, and data. Since the shared configuration contains paths that may contain drive letters, the shared file system must be mounted using the same drive letter on each of the nodes.

To start the primary server from the shared drive on Windows, another service must map the drive for the Integrity Lifecycle Manager server. To do this, you create a mount start up script that:

Mounts the drive with the Integrity Lifecycle Manager server installation to a drive letter.

The Integrity Lifecycle Manager server must wait until the network redirectors are ready. Services are started in parallel with the network redirectors, so the network may not yet be available.

Starts the Integrity Lifecycle Manager server Service.

The Integrity Lifecycle Manager server is configured with a manual startup type, to delay the start up until the mount is complete.

#### To create a start up script

1. Create a mount shares . bat script, updating the mount line in the script as needed for the required permissions, for example:

```
echo %DATE% %TIME%
:loop
mount -o mtype=hard -o anon \\NAS\SHARENAME Z:
if not errorlevel 1 goto :done
echo Exit code: %ERRORLEVEL%
sleep 5
goto :loop
:done
net start "Integrity Server 10"
```

If you are using the Windows NFS Server and do not have an appropriate setup method for NFS UNIX Identity mapping, you can configure the NFS share to be valid for the cluster members only. For example:

```
nfsshare sharename=drive -o anon=yes -o rw=cluster-
node1:cluster-node2
```

Only the specified nodes can mount the NFS share; however, with anonymous access permissions.

2. Start the Microsoft Management Console by typing the following from the **Run** prompt:

mmc

- 3. In the console, select File ► Add/Remove Snap-in.
- 4. Click Add, and then select Group Policy Object Editor from the list.
- 5. Click Add.
- 6. Click Finish.
- 7. From Windows Explorer, copy mountshares.bat to the following directory (the GroupPolicy directory may be hidden):

```
c:\windows\system32\GroupPolicy\Machine\Scripts\
Startup
```

- 8. In the Microsoft Management Console, you should see the Local Computer Policy tree. Expand the Computer Configuration and the Windows Settings node below it.
- 9. Under Windows Settings, select Scripts (Startup/Shutdown), and then double-click Startup in the right panel.
- 10. In the Startup Properties dialog box, click Add.
- 11. In the Script Name field, browse to the mountshares.bat script you created, and then add >mountshare.log to the Script Parameters field. The output from running the mountshares.bat script appears in the mountshares.log.
- 12. Click **OK** and close the Microsoft Management Console.

The next time you start Windows, the  ${\tt mountshares.bat}$  script runs before any logins or services start.

2

# **Installation and Configuration**

Installing a Failover Configuration	16
To install a standard failover configuration (Windows and Solaris)	16
To install a Sun Failover Configuration (Solaris)	19
Defining a Cluster Name	22
Defining Cluster Member Names	22
Defining Bind Addresses for Members	22
Configuring Additional Properties Files	23
Using an Oracle RAC Configuration	24
Configuring the Layer 4 Switch	24
Defining a Load-Balance Using a Cisco Layer 4 Switch	26

This chapter covers the installation and configuration of a failover mechanism, as well as the layer 4 switch.

### Installing a Failover Configuration

Choose an installation type:

- To install a standard failover configuration (Windows and Solaris) on page 16
- To install a Sun Failover Configuration (Solaris) on page 19

## To install a standard failover configuration (Windows and Solaris)

- 1. Set up the hardware and ensure connectivity.
- 2. Configure the shared file system and ensure that it is accessible to every node.
- 3. Configure host names for each node (see Defining Cluster Member Names on page 22), and a cluster host name (see Defining a Cluster Name on page 22) so that every node can resolve each host name.



### 🖣 Tip

To avoid confusion, the node's host name should contain the node's member name.

By default, the failover configuration binds the Integrity Lifecycle Manager server ports to local addresses. If the server machine contains multiple network interfaces, you can optionally choose to bind the ports to a specific address on each server. For more information, see Defining Bind Addresses for Members on page 22

- 4. On the shared file system, create a base directory for the Integrity Lifecycle Manager server installation, for example, /shared/mks/servers.
- 5. Install the Integrity Lifecycle Manager server in the specified base directory (on one node).
- 6. Make the necessary changes to security and configuration properties as per a normal standalone Integrity Lifecycle Manager server installation.
- 7. To ensure a successful installation and configuration, start the Integrity Lifecycle Manager server as a normal standalone server. Verify basic functionality and stop the server.
- 8. In installdir/config/properties/is.properties, set the following properties:
  - mksis.ha.type=failover

#### Note

Any other value causes the server to run in a normal configuration.

If you are upgrading from Integrity Lifecycle Manager 2009, manually add the property.

#### Caution

If you remove the failover-service.xml file but do not set the mksis.ha.type property, multiple servers will point to the same database, unaware that they are running in a failover configuration. This can lead to serious problems.

- mksis.hostname=host name assigned to the cluster This is the host name that clients use to connect to the cluster.
- mksis.clear.port and/or mksis.secure.port=chosen port for your service
- 9. If needed, on each node create a directory for storing bulk data on the local file system.
- 10. Select a member name (Node ID) for each node. Typically, nodes names are numbers (1, 2, 3, ...); however, any short string may be used as long as it is unique to other nodes.
- 11. In installdir/config/properties/im.properties, add the following bulk cache property for each node:

im.servercache.ha.member name.bulkrootdir=local bulk data directory

- 12. Determine if additional properties need to be configured. For more information, see Defining a Cluster Name on page 22
- 13. To start and stop the Integrity Lifecycle Manager server on each of the nodes, install the application service. To do this, you create a copy of the Integrity Lifecycle Manager server startup script and customize it for each node by setting a unique member name.
  - a. Browse to server install dir/bin.

#### Note

On Windows, use mksis.bat to remove the Integrity Lifecycle Manager Windows service created during the installation. It is replaced with a member specific service

- b. Create a copy of the mksis.bat (Windows) or mksis (Solaris) file for each node, specifying the member name as part of the file name. For example, mksis-1(.bat) and mksis-2(.bat).
- c. In each copy of the startup script, uncomment and set the MEMBER NAME property to the appropriate member name. For example, in mksis-1 (.bat) set MEMBER NAME=1.
- d. Create log and temp directories for each member. The log and temp directories allow you to distinguish diagnostic messages for each server. For more information, see Defining Log and Temp Directories on page 30
- e. On Windows, log in to each node and use the appropriate customized mksis.bat file to install the service. For example, on member 1, run mksis-1, bat to install the service
  - On Solaris, log in to each node and copy the appropriate customized mksis file to the proper rc directory and set up any necessary soft links. For example, on member 1, copy the mksis-1 file.
- 14. Configure the load balancer. For detailed information, see Configuring the Layer 4 Switch on page 24. In general, the balancer requires the following settings:
  - Hostname set to the cluster host name.
  - Listen ports configured to the selected clear and secure ports, as well as any other ports (HLL adapter port, etc.).
  - Each node's host name and ports configured as a destination. The node's port should match the cluster port.
  - Sticky sessions. This means that requests from clients coming from the same IP address should be directed to the same cluster node
  - Timeouts disabled. Some balancers can timeout connections after inactivity; however, this functionality should be disabled.

- Configure probing to check if the server is up and active. Most balancers can verify this with port status.
- Configure balancing algorithm. For simple deployments, an algorithm that chooses the next node on the list is sufficient.
- 15. Start the cluster by doing the following:
  - Start the balancer.
  - Log in to each node and run the appropriate customized startup script with the start parameter. For example, on node 1, type the following from a command line:

mksis-1 start



#### 界 Tip

On Windows, you can use the Windows Service Manager to start each

## To install a Sun Failover Configuration (Solaris)

- 1. Set up the hardware, ensure connectivity, and install Sun Cluster software.
- 2. Make sure the Sun cluster bin directory is part of the system PATH.
- 3. Use Sun clustering to configure a global file system that is available to all nodes.
- 4. Configure host names for each node (see Defining Cluster Member Names on page 22), and a cluster host name (see Defining a Cluster Name on page 22) so that every node can resolve each host name.



### 👎 Tip

To avoid confusion, the node's host name should contain the node's member name.

By default, the failover configuration binds the Integrity Lifecycle Manager server ports to local addresses. If the server machine contains multiple network interfaces, you can optionally choose to bind the ports to a specific address on each server. For more information, see Defining Bind Addresses for Members on page 22.

- 5. Create a base directory for the Integrity Lifecycle Manager server installation on the global file system, for example, /global/mks/servers.
- 6. Install the Integrity Lifecycle Manager server by running mksserver.bin and following the installation steps. Ensure that you change the installation directory to the one specified on the global file system.
- 7. Make the necessary changes to security and configuration properties as per a normal standalone Integrity Lifecycle Manager server installation.
- 8. To ensure a successful installation and configuration, start the Integrity Lifecycle Manager server as a normal standalone server. Verify basic functionality and stop the server.
- 9. In installdir/config/properties/is.properties, set the following properties
  - mksis.ha.type=failover



#### Note

Any other value causes the server to run in a normal configuration.

If you are upgrading from Integrity Lifecycle Manager 2009, manually add the property.



#### Caution

If you remove the failover-service.xml file but do not set the mksis.ha.type property, multiple servers will point to the same database, unaware that they are running in a failover configuration. This can lead to serious problems.

- mksis.hostname=host name assigned to the cluster This is the host name that clients use to connect to the cluster.
- mksis.clear.port and/or mksis.secure.port=chosen port for your service
- 10. For each node, obtain and record the local node ID by typing the following from a command line:

```
scha cluster get -O NODEID LOCAL
```

- 11. On each node, create a directory for storing bulk data on the local file system.
- 12. In *installdir*/config/properties/im.properties, add the following bulk cache property for each node:

im.servercache.ha.node ID.bulkrootdir=local bulk data
directory (on the specific node)

- 13. One one of the nodes, change to the Integrity Lifecycle Manager server installation directory on the global file system.
- 14. Run the scdsbuilder command and set the following information in the Sun Cluster Agent Builder:

Vendor Name: MKS

• Application Name: Integrity

• Working Directory: server install dir

• Type: Failover

Network Aware: checked

Type of RT: GDS

- 15. Click Create.
- 16. After the creation of the resource type, click **Next**.
- 17. Set the following commands:
  - Start: server install dir/bin/mksis start
  - **Stop**: server install dir/bin/mksis stop
- 18. Click Configure.
- 19. An MKSIntegrity directory now exists in your server installation directory, containing the configured agent.
- 20. On each node:
  - Change to the server install dir/MKSIntegrity/pkg directory.
  - Add the package to each system: pkgadd -d . MKSIntegrity.
- 21. Each node should have an /opt/MKSIntegrity package. The package contains commands to start, stop and remove the cluster.
- 22. Create log and temp directories for each member. The log and temp directories allow you to distinguish diagnostic messages for each server. For more information, see Defining Log and Temp Directories on page 30.
- 23. On one of the nodes, go to the /opt/MKSIntegrity/util and run the following command to configure and start the cluster:
  - ./startIntegrity -h hostname -p port/type list -l Lb sticky

#### where:

- hostname is the host name that becomes the shared address of the cluster.
- port/type is the selected port (mksis.clear.port) and type. If other ports are in use (secure, HLL) they must be specified, for example, "7001/tcp, 7011/tcp, 6667/tcp".

### **Defining a Cluster Name**

If you have a large number of servers running in the same network segment, for example, a cluster of staging servers and production servers, PTC recommends specifying a customized partition name to distinguish the different clusters and avoid accidentally joining a logically distinct cluster that has the default cluster name.

To change the default cluster partition name, add the following line at the end of the mks.java.additional section in <code>installdir/config/mksservice.conf</code>:

mks.java.additional.##=-Djboss.partition.name=cluster name

### **Defining Cluster Member Names**

On the primary and secondary servers, the service parameters must be modified to set the MEMBER\_NAME variable to the name appropriate for the server. This defines a unique name for each member in the cluster and allows you to differentiate member names in diagnostic messages. For example, the primary server could be named mks-1 and the secondary server could be called mks-2.

Edit installdir/config/mksservice.conf, adding %MEMBER\_NAME% for each member node.

### **Defining Bind Addresses for Members**

By default, the failover configuration binds the Integrity Lifecycle Manager server ports to local addresses. If the server machine contains multiple network interfaces, you can optionally choose to bind the ports to a specific address on each server

#### To define the bind address for a member

1. Add the following line at the end of the mks.java.additional section in installdir//config/mksservice.conf:

```
mks.java.additional.##=-Dmksis.bindAddr=%MEMBER ADDR%
```

2. The service parameters on the primary and secondary machines must be modified to include the MEMBER\_NAME and MEMBER\_ADDR variables. For example, the primary server should include the following executable line:

```
..../mksservice.exe -s .../config/mksservice.conf
```

Modify the executable line to include the member name and bind address, for example:

```
..../mksservice.exe -s .../config/mksservice.conf
"set.MEMBER_NAME=secondary"
   "set.MEMBER_ADDR=1.0.0.2"
```

3. On the secondary server, modify the service parameters, for example:

```
..../mksservice.exe -s .../config/mksservice.conf
"set.MEMBER_NAME=secondary"
   "set.MEMBER_ADDR=1.0.0.2"
```

### **Configuring Additional Properties Files**

Additional configuration properties can point to files external to the Integrity Lifecycle Manager server root directory. If you need to configure them, ensure that they are also on the shared drive. For example, point the following property files to the directories:

• installdir/config/properties/si.properties:

```
si.Cache.default.bulkRootDir=/shared/server/mks/bulk
```

- shared/data/public html
- In the Integrity Lifecycle Manager administration client, under the **Configuration Properties** node set the following properties:

```
triggers.environmentVariables=/shared/server/data/triggers/env.properties
si.triggers.events=/shared/server/data/triggers/events
triggers.scripts=/shared/server/data/triggers/scripts
```

- If you are using SSL, tls directory.
- All members of the cluster must use the same host name when identifying themselves to Integrity Lifecycle Manager client systems and each Integrity Lifecycle Manager server they encounter.

Set the following properties in *installdir*/config/properties/is.properties:

mksis.hostname=myname

mksis.hostnameuseip=false

### **Using an Oracle RAC Configuration**

To use the failover configuration with an Oracle RAC configuration, you must also modify the JDBC connection string in <code>installdir/config/properties/is.properties</code>. For example, if you have two nodes in an Oracle RAC configuration:

url=jdbc:oracle:thin:@(DESCRIPTION=(LOAD\_BALANCE=on) (FAILOVER=on) (ADDRESS=(P
ROTOCOL=TCP) (HOST=node1) (PORT=port1)) (ADDRESS=(PROTOCOL=TCP) (HOST=node2)
(PORT=port2)) (CONNECT\_DATA=(SERVICE\_NAME=service name))), \

#### where

- *node1* and *port1* are the name and port number of the first node in the Oracle RAC configuration.
- *node2* and *port2* are the name and port number of the second node in the Oracle RAC configuration.
- *service name* is the name of the Oracle RAC service



A known issue (Oracle Metalink note 364855.1) in the Oracle Net Configuration Assistant causes a configuration error when setting up a default Oracle RAC configuration. This known issue causes triggers and commands to fail. To resolve the Oracle issue, refer to the example described at:

http://www.ardentperf.com/2007/04/02/local\_listener-and-ora-12545/


### **Configuring the Layer 4 Switch**

To set up a front-end application switch, you must have hardware that is capable of defining a pool of resources (servers with an application that responds to a specific port). The pool is assigned a single virtual IP address (VIP), which is used by the application users to access the pool. The switch continually probes the pool to determine which servers are available and redirects requests from the VIP address to an available server in the pool. The switch software is also able to load-balance the pool, for example, using the least used connections. In the case of a failover configuration, only one server is recognized by the switch to be available at any one time, directing all traffic to it until a failover occurs.

For a Cisco Layer 4 switch, the load-balance is defined using Virtual Local Area Networks (VLANs). Most load-balancing general purpose switches use VLANs because they allow individual ports of a multi-port switch to be assigned specific subnets, which can be used to pool the appropriate resources.

The diagram below illustrates a Cisco-Bridged VLAN, using a Cisco Layer 4 switch and a Cisco Content Switching (CSM) module. You can implement any switch that has some form of application load-balancing feature; however, the following is mandatory:

- the switch can define an address which is re-directed to a pool of servers (VIP address)
- the switch is able to probe the pool and determine which servers are able to respond so that it will not re-direct traffic to an inactive server



Cisco-Bridged Virtual Local Area Network

PTC assumes that you have your own load-balancing solution and understand how to use it. You can accomplish the desired configuration using switches, servers with load-balancing software, and dedicated load-balancing equipment which combine both or any combination of the above. You should understand if it is necessary to define VLANs in your environment and know the specific IP ranges to use.

For more information on configuring a Cisco CSM module, browse to:

http://www.cisco.com/en/US/products/hw/modules/ps2706/ps780/tsd\_products\_support\_model\_home.html

## Defining a Load-Balance Using a Cisco **Layer 4 Switch**

#### Note

Using the above diagram as a reference, the following is a basic example of defining a load-balance. It does not define a probe (which is possible for some switches). It does not define what, if any, load balancing is to occur (in general, the next node on the list is selected, if left unspecified). The example defines two servers and one pool, marking them active (available).

PTC assumes that some ports of the switch already exist on the client VLAN (VLAN-A); therefore, interfaces assigned to the client VLAN are omitted in the diagram.

For example, VLAN-A has an address of 10.0.0/20; however, it can be any valid network definition defined on any VLAN

Individual interfaces are assigned to the server VLAN (VLAN-B). For example, using a Cisco 11501 switch, ports e1 and e2 are assigned to VLAN-B, which has a network range of 10.10.0.0/24. The range can be anything; however, if it contains only a few addresses, it is likely smaller than a full 255 addresses (/24).

The VLANs are assigned addresses to enable the switch to handle the routing. For example, VLAN-A is assigned 10.0.5.44, and VLAN-B is assigned 10.10.0.1. VLANs are individual segments within a switch, and the addresses are used as the gateway addresses to each segment.

Next, define each Integrity Lifecycle Manager server in the VLAN. The IP address and the ports used by each Integrity Lifecycle Manager server (MKS-1 and MKS-2) belong to the server VLAN (VLAN-B), for example, 10.10.0.x. The port is the port used by the Integrity Lifecycle Manager process.

The next step is to define the pool. You define the address used by the switch to direct traffic to the pool, the port being redirected, and the resources that belong to the pool. For example, the address is 10.0.3.43; however, it can be anything visible to the client network, routable by the switch. In the simplest configuration, it is an address on the same VLAN as the client machines. The port is 7001, the same as the one used by the Integrity Lifecycle Manager server systems.

After the load balance is defined, the client requests a connection to the VIP address of the pool. This is made visible by the switch as soon as the pool is marked active. VIP is defined on VLAN-A, the users are on VLAN-A, and the switch has an address that belongs to VLAN-A, which allows routing to occur without the need for explicit routes.

The packets arrive at the switch and are handled by the load-balancer. The balancer continually polls the address and port of the defined services within the pool to determine if they are active. In a failover configuration, only one server responds to queries on that port so that server is the only one logged as active by the switch. The packets are directed to the available server on VLAN-B. The connection is generally handled by network address translation (NAT), so the responses to the user appear to come from the VIP address.

# **Diagnostics and Troubleshooting**

Defining Log and Temp Directories	30
Configuring the Primary Server's Heartbeat	30
Reconnecting After a Failover	31
Forcing a Failover	31
Forcing a Shutdown	31
Forcing a Restart	32
mks.logfile Parent Directory Not Created	32
Troubleshooting	32
Getting Help	32

### **Defining Log and Temp Directories**

To distinguish diagnostic messages for members in the cluster, you must enter variables for the member names. This moves the location of the log and temp directories, storing log files and temporary files in directories with suffixes based on member names, for example, the primary server could contain log.primary and tmp.primary, and the secondary server could contain log.secondary and tmp.secondary.

1. Open installdir/config/mksservice.conf and change the following lines:

```
mks.java.additional.##=-Djboss.server.log.dir=.../log
mks.java.additional.##=-Djboss.server.temp.dir=.../mks/tmp
to
mks.java.additional.##=-Djboss.server.log.dir=.../log.%MEMBER NAME%
mks.java.additional.##=-Djboss.server.temp.dir=.../mks/tmp.%MEMBER NAME%
```

2. To separate the log files for each member in the cluster, modify the mks.logfile(controls startup.log location) and mks.java.gcfile (controls gc.out location) properties by adding the following line to the directory used for logging:

```
.../log/... -> .../log.%MEMBER NAME%/...
```

### Configuring the Primary Server's Heartbeat

To configure the primary server's heartbeat, modify the mksis.heartbeat property in the Integrity Lifecycle Manager administration client. By default, the heartbeat is set to 20 seconds, with a minimum value of 5 seconds and a maximum value of 1000 seconds. For example, if you set the property to 20 seconds, the secondary server waits two 20 second intervals to give the primary server a chance to win the election.



#### Note

Increasing the mksis.heartbeat property can prevent unnecessary switch overs; however, a necessary switch over may take longer. Given that the length of garbage collection for servers may vary, PTC recommends modifying this property to suit your environment.

### Reconnecting After a Failover

If a failover occurs while the create Sandbox or resynchronize commands are running, the GUI and CLI include options that specify whether the commands fail and automatically reconnect.

In the GUI, the Continue After Recoverable Outages option is enabled by default for the Create Sandbox and Resynchronize commands in the Preferences Configuration dialog box, and toggle.

In the CLI, the --awaitServer option is enabled by default for si creates and box and si resynchronize. To prevent these commands from automatically reconnecting, specify -- noawaitServer.

### Forcing a Failover

To force an immediate failover of the primary server, type the following from the command line:

```
si/im diag --hostname=value --port=value --diag=failover
```

where --hostname=value and --port=value is the server information for the Layer 4 switch

The secondary server wins the election immediately, becoming the primary server and the old primary server restarts.

### Forcing a Shutdown

To shutdown the primary server, type the following from the command line:

```
si/im diag --hostname=value --port=value --diag=shutdown
```

where --hostname=value and --port=value is the server information for the primary server.

Unlike a forced failover, the normal failover rule applies: a secondary must win the election after the appropriate time has elapsed.



#### Note

The failover only works if the machine is clustered, while a shutdown always works.

Both commands do not wait for anything in progress to complete, shutting down immediately.

### Forcing a Restart

To restart the primary server, type the following from the command line:

si/im diag --hostname=value --port=value --diag=restart

where --hostname=value and --port=value is the server information for the primary server.

Both commands do not wait for anything in progress to complete, restarting immediately.

### mks.logfile Parent Directory Not Created

During the initial start up of each server, the mksservice.conf does not create the parent mks.logfile directory containing the log file. The next time each server starts, the mks.logfile directory is automatically created for each member node.

### **Troubleshooting**

If you are unable to diagnose any problems with your failover configuration, collect a support package and contact PTC Technical Support.

### **Getting Help**

PTC Technical Support is focused on delivering the right solutions to issues as they arise. For assistance, you can choose online support or telephone a customer service representative. Online support provides easy access to e-mail, Web request services, automatic product notifications, and the PTC Integrity eSupport portal — a secure database that provides helpful resources such as product documentation, knowledge base articles, product downloads, user forums, presentations, and more. For online support, browse to http://support.ptc.com/support/integrity.htm.

PTC Technical Support professionals comprise a tightly knit team of problem solvers, sharing critical information to help you resolve issues in the shortest possible time with optimal results. Customer Service representatives can provide you with a variety of product related tips and innovative solutions to your unique requirements.