MICROMAX SUGAR MILLS ERP · SETUP GUIDE

Setting up the mill

Step by step, in the order the system needs them: company settings and the season, the mill site, zones, circles and villages, and the growers.

1 · Company

Sugar Settings, accounts, season rates.

2 · Site

Sources, loading points, depots, vehicles, weighbridges, cameras.


3 · Areas

Zone → circle (code) → village (code).

4 · Growers


Grower, bank, passbook, Excel import.

Who: **Cane Admin / Cane Manager** (settings, site, areas) · **Cane Staff** (growers) · **Accounts** (ledgers, banks). Everything is under **Sugar Setup** (Desktop → Sugar Setup).




Sugar Setup: Mill, Area, Sources, Growers, Crop, Vehicles & Weighbridge.

DFD level 0 — setup (masters)




DFD level 1 — setup (masters)

1.0 company & season · 2.0 site · 3.0 areas · 4.0 growers · 5.0 passbooks & import





1 Company settings and the season

1. **Sugar Settings → General**: the company, the **active season**, the maund (40 kg), the hour the crushing day starts (07:00), the mill's location, journey standards and survey tolerances.
2. **Accounts**: the ledgers every cane entry posts to — grower payable, cane purchase clearing, TPT bilty payable, road cess, grower loans, cash counter, JazzCash, strong room, short & excess. They are created on setup; check them with the accountant.
3. **Crushing Seasons → 2026-27**: dates, crushing target, the **notified rate** (per 40 kg), road cess and the grower's share, subsidies, TPT, binding and garbage, and production norms. Tokens copy the rates when issued — change them only at a season boundary.



General: company, season, maund, day start, mill location.





Season 2026-27: rates and production norms.

1 By-product NRV on the season

NRV stands for **Net Realisable Value**: the money a by-product actually brings in after the cost of selling it.

> **NRV = sale price – selling and handling cost**

The Crushing Season form uses it in three fields under **Production**: **Molasses NRV**, **Bagasse NRV** and **Press Mud NRV**, each per kg.

How costing uses it

The mill's total cost covers cane plus processing. The by-products carry part of that cost at their NRV, and the rest falls on sugar:

> **cane cost + processing cost – by-product credit (at NRV) = net cost of sugar**

Example

Molasses sells for Rs 30,000 a ton and costs Rs 1,100 a ton to sell and handle. Its NRV is Rs 28,900 a ton, which is **Rs 28.90 per kg**.


At the end

The actual sale value minus selling cost minus the NRV that was credited is posted to the **By-product Variance** account. The **By-product Realization** report shows this.


> Each NRV field on the season form carries the one-line reminder *"Net Realisable Value = sale price – selling and handling cost, per kg"*.

2 Site setup

Sugar Setup →	What to enter
Sources	The mill gate, check posts and depots; each source has its rates and TPT per vehicle type.
Loading Points	Source, circle, contractor, loading rate, season target; the **pin and geofence radius** (ELP photos must be taken inside it); the standard journey time to the mill.
Depots	Purchase points away from the mill: warehouse, weighbridge, users.
Vehicle Types	Gross and tare limits per type (a weight outside them is refused), default lane.
Weighbridge Terminals	The PC's IP, allowed weights (gross / tare / both), lane, indicator; **platform sensors** and **auto-weigh**.
CCTV Cameras	Place (gate / weighbridge), view (front, left, right, rear, top, ANPR, cabin), snapshot address and login.
Cash counters, drivers	Cash Counter 1 / 2 are created on setup; drivers are registered at the gate.



Loading point: location, geofence and journey to the mill.




Weighbridge terminal: IP, indicator, sensors, auto-weigh.


3 Zone, circle, village

The order is **division → district → zone → circle → sector → village**. The **Area map** shows the whole tree with pins and boundaries.


1. **Zones → New**: zone name and district. Draw the boundary on the map (tap the corners), walk it with GPS, or paste it. Drop the pin.
2. **Circles → New**: circle name, a **3-digit circle code** (e.g. 013) and the zone; the circle officer, quota and incentives.
3. **Villages → New**: village name, a **3-digit village code** unique in the circle (001), and the circle. The village becomes **013-001**.



East Zone in Sargodha, with its boundary and pin maps.




Chak 45 NB, village 013-001 in circle Kot Momin East.




Circle Kot Momin East, code 013.

4 Grower setup


1. **Growers → New**: name, father / husband, **CNIC** (13 digits), **mobile** (11 digits starting 03), circle and village. Wrong numbers are shown in red as you type.
2. **Bank** tab: the **IBAN** (24 characters, checked) — the bank fills itself in from it. Growers without an IBAN are paid by cheque.
3. **Save**: the **grower code** is given — **013-001-0001** = circle 013, village 001, serial 0001 — and the grower's payable account is set.
4. **Passbooks → New**: passbook no., the grower, the season, and the land holdings (murabba, killa, acres, ownership).
5. Many growers at once: **Grower Import (Excel)** — download the template, fill it, upload. Each row is checked (CNIC, mobile, IBAN, bank, circle and village codes); the errors come back in a sheet.




New grower: identity and location.



Saved: grower code 013-001-0001.



Bank: IBAN checked; bank filled from it.



Passbook PB-013-001-0001 for 2026-27.

Screens from the MicroMax test system (2 November 2026). Video: *12-Setup-company-site-zone-circle-village-grower.mp4*.