

Data Architecture

SAP PowerDesigner Documentation Collection



Content

1	Building Data Models	8
1.1	Getting Started with Data Modeling	8
	Conceptual Data Models	8
	Logical Data Models	9
	Physical Data Models	9
	Creating a Data Model	10
	Customizing your Modeling Environment	15
1.2	Conceptual and Logical Diagrams	27
	Supported CDM/LDM Notations	28
	Conceptual Diagrams	32
	Logical Diagrams	44
	Data Items (CDM)	47
	Entities (CDM/LDM)	50
	Attributes (CDM/LDM)	55
	Identifiers (CDM/LDM)	58
	Relationships (CDM/LDM)	59
	Inheritances (CDM/LDM)	70
	Associations and Association Links (CDM)	74
1.3	Physical Diagrams	81
	Tables (PDM)	83
	Columns (PDM)	99
	Primary, Alternate, and Foreign Keys (PDM)	115
	Indexes (PDM)	119
	Views (PDM)	123
	Triggers (PDM)	130
	Stored Procedures and Functions (PDM)	148
	Users, Groups, and Roles (PDM)	164
	Synonyms (PDM)	174
	Defaults (PDM)	176
	Domains (CDM/LDM/PDM)	179
	Sequences (PDM)	186
	Abstract Data Types (PDM)	188
	References (PDM)	191
	View References (PDM)	199
	Business Rules (CDM/LDM/PDM)	202
	Lifecycles (PDM)	206

Tablespaces and Storages (PDM)	216
Web Services (PDM)	218
1.4 Multidimensional Diagrams	231
Identifying Fact and Dimension Tables	232
Generating Cubes	233
Facts (PDM)	235
Dimensions (PDM)	238
Associations (PDM)	242
Operational to Warehouse Data Mappings	243
Generating Data Warehouse Extraction Scripts	245
Generating Cube Data	246
1.5 Checking a Data Model	248
Abstract Data Type Checks (PDM)	249
Abstract Data Type Procedure Checks (PDM)	249
Association Checks (CDM)	250
Association Checks (PDM)	252
Column Checks (PDM)	252
Cube Checks (PDM)	255
Database Checks (PDM)	255
Database Package Checks (PDM)	256
Database Package Sub-Object Checks (PDM)	257
Data Format Checks (CDM/LDM/PDM)	258
Data Item Checks (CDM)	258
Data Source Checks (PDM)	260
Default Checks (PDM)	260
Dimension Checks (PDM)	261
Domain Checks (CDM/LDM/PDM)	263
Entity Attribute Checks (CDM/LDM)	264
Entity Identifier Checks (CDM/LDM)	265
Entity Checks (CDM/LDM)	266
Fact Checks (PDM)	268
Fact Measure, Dimension Hierarchy, and Attribute Checks (PDM)	269
Horizontal and Vertical Partitioning and Table Collapsing Checks (PDM)	269
Index and View Index Checks (PDM)	270
Inheritance Checks (CDM/LDM)	271
Join Index Checks (PDM)	272
Key Checks (PDM)	273
Lifecycle and Lifecycle Phase Checks (PDM)	274
Package Checks (CDM/LDM/PDM)	276
Procedure Checks (PDM)	277
Reference and View Reference Checks (PDM)	278

Relationship Checks (CDM/LDM)	279
Sequence Checks (PDM)	281
Synonym Checks (PDM)	281
Table and View Checks (PDM)	282
Tablespace and Storage Checks (PDM)	284
Trigger and DBMS Trigger Checks (PDM)	285
User, Group, and Role Checks (PDM)	286
View Checks (PDM)	286
Web Service and Web Operation Checks (PDM)	287
1.6 Generating and Reverse-Engineering Databases	288
Writing SQL Code in PowerDesigner	288
Previewing SQL Statements	292
Connecting to a Database	296
Generating a Database from a PDM	298
Generating an SAP BusinessObjects Universe	311
Generating Test Data to a Database	315
Estimating Database Size	317
Modifying a Database	319
Displaying Data from a Database	322
Reverse Engineering a Database into a PDM	323
Reverse-Engineering an SAP BusinessObjects Universe	335
Archive PDMs	337
1.7 Generating Other Models from a Data Model	337
Generating Other Models from a CDM	338
Generating Other Models from an LDM	342
Generating Other Models from a PDM	342
1.8 Migrating from ERwin to PowerDesigner	348
Importing Individual ERwin Files	349
Importing Multiple ERwin Files	351
Post-Import	352
PowerDesigner vs ERwin Terminology	353
Getting Started Using PowerDesigner for Former ERwin Users	354
2 DBMS Definition Reference	357
2.1 Amazon Redshift	357
Schemas (Redshift)	359
External Schemas (Redshift)	360
2.2 Hadoop Hive	361
Partitions and Partition Values (Hadoop Hive)	363
2.3 HP Neoview	364
Materialized View Groups (Neoview)	368
2.4 IBM DB2 for z/OS (formerly OS/390)	369

Trusted Contexts (DB2)	373
Auxiliary Tables (DB2)	374
Tablespace Prefix (DB2)	375
Materialized Query Tables (DB2)	376
Masks (DB2)	378
Row Permissions (DB2)	379
2.5 IBM DB2 for Common Server	380
Database Partition Groups (DB2)	386
Index Extensions (DB2)	387
Security Policies (DB2)	388
Event Monitors (DB2)	391
Federated Systems (DB2)	394
2.6 Greenplum	403
Conversions (Greenplum)	412
Aggregates (Greenplum)	413
Rules (Greenplum)	415
Resource Queues (Greenplum)	416
2.7 JSON	417
2.8 Microsoft SQL Server	418
Horizontal Partitioning (SQL Server)	431
Common Language Runtime (CLR) Integration (SQL Server)	433
Encryption (SQL Server)	438
Full Text Search (SQL Server)	442
Spatial Indexes (SQL Server)	444
XML Indexes (SQL Server)	446
XML Data Types (SQL Server)	447
Database Mirroring (SQL Server)	449
Service Broker (SQL Server)	451
Resource Governor (SQL Server)	461
Schemas (SQL Server)	463
Synonyms (SQL Server)	464
Analysis Services (SQL Server)	465
2.9 Netezza	475
History Configurations (Netezza)	479
2.10 Oracle	481
Object and SQLJ Object Data Types (Oracle)	489
Bitmap Join Indexes (Oracle)	490
Database Packages (Oracle)	492
Transparent Data Encryption (Oracle)	501
Clusters (Oracle)	502
Database Links (Oracle)	503

Materialized View Logs (Oracle)	505
Editions (Oracle)	506
2.11 SAP Business Suite	506
Importing an SAP Business Suite Data Dictionary	515
Generating an SAP Business Suite Data Dictionary to HANA	521
2.12 SAP HANA	522
Modeling for HANA Database	524
Modeling for Core Data Services (CDS)	550
2.13 SAP Adaptive Server Enterprise	564
Proxy Tables (ASE)	568
Encryption Keys (ASE)	569
2.14 SAP IQ	571
Reference Architecture Modeling (IQ)	577
Information Lifecycle Management (IQ)	577
Events (IQ/SQL Anywhere)	577
Dbspaces (IQ)	579
Table and Column Partitions (IQ)	580
Logical Servers and Policies (IQ)	582
Multiplex Servers (IQ)	584
Login Policies (IQ/SQL Anywhere)	585
LDAP Servers (IQ)	587
Remote Servers (IQ)	588
External Logins (IQ)	589
Spatial Data (IQ/SQL Anywhere)	589
Full Text Searches (IQ/SQL Anywhere)	593
Indexes (IQ)	594
Join Indexes (IQ/Oracle)	597
IQ Data Movement Scripts	601
2.15 SAP SQL Anywhere	603
Auto-Increment Columns	607
Mirror Servers (SQL Anywhere)	607
Spatial Data (SQL Anywhere)	609
Events, Login Policies, and Full Text Searches (SQL Anywhere)	609
Certificates (SQL Anywhere)	609
Proxy Tables (ASE/SQL Anywhere)	610
2.16 Teradata	611
Partitions (Teradata)	619
Transform Groups (Teradata)	621
Database Permissions (Teradata)	622
Primary Indexes (Teradata)	622
Error Tables (Teradata)	623

Join Indexes (Teradata)	624
Hash Indexes (Teradata)	625
Glop Sets (Teradata)	626
Replication Groups (Teradata)	627
Replication Rules and Rule Sets (Teradata)	628
2.17 Other Databases	629
Informix SQL	629
Ingres	630
Interbase	631
Microsoft Access	632
MySQL	634
NonStop SQL	636
PostgreSQL	637
Red Brick Warehouse	641

1 Building Data Models

The chapters in this part explain how to model your data systems in SAP® PowerDesigner®.

1.1 Getting Started with Data Modeling

A data model is a representation of the information consumed and produced by a system, which lets you analyze the data objects present in the system and the relationships between them. PowerDesigner provides conceptual, logical, and physical data models to allow you to analyze and model your system at all levels of abstraction.

Suggested Bibliography

- Graeme Simsion, Van Nostrand Reinhold, *Data Modeling Essentials*, 1994, 310 pages; paperbound; ISBN 1850328773
- James Martin, Prentice Hall, *Information Engineering*, 1990, three volumes of 178, 497, and 625 pages respectively; clothbound, ISBN 0-13-464462-X (vol. 1), 0-13-464885-4 (vol. 2), and 0-13-465501-X (vol. 3).
- Joe Celko, *Joe Celko's SQL for Smarties* (Morgan Kaufmann Publishers, Inc., 1995), 467 pages; paperbound; ISBN 1-55860-323-9.

1.1.1 Conceptual Data Models

A conceptual data model (CDM) helps you analyze the conceptual structure of an information system, to identify the principal entities to be represented, their attributes, and the relationships between them. A CDM is more abstract than a logical (LDM) or physical (PDM) data model.

A CDM allows you to:

- Represent the organization of data in a graphic format to create Entity Relationship Diagrams (ERD).
- Verify the validity of data design.
- Generate a Logical Data Model (LDM), a Physical Data Model (PDM) or an Object-Oriented Model (OOM), which specifies an object representation of the CDM using the UML standard.

To create a CDM, see [Creating a Data Model \[page 10\]](#). For detailed information about conceptual diagrams, see [Conceptual Diagrams \[page 32\]](#).

1.1.2 Logical Data Models

A logical data model (LDM) helps you analyze the structure of an information system, independent of any specific physical database implementation. An LDM has migrated entity identifiers and is less abstract than a conceptual data model (CDM), but does not allow you to model views, indexes and other elements that are available in the more concrete physical data model (PDM).

You can use a logical model as an intermediary step in the database design process between the conceptual and physical designs:


- Start with a CDM containing entities, attributes, relationships, domains, data items and business rules. If need be, you may develop the CDM in several design steps starting from a high level model to a low level CDM
- Generate an LDM. Create indexes and specify FK column names and other common features
- Generate one or more PDMs, each targeted to a specific DBMS implementation

This design process allows you to keep everything consistent in a large development effort.

To create an LDM, see [Creating a Data Model \[page 10\]](#). For detailed information about logical diagrams, see [Logical Diagrams \[page 44\]](#).

1.1.3 Physical Data Models

A physical data model (PDM) helps you to analyze the tables, views, and other objects in a database, including multidimensional objects necessary for data warehousing. A PDM is more concrete than a conceptual (CDM) or logical (LDM) data model. You can model, reverse-engineer, and generate for all the most popular DBMSs.



PowerDesigner provides you with tools for modeling your operational and business intelligence environments:

- Operational/relational environment - modeled in physical diagrams (see [Physical Diagrams \[page 81\]](#)). The physical analysis may follow a conceptual and/or logical analysis, and addresses the details of the actual physical implementation of data in a database, to suit your performance and physical constraints.
- Business intelligence environment:
 - Data warehouse or data mart database tables - can be modeled in physical diagrams and mapped to their source operational tables to generate data extraction scripts.
 - Data warehouse cubes (in ROLAP or HOLAP environments) - can be modeled in multidimensional diagrams (see [Multidimensional Diagrams \[page 231\]](#)) and mapped to their source warehouse tables.
 - SAP® BusinessObjects™ Universes - can be generated from warehouse PDMs for direct consumption or for editing in BusinessObjects environments (see [Generating an SAP BusinessObjects Universe \[page 311\]](#)).
 - OLAP cubes - can be modeled in multidimensional diagrams and mapped to their source operational or warehouse tables to generate cube data.

PowerDesigner provides support for a wide range of database families through DBMS definition files (*.xdb, located in Resource Files\DBMS inside your installation directory), which customize the metamodel to support the specific syntax of a DBMS, through extended attributes, objects, and generation templates. To view and edit the resource file for your DBMS, select [Database](#) [Edit Current DBMS](#). For detailed information about working with these files, see *Customizing and Extending PowerDesigner > DBMS Definition Files*.

1.1.4 Creating a Data Model

You create a new data model by selecting [File](#) [New Model](#).

Context


Note

In addition to creating a data model from scratch with the following procedure, you can also:

- create a CDM by importing an ERwin model (.ERX) or by generating it from another PowerDesigner model.
- create an LDM by generating it from another PowerDesigner model.
- create a PDM by reverse-engineering it from an existing database (see [Reverse Engineering a Database into a PDM \[page 323\]](#)) or generating it from another PowerDesigner model.

The New Model dialog is highly configurable, and your administrator may hide options that are not relevant for your work or provide templates or predefined models to guide you through model creation. When you open the dialog, one or more of the following buttons will be available on the left hand side:

- [Categories](#) - which provides a set of predefined models and diagrams sorted in a configurable category structure.
- [Model types](#) - which provides the classic list of PowerDesigner model types and diagrams.
- [Template files](#) - which provides a set of model templates sorted by model type.



Procedure

1. Select **File > New Model** to open the New Model dialog.
2. Click a button, and then select a category or model type (*Conceptual Data Model*, *Logical Data Model* or *Physical Data Model*) in the left-hand pane.
3. Select an item in the right-hand pane. Depending on how your New Model dialog is configured, these items may be first diagrams or templates on which to base the creation of your model.
Use the *Views* tool on the upper right hand side of the dialog to control the display of the items.
4. Enter a model name. The code of the model, which is used for script or code generation, is derived from this name using the model naming conventions.
5. [PDM only] Select a target DBMS, which customizes PowerDesigner's default modifying environment with target-specific properties, objects, and generation templates.

By default, PowerDesigner creates a link in the model to the specified file. To copy the contents of the resource and save it in your model file, click the *Embed Resource in Model* button to the right of this field. Embedding a

file in this way enables you to make changes specific to your model without affecting any other models that reference the shared resource.

6. [optional] Click the *Select Extensions* button and attach one or more extensions to your model.
7. Click *OK* to create and open the data model .

i Note

Sample data models are available in the Example Directory.

1.1.4.1 Data Model Properties

You open the model property sheet by right-clicking the model in the Browser and selecting *Properties*.

Each data model has the following model properties:


Property	Description
Name/Code/Comment	Identify the model. The name should clearly convey the model's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the model. By default the code is auto-generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Filename	Specifies the location of the model file. This box is empty if the model has never been saved.
Author	Specifies the author of the model. If you enter nothing, the Author field in diagram title boxes displays the user name from the model property sheet Version Info tab. If you enter a space, the Author field displays nothing.
Version / Repository	Specify a user-defined version name and the read-only repository version number of the model. You can control which of these version values is displayed in a diagram Title symbol through the display preferences for the Title symbol.
DBMS	[PDM only] Specifies the model target.
Database	Specifies the database that is the target for the model. You can create a database in the model by clicking the Create tool to the right of this field. If your DBMS supports multiple databases in a single model (enabled by the <code>EnableManyDatabases</code> entry in the Database category of the DBMS), this field is not present, and is replaced by a list of databases in the <i>Model</i> menu. A Database category is also displayed in the physical options of your database objects.
Default diagram	Specifies the diagram displayed by default when you open the model.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

1.1.4.1.1 Creating a Database in the Model

You can create a database from the *General* tab of the model property sheet or, if your DBMS supports multiple databases in a single model, from the list of databases in the Model menu.

Context

Creating a database in your model allows you to specify physical options for it and to reference the database in the physical options of other objects. For example, you can specify that a table is created in a particular tablespace with the `in [<db>.]<tablespace>` physical option:



Procedure

1. Select **Model > Model Properties** or right-click the diagram background and select *Properties*.
2. Click the *Create* tool to the right of the *Database* field and click *Yes* in the confirmation dialog to open the database property sheet.

3. Enter the following properties for the database as appropriate:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
DBMS	DBMS for the database
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- *Physical Options/Physical Options (Common)* - Specifies the physical options associated with the database (see [Physical Options \(PDM\) \[page 96\]](#)).
- *Script* - Specifies begin and end scripts to bookend the database creation script (see [Customizing Creation Statements \[page 310\]](#)).
- *Rules* - Specifies the business rules associated with the database (see [Business Rules \(CDM/LDM/PDM\) \[page 202\]](#)).
- *Dependencies* - Lists the objects that reference the database in their physical options.

1.1.5 Customizing your Modeling Environment

The PowerDesigner data model provides various means for customizing and controlling your modeling environment.

1.1.5.1 Setting CDM/LDM Model Options

You can set CDM/LDM model options by selecting ► *Tools* ► *Model Options* or right-clicking the diagram background and selecting *Model Options*.

You can set the following options on the *Model Settings* page:

Option	Description
Name/Code case sensitive	Specifies that the names and codes for all objects are case sensitive, allowing you to have two objects with identical names or codes but different cases in the same model. If you change case sensitivity during the design process, we recommend that you check your model to verify that your model does not contain any duplicate objects.
Enable links to requirements	Displays a Requirements tab in the property sheet of every object in the model, which allows you to attach requirements to objects (see <i>Requirements Management</i>).
Enforce non-divergence	Specifies that attributes attached to a domain must remain synchronized with the selected properties (see Controlling Non-Divergence from a Domain [page 184]).
Use data type full name	Specifies that the complete data type is displayed in entity symbols.
Default data type	Specifies the default data type to apply to domains and attributes if none is selected for them.
External Shortcut Properties	Specifies the properties that are stored for external shortcuts to objects in other models for display in property sheets and on symbols. By default, <i>All</i> properties appear, but you can select to display only <i>Name/Code</i> to reduce the size of your model. <p>Note This option only controls properties of external shortcuts to models of the same type (PDM to PDM, EAM to EAM, etc). External shortcuts to objects in other types of model can show only the basic shortcut properties.</p>

Option	Description
Notation	<p>You can choose between the following notations:</p> <ul style="list-style-type: none"> • Entity / Relationship [Default – used throughout this manual] Entity/relationship notation connects entities with links representing one of four relationships between them. These relationships have properties that apply to both entities involved in the relationship • Merise - uses associations instead of relationships • E/R + Merise - both entity/relationship and Merise are used in the same model • IDEF1X - data modeling notation for relationships and entities. In this notation, each set of relationship symbols describes a combination of the optionality and cardinality of the entity next to it • Barker – inheritances are represented by placing the child entities inside the parent entity symbol, and relationships are drawn in two parts, each reflecting the multiplicity of the associated entity role. <p>For more information about these notations, see Supported CDM/LDM Notations [page 28]</p>
Unique code	Requires that data items or relationships have unique codes
Allow n-n relationships	[LDM only] Allows n-n relationships to be displayed.
Allow reuse	<p>Allows the reuse of one data item as an attribute for more than one entity provided the attributes have same name and data type and do not belong to a primary key.</p> <p>When deselected or when the attribute belongs to a primary key, the data item cannot be reused. In this case, if the Unique code check box is selected, a new data item with identical name but different code is created, otherwise a new data item with identical name and code is created.</p> <p>When you delete an entity or entity attributes, these options determine whether or not the corresponding data items are also deleted, as follows:</p> <ul style="list-style-type: none"> • Both – deletes the entity attribute. • Unique Code only – deletes the entity attribute. • Allow Reuse only – deletes the entity attribute and the corresponding data item (if it is not used by another entity). • None – deletes the entity attribute and the corresponding data item.

For information about controlling the naming conventions of your models, see *Core Features Guide > Modeling with PowerDesigner > Objects > Naming Conventions*.

1.1.5.1.1 Assertion Template

The assertion template is a GTL template used to automatically generate sentences from the role names you specify on the *Cardinalities* tab of relationship property sheets. To review or edit the template, select  *Tools > Model Options > Assertion Template*.

The PowerDesigner Generation Template Language (GTL) is used to generate text from the objects, properties, and relationships defined in the PowerDesigner metamodel and in extensions to it.

The GTL code in the template extracts various properties of the relationship object and the entities it connects to generate the assertion statements. The mandatory property and cardinalities are evaluated in each direction in order to generate the appropriate wording around the entity and role names.

You can edit the assertion template as necessary, to change the wording or to reference other properties. To reference extended attributes or other extensions, you must specify the extension file for the template to use in the [Assertion Extension](#) list.

A sample extension file, `Relationship Assertion with Plural Entity Names`, is provided, which provides support for using plural entity names in assertions. For information about attaching this or any other xem to your model, see [Extending your Modeling Environment \[page 25\]](#)

For detailed information about working with GTL, see *Customizing and Extending PowerDesigner > Customizing Generation with GTL*.

1.1.5.1.2 Migration Settings (LDM)

To set migration settings, select and select the Migration settings sub-category under *Model Settings*.

These options control the migration of identifiers along relationships:




Option	Description
Migrate attribute properties	Enables the domain, the checks or the rules to be kept when an attribute is migrated.
Foreign attribute name	<p>Specifies the naming convention for migrated foreign identifiers. You can select one of the default templates from the list or enter your own using the following variables:</p> <ul style="list-style-type: none">• %PARENT% - Name/Code of the parent entity• %ATTRIBUTE% - Name/Code of the parent attribute• %IDENTIFIER% - Name/Code of the identifier constraint attached to the relationship• %RELATIONSHIP% - Name/Code of the relationship• %PARENTROLE% - Role of the entity that generated the parent entity, this variable proceeds from the conceptual environment. If no role is defined on the relationship, %PARENTROLE% takes the content of %PARENT% to avoid generating an attribute with no name <p>The following example checks the %PARENTROLE% value; if it is equal to the parent name (which is the replacement value) then the template "%3:PARENT%_%ATTRIBUTE%" will be used, otherwise template "%PARENTROLE%" will be used because the user has entered a parent role for the relationship:</p> <p>Note that customized naming templates reappear in the generation dialog box the next time you open it, but are not saved to the list of predefined templates.</p>
Use template	Controls when the primary identifier attribute name template will be used. You can choose between: <ul style="list-style-type: none">• Always use template.• Only use template in case of conflict.

1.1.5.2 Setting PDM Model Options

You can set PDM model options by selecting [Tools](#) [Model Options](#) or right-clicking the diagram background and selecting [Model Options](#).

You can set the following options on the [Model Settings](#) page:

Option	Function
Name/Code case sensitive	Specifies that the names and codes for all objects are case sensitive, allowing you to have two objects with identical names or codes but different cases in the same model. If you change case sensitivity during the design process, we recommend that you check your model to verify that your model does not contain any duplicate objects.
Enable links to requirements	Displays a Requirements tab in the property sheet of every object in the model, which allows you to attach requirements to objects (see Requirements Management).
External Shortcut Properties	Specifies the properties that are stored for external shortcuts to objects in other models for display in property sheets and on symbols. By default, All properties appear, but you can select to display only Name/Code to reduce the size of your model. <div style="background-color: #ffffcc; padding: 10px; margin-top: 10px;"><p> Note</p><p>This option only controls properties of external shortcuts to models of the same type (PDM to PDM, EAM to EAM, etc). External shortcuts to objects in other types of model can show only the basic shortcut properties.</p></div>

Option	Function
Notation	<p>Specifies the use of one of the following notation types for the model. You can choose between:</p> <ul style="list-style-type: none"> Relational - Arrow pointing to primary key. This option is the default, and is used in this manual.  <ul style="list-style-type: none"> CODASYL - Arrow pointing to foreign key.  <ul style="list-style-type: none"> Conceptual - Cardinality displayed in IE format (crow's feet).  <ul style="list-style-type: none"> IDEF1X - Cardinality and mandatory status displayed on reference, primary columns in separate containers and dependent tables with rounded rectangles.  <p>When you change notation, all symbols in all diagrams are updated accordingly. If you switch from Merise to IDEF1X, all associations are converted to relationships.</p>

For information about controlling the naming conventions of your models, see *Core Features Guide > Modeling with PowerDesigner > Objects > Naming Conventions*.

1.1.5.2.1 Column and Domain Model Options

To set model options for columns and domains, select **Tools** **Model Options**, and select the Column & Domain sub-category in the left-hand Category pane.

You can set the following options on this tab:

Option	Function
Enforce non-divergence	Specifies that columns attached to a domain must remain synchronized with the selected properties (see Controlling Non-Divergence from a Domain [page 184]).
Default data type	Specifies the default data type to be applied to columns and domains if none is selected for them.
Column / Domain: Mandatory by default	Specifies that columns or domains are created, by default, as mandatory and that they may must, therefore contain non-null values.

1.1.5.2.2 Reference Model Options

To set model options for references, select **Tools** **Model Options**, and select the Reference sub-category in the left-hand Category pane.

You can set the following options on this tab:

Option	Function
Unique code	Requires that references have unique codes. If this option is not selected then different references can have the same code (except when two references share the same child table).
Auto-reuse / Auto-migrate columns	Enable the reuse of columns in child tables as foreign key columns and the migration of primary key columns to child tables during the creation of references (see Automatic Reuse and Migration of Columns [page 195]).
Mandatory parent	Specifies that the relationship between child and parent tables is, by default, mandatory, i.e., each foreign key value in the child table must have a corresponding key value, in the parent table.
Change parent allowed	Specifies that a foreign key value can change to select another value in the referenced key in the parent table.
Check on commit	Specifies that referential integrity is checked only on commit, rather than immediately after row insertion. This feature can be useful when working with circular dependencies. Not available with all DBMSs.
Propagate column properties	Propagates changes made to the name, code, stereotype, or data type of a parent table column to the corresponding child column.

Option	Function
Default link on creation	Specifies how reference joins are created (see Automatic Reuse and Migration of Columns [page 195]).
Default implementation	Specifies how referential integrity is implemented in the reference. You can select either: <ul style="list-style-type: none"> • Declarative – referential integrity is defined by constraint in foreign declarations • Trigger – referential integrity is implemented by triggers For more information on referential integrity, see Reference Properties [page 192] .
Default Constraints: Update	Controls how updating a key value in the parent table will, by default, affect the foreign key value in the child table. Depending on your DBMS, you can choose from some or all of the following settings: <ul style="list-style-type: none"> • None – no effect • Restrict – cannot update parent value if one or more matching child values exist (no effect) • Cascade - update matching child values • Set null - set matching child values to NULL • Set default – set matching child values to default value
Default Constraints: Delete	Controls how deleting a key value in the parent table will, by default, affect the foreign key value in the child table. Depending on your DBMS, you can choose from some or all of the following settings: <ul style="list-style-type: none"> • None – no effect • Restrict – cannot delete parent value if one or more matching child values exist (no effect) • Cascade - delete matching child values • Set null - set matching child values to NULL • Set default – set matching child values to default value

1.1.5.2.3 Other Object Model Options

To set model options for tables and views, indexes, join indexes, procedures, sequences, triggers, and database packages select  [Tools](#)  [Model Options](#), and select the appropriate sub-category under [Model Settings](#).

You can set the following options for these objects:

Option	Function
Default owner	Specifies a default owner for the specified object from the list of users (see Creating a User, Group, or Role [page 165]). To create a user, click on the ellipsis button to open the List of Users, and click the Add a Row tool. If the user specified is subsequently deleted, this option (and the ownership of all associated objects) will be reset to none.

Option	Function
Ignore identifying owner	<p>[tables and views] Specifies that the owner of a table or view is ignored for identification purposes. Since, by default, both the name/code and the owner are considered during a uniqueness check, this option enables you to enforce distinct names for these objects.</p> <p>For example, if a model contains a table called "Table_1", which belongs to User_1, and another table, also called "Table_1", which belongs to User_2, it will, by default, pass a uniqueness check because of the different owners.</p>
Rebuild automatically triggers	<p>[triggers] Automatically rebuilds the triggers on the child and parent tables of a reference when you:</p> <ul style="list-style-type: none"> • change the implementation of a reference • change the referential integrity rules of a reference implemented by a trigger • change the child or parent table of a reference implemented by a trigger (new and old) • create or delete a reference implemented by a trigger • change the maximum cardinality of the references <p>If this option is not selected, you can manually instruct PowerDesigner to rebuild triggers at any time by selecting  <i>Tools</i>  <i>Display Preferences</i> .</p>

1.1.5.3 Setting Data Model Display Preferences

PowerDesigner display preferences allow you to customize the format of object symbols, and the information that is displayed on them. To set data model display preferences, select  *Tools*  *Display Preferences*  or right-click the diagram background and select *Display Preferences*.

In the *Display Preferences* dialog, select the type of object in the list in the left pane, and modify its appearance in the right pane.

You can control what properties it will display on the *Content* tab, and how it will look on the *Format* tab. If the properties that you want to display are not available for selection on the *Content* tab, click the *Advanced* button and add them using the *Customize Content* dialog.

For detailed information about controlling the appearance and content of object symbols, see *Core Features Guide* > *Modeling with PowerDesigner* > *Diagrams, Matrices, and Symbols* > *Display Preferences*.

1.1.5.4 Viewing and Editing the DBMS Definition File

Each PDM is linked to a definition file that extends the standard PowerDesigner metamodel to provide objects, properties, data types, and generation parameters and templates specific to the language being modeled. Definition files and other resource files are XML files located in the *Resource Files* directory inside your installation directory, and can be opened and edited in the PowerDesigner Resource Editor.

Caution

The resource files provided with PowerDesigner inside the `Program Files` folder cannot be modified directly. To create a copy for editing, use the [New](#) tool on the resource file list, and save it in another location. To include resource files from different locations for use in your models, use the [Path](#) tool on the resource file list.

To open your model's definition file and review its extensions, select  [Database](#) .

For detailed information about the format of these files, see *Customizing and Extending PowerDesigner > DBMS Definition Files*.

Note

Some resource files are delivered with "Not Certified" in their names. We will perform all possible validation checks, but we do not maintain specific environments to fully certify these resource files. We will support them by accepting bug reports and providing fixes as per standard policy, with the exception that there will be no final environmental validation of the fix. You are invited to assist us by testing fixes and reporting any continuing inconsistencies.

1.1.5.4.1 Changing the DBMS

You can change the [DBMS](#) being modeled in your PDM at any time.

Context

If you change the DBMS being modeled, the model will be altered to conform with the new DBMS as follows:


- All data types specified in your model will be converted to their equivalents in the new DBMS.
- Any objects not supported by the new DBMS will be deleted
- Certain objects, whose behavior is heavily DBMS-dependent may lose their values.

Note

You may be required to change the DBMS if you open a model and the associated definition file is unavailable.

Procedure


1. Select  [Database](#) .



2. Select a **DBMS** from the list.

By default, PowerDesigner creates a link in the model to the specified file. To copy the contents of the resource and save it in your model file, click the **Embed Resource in Model** button to the right of this field. Embedding a file in this way enables you to make changes specific to your model without affecting any other models that reference the shared resource.

3. [optional] Click the **DBMS Preserve Options** tab, and select the check boxes for the objects and options that you want to preserve:
 - Triggers and stored procedures – triggers are always rebuilt when you change DBMS.
 - Physical options - if the syntax of an option is incompatible with the new DBMS, the values will be lost, even if you have selected to preserve the physical option. For example, the physical option *in* used by ASA is not supported by Oracle and any values associated with that option will be lost.
 - DBMS-specific objects - databases, storages, tablespaces, abstract data types, sequences.
 - Extended attributes - which are defined for a particular DBMS.



i Note

If you are changing DBMS within a database family, for example between SAP® Adaptive Server® Enterprise 12.5 and 15, all preserve options available are selected by default. The database objects not supported by the old and new DBMSs are disabled.

4. Click **OK**.

A message box opens to tell you that the DBMS has been changed.


5. Click **OK** to return to the model.

1.1.5.5 Extending your Modeling Environment

You can customize and extend PowerDesigner metaclasses, parameters, and file generation with extensions, which can be stored as part of your model or in separate extension files (*.xem) for reuse with other models.

To access extensions defined in a *.xem file, simply attach the file to your model. You can do this when creating a new model by clicking the **Select Extensions** button at the bottom of the New Model dialog, or at any time by selecting **Model > Extensions** to open the List of Extensions and clicking the **Attach an Extension** tool.

In each case, you arrive at the Select Extensions dialog, which lists the extensions available, sorted on sub-tabs appropriate to the type of model you are working with:



To quickly add a property or collection to an object from its property sheet, click the menu button in the bottom-left corner (or press F11) and select [New Attribute](#) or [New List of Associated Objects](#). For more information, see [Core Features Guide > Modeling with PowerDesigner > Objects > Extending Objects](#).

To create a new extension file and define extensions in the Resource Editor, select [Model > Extensions](#), click [Add a Row](#), and then click [Properties](#). For detailed information about working with extensions, see [Customizing and Extending PowerDesigner > Extension Files](#).

1.1.5.6 Traceability Links

Traceability links provide a flexible means for creating a connection between any object in any type of model and any other object in the same model or any other model open in your workspace. Traceability links have no formal semantic meaning, but can be followed when performing an impact analysis or otherwise navigating through the model structure.

To create a traceability link between objects in the same diagram, select the [Link/Traceability Link](#) tool in the Toolbox. Click inside the symbol of the object that is dependent and, while continuing to hold down the mouse button, drag the cursor and release it on the symbol of the object on which it depends. In this example, the **Work** entity is shown as being dependent on **School** through a traceability link:



To create a traceability link to any object in any model that is open in the Workspace, open the property sheet of the dependent object, click its [Traceability Links](#) tab, and click the [Add Objects](#) tool. Use the [Model](#) list to select a

different model, select the object to point to and click *OK* to create the link and return to the dependent object's *Traceability Links* tab. You can optionally specify a type for any traceability link in the *Link Type* column.

Click the *Types and Grouping* tool to perform various actions on this tab:

- To make a link type available for selection in the *Link Type* column, click the *Types and Grouping* tool and select *New Link Type*. Enter a *Name* for the link type and, optionally, a *Comment* to explain its purpose, and then click *OK*.

i Note

Traceability link types created in this way are stored as stereotypes in an extension file embedded in the model. To work directly with this file click the *Types and Grouping* tool and select *Manage Extensions*. For detailed information about working with these files, see *Customizing and Extending PowerDesigner > Extension Files*.

- To control the display and grouping of links, click the *Types and Grouping* tool and select:
 - *No Grouping* - to display all the links in a single list.
 - *Group by Object Type* - to display links to different types of objects on separate sub-tabs. To add a link to a new object type, click the plus sign on the leftmost sub-tab.
 - *Group by Link Type* - to display different link types on separate sub-tabs. To add a new link type, click the plus sign on the leftmost sub-tab.

i Note

To see all of the objects that point to an object via traceability links, open its property sheet, click its *Dependencies* tab, and click the *Incoming Traceability Links* sub-tab.

1.2 Conceptual and Logical Diagrams

The data models in this chapter allow you to model the semantic and logical structure of your system.

PowerDesigner provides you with a highly flexible environment in which to model your data systems. You can begin with either a CDM (see [Conceptual Diagrams \[page 32\]](#)) or an LDM (see [Logical Diagrams \[page 44\]](#)) to analyze your system and then generate a PDM (see the [Physical Diagrams \[page 81\]](#)) to work out the details of your implementation. Full support for database reverse-engineering allows you to take existing data structures and analyze them at any level of abstraction.


For more information about intermodel generation, see [Generating Other Models from a Data Model \[page 337\]](#).

1.2.1 Supported CDM/LDM Notations



PowerDesigner supports the most popular data modeling notations in the CDM and LDM. You can choose your notation by clicking **Tools > Model Options** and selecting it in the **Notation** list.

Entity/relationship Notation


In the Entity/relationship notation, entities are represented as rectangles and divided in three compartments: name, attributes, and identifiers.



The termination points of relationships indicate the cardinality as follows:



(Note that the Merise notation uses associations instead of relationships):




Inheritance symbols indicate if they are complete and if they have mutually exclusive children:


Complete	Mutually exclusive	Symbol
No	No	∅
Yes	No	∅
No	Yes	∅
Yes	Yes	∅

IDEF1X Notation

In the Idef1x notation, entity names are displayed outside the symbol, and dependent entities are drawn with round corners.



Relationship symbols indicate the cardinality as follows:




Inheritance symbols indicate if the inheritance is complete:

Complete	Symbol
Yes	
No	

Barker Notation


In the Barker notation, entities are drawn with round corners, and inheritances are displayed by placing children inside the parent entity.




Only attributes are listed and a symbol specifies whether each attribute is a key, a mandatory or an optional attribute as follows:

- # Primary
- * Mandatory
- o Optional

Relationship symbols indicate the cardinality as follows:




The line style specifies if a relationship is mandatory:



1.2.2 Conceptual Diagrams

A conceptual data diagram provides a graphical view of the conceptual structure of an information system, and helps you identify the principal entities to be represented, their attributes, and the relationships between them.

In the following example, the Teacher and Student entities inherit attributes from the Person parent entity. The two child entities are linked with a one-to-many relationship (a teacher has several students but each student has only one main teacher) and the other entities are linked through one-to-many or many-to-many relationships:



Note

To create a conceptual diagram in an existing CDM, right-click the model in the Browser and select **New > Conceptual Diagram**. To create a new model, select **File > New Model**, choose Conceptual Data Model as the model type and **Conceptual Diagram** as the first diagram, and then click **OK**.

The following objects can be created in a conceptual diagram:

Tool	Description
[none]	Data Item - An elementary piece of information. See Data Items (CDM) [page 47] .
	Entity - A person, place, thing, or concept that is of interest to the enterprise. See Entities (CDM/LDM) [page 50] .
[none]	Entity Attribute - An elementary piece of information attached to an entity. See Attributes (CDM/LDM) [page 55] .
[none]	Domain - A set of values for which a data item is valid. See Domains (CDM/LDM/PDM) [page 179] .

Tool	Description
[none]	Identifier - One or many entity attributes, whose values uniquely identify each occurrence of the entity. See Identifiers (CDM/LDM) [page 58] .
	One-Many, One-Many Dependent, Many-Many Relationship - A connection between entities (ER modeling methodology). See Relationships (CDM/LDM) [page 59] .
	Inheritance - A relationship that defines an entity as a special case of a more general entity. See Inheritances (CDM/LDM) [page 70] .
	Association - A connection or association between entities (Merise modeling methodology). See Associations and Association Links (CDM) [page 74] .
	Association Link - A link that connects an association to an entity. See Associations and Association Links (CDM) [page 74] .

1.2.2.1 Example: Building a Data Dictionary in a CDM

PowerDesigner supports the definition and maintenance of an enterprise data dictionary in a CDM. A data dictionary defines the data items, entities and attributes of the enterprise, and by managing it in a CDM and linking it (through generation or through the mapping editor) with your data and other models, you can ensure consistency of use and benefit from sophisticated impact analysis and "where used" reporting.

Context

Data dictionaries ensure consistency of use by providing a single authoritative definition for all common data elements used across the enterprise. They are used to standardize data content, context, and definitions and to achieve consistency and reusability while increasing the quality of the data used throughout the organization. By clearly defining and delineating the objects that comprise the enterprise and its systems, they enable:


- easier integration and communication between systems
- more standardized messaging between applications
- higher quality business intelligence and analytics
- better understanding between all subject matter experts
- more agile response to change and more complete impact analysis

A data dictionary defined in a PowerDesigner CDM provides:


- a unique list of entities and data items
- data items as descriptions of data artifacts
- entities connected to data items through attributes
- entity-to-entity relationships
- traceability from the data dictionary to logical and physical data models and other models
- impact analysis and "where used" reporting capabilities

Procedure

1. Select **File > New** to open the New Model dialog, select to create a new CDM and give it an appropriate name, for example, **Enterprise Data Dictionary**.



2. Select **Model > Data Items** to open the List of Data Items and enter some concepts that you want to define. Each data item is an elementary piece of information, which represents a fact or a definition defined using business terms.



Some examples of data items are **Customer Name**, **Order Description**, and **Zip Code**. Data items exist independently of any containing entity, which is important in a data dictionary as you are seeking to define atomic business data and terms, independent of how they may ultimately be used by entities. For more information about defining data items, see [Data Items \(CDM\) \[page 47\]](#).


3. Select  **Model**  **Entities**  to open the List of Entities and enter some of the entities that you want to define. Entities represent more complex business structures composed of one or more attributes (which are associated with data items).

Some examples of entities are **Customer**, **Product**, **Order**. When you create entities, a symbol for each one will be created in the CDM diagram. While such a graphical representation is not strictly necessary for the purposes of creating a data dictionary, you may find this diagram useful to help you visualize the content and structure of business concepts.



For more information about defining entities, see [Entities \(CDM/LDM\) \[page 50\]](#).

- Double-click an entity in the Browser or diagram to open its property sheet, and click the *Attributes* tab. Entity attributes provide the link between an entity and a data item:




Create a new attribute by reusing an existing data item by clicking the *Reuse Data Item* tool and selecting the data item that you want to reuse. By default, PowerDesigner allows you to reuse a data item for more than one entity attribute so that, for example, you can define a **Zip Code** data item once, and reuse it in whatever entities contain addresses. If you then update the data item, your changes will simultaneously cascade down to all the entity attributes that use it. This is a great way to enforce consistency throughout the data dictionary model.


You can also create data items in this list by clicking the *Insert a Row* or *Add a Row* tool to add a new line in the list and entering an appropriate name. PowerDesigner will create the attribute and an associated data item.

You can also create a new attribute by creating a copy of an existing data item. Click the [Add Data Item](#) tool and select the data item that you want to copy. Any changes made through this attribute or directly to this copy of the data item will only affect this attribute and no others.

- Double-click one of your entity symbols (or its Browser entry) to open its property sheet so that you can provide a precise definition for it. The *Comment* field on the *General* tab is intended for a simple, short description in unformatted text, while the *Description* field on the Definition tab allows for fully formatted text, and is intended to contain the complete, detailed definition from the business:




6. [optional] Select the *Relationship* tool in the pallet and create relationships between the entities in your data dictionary. Click and hold in one entity, then drag the cursor to a second entity and release the mouse button. Draw other relationships as necessary and then right-click anywhere in the diagram to drop the tool. Double-click a relationship line to open its property sheet and specify properties such as role name and cardinality.




For detailed information about defining relationships, see [Relationships \(CDM/LDM\) \[page 59\]](#).

7. The purpose of a data dictionary is to map the concepts that it defines to the concepts, logical entities, and physical tables that make up the implementation of these ideas in the enterprise. PowerDesigner provides two complementary methods for connecting the data dictionary with your other models:
 - o Generation - If you have no existing PDM, you can generate a new model from your data dictionary. Click **Tools** **Generate Physical Data Model** to open the Generate dialog, select the **Generate new...** option, and specify a name for the model to generate. Click the **Selection** tab and select the concepts you want to generate to the new model, and then click **OK**.



You can review the links created between the data dictionary and your other models in the Generation Links Viewer (select **Tools > Generation Links > Derived Models**).


You can regenerate whenever necessary to propagate updates or additions in the data dictionary to your other models. The Merge Models dialog (see *Core Features Guide > Modeling with PowerDesigner > Comparing and Merging Models*) will appear, which lets you review and approve (or reject) the changes that will be propagated from the data dictionary to the model.



For detailed information about generating models, see [Generating Other Models from a Data Model \[page 337\]](#).

- Mapping Editor - If you have an existing PDM or other model it may be more appropriate to map your data dictionary concepts to your PDM objects using the Mapping Editor, which provides a finer degree of control and a simple drag and drop interface.

Open the model containing the objects you want to link with your data dictionary and select **Tools > Mapping Editor**. In the Data Source Creation Wizard, enter **Data Dictionary** in the **Data Source** field, select **Conceptual Model** in the **Model type** list, and click **Next**. Select your data dictionary CDM and click **Next**. Select the **Create default mapping** option to instruct PowerDesigner to auto-create mappings where possible based on shared names, and click **Finish** to open your model and the data dictionary in the Mapping Editor:




You can create additional mappings as necessary by dragging and dropping entities and attributes from the data dictionary onto objects in the target model. Note that mappings created in this way will not automatically propagate changes.


For detailed information about using the Mapping Editor, see *Core Features Guide > Linking and Synchronizing Models > Object Mappings*.

- Once the data dictionary is established and linked to the other models used in the enterprise to define the information architecture, you will need to manage changes to it. New concepts will be added and existing elements updated due to refinements in understanding the business or changes to business operations. Some elements may also be removed (though this will probably be rare). Maintaining your data dictionary in a PowerDesigner CDM enables you to leverage sophisticated impact analysis tools to help you understand the time, cost and risk associated with proposed changes.

To launch an impact analysis, select one or more objects in a diagram or the Browser and select **Tools > Impact and Lineage Analysis**:



You can edit the rule sets used to control the analysis and manually adjust the tree view by right-clicking items. Once the analysis view contains the level of detail you want, click the [Generate Diagram](#) button to create an impact analysis diagram. This diagram, which can be saved and compared to other impact analysis snapshots, shows the connections that link your dictionary concepts through intermediate objects and models to the physical objects that implement them, providing a graphical "where used" report:



The diagram helps you plan the implementation of a change, as everything defined in the diagram will require further assessment to ensure the change does not invalidate any specific work we have done at the implementation level.

For detailed information about working with impact analysis, see *Core Features Guide > Linking and Synchronizing Models > Impact and Lineage Analysis*.


9. Share your data dictionary with your modeling team and ensure that the latest version is always available to them, by checking it into your PowerDesigner repository library as a reference model (see *Core Features Guide > Administering PowerDesigner > Deploying an Enterprise Glossary and Library*).
10. Share your data dictionary with other members of your organization through the *PowerDesigner Portal* (see *Core Features Guide > Modeling with PowerDesigner > The Repository > Repository Web Clients > The PowerDesigner Portal*) or by publishing it to HTML or RTF (see *Core Features Guide > Modeling with PowerDesigner > Reports*).

1.2.3 Logical Diagrams

A logical data diagram provides a graphical view of the structure of an information system, and helps you analyze the structure of your data system through entities and relationships, in which primary identifiers migrate along one-to-many relationships to become foreign identifiers, and many-to-many relationships can be replaced by intermediate entities.

To create a logical diagram in an existing LDM, right-click the model in the Browser and select **New > Logical Diagram**. To create a new model, select **File > New Model**, choose Logical Data Model as the model type and *Logical Diagram* as the first diagram, and then click **OK**.

The following logical diagram represent the same system as that in our CDM example (see *Conceptual Diagrams [page 32]*), but primary identifiers have migrated along one-to-many relationships to become foreign identifiers, and many-to-many relationships are replaced with an intermediary entity linked with one-to-many relationships to the extremities.



The following objects can be created in a conceptual diagram:


Tool	Description
	Entity - A person, place, thing, or concept that is of interest to the enterprise. See Entities (CDM/LDM) [page 50] .
[none]	Entity Attribute - An elementary piece of information attached to an entity. See Attributes (CDM/LDM) [page 55] .
[none]	Domain - A set of values for which a data item is valid. See Domains (CDM/LDM/PDM) [page 179] .
[none]	Identifier - One or many entity attributes, whose values uniquely identify each occurrence of the entity. See Identifiers (CDM/LDM) [page 58] .
	One-Many, One-Many Dependent, Many-Many Relationship - A connection between entities (ER modeling methodology). See Relationships (CDM/LDM) [page 59] .
	Inheritance - A relationship that defines an entity as a special case of a more general entity. See Inheritances (CDM/LDM) [page 70] .

1.2.3.1 Importing a Deprecated PDM Logical Model

If you have previously created a PDM with the logical model DBMS, you will be invited to migrate to an LDM when you open it.

Procedure

1. Select **File > Open** and browse to the PDM logical model to open.
2. Click **Open** to display the Import Logical Data Model dialog:



3. Choose one of the following options:
 - Convert the model to a logical data model – Note that only tables, columns, keys and references are preserved
 - Change the DBMS target to "ANSI Level 2" and open it as a PDM
4. Click **OK** to open the model.

Results

i Note


A PDM with the logical model DBMS that had been generated from a CDM will retain its links to the source CDM when you convert it to an LDM. However, for any PDM generated from the old LDM, you will need to restore the generation links by regenerating the PDM from the new LDM, using the Update existing PDM option (see *Core Features Guide > Linking and Synchronizing Models > Generating Models and Model Objects*).

1.2.3.2 Importing Multiple Interconnected PDM Logical Models

If you have previously created multiple PDMS with the logical model DBMS, and these models are connected by shortcuts and generation or other links, you can convert them en masse to logical data models and preserve their interconnections.

Procedure

1. Select **File > Import > Legacy Logical Data Models** to open the Import Logical Data Models dialog:



2. Click **Open**, browse to the legacy PDMS you want to import, select them, and then click **OK** to add them to the list. You can, if necessary, add multiple PDMS from multiple directories by repeating this step.
3. When you have added all the necessary PDMS to the list, click **OK** to import them into interconnected LDMs.

1.2.4 Data Items (CDM)

A data item is an elementary piece of information, which represents a fact or a definition in an information system, and which may or may not have any eventual existence as a modeled object.

You can attach a data item to an entity (see [Entities \(CDM/LDM\) \[page 50\]](#)) in order to create an entity attribute (see [Attributes \(CDM/LDM\) \[page 55\]](#)), which is associated with the data item.

There is no requirement to attach a data item to an entity. It remains defined in the model and can be attached to an entity at any time.

Data items are not generated when you generate an LDM or PDM.

Example

In the information system for a publishing company, the last names for authors and customers are both important pieces of business information. The data item LAST NAME is created to represent this information. It is attached to the entities AUTHOR and CUSTOMER, and becomes entity attributes of those entities.

Another piece of information is the date of birth of each author. The data item BIRTH DATE is created but, as there is no immediate need for this information in the model, it is not attached to any entity.

1.2.4.1 Creating a Data Item

You can create a data item from the Browser or *Model* menu. Data items are automatically created when you create entity attributes.

- Select ► *Model* ► *Data Items* ▾ to access the List of Data Items, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select ► *New* ► *Data Item* ▾.
- Create an entity attribute (see [Attributes \(CDM/LDM\) \[page 55\]](#)). A data item will be automatically created.

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.2.4.2 Data Item Properties

To view or edit a data item's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Data type/ Length/ Precision	Specifies the form of data to be stored, such as numeric, alphanumeric, or Boolean, and, where appropriate, the maximum number of characters or numerals that can be stored, and the maximum number of places after the decimal point. Click the ellipsis button to choose from the list of standard data types (see PowerDesigner Standard Data Types [page 181]).

Property	Description
Domain	Specifies the domain associated with the object (see Domains (CDM/LDM/PDM) [page 179]). Use the tools to the right of this field to create or browse to a domain, or to open the property sheet of the selected domain.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- *Standard Checks* - Specifies constraints to control the range and format of permitted data (see [Setting Data Profiling Constraints \[page 102\]](#))
- *Additional Checks* - Displays an editable SQL statement, initialized with the standard checks, which can be used to generate more complex constraints (see [Specifying Advanced Constraints \[page 106\]](#)).
- *Rules* - Lists the business rules associated with the object (see [Business Rules \(CDM/LDM/PDM\) \[page 202\]](#)).

1.2.4.3 Controlling Uniqueness and Reuse of Data Items

You can control naming restraints and reuse for data items with CDM model options, by selecting .

Context

Option	When selected	When cleared
Unique code	<p>Each data item must have a unique code.</p> <p>If you try to select this option and some existing data items are already sharing a code, the following error will be displayed:</p> <p><i>Unique Code</i> option could not be selected because two data items have the same code: <code><data_item_code></code></p> <p>To be able to select the option, you must first assign unique codes to all data items.</p>	<p>Multiple data items can have the same code, and you differentiate them by the entities that use them. The entities are listed in the <i>Used By</i> column of the list of data items.</p> <div style="background-color: #ffffcc; padding: 10px;"> <p> Note</p> <p>To make an item visible in a list, click the <i>Customize Columns and Filter</i> tool in the list toolbar, select the appropriate check box from the list of filter options that is displayed, and click OK.</p> </div>
Allow reuse	One data item can be an entity attribute for multiple entities.	Each data item can be an entity attribute for only one entity

For more information about CDM model options, see [Setting CDM/LDM Model Options \[page 15\]](#).

1.2.5 Entities (CDM/LDM)

An entity represents an object about which you want to store information. For example, in a model of a major corporation, the entities created may include Employee and Division.

When you generate a PDM from a CDM or LDM, entities are generated as tables.

1.2.5.1 Creating an Entity

You can create an entity from the Toolbox, Browser, or *Model* menu.

- Use the *Entity* tool in the Toolbox.
- Select *Model* to access the List of Entities, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select *New* .

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.2.5.2 Entity Properties

To view or edit an entity's properties, double-click its diagram symbol or Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Number	Specifies the estimated number of occurrences in the physical database for the entity (the number of records).
Generate	Specifies that the entity will generate a table in a PDM. When modeling in the Barker notation (see Supported CDM/LDM Notations [page 28]), only leaf subtypes can be generated as PDM tables, and so this option is disabled on Barker supertype property sheets.

Property	Description
Parent Entity	[read-only] Specifies the parent entity. Click the Properties tool at the right of the field to open the parent property sheet.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- Attributes - lists the attributes associated with the entity (see [Attributes \(CDM/LDM\) \[page 55\]](#)).
- Identifiers - lists the attributes associated with the entity (see [Identifiers \(CDM/LDM\) \[page 58\]](#)).
- Rules - lists the business rules associated with the entity (see [Business Rules \(CDM/LDM/PDM\) \[page 202\]](#)).
- Subtypes – [Barker only] lists the subtypes that inherit from the entity.

1.2.5.3 Copying Entities

You can make a copy of an entity within the same model or between models. When you copy an entity, you create a new entity with a new name and code, attributes, and identifiers. Model options control whether you create new data items or reuse the data items that are attached to the original entity.

Procedure

- Select an entity in the CDM/LDM, and then select **Edit** > **Copy** (or press **Ctrl** + **C**).
- Select the diagram or model to where you want to copy the entity and select **Edit** > **Paste** (or press **Ctrl** + **V**).

The entity is copied and the new entity is displayed in the Browser and diagram.

i Note

When copying an entity to the same model, a new entity with a new name and code, attributes, and identifiers is always created, but the creation of new data items is controlled by data item model options (see [Setting CDM/LDM Model Options \[page 15\]](#)). Select:

- Allow reuse** - to attach the original data items to the new entity attributes. If this option is not selected, the original data items will be copied and these copies will be attached to the new entity attributes.
- Unique code** - to force all data items to have unique codes (though two or more data items can have the same name). If neither this option nor **Allow reuse** is selected, then duplicate data items will be created with the same names and codes.




1.2.5.4 Displaying Attributes and Other Information on an Entity Symbol

To set display preferences for entities, select *Tools* *Display Preferences*, and select the Entity sub-category in the left-hand Category pane.

Entity


By default the following properties can be displayed on entity symbols:

Preference	Display description
Attributes	<p>Specifies whether Attributes are displayed on entity symbols. If selected, you can choose between displaying:</p> <ul style="list-style-type: none">• All attributes - All attributes: • Primary attributes - Only primary identifier attributes: • Identifying attributes - All identifier attributes: • Display limit - Number of attributes shown depends on defined value. For example, if set to 5:


Preference	Display description
	
Identifiers	All identifier attributes for the entity are listed at the bottom of the entity symbol: 
Stereotype	Stereotype of the entity.
Comment	Comment of the entity. When selected, all other check boxes are deselected, except for Stereotype: 

Entity Attributes

By default the following properties can be displayed for entity attributes:

Preference	Display description
Data type	Data type for each entity attribute: 
Domain or data type	Domain for each entity attribute. You can only display domains when the Data type check box is selected.

Preference	Display description												
Domain	<p>Domain of an attribute in an entity. This display option interacts with the selection for Data types. As a result, there are four display options:</p> <ul style="list-style-type: none"> • Data types - Displays only the data type, if any: <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <table border="1" style="width: 100%; border-collapse: collapse;"> <tr> <td style="padding: 2px;">CUSTOMER</td> </tr> <tr> <td style="padding: 2px;">Customer Number <UNDEF></td> </tr> <tr> <td style="padding: 2px;">Customer Name A30</td> </tr> </table> </div> <ul style="list-style-type: none"> • Domains - Displays only the domain, if any: <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <table border="1" style="width: 100%; border-collapse: collapse;"> <tr> <td style="padding: 2px;">CUSTOMER</td> </tr> <tr> <td style="padding: 2px;">Customer Number Identifier</td> </tr> <tr> <td style="padding: 2px;">Customer Name <None></td> </tr> </table> </div> <ul style="list-style-type: none"> • Data types and Domain - Displays both data type and domain, if any: <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <table border="1" style="width: 100%; border-collapse: collapse;"> <tr> <td style="padding: 2px;">CUSTOMER</td> </tr> <tr> <td style="padding: 2px;">Customer Number <UNDEF> Identifier</td> </tr> <tr> <td style="padding: 2px;">Customer Name A30 <None></td> </tr> </table> </div> <ul style="list-style-type: none"> • Data types and Replace by domains - Displays either data type or domain, if any, and domain if both are present: <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <table border="1" style="width: 100%; border-collapse: collapse;"> <tr> <td style="padding: 2px;">CUSTOMER</td> </tr> <tr> <td style="padding: 2px;">Customer Number IDENTIFIER</td> </tr> <tr> <td style="padding: 2px;">Customer Name A30</td> </tr> </table> </div>	CUSTOMER	Customer Number <UNDEF>	Customer Name A30	CUSTOMER	Customer Number Identifier	Customer Name <None>	CUSTOMER	Customer Number <UNDEF> Identifier	Customer Name A30 <None>	CUSTOMER	Customer Number IDENTIFIER	Customer Name A30
CUSTOMER													
Customer Number <UNDEF>													
Customer Name A30													
CUSTOMER													
Customer Number Identifier													
Customer Name <None>													
CUSTOMER													
Customer Number <UNDEF> Identifier													
Customer Name A30 <None>													
CUSTOMER													
Customer Number IDENTIFIER													
Customer Name A30													
Mandatory	<p><M> indicators are displayed next to each mandatory attribute:</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <table border="1" style="width: 100%; border-collapse: collapse;"> <tr> <td style="padding: 2px;">Customer</td> </tr> <tr> <td style="padding: 2px;">Customer number <M></td> </tr> <tr> <td style="padding: 2px;">Customer name <M></td> </tr> <tr> <td style="padding: 2px;">Customer address <M></td> </tr> <tr> <td style="padding: 2px;">Customer activity</td> </tr> <tr> <td style="padding: 2px;">Customer telephone</td> </tr> <tr> <td style="padding: 2px;">... ...</td> </tr> </table> </div>	Customer	Customer number <M>	Customer name <M>	Customer address <M>	Customer activity	Customer telephone					
Customer													
Customer number <M>													
Customer name <M>													
Customer address <M>													
Customer activity													
Customer telephone													
... ...													

Preference	Display description
Identifier indicators	<pi> indicators are displayed next to primary identifiers and <ai> indicators next to non-primary identifiers:  <p>The screenshot shows a table titled 'Customer' with five rows: 'Customer number' (with a primary indicator <pi>), 'Customer name', 'Customer address', 'Customer activity', and 'Customer telephone'. Each row has three columns: the attribute name, its data type, and the identifier indicator.</p>
Stereotype	Displays the stereotype of the entity attributes

i Note

For information about selecting other properties to display, see *Core Features Guide > Modeling with PowerDesigner > Diagrams, Matrices, and Symbols > Display Preferences*.

1.2.6 Attributes (CDM/LDM)

In a CDM, attributes are data items attached to an entity, association, or inheritance. In an LDM, there are no data items, and so attributes exist in entities without a conceptual origin.

When you generate a PDM from a CDM or LDM, entity attributes are generated as table columns.

1.2.6.1 Creating an Attribute

You can create an entity attribute from the *Attributes* tab in the property sheet of an entity, association, or inheritance.

You can use the following tools, available on the *Attributes* tab:

Tool	Description
	<p><i>Add a Row</i> – Creates a new attribute and associated data item.</p> <p>If you have enabled the <i>Allow Reuse</i> model option (see Setting CDM/LDM Model Options [page 15]), the new data item can be used as an attribute for other objects.</p> <p>If you have enabled the <i>Allow Reuse</i> and <i>Unique Code</i> model options and you type the name of an existing data item, it will be automatically reused.</p>

Tool	Description
	<p>Add Data Item (CDM)/Add Attributes (LDM) - Opens a Selection window listing all the data items/attributes available in the model. Select one or more data items/attributes in the list and then click OK to make them attributes to the object.</p> <p>If the data item/attribute has not yet been used, it will be linked to the object. If it has already been used, it will be copied (with a modified name if you have enabled the Unique code model option) and the copy attached to the object.</p>
	<p>Reuse Data Item (CDM) - Opens a Selection window listing all the data items/attributes available in the model. Select one or more data items/attributes in the list and then click OK to make them attributes to the object.</p>

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.2.6.2 Attribute Properties

To view or edit an attribute's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The [General](#) tab contains the following properties:

i Note

Unlike the majority of PowerDesigner objects, entity attributes do not support new properties or other extensions.

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the Code field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Entity/ Association/ Inheritance	[read-only] Specifies the parent object. Click the tool to the right of the field to open its property sheet.
Data Item	[CDM only, read-only] Specifies the related data item (see Data Items (CDM) [page 47]). Click the tool to the right of the field to open its property sheet.
Inherited from	[LDM only, read-only] Specifies the parent entity from which the attribute is migrated through an inheritance.

Property	Description
Data type/ Length/ Precision	Specifies the form of data to be stored, such as numeric, alphanumeric, or Boolean, and, where appropriate, the maximum number of characters or numerals that can be stored, and the maximum number of places after the decimal point. Click the ellipsis button to choose from the list of standard data types (see PowerDesigner Standard Data Types [page 181]).
Domain	Specifies the domain associated with the object (see Domains (CDM/LDM/PDM) [page 179]). Use the tools to the right of this field to create or browse to a domain, or to open the property sheet of the selected domain.
Primary Identifier	[entity attributes only] Specifies that the attribute is the primary identifier of the entity.
Displayed	[entity and association attributes] Displays the attribute in the object symbol.
Mandatory	Specifies that every object occurrence must assign a value to the attribute. Identifiers (see Identifiers (CDM/LDM) [page 58]) are always mandatory.
Foreign identifier	[LDM only, read-only] Specifies that the attribute is the foreign identifier of the entity.

The following tabs are also available:

- *Standard Checks* - Specifies constraints to control the range and format of permitted data (see [Setting Data Profiling Constraints \[page 102\]](#))
- *Additional Checks* - Displays an editable SQL statement, initialized with the standard checks, which can be used to generate more complex constraints (see [Specifying Advanced Constraints \[page 106\]](#)).
- *Rules* - Lists the business rules associated with the object (see [Business Rules \(CDM/LDM/PDM\) \[page 202\]](#)).

1.2.6.3 Deleting Attributes (CDM)

When you delete an attribute, model options determine whether or not the corresponding data items are also deleted:

Model options selected	Result of deleting an attribute
Unique Code and Allow Reuse	Does not delete corresponding data item
Unique Code only	Does not delete corresponding data item
Allow Reuse only	Deletes corresponding data item if it is not used by another entity
None	Deletes corresponding data item

1.2.7 Identifiers (CDM/LDM)

An identifier is one or many entity attributes, whose values uniquely identify each occurrence of the entity.

Each entity must have at least one identifier. If an entity has only one identifier, it is designated by default as the primary identifier.

When you generate a PDM from a CDM or LDM, identifiers are generated as primary or alternate keys.

1.2.7.1 Creating an Identifier

You can create an identifier from the property sheet of an entity.

- Open the *Attributes* tab in the property sheet of an entity, select one or more attributes, and click the *Create Identifier* tool. The selected attributes are associated with the identifier and are listed on the attributes tab of its property sheet.
- Open the *Identifiers* tab in the property sheet of an entity, and click the *Add a Row* tool.

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.2.7.2 Identifier Properties

To view or edit an identifier's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Entity	Specifies the name of the entity to which the identifier belongs.
Primary identifier	Specifies that the identifier is a primary identifier.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- Attributes - lists the attributes (see [Attributes \(CDM/LDM\) \[page 55\]](#)) associated with the identifier: Click the [Add Attributes](#) tool to add an attribute.

1.2.8 Relationships (CDM/LDM)

A relationship is a link between entities. For example, in a model that manages human resources, the **Member** relationship links the **Employee** and **Team** entities and expresses that each employee works in a team, and each team has employees.



For example, *the employee Martin works in the Marketing team* is one occurrence of the **Member** relationship.

When you generate a PDM from a CDM or LDM, relationships are generated as references.

i Note

Relationships are used to link entities in the ER, Barker, and IDEF1X methodologies, while Merise uses associations (see [Associations and Association Links \(CDM\) \[page 74\]](#)). PowerDesigner lets you use relationships or associations exclusively, or combine the two methodologies in the same model. The following examples use the ER format. For more information about the other notations, see [Supported CDM/LDM Notations \[page 28\]](#).

A one-to-many relationship links one instance of the first entity to multiple instances of the second entity. Additional properties can make one or both sides of this relationship mandatory and define identification rules:

One-to-many relationship	Description
	<p>Each division may have zero or more employees Each employee may belong to zero or one division</p>
	<p>Each division must have one or more employees Each employee may belong to zero or one division</p>

One-to-many relationship	Description
<pre> classDiagram class Division { Division number <pk> Division name Division address } class Employee { Employee number <pk> First name Last name Employee number <not null> Employee salary } Division "1" -- "o" Employee </pre>	<p>Each division may have zero or more employees</p> <p>Each employee must belong to one and only one division</p>
<pre> classDiagram class Division { Division number <pk> Division name Division address } class Employee { Employee number <pk> First name Last name Employee number <not null> Employee salary } Division "1" -- "o" Employee </pre>	<p>Each division must have one or more employees</p> <p>Each employee must belong to one and only one division</p>
<pre> classDiagram class Division { Division number <pk> Division name Division address } class Employee { Employee number <pk> First name Last name Employee number <not null> Employee salary } Division "1" -- "o" Employee </pre>	<p>Each division may have zero or more employees</p> <p>Each employee must belong to one and only one division</p> <p>Each employee is identified uniquely by division number and employee number</p>
<pre> classDiagram class Division { Division number <pk> Division name Division address } class Employee { Employee number <pk> First name Last name Employee number <not null> Employee salary } Division "1" -- "o" Employee </pre>	<p>Each division must have one or more employees</p> <p>Each employee must belong to one and only one division</p> <p>Each employee is identified uniquely by division number and employee number</p>

A one-to-one relationship links one instance of the first entity with one instance of the second entity:

One-to-one relationship	Description
<pre> classDiagram class Team { Team number <pk> Speciality } class Project { Project number <pk> Project name Project label Start date End date } Team "1" -- "1" Project </pre>	<p>Each team works on zero or one project</p> <p>Each project is managed by zero or one team</p>

One-to-one relationship	Description
<pre> classDiagram class Team { Team number <pk> Team name Speciality } class Project { Project number <pk> Project name Project label Start date End date } Team "1" --> "1" Project </pre>	<p>Each team works on one and one project only</p> <p>Each project is managed by zero or one team</p>
<pre> classDiagram class Team { Team number <pk> Team name Speciality } class Project { Project number <pk> Project name Project label Start date End date } Team "1" --> "1" Project </pre>	<p>Each team works on zero or one project</p> <p>Each project is managed by one and one team only</p>
<p>A many-to-many relationship links multiple instances of the first entity to multiple instances of the second entity. This type of relationship is not permitted, by default, in the LDM (see Enabling Many-to-many Relationships in an LDM [page 67]):</p>	
<pre> classDiagram class Division { Division number <pk> Division name Division address } class Employee { Employee number <pk> First name Last name Employee number <pk> Employee salary } Division "2..>" --> "2..>" Employee </pre>	<p>Each division may have zero or more employees</p> <p>Each employee may belong to zero or more divisions</p>
<pre> classDiagram class Division { Division number <pk> Division name Division address } class Employee { Employee number <pk> First name Last name Employee number <pk> Employee salary } Division "2..>" --> "0..1" Employee </pre>	<p>Each division must have one or more employees</p> <p>Each employee may belong to zero or more divisions</p>
<pre> classDiagram class Division { Division number <pk> Division name Division address } class Employee { Employee number <pk> First name Last name Employee number <pk> Employee salary } Division "0..1" --> "2..>" Employee </pre>	<p>Each division may have zero or more employees</p> <p>Each employee must belong to one or more divisions</p>


Many-to-many relationship	Description
<pre> classDiagram class Department { Division number <pk> Division name Division address } class Employee { Employee number <pk> First name Last name Employee number Employee salary } Department "2..>" Employee "2..>" </pre>	<p>Each division must have one or more employees Each employee must belong to one or more divisions</p>

1.2.8.1 Creating a Relationship

You can create a relationship from the Toolbox, Browser, or *Model* menu.

- Use one of the *Relationship* tools in the Toolbox. Click inside the first entity and drag to the second entity:

Tool	Description
	<p><i>One-Many Relationship</i> - Link one instance of the first entity to multiple instances of the second entity. In this example, each department can contain many employees and each employee can belong to one department:</p> <pre> classDiagram class Department class Employee Department "1..>" Employee "M.." Department --> Employee : Department_Employee </pre>
	<p><i>Many-Many Relationship</i> - Link multiple instances of the first entity to multiple instances of the second entity. In this example, each employee can work on multiple projects and each project can have multiple employees working on it:</p> <pre> classDiagram class Employee class Project Employee "M..>" Project "M..>" Employee --> Project : Employee_Project </pre>

Tool	Description
	<p><i>One-Many Dependent Relationship</i> - Link one instance of the first entity to multiple instances of the second entity and specifies that each of the many second entities is dependent on and is partially identified by the first entity. In this example, each project can contain multiple tasks and each task must belong to one project:</p>  <pre> classDiagram class Project class Task Project "1" -- "*" Task : Project_Task </pre>

i Note

You can further refine or change the nature of the relationship in its property sheet.

- Select **Model > Relationships** to access the List of Relationships, and click the **Add a Row** tool.
- Right-click the model (or a package) in the Browser, and select **New > Relationship**.

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.2.8.2 Relationship Properties

To view or edit a relationship's properties, double-click its diagram symbol or Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The **General** tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the Code field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Entity1 Entity2	Specifies the two entities linked by the relationship. Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object.

Property	Description
Generate	Specifies that the relationship should be generated as a reference when you generate a PDM.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

Cardinalities Tab

The *Cardinalities* tab allows you to specify the nature of the relationship between the two entities. The following properties are available:

Property	Description
Cardinality	<p>Specifies the number of instances (none, one, or many) of an entity in relation to another entity. You can choose from the following values:</p> <ul style="list-style-type: none"> • One-to-one (<1..1>) - One instance of entity A can correspond to only one instance of entity B. • One-to-many (<1..n>) - One instance of entity A can correspond to more than one instance of entity B. • Many-to-one (<n..1>) - More than one instance of entity A can correspond to the same one instance of entity B. • Many-to-many (<n..n>) - More than one instance of entity A can correspond to more than one instance of entity B. To use n..n relationships in an LDM, see Enabling Many-to-many Relationships in an LDM [page 67]. <p>For information about the termination points of the relationships in each of the supported notations, see Supported CDM/LDM Notations [page 28].</p>

Property	Description
Dominant role	<p>[one-to-one relationships only] Specifies one direction of the relationship as dominant. If you define a dominant direction, the one-to-one relationship generates one reference in a PDM, with the dominant entity as the parent table. If you do not define a dominant direction, the one-to-one relationship generates two references.</p> <p>In the following example, the author is the dominant entity:</p> <pre> classDiagram class Author { Author ID <pk> Author Last Name Author First Name } class Picture { Picture ID <pk> Picture } Author "0..1" --> "1..1" Picture : is shown in </pre> <p>In a PDM, this relationship generates a reference with Author as the parent table, and its primary key migrated to the Picture table as a foreign key:</p> <pre> pdmDiagram class AUTHOR { AU_ID <pk> AU_LNAME AU_FNAME AUTHO_R_PK <pk> } class PICTURE { PIX_ID <pk> AU_ID <fk> PIX_PICTURE PICTURE_PK <pk> } AUTHOR "0..1" --> "1..1" PICTURE : AU_ID = AU_ID </pre>

In addition, this tab contains a groupbox for each direction of the relationship, containing the following properties:

Property	Description
Role name	<p>Text that describes the relationship of EntityA to EntityB, and which is used to generate the assertion statements displayed at the top of this tab. You should use the infinitive phrase that describes the relationship of one entity to the other. For example, Each Order may <contain> one or more line., and Each line must <belong to> one and only one Order.</p> <p>To modify the sentences generated from your role names, edit your model's assertion template (see Assertion Template [page 16]).</p>
Dependent	<p>Specifies that the entity is dependent on and partially identified by the other entity.</p> <p>In the following example, the task entity is dependent on the project entity. Each task is a part of a project and each project can contain zero or more tasks:</p> <pre> classDiagram class Task { Task name <pk> Task cost } class Project { Project number <pk> Project name Project label Start date End date } Task "0..n" --> "1..1" Project </pre>

Property	Description
Mandatory	<p>Specifies that each instance of the entity requires at least one instance of the other entity.</p> <p>For example, the subcontract relationship is optional from customer to project, but mandatory from project to customer. Each project must have a customer, but each customer does not have to have a project.</p> <p>Implied by dependent</p>
Cardinality	<p>Specifies the maximum and minimum number of instances of EntityA in relation to EntityB (if mandatory, at least 1). You can choose from the following values:</p> <ul style="list-style-type: none"> • 0..1 – Zero to one instances • 0..n – Zero to many instances • 1..1 – Exactly one instance • 1..n – one to many instances

Joins Tab (LDM)

The **Joins** tab lists the joins defined between parent and child entity attributes. Joins can link primary, alternate, or foreign identifiers, or any user-specified attributes.

On this tab, you can either:

- Select an identifier from the parent entity in the *Parent* field on which to base the join to autopopulate the list with its associated parent and child attributes. If necessary, you can modify the specified child attributes.
- Specify **<None>** in the *Parent* field and specify your own attribute pairs on which to base the join using the following tools:

Tool	Description
	<i>Reuse Attributes</i> - Create a join by matching parent and child attributes that share the same code.
	<i>Migrate Attributes</i> - First specify attributes in the <i>Parent Attribute</i> column and then click this tool to migrate them to foreign identifier attributes in the child table. If the attributes do not exist in the child table, they are created.
	<i>Cancel Migration</i> - Remove any attributes migrated to the child table.
	<i>Insert a Row</i> - Inserts a row before the selected row in the list to specify another attribute to join on.

Tool	Description
	<i>Add a Row</i> - Adds a row at the end of the list to specify another attribute to join on.

1.2.8.3 Enabling Many-to-many Relationships in an LDM

In an LDM, many-to-many relationships are, by default, not permitted and are represented with an intermediary entity. If you allow many-to-many relationships, you can select the many-to-many value in the cardinalities tab.

Procedure

1. Select  *Tools*  *Model Options* .
2. Select the *Allow n-n relationships* check box in the Relationship groupbox, and then click *OK* to return to the model.

Note


When generating an LDM from a CDM, you can authorize the generation of many-to-many relationships by clicking the *Configure Model Options* button on the *General* tab of the generation dialog, and selecting the *Allow n-n relationships* option.

1.2.8.4 Creating a Reflexive Relationship

A reflexive relationship is a relationship between an entity and itself.

Context

In the following example, the reflexive relationship *<Supervise>* expresses that an employee (Manager) can supervise other employees.




i Note

To obtain clean lines with rounded corners when you create a reflexive relationship, select  [Display Preferences](#)  [Format](#)  and modify the Line Style with the appropriate type from the Corners list.

Procedure

1. Click the [Relationship](#) tool in the Toolbox.
2. Click inside the entity symbol and, while continuing to hold down the mouse button, drag the cursor a short distance within the symbol, before releasing the button.

A relationship symbol loops back to the same entity.



Results

i Note

In the Dependencies page of the entity, you can see two identical occurrences of the relationship, this is to indicate that the relationship is reflexive and serves as origin and destination for the link

1.2.8.5 Defining a Code Option for Relationships

You can control naming restraints for relationships so that each relationship must have a unique code.

Context

If you do not select [Unique Code](#), two relationships can have the same code, and you differentiate them by the entities they link.

The following error message is displayed when the option you choose is incompatible with the current CDM:

Error message	Solution
Unique Code option could not be selected because at least two relationships have the same code: <relationship_code>.	Change the code of one relationship

Procedure

1. Select  **Tools**  to open the Model Options dialog box:
2. Select or clear the *Unique Code* check box in the *Relationship* groupbox, and then click *OK* to return to the model.

1.2.8.6 Changing a Relationship into an Associative Entity

You can transform a relationship between two entities into an associative entity linked by two relationships, and then attach entity attributes to the associative entity that you could not attach to the relationship.

Procedure

1. Right-click a relationship symbol and select  *Change to Entity*.
- The original relationship is split in two and an associative entity is created between the two new relationships, taking the name and code of the original relationship.
2. Open the property sheet of the associative entity or one of the new relationships to modify their properties as appropriate.

1.2.8.7 Identifier Migration Along Relationships

Migrations are made instantaneously in an LDM or during generation if you generate a PDM from a CDM.


Relationship type	Migration
Dependent one-to-many	Foreign identifiers become attributes of the primary identifier of the child entity.
Many-to-many	No attributes are migrated.
Dominant one-to-one	Primary identifier migrate from the dominant attribute.

Relationship type	Migration
Mandatory one-to-many	If the child to parent role is mandatory, migrated attributes are mandatory.

1.2.9 Inheritances (CDM/LDM)

An inheritance allows you to define an entity as a special case of a more general entity. The general, or supertype (or parent) entity contains all of the common characteristics, and the subtype (or child) entity contains only the particular characteristics.

In the example below, the Account entity represents all the bank accounts in the information system. There are two subtypes: checking accounts and savings accounts.



The inheritance symbol displays the inheritance status:

IDEF1X	E/R and Merise	Description
		Standard
—		Mutually exclusive inheritance
		Complete inheritance
—		Mutually exclusive and complete inheritance


Note

There is no separate inheritance object in the Barker notation (see [Supported CDM/LDM Notations \[page 28\]](#)), as inheritances are represented by placing one entity symbol on top of another. Barker inheritances are always complete and mutually exclusive, and the supertype lists its subtypes on the [Subtypes tab](#) (see [Entity Properties \[page 50\]](#)). Only leaf subtypes can be generated as PDM tables, and the [Generate](#) option is disabled on Barker supertype property sheets.


1.2.9.1 Creating an Inheritance

You can create an inheritance from the Toolbox, Browser, or [Model](#) menu.

- Select the [Inheritance](#) tool in the diagram Toolbox, click and hold inside the child entity and then drag to the parent entity and release the mouse button to create a link between the two entities with a half-circle symbol in the middle with the arrow pointing to the parent entity:



To add further child entities, click and hold inside the child entity and then drag to the inheritance half circle and release the mouse button:



- Select  [Model](#)  to access the List of Inheritances, and click the [Add a Row](#) tool. You will be required to specify a parent entity.
- Right-click the model or package in the Browser, and select  [New](#)  . You will be required to specify a parent entity.

For general information about creating objects, see [Core Features Guide > Modeling with PowerDesigner > Objects](#).

1.2.9.2 Inheritance Properties

To view or edit an inheritance's properties, double-click its diagram symbol or Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Parent	Specifies the name of the parent entity. Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object.
Mutually exclusive children	Specifies that only one child can exist for one occurrence of the parent entity.
Complete	Specifies that all instances of the parent entity (surtype) must belong to one of the children (subtypes). For example, entity Person has 2 sub-types Male and Female; each instance of entity Person is either a male or a female.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

Generation Tab

This tab allows you to specify how the inheritance structure will be generated to a PDM, including which attributes will be inherited.

Property	Description
Generation Mode	<p>Specifies which parts of the inheritance will be generated. You can specify one or both of the following:</p> <ul style="list-style-type: none"> • <i>Generate parent</i> - Generates a table corresponding to the parent entity. If one or more child entities are not generated, the parent will take on their attributes and references. • <i>Generate children</i> - Generates a table corresponding to each child entity. The primary key of each child table is the concatenation of the child entity identifier and the parent entity identifier. You must additionally choose between: <ul style="list-style-type: none"> ◦ <i>Inherit all attributes</i> – Each table inherits all the entity attributes of the parent entity ◦ <i>Inherit only primary attributes</i> - Each table inherits only the identifier of the parent entity <p>i Note</p> <p>For LDM inheritances, primary identifiers of a parent entity always migrate to all child entities, even if the children are not selected for generation, and any changes you make on this tab will have an immediate effect on the inheritance of attributes in the LDM.</p> <p>i Note</p> <p>You can control the generation of individual child tables using the <i>Generate</i> option in the property sheet of each child entity (see Entity Properties [page 50]).</p>
Specifying attributes	<p>In the case of parent-only generation, you can choose to define a specifying attribute, an entity attribute that is defined for a parent entity which differentiates occurrences of each child. For information about the tools on this tab, see Creating an Attribute [page 55].</p> <p>In the example below, the TITLE entity has two non-generated children, NONPERIODICAL and PERIODICAL, and a specifying entity attribute PERIODICAL is defined for the inheritance link to differentiate between the two child entities.</p> <pre> classDiagram class Title { Title ISBN <pi> Title Text Title Type Title Price } class Nonperiodical { Book collection } class Periodical { Periodical Format Periodical Pub Frequency } Title "2" --> Nonperiodical : Title "2" --> Periodical : Title "2" --> Periodical : PERIODICAL </pre> <p>In the PDM, the child entity attributes will generate columns in the table TITLE, and the specifying entity will generate a boolean PERIODICAL column, which indicates whether an instance of TITLE is a periodical.</p>

The following tabs are also available:

- [Children](#) - lists the child entities of the inheritance. Use the [Add Children](#) and [Delete](#) tools to modify the contents of the list.


1.2.9.3 Making Inheritance Links Mutually Exclusive

When an inheritance link is mutually exclusive, one occurrence of the parent entity cannot be matched to more than one child entity. This information is for documentation only and has no impact in generating the PDM.

To make an inheritance link mutually exclusive, open the inheritance property sheet and select the Mutually Exclusive Children check box. Then click [OK](#) to return to the diagram.

The mutually exclusive inheritance link displays an X on its half-circle symbol.

In the diagram below, the inheritance link is mutually exclusive, meaning that an account is either checking or savings, but never both.




1.2.10 Associations and Association Links (CDM)

In the Merise modeling methodology an association is used to connect several entities that each represents clearly defined objects, but are linked by an event, which may not be so clearly represented by another entity.


Each instance of an association corresponds to an instance of each entity linked to the association.

When you generate a PDM from a CDM, associations are generated as tables or references.

In the following example, three entities *VIDEOK7*, *CLIENT*, and *STORE* contain video cassette, client, and store information. They are linked by an association which represents a video cassette rental (*K7RENTAL*). The *K7RENTAL* association also contains the attributes *DATE* and *STAFF_ID*, which give the date of the rental, and the identity of the staff member who rented out the video cassette.



When you generate a PDM, K7RENTED is generated as a table with five columns, STORE_ID, K7_ID, CLIENT_ID, DATE, and STAFF_ID.



You can use associations exclusively in your CDM, or use both associations and relationships.

Association Links

An association is connected to an entity by an association link, which symbolizes the role and the cardinality between an association and an entity.


1.2.10.1 Creating an Association with Links

The easiest way to create an association between entities is to use the Association Link tool, which will create the association and the necessary links as well.

Procedure

1. Click the *Association Link* tool in the Toolbox.
2. Click inside the first entity and while continuing to hold down the mouse button, drag the cursor to a second entity. Release the mouse button.

An association symbol is created between the two entities.



1.2.10.2 Creating an Association Without Links

You can create an association without links from the Toolbox, Browser, or *Model* menu.

- Use the *Association* tool in the Toolbox..
- Select **Model > Associations** to access the List of Associations, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select **New > Association**.

Once you have created the association, you can link it to the relevant entities by using the Association Link tool.

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.2.10.3 Association Properties

To view or edit an association's properties, double-click its diagram symbol or Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Number	Specifies the estimated number of occurrences in the physical database for the association (the number of records).
Generate	Specifies that the association will generate a table in a PDM.
Attributes	Specifies the data item attached to an association.
Rules	Specifies the business rules associated with the association.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

1.2.10.4 Association Link Properties

To view or edit an association link's properties, double-click its diagram symbol or Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Entity	Specifies the entity connected by the association link. Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object.
Association	Specifies the association connected by the association link.
Role	Specifies the label indicating the role of the association link.


Property	Description
Identifier	Indicates if the entity is dependent on the other entity.
Cardinality	<p>Specifies the number of occurrences (one or many) that one entity has relative to another. You define the cardinality for each association link between the association and the entity. You can choose between:</p> <ul style="list-style-type: none"> • 0..1 - There can be zero or one occurrence of the association in relation to one instance of the entity. The association is not mandatory • 0..n - There can be zero or many occurrences of the association in relation to one instance of the entity. The association is not mandatory • 1..1 - One occurrence of the entity can be related to only one occurrence of the association. The association is mandatory • 1..n - One occurrence of the entity can be related to one or many occurrences of the association. The association is mandatory <p>You can change the default format of cardinalities from the registry:</p> <pre>HKEY_CURRENT_USER\Software\Sybase\<PowerDesigner <version> \ModelOptions\Conceptual Options CardinalityNotation=1 (0..1) or 2 (0,1)</pre>
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

1.2.10.5 Creating a Reflexive Association

A reflexive association is a relationship between an entity and itself.

Procedure

1. Click the *Association Link* tool in the Toolbox.
2. Click inside the entity symbol and, while continuing to hold down the mouse button, drag the cursor a short distance within the symbol, before releasing the button.
3. Drag the resulting association symbol away from entity to make clear its two links to the entity:



In the example above, the reflexive association *Manager* expresses that an employee (Manager) can manage other employees.


1.2.10.6 Defining a Dependent Association

In a dependent association, one entity is partially identified by another. Each entity must have an identifier. In some cases, however, the attributes of an entity are not sufficient to identify an occurrence of the entity. For these entities, their identifiers incorporate the identifier of another entity with which they have a dependent association.


Context

An entity named *Task* has two entity attributes, *TASK NAME* and *TASK COST*. A task may be performed in many different projects and the task cost will vary with each project.

To identify each occurrence of *TASK COST* the unique *Task* entity identifier is the compound of its *Task name* entity attribute and the *Project number* identifier from the *Project* entity.



When you generate a PDM, the *TASK* table contains the *PROJECT NUMBER* column as a foreign key, which is also a primary key column. The primary key therefore consists of both *PROJECT NUMBER* and *TASK NAME* columns.



Note

The same association can not have two identifier association links.

Procedure

1. Double-click an association link symbol to display the association link property sheet.

2. Select the Identifier check box and then click **OK** to return to the model.


The cardinality of the association link is enclosed in parenthesis to indicate that the association link is an identifier.

1.2.10.7 Changing an Association into an Associative Entity


You can transform an association into an associative entity linked by two associations. The associative entity gets the name and code of the association. The two new associations handle cardinality properties.

Context


Two entities *PROJECT MANAGER* and *CONTRACTOR* are linked by the association *WORKS ON PROJECT WITH*:



You can represent this association with an associative entity:



The two new associations can be represented as follows:



Procedure

Right-click an association symbol, and select Change to Entity from the contextual menu.

An associative entity that is linked to two associations replaces the original association. The associative entity takes the name of the original association.

1.2.10.8 Creating an Association Attribute

The tools used for creating association attributes on this tab are the same as those for creating entity attributes.


For more information, see [Creating an Attribute \[page 55\]](#).

1.3 Physical Diagrams

A physical data diagram provides a graphical view of your database structure, and helps you analyze its tables (including their columns, indexes, and triggers), views, and procedures, and the references between them.

To create a physical diagram in an existing PDM, right-click the model in the Browser and select **New > Physical Diagram**. To create a new model, select **File > New Model**, choose Physical Data Model as the model type and *Physical Diagram* as the first diagram, and then click **OK**.

In the following example, the Employee table is shown in relation to the Team, Division, Material, Task, and Project tables:



The following objects can be created in a physical diagram:

Tool	Description
	Table - A collection of rows (records) that have associated columns (fields). See Tables (PDM) [page 83] .
[none]	Column - A data structure that contains an individual data item within a row (record), model equivalent of a database field. See Columns (PDM) [page 99] .
[none]	Primary Key - A column or columns whose values uniquely identify each row in a table, and are designated as the primary identifier of each row in the table. See Primary, Alternate, and Foreign Keys (PDM) [page 115] .
[none]	Alternate Key - A column or columns whose values uniquely identify each row in a table, and which is not a primary key. See Primary, Alternate, and Foreign Keys (PDM) [page 115] .
[none]	Foreign Key - A column or columns whose values depend on and migrate from a primary or alternate key in another table. See Primary, Alternate, and Foreign Keys (PDM) [page 115] .
[none]	Index - A data structure associated with one or more columns in a table, in which the column values are ordered in such a way as to speed up access to data. See Indexes (PDM) [page 119] .
[none]	Default - [certain DBMSs] A default value for a column. See Defaults (PDM) [page 176] .
[none]	Domain - Defines valid values for a column. See Domains (CDM/LDM/PDM) [page 179] .
[none]	Sequence - [certain DBMSs] Defines the form of incrementation for a column. See Sequences (PDM) [page 186] .
[none]	Abstract data type [certain DBMSs] A user-defined data type. See Abstract Data Types (PDM) [page 188] .
	Reference - A link between a primary or an alternate key in a parent table, and a foreign key of a child table. Depending on its selected properties, a reference can also link columns that are independent of primary or alternate key columns. See References (PDM) [page 191] .
	View - A data structure that results from a SQL query and that is built from data in one or more tables. See Views (PDM) [page 123] .
	View reference - A link between a table and a view. See View References (PDM) [page 199] .
[none]	Trigger - A segment of SQL code associated with a table or a view. See Triggers (PDM) [page 130] .
	Procedure - A precompiled collection of SQL statements stored under a name in the database and processed as a unit. See Stored Procedures and Functions (PDM) [page 148] .
[none]	Database - The database of which the PDM is a representation. See Creating a Database in the Model [page 13] .
[none]	Storage - A partition on a storage device. See Tablespaces and Storages (PDM) [page 216] .
[none]	Tablespace - A partition in a database. See Tablespaces and Storages (PDM) [page 216] .

Tool	Description
[none]	User - A person who can log in or connect to the database. See Users, Groups, and Roles (PDM) [page 164] .
[none]	Role - A predefined user profile. See Users, Groups, and Roles (PDM) [page 164] .
[none]	Group - Defines privileges and permissions for a set of users. See Users, Groups, and Roles (PDM) [page 164] .
[none]	Synonym - An alternative name for various types of objects. See Synonyms (PDM) [page 174] .
[none]	Web service - A collection of SQL statements stored in a database to retrieve relational data in HTML, XML, WSDL or plain text format, through HTTP or SOAP requests. See Web Services (PDM) [page 218] .
[none]	Web operation - A sub-object of a Web service containing a SQL statement and displaying Web parameters and result columns. See Web Operations (PDM) [page 222] .

1.3.1 Tables (PDM)

A table is used to store data in a set of columns. Each record in the table is represented as a row, which is uniquely identified by the values in its primary key column or columns.

Tables are generally defined using the following sub-objects:

- Columns - are named properties of a table that describe its characteristics (see [Columns \(PDM\) \[page 99\]](#)).
- Primary Keys - Uniquely identify rows through the values in the column or columns with which they are associated (see [Primary, Alternate, and Foreign Keys \(PDM\) \[page 115\]](#)). Each key can generate a unique index or a unique constraint in a target database.
- Indexes - Help improve search times by ordering the values in the column or columns with which they are associated (see [Indexes \(PDM\) \[page 119\]](#)).
- Triggers - SQL code invoked automatically whenever there is an attempt to modify data in the tables (see [Triggers \(PDM\) \[page 130\]](#)).

Tables are linked together by references (see [References \(PDM\) \[page 191\]](#)).

1.3.1.1 Creating a Table

You can create a table from the Toolbox, Browser, or *Model* menu.

- Use the *Table* tool in the Toolbox.
- Select *Model* to access the List of Tables, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select *New* .

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.3.1.2 Table Properties

To view or edit a table's properties, double-click its diagram symbol or Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The [General](#) tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the Code field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Owner	Specifies the user who is the owner of the object. This is usually its creator. Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object.
Number	Specifies the estimated number of records in the table, which is used to estimate database size. This field is automatically populated during reverse engineering if you select the Statistics option (see Reverse Engineering from a Live Database [page 326]). You can enter your own value in this field, or refresh its statistics (along with those for all of the table's columns) at any time by right-clicking the table and selecting Update Statistics . To update the statistics for all tables, select Tools Update Statistics (see Reverse Engineering Database Statistics [page 333]).
Generate	Selects the table for generation to the database.
Dimensional type	Specifies the type of the table for purposes of creating star or snowflake schemas containing fact tables and dimensions. You can choose between: <ul style="list-style-type: none">• Fact - see Facts (PDM) [page 235]• Dimension - see Dimensions (PDM) [page 238]• Exclude - PowerDesigner will not consider the table when identifying or generating multidimensional objects. You can instruct PowerDesigner to complete this field for you (see Identifying Fact and Dimension Tables [page 232]). PowerDesigner's support for the generation of BusinessObjects universes (see Generating an SAP BusinessObjects Universe [page 311]) and of facts and dimensions in a multidimensional diagram (see Generating Cubes [page 233]) depends on the value of this field.
Type	[if your DBMS supports various types of table] Specifies the type of the table. You can choose between: <ul style="list-style-type: none">• Relational - Standard tables.• Object - Tables based on abstract data types (see Linking a Table to an Abstract Data Type [page 86]).• XML - Tables storing XML documents (see Creating an XML Table or View [page 86]).

Property	Description
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- [Columns](#) - Lists the columns associated with the table (see [Columns \(PDM\) \[page 99\]](#)). The following tools are available on this tab:

Tool	Description
	Insert a Row / Add a Row - Creates a column above the selected column or at the end of the list.
	Add Columns / Replicate Columns - Copies or replicates columns from another table (see Copying or Replicating a Column from Another Table [page 114]).
	Create Index - Creates an index associated with the selected columns (see Creating Standard, Key, or Function-Based Indexes [page 120]).
	Create Key - Creates a (by default, alternate) key associated with the selected columns (see Creating Alternate Keys [page 117]).

- [Indexes](#) - Lists the indexes associated with the table (see [Indexes \(PDM\) \[page 119\]](#)).
- [Keys](#) - Lists the keys associated with the table (see [Primary, Alternate, and Foreign Keys \(PDM\) \[page 115\]](#)).
- [Triggers](#) - Lists the triggers associated with the table (see [Triggers \(PDM\) \[page 130\]](#)).
- [Procedures](#) - Lists the procedures associated with the table (see [Stored Procedures and Functions \(PDM\) \[page 148\]](#)).
- [Check](#) - Specifies the constraints associated with the table (see [Setting Data Profiling Constraints \[page 102\]](#)).
- [Physical Options](#) - Lists the physical options associated with the table (see [Physical Options \(PDM\) \[page 96\]](#)).
- [Preview](#) - Displays the SQL code associated with the table (see [Previewing SQL Statements \[page 292\]](#)).
- [Lifecycle](#) - [if data lifecycle modeling is supported for your DBMS] Specifies how the table will be governed by a lifecycle (see [Lifecycles \(PDM\) \[page 206\]](#)):

Property	Description
Lifecycle	Specifies the lifecycle with which the table is associated. Select a lifecycle from the list or click the tools to the right of this field to create a new lifecycle or open the property sheet of the currently selected one.
Start date	Specifies the start date from which to generate the first partition. Click the Generate Partitions tool to the right of this field to create partitions for the table, based on the partition range and start date.
Partition range	[read only] Specifies the duration of the partitions that will be created for the table. This value is controlled by the lifecycle (see Lifecycle Properties [page 210]).
Row growth rate (per year)/Initial Rows	Specifies an estimate of the increase of the size of the table per year, and the number of rows to start from as a basis for the calculation of cost savings. Click the Estimate Cost Savings tool to the right of this field to perform the calculation.

Property	Description
Cost Savings	This groupbox lists the cost savings that accrue to the storage of this table's data through its association with the lifecycle. Each line in the grid represents one year of savings, which are shown as a monetary value and as a percentage of the cost of storing the data statically outside of a lifecycle.

- **Security Procedures** - [data lifecycle modeling only] Lists the procedures which control access to the table (see [Stored Procedures and Functions \(PDM\) \[page 148\]](#)).

1.3.1.3 Linking a Table to an Abstract Data Type

If your DBMS supports it, PowerDesigner allows you to base tables on abstract data types (ADT), where the table uses the properties of the ADT and the ADT attributes become table columns. To link a table to an ADT, open the table property sheet to the *General* tab, and select the ADT (of type Object, SQLJ Object, or Structured type) in the *Based On* field.

For detailed information about working with abstract data types, see [Abstract Data Types \(PDM\) \[page 188\]](#).

1.3.1.4 Creating an XML Table or View

If your DBMS supports it, PowerDesigner allows you to create XML tables and views. An XML table does not contain columns, and instead stores an XML document. You must associate the table with a registered XML schema to validate the XML document stored in the table, and can specify a root element for the structure stored in your table.

When you select the XML in the *Type* field, the *Column* tab is removed and the following properties are added to the *General* tab:

Property	Description
Schema	Enter the target namespace or name of an XML model (see XML Architecture) or use the <i>Select</i> tool to the right of the field to connect to the database and select a registered schema. The schema must be registered in the database to be used for validating XML documents.
Element	Allows you to specify a root element in the XML document. You can enter an element name or click the <i>Select</i> tool to the right of the field to select an element from an XML model open in the workspace or from the schema registered in the database If you select an element from a PowerDesigner XML model, the <i>Schema</i> property is set to the XML model target namespace.

1.3.1.5 Specifying Table Constraints

The table *Check* tab is initialized with the PowerDesigner %RULES% variable to generate validation rules specified on the *Rules* tab. You can edit the code on this tab by entering an appropriate SQL expression to supplement, modify, or replace these constraints.

You can override the default *Constraint name*. To revert to the default name, click to reset the *User-Defined* button to the right of the field:

For information about business rules, see [Business Rules \(CDM/LDM/PDM\) \[page 202\]](#). For information about setting column constraints, see [Setting Data Profiling Constraints \[page 102\]](#).

1.3.1.6 Denormalizing Tables and Columns

Database normalization consists in eliminating redundancy and inconsistent dependencies between tables. While normalization is generally considered the goal of database design, denormalization, the deliberate duplication of certain data in order to speed data retrieval, may sometimes be more desirable.

PowerDesigner supports denormalization through:

- Horizontal partitioning - dividing a table into multiple tables containing the same columns but fewer rows.
- Vertical partitioning - dividing a table into multiple tables containing the same number of rows but fewer columns.
- Table collapsing - merging tables in order to eliminate the join between them.
- Column denormalization - repeating a column in multiple tables in order to avoid creating a join between them.

Horizontal and vertical partitioning involve tradeoffs in terms of performance and complexity. Though they can improve query response time and accelerate data backup and recovery, they require additional joins and unions to retrieve data from multiple tables, more complex queries to determine which table contains the requested data, and additional metadata to describe the partitioned table. Column denormalization can simplify queries but requires more maintenance and storage space as data is duplicated.

When deciding whether to denormalize, you should analyze the data access requirements of the applications in your environment and their actual performance characteristics. Often, good indexing and other solutions may more effectively address performance problems. Denormalization may be appropriate when:

- Critical queries rely upon data from more than one table.
- Many calculations need to be applied to columns before queries can be successfully answered.
- Tables need to be accessed in different ways by different kinds of users simultaneously.
- Certain columns are queried extremely frequently.

1.3.1.6.1 Horizontal Partitions

Horizontal partitioning consists in segmenting a table into multiple tables each containing a subset of rows and the same columns in order to optimize data retrieval. You can use any column, including primary keys, as partitioning criteria.

Procedure

1. Select **Tools** **Denormalization** **Horizontal Partitioning**, or right-click a table in the diagram and select **Horizontal Partitioning** to open the Horizontal Partitioning Wizard.
2. Select the table to partition, specify whether you want to keep the original table after partitioning, and then click **Next**.
3. Create as many partition tables as necessary using the **Insert** and **Add a Row** tools (specifying an appropriate name for each, which must be unique in the model), and then click **Next**.
4. Click the **Add Columns** tool to select one or more discriminant columns to use as partition criteria (these columns will be excluded from the partitions), and then click **Next**.
5. Specify a name and code for the transformation object that will be created to preserve information about the partitioning, and then click **Finish** to create a table for each partition, taking the name of the partition. All references to the original table are created on each partition table.

In this example, the table **Annual Sales**, which contains a very large amount of data is horizontally partitioned on the **Year** column:

Before	After																																							
<table border="1"><thead><tr><th colspan="3">Annual Sales</th></tr><tr><th>OrderId</th><th>INTEGER</th><th><pk></th></tr><tr><th>Amount</th><th>NUMERIC</th><th></th></tr><tr><th>Year</th><th>DATE</th><th></th></tr></thead></table>	Annual Sales			OrderId	INTEGER	<pk>	Amount	NUMERIC		Year	DATE		<table border="1"><thead><tr><th colspan="3">Annual Sales_2010</th></tr><tr><th>OrderId</th><th>INTEGER</th><th><pk></th></tr><tr><th>Amount</th><th>NUMERIC</th><th></th></tr></thead></table> <table border="1"><thead><tr><th colspan="3">Annual Sales_2011</th></tr><tr><th>OrderId</th><th>INTEGER</th><th><pk></th></tr><tr><th>Amount</th><th>NUMERIC</th><th></th></tr></thead></table> <table border="1"><thead><tr><th colspan="3">Annual Sales_2012</th></tr><tr><th>OrderId</th><th>INTEGER</th><th><pk></th></tr><tr><th>Amount</th><th>NUMERIC</th><th></th></tr></thead></table>	Annual Sales_2010			OrderId	INTEGER	<pk>	Amount	NUMERIC		Annual Sales_2011			OrderId	INTEGER	<pk>	Amount	NUMERIC		Annual Sales_2012			OrderId	INTEGER	<pk>	Amount	NUMERIC	
Annual Sales																																								
OrderId	INTEGER	<pk>																																						
Amount	NUMERIC																																							
Year	DATE																																							
Annual Sales_2010																																								
OrderId	INTEGER	<pk>																																						
Amount	NUMERIC																																							
Annual Sales_2011																																								
OrderId	INTEGER	<pk>																																						
Amount	NUMERIC																																							
Annual Sales_2012																																								
OrderId	INTEGER	<pk>																																						
Amount	NUMERIC																																							

Note

Horizontal partitions created in a PDM generated from another model are preserved when applying changes from the original model. The absence of discriminant columns in the target PDM is respected in the Merge dialog (see *Core Features Guide > Modeling with PowerDesigner > Comparing and Merging Models*), and changes in the source model are selected, by default, to be cascaded as appropriate to all partition tables.

1.3.1.6.2 Vertical Partitions

Vertical partitioning consists in segmenting a table into multiple tables each containing a subset of columns and the same number of rows as the partitioned table. The partition tables share the same primary key.

Procedure

1. Select **Tools** **Denormalization** **Vertical Partitioning**, or right-click a table in the diagram and select **Vertical Partitioning** to open the Vertical Partitioning Wizard.
2. Select the table to partition, specify whether you want to keep the original table after partitioning, and then click **Next**.
3. Create as many partition tables as necessary using the **Insert** and **Add a Row** tools (specifying an appropriate name for each, which must be unique in the model), and then click **Next**.
4. Drag columns from under the original table in the **Available columns** pane, to the appropriate partition table in the **Columns distribution** pane, (or select source and target tables and use the **Add** and **Remove** buttons), and then click **Next**.
5. Specify a name and code for the transformation object that will be created to preserve information about the partitioning, and then click **Finish** to create a table for each partition, taking the name of the partition. All references to the original table are created on each partition table.

In this example, the table **Customer**, is divided into two tables, each of which details one type of information about the customer:

Before	After																																																																		
<table border="1"><thead><tr><th colspan="3">Customer</th></tr></thead><tbody><tr><td>CustomerID</td><td>INT</td><td> <pk></td></tr><tr><td>FirstName</td><td>VARCHAR(0)</td><td></td></tr><tr><td>LastName</td><td>VARCHAR(0)</td><td></td></tr><tr><td>Street</td><td>VARCHAR(0)</td><td></td></tr><tr><td>City</td><td>VARCHAR(0)</td><td></td></tr><tr><td>ZipCode</td><td>VARCHAR(0)</td><td></td></tr><tr><td>Country</td><td>VARCHAR(0)</td><td></td></tr><tr><td>CreditCardNo</td><td>INT</td><td></td></tr><tr><td>AccountNo</td><td>INT</td><td></td></tr></tbody></table>	Customer			CustomerID	INT	<pk>	FirstName	VARCHAR(0)		LastName	VARCHAR(0)		Street	VARCHAR(0)		City	VARCHAR(0)		ZipCode	VARCHAR(0)		Country	VARCHAR(0)		CreditCardNo	INT		AccountNo	INT		<table border="1"><thead><tr><th colspan="3">Customer_Identity</th></tr></thead><tbody><tr><td>CustomerID</td><td>INT</td><td> <pk></td></tr><tr><td>FirstName</td><td>VARCHAR(0)</td><td></td></tr><tr><td>LastName</td><td>VARCHAR(0)</td><td></td></tr><tr><td>Street</td><td>VARCHAR(0)</td><td></td></tr><tr><td>City</td><td>VARCHAR(0)</td><td></td></tr><tr><td>ZipCode</td><td>VARCHAR(0)</td><td></td></tr><tr><td>Country</td><td>VARCHAR(0)</td><td></td></tr></tbody></table> <table border="1"><thead><tr><th colspan="3">Customer_Payments</th></tr></thead><tbody><tr><td>CustomerID</td><td>INT</td><td> <pk></td></tr><tr><td>CreditCardNo</td><td>INT</td><td></td></tr><tr><td>AccountNo</td><td>INT</td><td></td></tr></tbody></table>	Customer_Identity			CustomerID	INT	<pk>	FirstName	VARCHAR(0)		LastName	VARCHAR(0)		Street	VARCHAR(0)		City	VARCHAR(0)		ZipCode	VARCHAR(0)		Country	VARCHAR(0)		Customer_Payments			CustomerID	INT	<pk>	CreditCardNo	INT		AccountNo	INT	
Customer																																																																			
CustomerID	INT	<pk>																																																																	
FirstName	VARCHAR(0)																																																																		
LastName	VARCHAR(0)																																																																		
Street	VARCHAR(0)																																																																		
City	VARCHAR(0)																																																																		
ZipCode	VARCHAR(0)																																																																		
Country	VARCHAR(0)																																																																		
CreditCardNo	INT																																																																		
AccountNo	INT																																																																		
Customer_Identity																																																																			
CustomerID	INT	<pk>																																																																	
FirstName	VARCHAR(0)																																																																		
LastName	VARCHAR(0)																																																																		
Street	VARCHAR(0)																																																																		
City	VARCHAR(0)																																																																		
ZipCode	VARCHAR(0)																																																																		
Country	VARCHAR(0)																																																																		
Customer_Payments																																																																			
CustomerID	INT	<pk>																																																																	
CreditCardNo	INT																																																																		
AccountNo	INT																																																																		

Note

Vertical partitions created in a PDM generated from another model are preserved when applying changes from the original model. The columns absent from each partition table in the target PDM are shown but not selected in the Merge dialog (see *Core Features Guide > Modeling with PowerDesigner > Comparing and Merging Models*). Any changes in the source model are proposed, where appropriate, to each of the partition tables, and you should deselect the change for those partitions to which you do not want to apply it.


1.3.1.6.3 Table Collapsing

Table collapsing consists in merging tables in order to eliminate joins and to improve query performance. You can collapse tables related to each other with a reference or tables with identical primary keys.

Procedure

1. Select **Tools > Denormalization > Table Collapsing**, or right-click a reference between the tables to collapse and select **Table Collapsing** to open the Table Collapsing Wizard.
2. Specify a name and code for the table to be created, and then click **Next**.
3. Click the **Add Tables** tool to select tables to collapse into the new table, specify whether you want to keep the original tables after collapsing, and then click **Next**.
4. Specify a name and code for the transformation object that will be created to preserve information about the collapsing, and then click **Finish** to collapse the selected tables into a single unified table (with graphical synonyms replacing each original table symbol in the diagram to minimize disruption of references).

In this example, the tables **Customer** and **Order** are collapsed together to eliminate the join and optimize data retrieval. The result is a single table (with 2 synonym symbols) with the primary key of the child table:



5. [optional] Delete one of more of the synonyms. References will redirect to the remaining symbol.

1.3.1.6.4 Column Denormalization

Column denormalization consists in replicating columns from one table to another to reduce the number of joins needed for frequently called queries. Though it can provide improved performance, column denormalization requires more maintenance and disk space as the data in the replicated column is stored twice.


Procedure

1. Select **Tools > Denormalization > Column Denormalization**, or right-click the table to which you want to replicate columns and select **Column Denormalization** to open the Column Denormalization Wizard.
2. Specify the table to which you want to replicate columns, and then click **Next**.
3. Select one or more columns, and then click **Finish** to replicate them to the selected table.

i Note

Replicas are, by default, read-only copies of objects. Any changes made to the original column are automatically propagated to the replica. This synchronization is controlled by a replication object for each replica, a list of which is available by selecting **Model > Replications**. To revert a column denormalization, simply delete the duplicated column from the target table property sheet. For detailed information about working with replicas and replications, see *Core Features Guide > Linking and Synchronizing Models > Shortcuts and Replicas*.

In this example, to obtain the division name on the pay slip of each employee without requiring a link to the **Division** table, the **DivisionName** column is replicated to the **PaySlip** table:



1.3.1.6.5 Denormalization Object Properties

A denormalization transformation object is automatically created when you partition a table using the Horizontal or Vertical Partitioning Wizard or collapse tables with the Table Collapsing Wizard. To access the property sheet of

this object, select **Model** **Transformations** to open the List of Transformations, select the appropriate denormalization, and then click the **Properties** tool.

The **General** tab contains the following properties:

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the Code field.
Partitioned table	[partitionings only] Specifies the name of the table used to create the table partitions.
Discriminant Columns	[horizontal partitionings] Specifies the name and code of the columns used as partition criteria.
Target table	[collapsings] Specifies the name of the table resulting from the collapsing of the tables.

The following tabs are also available:

- **Partitions** - [partitionings] Lists the tables associated with the partitioning. You can create or delete partition tables, and edit their properties. If you delete a partition, you are prompted to specify whether you want to delete the corresponding table.
- **Partition Columns** - [vertical partitionings] Displays the distribution of columns between the partition tables. You can drag and drop columns between tables.
- **Source Tables** - [table collapsings] Lists the tables that were collapsed. These tables will no longer exist unless you selected to keep them in the wizard.

1.3.1.6.6 Removing Partitionings and Table Collapsings

You can remove partitionings or table collapsings and either keep or remove the associated tables.

Select **Model** **Transformations** to open the List of Transformations. The following tools are available for removing transformations:

Tool	Description
	Delete - Removes the denormalization but retains any tables created by it.
	Cancel [if the denormalization object is based upon a table generated from another model] Removes the denormalization and any tables created by it. You can recover the original table by regenerating it from the source model.

Note

You cannot move or paste a denormalization object to another model or package.


1.3.1.7 PowerBuilder DataWindow Extended Attributes

When designing tables to be used in a SAP® PowerBuilder® DataWindow, you can manage the extended attributes which PowerBuilder uses to store application-based information, such as label and heading text for columns, validation rules, display formats, and edit styles.

Context

PowerDesigner supports the modeling of this information through an extension file. To enable the PowerBuilder extensions in your model, select **Model > Extensions**, click the *Attach an Extension* tool, select the PowerBuilder file (on the *General Purpose* tab), and click *OK* to attach it.

When this extension file is attached, additional properties for two PowerBuilder system tables (PBCatTbl for tables and PBCatCol for columns) are available on the PowerBuilder tab of tables and columns:



To import the PowerBuilder extended attributes contained in your database to your PDM, select **Tools > PowerBuilder > Reverse Extended Attributes**, click the *Connect to a Data Source* tool, select a machine or file data source and click *Connect*. Select the tables you want to reverse-engineer, and click *OK*.

To update the PowerBuilder extended attribute system tables in your database, select ► *Tools* ► *PowerBuilder* ► *Generate Extended Attributes* ▾, click the *Connect to a Data Source* tool, select a machine or file data source and click *Connect*. Select the tables you want to generate, and click *OK*. Reversed extended attributes are compared with the translated default values in the PowerBuilder extension file. If these attributes match, the reversed value is replaced by the default value from the extension file.

1.3.1.8 Displaying Column, Domain, and Data Type Information on a Table Symbol

To set display preferences for tables, select ► *Tools* ► *Display Preferences* ▾, and select the Table sub-category in the left-hand Category pane.

Columns

Keys and indexes are represented by indicators in the table symbol. Each key and index indicator is assigned a number. You can use these numbers to keep track of the different groups of alternate keys, foreign keys, and indexes in your model.

By default, the following information about columns can be displayed on table symbols.

Preference	Displays	Example										
Data types	Data type for each column	<table border="1"><tr><td colspan="2">Publisher</td></tr><tr><td>Publisher ID</td><td>char(12)</td></tr><tr><td>Publisher Name</td><td>varchar(40)</td></tr><tr><td>City</td><td>varchar(20)</td></tr><tr><td>State</td><td>char(2)</td></tr></table>	Publisher		Publisher ID	char(12)	Publisher Name	varchar(40)	City	varchar(20)	State	char(2)
Publisher												
Publisher ID	char(12)											
Publisher Name	varchar(40)											
City	varchar(20)											
State	char(2)											
Replace by domains	Domain codes for each column attached to a domain	<table border="1"><tr><td colspan="2">Publisher</td></tr><tr><td>Publisher ID</td><td>AN_IDENTIFIER</td></tr><tr><td>Publisher Name</td><td>NAMES</td></tr><tr><td>City</td><td>SHORT_TEXT</td></tr><tr><td>State</td><td>char(2)</td></tr></table>	Publisher		Publisher ID	AN_IDENTIFIER	Publisher Name	NAMES	City	SHORT_TEXT	State	char(2)
Publisher												
Publisher ID	AN_IDENTIFIER											
Publisher Name	NAMES											
City	SHORT_TEXT											
State	char(2)											
Domains	Domain of an attribute in the table. This display option interacts with the selection for Data types. As a result, there are four display options	See the Display Domain and Data Type section below for options and examples.										

Preference	Displays	Example																						
Key Indicators	<pk>, <fk>, and <ak> indicators next to primary key, foreign key, and alternate key columns respectively. When the Keys preference is also selected, the key names are listed at the bottom of the table symbol.	<table border="1"> <thead> <tr> <th colspan="2">Publisher</th> </tr> </thead> <tbody> <tr> <td>Publisher ID</td> <td><pk></td> </tr> <tr> <td>Author ID</td> <td><fk></td> </tr> <tr> <td>Title ISBN</td> <td><fk></td> </tr> <tr> <td>Publisher Name</td> <td><ak></td> </tr> <tr> <td>City</td> <td></td> </tr> <tr> <td>State</td> <td></td> </tr> <tr> <td>» Primary Key</td> <td><pk></td> </tr> <tr> <td>» Pub_Name</td> <td><ak></td> </tr> </tbody> </table>	Publisher		Publisher ID	<pk>	Author ID	<fk>	Title ISBN	<fk>	Publisher Name	<ak>	City		State		» Primary Key	<pk>	» Pub_Name	<ak>				
Publisher																								
Publisher ID	<pk>																							
Author ID	<fk>																							
Title ISBN	<fk>																							
Publisher Name	<ak>																							
City																								
State																								
» Primary Key	<pk>																							
» Pub_Name	<ak>																							
Index indicators	<i(n)> indicator next to indexed columns. When the Indexes preference is also selected, the index names and corresponding numbers are listed at the bottom of the table symbol	<table border="1"> <thead> <tr> <th colspan="2">Sale</th> </tr> </thead> <tbody> <tr> <td>Sale Invoice ID</td> <td><i1></td> </tr> <tr> <td>Store ID</td> <td><i2></td> </tr> <tr> <td>Title ISBN</td> <td><i3></td> </tr> <tr> <td>Sale Date</td> <td></td> </tr> <tr> <td>Sale Amount</td> <td></td> </tr> <tr> <td>Sale Terms</td> <td></td> </tr> <tr> <td>Sale Quantity</td> <td></td> </tr> <tr> <td>■ SALE_PK</td> <td><i1></td> </tr> <tr> <td>■ STORE_SALES_FK</td> <td><i2></td> </tr> <tr> <td>■ SALES_TITLE_FK</td> <td><i3></td> </tr> </tbody> </table>	Sale		Sale Invoice ID	<i1>	Store ID	<i2>	Title ISBN	<i3>	Sale Date		Sale Amount		Sale Terms		Sale Quantity		■ SALE_PK	<i1>	■ STORE_SALES_FK	<i2>	■ SALES_TITLE_FK	<i3>
Sale																								
Sale Invoice ID	<i1>																							
Store ID	<i2>																							
Title ISBN	<i3>																							
Sale Date																								
Sale Amount																								
Sale Terms																								
Sale Quantity																								
■ SALE_PK	<i1>																							
■ STORE_SALES_FK	<i2>																							
■ SALES_TITLE_FK	<i3>																							
NULL/NOT NULL	Column indicator: null, not null, identity, or with default (DBMS-dependent)	<table border="1"> <thead> <tr> <th colspan="2">PUBLISHER</th> </tr> </thead> <tbody> <tr> <td>PUB_ID</td> <td>not null</td> </tr> <tr> <td>AU_ID</td> <td>null</td> </tr> <tr> <td>TITLE_ISBN</td> <td>null</td> </tr> <tr> <td>PUB_NAME</td> <td>null</td> </tr> <tr> <td>CITY</td> <td>null</td> </tr> <tr> <td>STATE</td> <td>null</td> </tr> </tbody> </table>	PUBLISHER		PUB_ID	not null	AU_ID	null	TITLE_ISBN	null	PUB_NAME	null	CITY	null	STATE	null								
PUBLISHER																								
PUB_ID	not null																							
AU_ID	null																							
TITLE_ISBN	null																							
PUB_NAME	null																							
CITY	null																							
STATE	null																							

Display Domain and Data Type

You can display the domain of an attribute in the symbol of a table. There are four display options available:

Preference	Displays	Example						
Data types	Only the data type, if it exists	<table border="1"> <thead> <tr> <th colspan="2">SALE</th> </tr> </thead> <tbody> <tr> <td>SALE ID</td> <td><Undefined></td> </tr> <tr> <td>STORE ID</td> <td>char(12)</td> </tr> </tbody> </table>	SALE		SALE ID	<Undefined>	STORE ID	char(12)
SALE								
SALE ID	<Undefined>							
STORE ID	char(12)							

Preference	Displays	Example						
Domains	Only the domain, if it exists	<table border="1"> <tr><td colspan="2">SALE</td></tr> <tr><td>SALE_ID</td><td>SALE_IDENTIFIER</td></tr> <tr><td>STORE_ID</td><td><None></td></tr> </table>	SALE		SALE_ID	SALE_IDENTIFIER	STORE_ID	<None>
SALE								
SALE_ID	SALE_IDENTIFIER							
STORE_ID	<None>							
Data types and Domains	Both data type and domain, if they exist	<table border="1"> <tr><td colspan="2">SALE</td></tr> <tr><td>SALE ID</td><td><Undefined> SALE IDENTIFIER</td></tr> <tr><td>STORE ID</td><td>char(12) <None></td></tr> </table>	SALE		SALE ID	<Undefined> SALE IDENTIFIER	STORE ID	char(12) <None>
SALE								
SALE ID	<Undefined> SALE IDENTIFIER							
STORE ID	char(12) <None>							
Data types and Replace by domains	If domain exists and data type does not exist, then displays domain. If domain does not exist and data type exists, then displays data type.	<table border="1"> <tr><td colspan="2">SALE</td></tr> <tr><td>SALE ID</td><td>SALE_IDENTIFIER</td></tr> <tr><td>STORE ID</td><td>char(12)</td></tr> </table>	SALE		SALE ID	SALE_IDENTIFIER	STORE ID	char(12)
SALE								
SALE ID	SALE_IDENTIFIER							
STORE ID	char(12)							

i Note

For information about selecting other properties to display, see *Core Features Guide > Modeling with PowerDesigner > Diagrams, Matrices, and Symbols > Display Preferences*.

1.3.1.9 Physical Options (PDM)

Physical options are DBMS-specific parameters that specify how an object is optimized or stored in a database, and are included at the end of the object's Create statement. Physical options are defined in the DBMS definition file, and may be available for tables, columns, indexes, tablespaces, and other objects. You can specify default physical options for all objects of a particular type and for individual objects (overriding the default, if one is specified).

Context

There are two different interfaces for specifying physical options for individual objects, both of which are accessible through tabs on the object's property sheet. Changes made on either of these tabs will be reflected on the other:

- *Physical Options (Common)* – this tab is displayed by default (along with the *Partition* tab, if applicable), and lists the most commonly-used physical options as a standard property sheet tab. Select or enter values for the appropriate options and click *OK*

- *Physical Options* – this tab is hidden by default, and lists all the available physical options for the object in a tree format. To display this tab, click the Property Sheet Menu button and select ► *Customize Favorite Tabs* ► *Physical Options (All)* . Follow the procedure in [Defining Default Physical Options \[page 97\]](#), to specify options and set values for them.

Physical options can vary widely by DBMS. For example, in Oracle, you specify the tablespace where the table is stored with the `Tablespace` keyword, while in SAP® SQL Anywhere®, you use `In`. When you change DBMS, the physical options selected are preserved as far as possible. If a specific physical option was selected, the default value is preserved for the option in the new DBMS. Unselected physical options are reset with the new DBMS default values.

For detailed information about the syntax of physical options and how they are specified, see *Customizing and Extending PowerDesigner > DBMS Definition Files > Physical Options* .

i Note

In Oracle, the `storage` composite physical option is used as a template to define all the storage values in a storage entry to avoid having to set values independently each time you need to re-use them same values in a storage clause. For this reason, the Oracle physical option does not include the storage name (%s).


1.3.1.9.1 Defining Default Physical Options

You can define default physical options for all the objects of a particular type in the model.

Procedure

1. Select ► *Database* ► *Default Physical Options* to open the *Default Physical Options* dialog. There is a tab for each kind of object that supports physical options.

The *Table* tab opens by default. The *Syntax* sub-tab in the left pane lists the physical options available in the DBMS, and the *Items* sub-tab in the right pane lists the physical options that have been selected for the object.




The following tools are available for adding and removing physical options to an object:

Tool	Action when clicked
	Adds physical option selected in Syntax tab (left pane) to Items tab (right pane)
	Aligns a selected physical option in the Items tab with the corresponding physical option in the Syntax tab
	Removes physical option selected in Items tab

- To add a default option for the object, select it in the *Syntax* pane and click the *Add* tool to copy it to the *Items* pane. To add only a sub-parameter for the option, expand the option in the *Syntax* pane, select the required parameter and then click the *Add* tool.
- To set a default value for a physical option parameter, select it in the *Items* pane and enter or select the appropriate value in the field below the pane. The entered value will then be displayed against the parameter in the Items list.
- Repeat the above steps as many times as necessary to specify all your required physical options. By default, these options will be applied to all tables created subsequently in the model. To apply them to existing tables, click the *Apply to* button to select the tables to which you want to apply the options, and then click *OK*.
- Select the other tabs to specify physical options for other object types. (Note that the *Apply to* button is not available on the *Database* tab).
- Click *OK* to close the dialog and return to your model.

To override the default physical options for a particular object, set the appropriate values on the the object's *Physical Options (Common)* or *Physical Options* tab

You can view the physical options set for an object in its *Preview* tab.



i Note

The default physical options are stored in your model file.

1.3.2 Columns (PDM)

A column is a set of values of a single type in a table. Each row of the table contains one instance of each column. Each table must have at least one column, which must have a name and code and to which you can assign a data type, either directly, or via a domain.

1.3.2.1 Creating a Column

You can create a column from the property sheet of, or in the Browser under, a table.

- Open the *Columns* tab in the property sheet of a table, and click the *Add a Row* or *Insert a Row* tool

- Right-click a table in the Browser, and select  **New > Column**

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.3.2.2 Column Properties

To view or edit a column's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Table	Specifies the table which contains the column.
Data type/ Length/ Precision	<p>Specifies the form of data to be stored, such as numeric, alphanumeric, or Boolean, and, where appropriate, the maximum number of characters or numerals that can be stored, and the maximum number of places after the decimal point. Click the ellipsis button to choose from the list of standard data types (see PowerDesigner Standard Data Types [page 181]).</p> <p>To review the data types permitted by your DBMS, select  Database > Edit Current DBMS and navigate to    Script > DataType > PhysDataType. The following variables specify length and precision requirements:</p> <ul style="list-style-type: none"> • %n - length • %s - length with precision • %p - decimal precision <p>For example, the data type <code>char (%n)</code>, requires you to specify a length.</p>
Domain	Specifies the domain associated with the object (see Domains (CDM/LDM/PDM) [page 179]). Use the tools to the right of this field to create or browse to a domain, or to open the property sheet of the selected domain.
Primary key	Specifies that the values in the column uniquely identify table rows (see Creating Primary Keys [page 116]).
Foreign key	Specifies that the column depends on and migrates from a primary key column in another table (see Creating Foreign Keys [page 118]).

Property	Description
Sequence	[if supported by your DBMS] Specifies the sequence associated with the column (see Sequences (PDM) [page 186]).
Displayed	Specifies that the column can be displayed in the table symbol.
With default	[if supported by your DBMS] Specifies that the column must be assigned a value that is not null.
Mandatory	[if supported by your DBMS] Specifies that a non-null value must be assigned.
Identity	[if supported by your DBMS] Specifies that the column is populated with values generated by the database. Identity columns are often used as primary keys.
Computed	[if supported by your DBMS] Specifies that the column is computed from an expression using values from other columns in the table (see Creating a Computed Column [page 112]).
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

Detail Tab

The Detail tab contain the following properties:

Property	Description
Column fill parameters	<p>The fields in this groupbox model the size and distinctness of data values that you expect to store in the column and are used in conjunction with test data profiles (see Populating Columns with Test Data [page 107]). You can specify:</p> <ul style="list-style-type: none"> • <i>Null values</i> - [Default: 0%] Specifies the percentage of values to leave empty. • <i>Distinct values</i> - [Default: 100%] Specifies the percentage of values that must be unique • <i>Average Length</i> - [read only] Used for estimating the size of the database (see Estimating Database Size [page 317]). The default value is the maximum length for the data type defined for the column. <p>You can enter values by hand or obtain them from your database by selecting the <i>Statistics</i> option in the Reverse Engineering dialog (see Reverse Engineering from a Live Database [page 326]).</p> <p>To refresh the values in these fields for all a table's columns at any time, right-click the table symbol or its entry in the Browser and select <i>Update Statistics</i>. To update the column statistics for all the tables in a model, select <i>Tools</i> <i>Update Statistics</i> (see Reverse Engineering Database Statistics [page 333]).</p>
Profile	Specifies a test data profile to use to generate test data (see Populating Columns with Test Data [page 107]). Use the tools to the right of this field to create or browse to a profile, or to open the property sheet of the selected profile.

Property	Description
Computed Expression	Specifies an expression used to compute data for the column (see Creating a Computed Column [page 112]).

The following tabs are also available:

- [Standard Checks](#) - Specifies constraints to control the range and format of permitted data (see [Setting Data Profiling Constraints \[page 102\]](#))
- [Additional Checks](#) - Displays an editable SQL statement, initialized with the standard checks, which can be used to generate more complex constraints (see [Specifying Advanced Constraints \[page 106\]](#)).
- [Rules](#) - Lists the business rules associated with the object (see [Business Rules \(CDM/LDM/PDM\) \[page 202\]](#)).

1.3.2.3 Setting Data Profiling Constraints

PowerDesigner allows you to define data profiling constraints to control the range and format of data allowed in your database. You can specify constraints on the [Standard Checks](#) and [Additional Checks](#) tabs of table columns in your PDM, entity attributes in your CDM or LDM, and domains. You can also specify data quality rules on the [Rules](#) tab of PDM tables and columns, CDM/LDM entities and attributes, and domains.

The following constraints are available on the [Standard Checks](#) tab of PDM columns, CDM/LDM entity attributes, and CDM/LDM/PDM domains:

Property	Description
Values	Specifies the range of acceptable values. You can set a: <ul style="list-style-type: none"> • Minimum - The lowest acceptable numeric value • Maximum - The highest acceptable numeric value • Default - The value assigned in the absence of an expressly entered value. For the PDM, you can directly enter a default value or select a keyword (defined in the <code>Script\Sql\Keywords\ReservedDefault</code> entry of the DBMS definition file) from the list. Default objects (see Defaults (PDM) [page 176]) are also available for selection if your DBMS supports them.
Characteristics	These properties are for documentation purposes only, and will not be generated. You can choose a: <ul style="list-style-type: none"> • Format - A number of standard formats are available in the list. You can enter a new format directly in the field or use the tools to the right of the field to create a data format for reuse elsewhere. • Unit - A standard measure. • No space - Space characters are not allowed. • Cannot modify - The value cannot be updated after initialization.

Property	Description
Character case	<p>Specifies the acceptable case for the data. You can choose between:</p> <ul style="list-style-type: none"> • Mixed case [default] • Uppercase • Lowercase • Sentence case • Title case
List of values	<p>Specifies the various values that are acceptable.</p> <p>When specifying strings in the list of values, single or double quotation marks (depending on the DBMS) will be added around the values in the generated script unless:</p> <ul style="list-style-type: none"> • You surround the value by the appropriate quotation marks. • You surround the value by tilde characters. • The value is a keyword (such as NULL) defined in the DBMS. • PowerDesigner does not recognize your data type as a string. <p>The following examples show how string values are generated for a DBMS that uses single quotation marks:</p> <ul style="list-style-type: none"> • Active - generates as 'Active' • 'Active' - generates as 'Active' • "Active" - generates as '"Active"' • ~Active~ - generates as Active • NULL - generates as NULL <p>If you have specified a non-automatic test data profile, you can use the values defined in the profile to populate the list by clicking the Update from Test Data Profile tool.</p> <p>Select the Complete check box beneath the list to exclude all other values not appearing in the list.</p>

1.3.2.3.1 Specifying Constraints Through Business Rules

In addition to the constraints specified on the [Standard Checks](#) tab, you can specify business rules of type [Validation](#) or [Constraint](#) to control your data. Both types of rule contain SQL code to validate your data, and

you can attach them to tables and table columns in your PDM, entities and entity attributes in your CDM or LDM, and domains.

Context

You can use the following PowerDesigner variables when writing your rule expression:

Variable	Value
%COLUMN%	Code of the column to which the business rule applies
%DOMAIN%	Code of the domain to which the business rule applies
%TABLE%	Code of the table to which the business rule applies
%MINMAX%	Minimum and maximum values for the column or domain
%LISTVAL%	List values for the column or domain
%RULES%	Server validation rules for the column or domain

To attach a business rule (see [Business Rules \(CDM/LDM/PDM\) \[page 202\]](#)) to a table, column, entity, attribute, or domain, open the object's property sheet, select the *Rules* tab, and click the *Add Objects* tool.

At generation time, business rules of type **validation** are concatenated together into a single constraint, while rules of type **Constraint** will be generated as separate constraints if your DBMS supports them.

1.3.2.3.2 Creating Data Formats For Reuse

You can create data formats to reuse in constraints for multiple objects by clicking the *New* button to the right of the *Format* field on the *Standard Checks* tab. Data formats are informational only, and are not generated as constraints.

i Note

To create multiple data formats, use the List of Data Formats, available by selecting **Model** **Data Formats**.

Data Format Properties

To view or edit a data format's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The **General** tab contains the following properties:


Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Type	Specifies the type of the format. You can choose between: <ul style="list-style-type: none">• Date/Time• String• Regular Expression
Expression	Specifies the form of the data to be stored in the column; For example, 9999 . 99 would represent a four digit number with two decimal places.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

1.3.2.3.3 Specifying Advanced Constraints

The *Additional Checks* tab is initialized with PowerDesigner variables to generate the data profiling constraints specified on the *Standard Checks* tab and the validation rules specified on the *Rules* tab. You can edit the code on this tab by entering an appropriate SQL expression to supplement, modify, or replace these constraints.

Context

For columns, you can override the default *Constraint name*. To revert to the default name, click to reset the *User-Defined* button to the right of the field:



The following variables are inserted by default:

- %MINMAX% - Minimum and maximum values specified on the *Standard Checks* tab
- %LISTVAL% - List of values specified on the *Standard Checks* tab
- %CASE% - Character case specified on the *Standard Checks* tab
- %RULES% - Constraint and validation rules specified on the *Rules* tab

1.3.2.4 Populating Columns with Test Data

You can use test data to quickly fill your database with large amounts of data in order to test its performance and estimate its size. You can also use test data as the basis for data profiling. PowerDesigner allows you to create test data profiles, which generate or provide lists of data items and are assigned to columns or domains. You can create test data profiles that contain number, character, or date/time data.

For example, you could create a test data profile called Address that specifies character data appropriate to represent addresses, and then associate that profile with the columns Employee Location, Store Location, and Client Address.

If you associate a test data profile with a domain, its data will be generated to all columns that are attached to the domain. If you specify a data profile as the default for its type, its data will be generated to all columns that are not associated with another profile.

To generate test data with or without test data profiles, see [Generating Test Data to a Database \[page 315\]](#)

You can create a test data profile in any of the following ways:

- Select **Model** to access the List of Test Data Profiles, and click the **Add a Row** tool
- Right-click the model (or a package) in the Browser, and select **New**

Note

You can import and export test data profiles to reuse them across multiple models by using the commands under the: **Tools** menu. The *.xpf file format can contain one or more test data profiles.

1.3.2.4.1 Test Data Profile Properties

To view or edit a test data profile's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The **General** tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the Code field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.

Property	Description
Class	<p>Specifies the kind of data to be generated from the profile. You can choose between:</p> <ul style="list-style-type: none"> • Number - to populate numerical columns • Character - to populate text columns • Date & Time - to populate date columns
Generation source	<p>Specifies from where PowerDesigner will draw the data to populate the columns associated with the profile. You can choose between:</p> <ul style="list-style-type: none"> • Automatic - PowerDesigner generates the data based on the parameters you set on the <i>Detail</i> tab. • List - PowerDesigner draws the data from the list you define on the <i>Detail</i> tab. • Database - PowerDesigner draws the data using a query from a live database connection that you specify on the <i>Detail</i> tab. • File - PowerDesigner draws the data from the CSV file that you specify on the <i>Detail</i> tab.
Keywords	<p>Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.</p>

Detail Tab (Automatic Number Data)

If you have selected to automatically generate number data on the *General* tab, you must define the following properties on the *Detail* tab:

Property	Description
Type	Specifies whether the data is to be generated randomly or sequentially.
Range	Specifies the range of numbers to generate from and, if a sequential type is specified, the step value to use when traversing the range.
Decimal numbers	Specifies that the numbers to be generated are decimal, and the number of digits after the decimal point to generate.

Detail Tab (Automatic Character Data)

If you have selected to automatically generate character data on the *General* tab, you must define the following properties on the *Detail* tab:

Property	Description
Valid characters	Specifies the characters that can be generated (by default, all alphanumeric characters and spaces), separated by commas. You can specify: <ul style="list-style-type: none">Single characters or strings of characters - surrounded by double quotes. For example, "a", "bcd", "e".Character intervals - in which the boundary characters are surrounded by single quotes and separated by a dash. For example, 'a'-'z', 'A'-'Z' To allow any character, select the <i>All</i> checkbox.
Invalid characters	Specifies the characters that cannot be generated, using the same syntax as for the valid characters. To disallow accented characters, select the <i>No accents</i> checkbox.
Mask	Specifies the mask characters used to tell users what kind of character they must enter in a given context. By default the test data profile uses the following mask characters: <ul style="list-style-type: none">A - Letter9 - Number? - Any character
Case	Specifies the case in which to generate the data. If you select <i>Lower</i> or <i>Mixed</i> case, select the <i>First Uppercase</i> checkbox to require that each word begin with a capital letter.
Length	Specifies the length of character strings to generate. You can specify either an exact required length or a range.

Detail Tab (Automatic Date & Time Data)

If you have selected to automatically generate date and time data on the *General* tab, you must define the following properties on the *Detail* tab:

Property	Description
Date range	Specifies the upper and lower limits of the date range within which data can be generated.
Time range	Specifies the upper and lower limits of the time range within which data can be generated.
Step	Specifies step values for use when traversing the date and time ranges, if sequential values are generated.
Values	Specifies whether the values are to be generated randomly or sequentially.

i Note

The format in which date and time data is generated can be controlled by DBMS items in the *Script/Sql/Format* category (see *Customizing and Extending PowerDesigner > DBMS Definition Files > Script/Sql Category*).

Detail Tab (List Data)

If you have selected to provide list data on the *General* tab, enter as many value-label pairs as necessary on the *Detail* tab.

Detail Tab (Database Data)

If you have selected to provide data from a database on the *General* tab, you must define the following properties on the *Detail* tab:

Property	Description
Data Source	Specifies the data source from which to draw data for the profile. Click the <i>Select a Data Source</i> tool to the right of this field to open a separate dialog on which you can specify your connection parameters.
Login and Password	Specifies the login and password to use when connecting to the data source.
Table, Column, and Query	Specifies the table and column from which the data will be drawn. By default, a query selecting distinct values from the column is used.

Detail Tab (File Data)

If you have selected to provide data from a file on the *General* tab, you must define the following properties on the *Detail* tab:

Property	Description
File	Specifies the file from which to draw data for the profile.
Type	Specifies whether the values are to be drawn randomly or sequentially.

1.3.2.4.2 Assigning Test Data Profiles to Columns

You can associate a test data profile directly to a column or to a domain.

Context

i Note

To assign a test data profile to a domain (see [Domains \(CDM/LDM/PDM\) \[page 179\]](#), open the domain property sheet and select the appropriate test data profile in the *Profile* list on the *General* tab. A test data profile assigned to a domain will generate test data for all the columns attached to the domain.

Procedure

1. Open the property sheet of a column and click the *Detail* tab.
2. Select the appropriate test data profile.
3. [optional] Adjust the following properties in the *Column fill parameters* group box as appropriate:
 - *Null values* - [Default: 0%] Specifies the percentage of values to leave empty.
 - *Distinct values* - [Default: 100%] Specifies the percentage of values that must be unique. For example, if you set this field to 100 % for one column and to 80% for a second column, and then generate the table with 10 rows, all 10 rows in the first column will have different values, while 2 values in the second column will be repeated. This is a maximum value, and can change depending on the referential integrity parameters of primary key columns. Alternately, you can enter a specific value without a percentage sign, to indicate the exact number of column rows that should contain unique entries.

i Note

If you use a test data profile with a list generation source to a column with a given percentage of distinct values, PowerDesigner uses the values from the test data profile list. If there are not enough values declared in the list, a warning message is displayed in the Output window to inform you that the distinct value parameter cannot be enforced due to lack of distinct values in the list of values.

- *Average Length* - [read only] Used for estimating the size of the database (see [Estimating Database Size \[page 317\]](#)). The default value is the maximum length for the data type defined for the column.

i Note

These properties on the column property sheet *General* may override values entered in the *Column fill parameters* groupbox:

- *Mandatory* (M) - Specifies that the column must contain a value and sets *Null values* to 0%.
- *Unique* (U) - Specifies the column must contain a unique value and sets *Null value* to 0% and *Distinct values* to 100%.
- *Foreign* (F) - The column is a foreign key column and takes the values of the corresponding primary key column in the parent table.

4. Click *OK* to close the column property sheet and return to the model.

i Note

To quickly assign test data profiles to multiple columns, use the List of Columns or the Columns tab of a table property sheet. If the Test Data Profile column is not visible in your list, use the *Customize Columns and Filter* tool to display it.

5. [optional] Generate your test data (see [Generating Test Data to a Database \[page 315\]](#)).

1.3.2.5 Creating a Computed Column


Computed columns are columns whose content is computed from values in other columns in the table. Computed columns are not supported by all DBMSs.

Procedure

1. Open the table property sheet and click the *Columns* tab.
2. Click the *Add a Row* tool, and then click the *Properties* tool to open the property sheet for the new column.
3. On the *General* tab, select the *Computed* checkbox, and then click the *Detail* tab.

Simple computed expressions can be entered directly in the *Computed expression* field. For more complex expressions, click the Edit tool to the right of the field to access the SQL Editor (see [Writing SQL Code in PowerDesigner \[page 288\]](#)).

In the following example a column must be filled with the total sales of widgets computed by multiplying the number of widgets by the widget price:



4. Click **OK** to return to the column property sheet.

The expression is displayed in the *Computed Expression* pane.

1.3.2.6 Attaching a Column to a Domain

You can attach a column to a domain, and have the domain specify the data type, check parameters, and business rules for the column. Domains can help with data consistency across columns storing similar types of data.

Procedure

1. Double-click a table to open its property sheet, and click the *Columns* tab.
2. Select the required column and then click the *Properties* tool to open its property sheet.
3. Select a domain from the *Domain* list and then click **OK**.

For detailed information about working with domains, see [Domains \(CDM/LDM/PDM\) \[page 179\]](#).

1.3.2.7 Copying or Replicating a Column from Another Table


You can reuse existing columns from other tables by copying or replicating them using the tools on the table property sheet [Columns](#) tab or by drag and drop. If your table already contains a column with the same name or code as the copied column, the copied column is renamed.

Context

Copying a column creates a simple copy that you can modify as you wish. Replicating a column creates a synchronized copy which remains synchronized with any changes made to the original column (see [Core Features Guide > Linking and Synchronizing Models > Shortcuts and Replicas](#)).

Procedure

1. Open the property sheet of the table you want to copy or replicate the columns to, and click the [Columns](#) tab.
2. Click the [Add Columns](#) or [Replicate Columns](#) to open a selection box listing the columns attached to all other tables in the model.



3. Select one or more columns in the list and then click [OK](#) to copy or replicate them to the table.
4. Click [OK](#) to close the table property sheet and return to your model.

i Note

To copy or replicate a column from one table to another in the diagram or browser, select the column in the table symbol or its Browser entry, and then right-click and hold while dragging the column to over the second table symbol or its Browser entry. Release and select *Copy Here* or *Replicate Here*.

1.3.3 Primary, Alternate, and Foreign Keys (PDM)

A key is a column, or a combination of columns, that uniquely identifies a row in a table. Each key can generate a unique index or a unique constraint in a target database.

You can create the following types of keys:

- Primary keys - Contain one or more columns whose combined values uniquely identify every row in a table. Each table can have only one primary key.
- Alternate keys - Contain one or more columns whose combined values uniquely identify every row in a table.
- Foreign keys - Contain one or more columns whose values match a primary or alternate key in some other table.

In the following example, the **TITLE** table has a primary, alternate and foreign key:

Title	
Title ISBN	<pk>
Publisher ID	<fk>
Title Name	<ak>
Title Type	<ak>
Title Price	
Title Publication Date	
o- Title_ID	<pk>
o- Title_Name	<ak>

- The primary key, **TITLE_ID** contains the column **TITLE_ISBN**, and uniquely identifies each book in the table.
- The alternate key, **TITLE_NAME**, contains the columns **TITLE_NAME** and **TITLE_TYPE**, and enforces a constraint that no two titles of the same type can have the same name.
- The foreign key contains the column **PUBLISHER_ID** and references the primary key column in the **Publisher** table.

1.3.3.1 Creating Primary Keys

A primary key is the primary identifier for a table, and is attached to one or more columns whose combined values uniquely identify every row in the table. Every table must have a primary key.

Procedure

1. Open the property sheet of the table and click the *Columns* tab, which lists all the columns defined for the table (see [Columns \(PDM\) \[page 99\]](#)).
2. Select the check box in the *P* column for one or more columns in the list to associate them with the primary key.
3. [optional] Click the *Keys* tab and rename the key or select it and click the *Properties* tool to open its property sheet.
4. Click *OK* to close the property sheet and return to the diagram.

In the following example, **Employee number** is the primary key for the table **Employee**, and each employee must have a unique employee number:


Employee		
Employee number	numeric(5)	<pk>
Division number	numeric(5)	<fk>
First name	char(30)	
Last name	char(30)	
Employee function	char(30)	
Employee salary	numeric(8,2)	
 Primary Key		<pk>

1.3.3.1.1 Rebuilding Primary Keys

Rebuilding primary keys in a physical diagram updates primary keys for tables by creating primary keys for tables that have no key and a single unique index. Rebuilding primary keys is useful when not all of the primary keys could be reverse engineered from a database, or if you did not select the rebuild option for primary keys during reverse engineering.

Procedure

1. Select  *Tools*  *Rebuild Objects*  to open the Rebuild Primary Keys dialog box, which lists all the tables in the current model.



i Note

To rebuild the primary keys in package, select the package from the list at the top of the tab. To rebuild the primary keys in a sub-package, click the *Include Sub-Packages* tool, and then select a sub-package from the dropdown list.

2. Select the tables containing the primary keys that you want to rebuild and then click *OK*.

1.3.3.2 Creating Alternate Keys

An alternate key is a key associated with one or more columns whose values uniquely identify every row in the table, but which is not the primary key. For example, where the primary key for a table may be the employee id, the alternate key might combine the first, middle, and last names of the employee. Each alternate key can generate a unique index or a unique constraint in a target database.

Procedure

1. Open the property sheet of a table and select the *Columns* tab.
2. Select the column or columns to associate with the alternate key and click the *Create Key* tool.
The new key property sheet opens.
3. Enter a name for the key. Alternate keys are conventionally named **AK<x>_<ColumnCodes>** (for example **AK1_CUSNAME**).

4. [optional] Modify the default *Constraint Name*.
5. Click **OK** to complete the creation of your alternate key and return to the table property sheet.

i Note

You can also create an alternative key using the *Add a Row* tool on the table property sheet *Keys* tab, click the *Properties* tool to open its property sheet, and select the *Columns* tab to manually associate columns with the key.

1.3.3.3 Creating Foreign Keys

A foreign key is a primary or alternate key that migrates from another table. Foreign keys are generally migrated automatically when you draw a reference from a child to a parent table.

The columns that are defined in a foreign key can also be user-specified at creation and changed at any time from the *Joins* tab of the reference property sheet (see [References \(PDM\) \[page 191\]](#)). For information about automatic migration of foreign keys, see [Automatic Reuse and Migration of Columns \[page 195\]](#).

1.3.3.4 Key Properties

To view or edit a key's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Table	Specifies the name of the table where the key is defined.

Property	Description
Constraint name	<p>Specifies the name of the key constraint. A primary key constraint is a named check that enforces the uniqueness and the presence of values in a primary key column. PowerDesigner automatically creates a default constraint name for a key, which you can modify. To return to the default click to release the <i>User-Defined</i> button. You can use the following variables:</p> <ul style="list-style-type: none"> • %AK% and %AKNAME% - Code and name of the alternate key. • %TABLE%, %PARENT%, %CHILD% - Code of the table, the parent table, and the child table. • %REFRCODE% and %REFRNAME% - Code and name of the reference. <p>For a complete list of PDM variables, see <i>Customizing and Extending PowerDesigner > DBMS Definition Files > PDM Variables and Macros</i></p>
Primary key	Specifies that the key is the primary key of the table. There can be only one primary key in a table, so selecting this key as the primary key will deselect any existing primary key.
Cluster	Specifies that the key constraint is a clustered constraint (for those DBMSs that support clustered indexes).
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- *Columns* - Lists the columns associated with the key. Use the *Add Columns* tool to associate additional columns with the key.

1.3.4 Indexes (PDM)

An index is a data structure associated with one or more columns ordered by the column values. Indexes are typically created for columns that you are frequently searched on to improve response times. Most types of index are more effective when applied to columns with high cardinality.

For example, in an **Author** table, you might create an index for the primary key **ID** and another for the **Last Name** column, as it is regularly searched on, but you will probably not create an index for the **BirthCity** column, as it is not often searched on.

i Note

PowerDesigner supports the creation of indexes for materialized views, if your DBMS allows them (see [Materialized Views \[page 127\]](#)).

1.3.4.1 Creating Standard, Key, or Function-Based Indexes

You can create indexes by selecting columns on a table property sheet *Columns* tab and clicking the *Create Index* tool.

Procedure

1. Open the property sheet of a table and select the *Columns* tab.
2. Select the column or columns on which to base the index and click the *Create Index* tool.
The index is created and its property sheet opens.
3. Enter a name for the index and then click the *Columns* tab.
4. PowerDesigner supports the creation of the following types of index:
 - Standard indexes are associated with one or more columns containing high-cardinality values that are frequently searched on. Use the arrow buttons at the bottom of the list to reorder the columns in order of descending cardinality.
 - Key indexes are associated with a primary, foreign, or alternate key and based on the same columns as the key. Select the appropriate key from the *Columns definition* field above the list to empty the list and replace it with the columns associated with the key.

i Note

Key indexes are conventionally named after the table with a `_PK`, `_FK`, or `AK` suffix (for example, `Project_AK`).

- Function-based indexes [if supported by the DBMS] are populated with values derived from a function or expression based on one or more columns, and provide an efficient mechanism for evaluating statements that contain functions in their WHERE clauses. Click the *Add a Row* tool, then click in the *Expression* column and click the ellipsis button to open the SQL Editor to specify an expression.
5. Select an ascending or descending sort order for each column using the list's *Sort* column.
 6. Click **OK** to complete the creation of your index and return to the table property sheet.

i Note

You can alternatively create an index using the *Add a Row* tool on the table property sheet *Indexes* tab, click the *Properties* tool to open its property sheet, and select the *Columns* tab to manually associate columns with the index.

1.3.4.2 Index Properties

To view or edit an index's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Owner	[if supported by the DBMS] Specifies the user who is the owner of the object. This is usually its creator. Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object.
Table	Specifies the table to which the index belongs.
Type	Specifies the type of index (if supported by your DBMS). For information about SAP® IQ index types, see Indexes (IQ) [page 594] .
Unique	Specifies that the index cannot contain duplicate values.
Cluster	Specifies that the index is a clustered index. A table cannot have more than one clustered index. <div style="background-color: #ffffcc; padding: 10px; margin-top: 10px;"><p>i Note</p><p>Clusters in Oracle 11 and higher are modeled as extended objects with a <<Cluster>> stereotype (see Clusters (Oracle) [page 502]).</p></div>
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- *Columns* - Lists the columns with which the index is associated (see [Creating Standard, Key, or Function-Based Indexes \[page 120\]](#)). Use the following tools to specify columns:

Tool	Description
N/A	<i>Columns definition</i> - Select the appropriate key to empty the list and replace it with the columns associated with the key.

Tool	Description
	<i>Add Columns</i> - Choose columns from the table to add to the list.
	<i>Add / Insert a Row</i> [if your DBMS supports function-based indexes] - Create a new row, then click in the <i>Expression</i> column and click the ellipsis button to open the SQL Editor to specify an expression. For example, to define an index to convert all names to lowercase to simplify searching, you could enter an expression such as: lower (SURNAME)

1.3.4.3 Rebuilding Indexes

You can rebuild indexes at any time to reflect any changes that you have made to primary keys, foreign keys, or alternate keys in your model.

Procedure

1. Select  *Tools*  *Rebuild Objects* , and enter the appropriate options:

Option	Description
Primary key	Rebuilds primary key indexes. The field displays the naming convention for primary key indexes, which is by default %TABLE%_PK. You can use the following variables: <ul style="list-style-type: none"> ○ %TABLE% - Generated code of the table. The generated code of a variable is the code defined in the object property sheet, but may be truncated if it contains characters not supported by the DBMS. ○ %TNAME%, %TCODE%, %TLABL% - Table name, code, and comment.
Other keys	Rebuilds alternate key indexes. The field displays the naming convention for alternate key indexes, which is by default %KEY%_AK.
Foreign key indexes	Rebuilds foreign key indexes. The field displays the naming convention for foreign key indexes, which is by default %REFR%_FK. You can use the following variables: <ul style="list-style-type: none"> ○ %REFR%, %PARENT%, %CHILD% - Generated code of the reference, parent, and child table. ○ %PNAME%, %PCODE%, %PQUALIFIER% - Parent table name, code, and qualifier. ○ %CNAME%, %CCODE%, %CQUALIFIER% - Child table name or code, and qualifier. ○ %REFRNAME%, %REFRCODE% - Reference name or code.
Foreign key threshold	Specifies the minimum number of estimated records in a table (specified in the <i>Number</i> field in the table property sheet) that are necessary before a foreign key index can be created. If the <i>Number</i> field is empty, foreign key indexes are generated.

Option	Description
Mode	Specifies the type of rebuild. You can select: <ul style="list-style-type: none"> ○ <i>Delete and Rebuild</i> – Delete and rebuild all indexes attached to primary, alternate, and foreign keys. ○ <i>Add missing indexes</i> – Preserve existing key indexes and add any missing key indexes.

2. [optional] Click the *Selection* tab to specify which tables you want to rebuild indexes for.
3. Click *OK*. If you selected the Delete and Rebuild mode, a confirmation box asks you to confirm your choice. Click *Yes* to confirm the deletion and rebuild of the selected indexes.

1.3.5 Views (PDM)

A view is a query that provides access to all or a subset of the data in a table or multiple tables connected by joins. Views do not copy the data from their underlying tables and are updated when data in those tables changes. Views can reference other views, can order or filter data as necessary, and may be indistinguishable from tables for users accessing them.

1.3.5.1 Creating a View

You can create a view populated with columns from selected tables and other views via the *Tools* menu. Alternately, you can create an empty view from the Toolbox, Browser, or *Model* menu.

Procedure

1. [optional] Select one or more tables and views in the diagram. You can select multiple objects by holding down the *Shift* key while you select them.
2. Select  *Tools* .

If you have not selected any tables or views, then a selection box opens, allowing you to select the objects to be included in the view. Select the appropriate objects and then click *OK*.

A view symbol is created in the diagram, displaying all the columns in each of the tables and views selected for the view. The names for the tables and views appear at the bottom of the view symbol.



- [optional] Edit the view's query to remove unwanted columns or otherwise modify the view (see [View Queries \[page 125\]](#)).

Alternatively, you can create an empty view, which you should complete by specifying a query (see [View Queries \[page 125\]](#)) in the following ways:

- Use the [View](#) tool in the Toolbox.
- Select to access the List of Views, and click the [Add a Row](#) tool.
- Right-click the model (or a package) in the Browser, and select .

1.3.5.2 View Properties

To view or edit a view's properties, double-click its diagram symbol or Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The [General](#) tab contains the following properties:

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the Code field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Type	Specifies the type of the view, where supported by your DBMS (see Materialized Views [page 127] and Creating an XML Table or View [page 86]).


Property	Description
Owner	Specifies the user who is the owner of the object. This is usually its creator. Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object.
Usage	Specifies how the view will be used. You can choose between: <ul style="list-style-type: none"> Query only - Consultation only. The view cannot update tables. Updatable - Consultation and update of underlying tables. With Check options - Implements controls on view insertions.
Dimensional type	Specifies the type of the view for purposes of creating star or snowflake schemas containing fact tables and dimensions. You can choose between: <ul style="list-style-type: none"> Fact - see Facts (PDM) [page 235] Dimension - see Dimensions (PDM) [page 238] Exclude - PowerDesigner will not consider the view when identifying or generating multidimensional objects. You can instruct PowerDesigner to complete this field for you (see Identifying Fact and Dimension Tables [page 232]). PowerDesigner's support for the generation of BusinessObjects universes (see Generating an SAP BusinessObjects Universe [page 311]) and of facts and dimensions in a multidimensional diagram (see Generating Cubes [page 233]) depends on the value of this field.
Generate	Selects the view for generation to the database.
User-defined	By default, the view query is updated to reflect changes to model objects on which it is based. Selecting this option freezes the view and protects your manual changes.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- [Columns](#) - Lists the columns in the view based on the SELECT orders from the queries. You can modify column properties in this list but to add or remove columns, you must modify the appropriate view query. View column properties are initialized from the properties of their source columns. The read-only *Expression* column specifies the qualified name of the view column.
- [Indexes](#) - [materialized views] Lists the indexes defined on the materialized view (see [Indexes \(PDM\) \[page 119\]](#)).
- [SQL Query](#) - Displays the SQL code for all the queries associated with the view. You can edit this code directly in this tab or access the property sheets of individual queries (see [View Queries \[page 125\]](#)).
- [Triggers](#) - [if supported by your DBMSs] Lists the triggers associated with the view (see [Triggers \(PDM\) \[page 130\]](#)). You can define a trigger to fire when one or more attributes of a table view column are modified.
- [Preview](#) - Displays the SQL code to be generated for the view (see [Previewing SQL Statements \[page 292\]](#)).

1.3.5.3 View Queries

You can edit queries associated with a view from the [SQL Query](#) tab of the view property sheet.



Any number of queries may be associated with a view, and the totality of their SQL statements is shown in this tab, linked by any of the standard SQL constructs, such as Union, etc.

You can edit the code shown in the *SQL Query* tab:

- Directly in the tab.
- Click the *Edit with SQL Editor* tool to edit the code in the PowerDesigner SQL Editor (see [Writing SQL Code in PowerDesigner \[page 288\]](#)).
- Click the *Edit with* tool (**Ctrl** + **E**) to open the code in your favorite editor.

Any edits you make in this tab will propagate to the property sheets of the associated individual queries, which are available from the *Query* list at the bottom of the tab. Use the tools to the right of this list to create a new query (with the appropriate linking construct), delete the selected query, or open the property sheet of the selected query.

The following SQL constructs are available (if supported by your DBMS) for linking queries:

Construct	Result	Example
Union [default]	Displays all the data retrieved by both the queries, except where results are repeated.	SELECT 1: ABC SELECT 2: BCD Result: ABCD
Union All	Displays all the data retrieved by both the queries, including repeated results.	SELECT 1: ABC SELECT 2: BCD Result: ABCBCD

Construct	Result	Example
Intersect	Displays only the data retrieved by both the queries.	SELECT 1: ABC SELECT 2: BCD Result: BC
Minus	Displays only the data retrieved by one or other of the queries, but not by both.	SELECT 1: ABC SELECT 2: BCD Result: AD

The following tabs are available:

- **SQL** tab - displays the SQL code for the query. You can edit the query directly in this tab or in PowerDesigner's built-in SQL Editor (see [Writing SQL Code in PowerDesigner \[page 288\]](#)) by clicking the *Edit with SQL Editor* tool or in an external editor by clicking the *Edit with* tool ([**Ctrl**] + [**E**]). Any edits you make in this tab will propagate to the query's other tabs and the **SQL Query** tab of the parent view, as changes made in other tabs will propagate here and to the parent view.
- **Tables** tab - lists the tables in the `FROM` clause. You can add or delete tables in the list, and reorder the list using the arrows at the bottom of the tab. For each line, select a table or click the ellipsis button to enter a more complex expression in the SQL Editor and, optionally, enter an alias in the *Alias* column. For the second and subsequent lines in the list you can specify an appropriate join condition keyword, and then specify the join condition.
- **Columns** tab - lists the columns in the `SELECT` clause. You can add or delete columns in the list, specify aliases for them, and reorder the list using the arrows at the bottom of the tab.
- **Where** tab - lists the expressions in the `WHERE` clause. You can add or delete expressions in the list, and reorder the list using the arrows at the bottom of the tab. For each line, select a column in each of the two *Expression* columns (or click the ellipsis button to specify a more complex expression), and select the appropriate operator between them. You can optionally enter a prefix and suffix.
- **Group By** tab - lists the columns in the `GROUP BY` clause. You can add or delete columns in the list, and reorder the list using the arrows at the bottom of the tab.
- **Having** tab - lists the expressions in the `HAVING` clause. You can add or delete expressions in the list, and reorder the list using the arrows at the bottom of the tab. For each line, select a column in each of the two *Expression* columns (or click the ellipsis button to specify a more complex expression), and select the appropriate operator between them. You can optionally enter a prefix and suffix.
- **Order By** tab - lists the columns in the `ORDER BY` clause. You can add or delete columns in the list, and reorder the list using the arrows at the bottom of the tab. For each line, select a column (or click the ellipsis button to specify a more complex expression), and select ASC or DESC for the sort direction.

1.3.5.4 Materialized Views

A materialized view is a table containing the results of a query. PowerDesigner supports materialized views for the DB2, HP Neoview, Netezza, Oracle, and SQL Anywhere DBMS families.

Materialized views are supported in the following ways:


- DB2 - Select `materialized query table` (or for earlier versions, `summary table`) in the *Type* list on the **General** tab of a view property sheet.
- HP Neoview - Use the List of Materialized Views (available from ).
- Netezza - Use the List of Materialized Views (available from ).

- Oracle - Use the List of Materialized Views (available from *Model* *Materialized Views*).
- SQL Anywhere - Select *Materialized View* in the *Type* list on the *General* tab of a view property sheet to display the *DB space* field, and specify the dbspace in which to create the materialized view. The default is the current dbspace.

1.3.5.5 Showing View Dependencies using Traceability Links

You can use traceability links to make the relationships between views and tables clearer. These links are not interpreted and checked by PowerDesigner.

In the following example, the **Book Sales** view is shown as depending on the **Title** and **Sale** tables via two traceability links with their type set to **depends on**:



For detailed information about traceability links, see *Core Features Guide > Modeling with PowerDesigner > Objects > Traceability Links*.


1.3.5.6 Defining a Generation Order for Views

You can define the order of the generation of views by using traceability links with a type of **DBCreatAfter**. The view from which you start the traceability link is dependent on the view you link it to, and this influent view will be generated before the dependent view.

Context

For example you create the view **DEPARTMENT STORE** from the table **STORE**, and then another view called **COMPUTER COUNTER** from the view **DEPARTMENT STORE** to show only part of the department store offer.

By default, views are generated in alphabetical order, so the generation of **COMPUTER COUNTER** will fail since the view **DEPARTMENT STORE** on which it depends is not yet generated. To bypass this problem, you should create a traceability link of type <<DBCreatAfter>> from **COMPUTER COUNTER** to **DEPARTMENT STORE** to ensure that **DEPARTMENT STORE** is generated before **COMPUTER COUNTER**:




i Note

There is a model check to warn you if you create a reflexive or circular set of traceability links of type **DBCreatAfter**. If you generate without correcting this error, views will be generated in alphabetical order, without taking into account the generation order.

Procedure

1. Select the *Traceability Links* tool in the toolbox.
2. Click inside the dependent view and, while holding down the mouse button, drag the cursor into the influent view. Release the mouse button.
3. Double-click the traceability link to open the property sheet of the dependent object at the *Traceability Links* tab.
The influent view is displayed in the *Linked Object* column.
4. Click in the *Link Type* column, click the down arrow and select **DBCreatAfter**.



- Click **OK** to close the property sheet and return to your model.

i Note

You can, alternatively, create **DBCreateAfter** traceability links directly on the *Traceability Links* tab (see [Defining a Generation Order for Stored Procedures \[page 145\]](#)). For detailed information about traceability links, see *Core Features Guide > Modeling with PowerDesigner > Objects > Traceability Links*.

1.3.6 Triggers (PDM)

A trigger is a segment of SQL code associated with a table or a view, which is invoked automatically whenever there is an attempt to modify data in the associated table or view with an insert, delete, or update command. A DBMS trigger is not associated with any table or view, and fires on modifications to the database structure itself, such as the creation or dropping of a table or events like startup, shutdown, login etc. You can use triggers to enforce referential integrity (where declarative constraints are not sufficient) and to implement sequences for columns.

In the PowerDesigner interface, table and view triggers are called simply triggers, while DDL or database triggers are called DBMS triggers. View and DBMS triggers are not supported by all DBMSs.


PowerDesigner provides trigger templates to generate triggers (see [Trigger Templates \[page 139\]](#)) and template items, which are reusable blocks of SQL script that can be inserted into triggers or trigger templates (see [Trigger Template Items \[page 140\]](#)) and you can modify these templates and items and create your own.

1.3.6.1 Creating a Table or View Trigger

You can create a trigger for a table from its property sheet and base it on a PowerDesigner template, or on a template of your own, or write it from scratch.

Procedure

1. Open the table or view property sheet, and then click the *Triggers* tab.
2. Click the *Add a Row* tool to create a new trigger, enter a name and code, and then click the *Properties* tool to open its property sheet.
3. Click the *Body* tab, and select a trigger template (see [Trigger Templates \[page 139\]](#)) from the Template list. The time and event fields will be set and the template code copied into the editor.



Note

You can create a trigger by entering code by hand, but we recommend that you use a template as this will simplify reuse of your code and make your triggers more portable.

4. [optional] Modify the trigger code. You can insert trigger template items (see [Trigger Template Items \[page 140\]](#)), use PDM variables and macros and various other tools available from the toolbar (see [Writing SQL Code in PowerDesigner \[page 288\]](#)).

If you edit the code, then the trigger will be marked as user-defined and will be excluded from most forms of rebuilding (see [Rebuilding Triggers \[page 137\]](#)).

5. Click **OK** to return to your model.

1.3.6.2 Creating Triggers from References

You can create triggers to enforce referential integrity individually or instruct PowerDesigner to create them by default.

Procedure

1. Create a reference between two tables, and then double click the reference symbol to open its property sheet.
2. Click the **Integrity** tab, and then select **Trigger** from the **Implementation** list.
3. Specify the form of Update and Delete constraints using the radio buttons (see [Reference Properties \[page 192\]](#)), and then click **OK** to return to the diagram.
4. If you have set the **Automatically rebuild triggers** model option (see [Reference Model Options \[page 20\]](#)), then triggers will have been created automatically in the parent and child tables. To verify this open the table property sheet and click the **Triggers** tab. If the triggers are not present, you will need to rebuild your triggers manually (see [Rebuilding Triggers \[page 137\]](#)).

Note

To instruct PowerDesigner to implement referential integrity between tables using triggers by default whenever you create a reference, select **Tools > Model Options**, click **Model Settings > Reference** in the Category list, select **Trigger** in the **Default implementation** list.

1.3.6.3 Creating a DBMS Trigger

DBMS triggers are not associated with any table or view. You create them directly under the model.

Context

You can create a DBMS trigger in any of the following ways:

- Select to access the List of DBMS Triggers, and click the *Add a Row* tool
- Right-click the model (or a package) in the Browser, and select

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.3.6.4 Trigger and DBMS Trigger Properties

To view or edit a trigger's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Owner	Specifies the user who is the owner of the object. This is usually its creator. Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object.
Table	[Table or view triggers only] Specifies the table to which the trigger belongs.
Scope	[DBMS triggers only] Specifies the scope of the DBMS trigger. You can choose either Schema or Database, and this choice will control the types of events that you can select in the DBMS trigger definition.
Generate	Specifies to generate the trigger.
User-defined	[Read-only] Specifies that the trigger definition has been modified. You modify a trigger definition when you change the trigger template script in the Definition tab of the trigger

Property	Description
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

Body Tab

This tab allows you to enter code for the trigger. For information about the tools available on the toolbar, see [Writing SQL Code in PowerDesigner \[page 288\]](#). The following properties are available:

Property	Description
Template	Specifies the template on which the trigger is based (see Trigger Templates [page 139]). The <i>User-defined</i> button is automatically depressed when you modify the definition of a trigger. Click the button to release it and restore the template trigger definition.
Time	Specifies when the trigger will fire in relation to the associated event. The content of the list depends on the values defined in the trigger template and in the Time entry in the Trigger category of the DBMS.
Event	Specifies the event that will cause the trigger to fire. Click the ellipsis tool to the right of this field to select multiple events (see Defining Triggers with Multiple Events [page 137]) For table and view triggers, this field is a list, the content of which depends on the values defined in the trigger template and in the Event entry in the Trigger category of the DBMS. You can add your own events to this entry and they will appear in this list. For DBMS triggers, this field allows you to enter any text.
Order	[table and view triggers only] Specifies the firing order of trigger.

The following tabs are also available:

- *Template Items* - lists the trigger template items available for use in the trigger definition (see [Trigger Template Items \[page 140\]](#)).
- *Preview* - displays the SQL code that will be generated for the trigger (see [Previewing SQL Statements \[page 292\]](#)).

1.3.6.5 Trigger Naming Conventions

The pre-defined trigger templates that ship with PowerDesigner indicate naming conventions for the trigger scripts that it generates. The naming convention consists of a prefix indicating the trigger type followed by the table code.

Context

The default naming conventions include a variable (%L:TABLE). The name of the resulting trigger script replaces this variable with a lower-case table code. For example, a resulting trigger script may have the name ti_employee.

You can change the trigger naming convention in PowerDesigner pre-defined DBMS trigger templates from the *Trigger Templates* tab of the DBMS property sheet.

Procedure

1. Select to open the DBMS definition file in the Resource Editor, and then click the *Trigger Template* tab.
2. Click a trigger template in the list, and then click the *Properties* tool to open its property sheet.
3. Type a new trigger name in the Trigger Name text box at the bottom of the tab.
For example, mytempl_%TABLE%
4. Click *OK* in each of the dialog boxes.

1.3.6.6 Calling a Related Procedure in a Trigger Template

Some target databases do not accept code within a trigger statement. For these databases, a trigger template can call a related procedure as a parameter, which is defined in a procedure template. In these cases, procedure templates are listed in the list of trigger templates.

Example

Informix does not accept code in trigger templates. The template `InsertTrigger` calls the procedure in the form of the variable %PROC%, as follows:

```
-- Insert trigger "[%QUALIFIER%]%TRIGGER%" for table "[%QUALIFIER%]%TABLE%"  
create trigger [%QUALIFIER%]%TRIGGER% insert on [%QUALIFIER%]%TABLE%  
referencing new as new_ins  
  for each row (execute procedure %PROC%(.FKCOLN("new_ins.%COLUMN%", "", "", ""));")  
/
```

The template `InsertProc` defines the procedure, as follows:

```
-- Insert procedure "%PROC%" for table "[%QUALIFIER%]%TABLE%"  
create procedure %PROC%.FKCOLN("new_%.14L:COLUMN% %COLTYPE%", "", "", "", "")  
    .DeclInsertChildParentExist  
    .DeclInsertTooManyChildren  
    define errno integer;  
    define errmsg char(255);  
    define numrows integer;  
    .InsertChildParentExist  
    .InsertTooManyChildren  
end procedure;  
/
```

1.3.6.7 Indicating Trigger Order for Multiple Triggers

Some DBMSs allow you to have multiple triggers for the same insert, update, or delete event at the same time. You can indicate the order in which each trigger within the group fires.

Context

In the following example, a company is considering candidates for various positions, and must ensure that new employees are offered a salary that is within the range of others working in the same field, and less than their prospective manager.

The `EMPLOYEE` table contains two **BeforeInsert triggers** to perform these tests:

```
create trigger tibTestSalry1 before insert order 1 on EMPLOYEE  
referencing new as new_ins for each row  
begin  
    [Trigger code]  
  
end  
create trigger tibTestSalry2 before insert order 2 on EMPLOYEE  
begin  
    [Trigger code]  
  
end
```

Procedure

1. Open the trigger property sheet and click the *Body* tab.
2. Select a number from the *Order* list to indicate the position in which the trigger fires.
3. Click *OK* to return to your model.

1.3.6.8 Defining Triggers with Multiple Events

Some DBMSs support multiple events on triggers. If such is the case, the Ellipsis button to the right of the *Event* box on the trigger *Body* tab is available.

You can click the Ellipsis button to open the Multiple Events Selection box. If you select several events and click *OK*, the different events will be displayed in the *Event* box, separated by the appropriate delimiter.



1.3.6.9 Rebuilding Triggers

PowerDesigner can rebuild triggers to ensure that they are attached to all tables joined by references to ensure referential integrity. You can instruct PowerDesigner to automatically rebuild triggers whenever a relevant change is made and you can manually rebuild triggers at any time.

Context

The Rebuild Triggers function creates new triggers based on template items that correspond to trigger referential integrity defined for references and sequence implementation for columns.

To instruct PowerDesigner to automatically rebuild triggers, select **Tools > Model Options**, click **Model Settings > Trigger**, select *Automatically rebuild triggers*, and click *OK*. PowerDesigner rebuilds all triggers and will, from now on, rebuild triggers whenever you make a relevant change in the model.


To rebuild triggers manually:

Procedure

1. Select **Tools > Rebuild Objects > Rebuild Triggers**
2. Specify a rebuild mode. You can choose between:
 - *Delete and Rebuild* – all triggers attached to templates are deleted and rebuilt, including those to which you have made modifications
 - *Preserve* – only those triggers attached to templates that have not been modified are deleted and rebuilt. Any triggers that you have modified are preserved.
3. The *Trigger* selection box shows an expandable tree view of trigger types. Expand the tree and select the types to rebuild. There are three levels in this tree:
 - All trigger types supported by the current DBMS

- All trigger templates corresponding to the trigger types
- All template items defined for each trigger template

For example, in the list below, the two template items `InsertChildParentExist` and `InsertTooManyChildren` are used in the `BeforeInsertTrigger` template that is, in turn, used in all triggers with a time of `Before` and an event type of `Insert`:



4. [optional] Click the *Error Messages* tab to define the types of error messages to generate (see [Generating a User-Defined Error Message \[page 147\]](#)).
5. [optional] Click the *Selection* tab to specify which tables to rebuild the triggers for.
6. Click *OK* to begin the rebuild process.

Progress is shown in the Output window. You can view the triggers that have been created from the *Triggers* tab of the table property sheet, or from the List of Triggers.

Note

If you change the target DBMS family, for example from Oracle to IBM DB2, triggers are automatically rebuilt.

For information about rebuilding dependencies between triggers and other objects, see [Tracing Trigger and Procedure Dependencies \[page 151\]](#).

1.3.6.10 Trigger Templates

PowerDesigner trigger templates allow you to write trigger code in a modular reusable fashion. We provide basic templates for before, after, and with insert, update, and delete events and for other types of triggers where supported by the DBMS. You can modify the code specified in these templates or create your own templates in the DBMS definition file or in your model.

To apply a trigger template to your trigger definition, select the template from the list on the trigger property sheet **Body** tab (see [Trigger and DBMS Trigger Properties \[page 133\]](#)).

To review or modify the provided trigger templates, select ► **Database** ► **Edit Current DBMS** ▾, and then click the **Trigger Templates** tab. You cannot delete or rename these templates.

⚠ Caution

The resource files provided with PowerDesigner inside the **Program Files** folder cannot be modified directly. To create a copy for editing, use the **New** tool on the resource file list, and save it in another location. To include resource files from different locations for use in your models, use the **Path** tool on the resource file list.

To create a new template, click the **Create from Trigger Template** tool (to copy the code of an existing template to your new template) or the **Add a Row** tool (to start from scratch).

ℹ Note

You can, alternatively, create trigger templates in your model by selecting ► **Model** ► **Triggers** ► **Trigger Templates** ▾, but these templates will not be accessible from other models.

Trigger Template Properties

The **General** tab contains the following properties:

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the Code field.
DBMS	Specifies the parent DBMS.
Applies to	[for DBMSs supporting multiple types of triggers] Specifies whether the template can be applied to table, view, or DBMS triggers.
Trigger time	Specifies when triggers based on the template will fire in relation to their associated event.

Property	Description
Trigger event	Specifies the event that will cause the firing of triggers based on the template.
Trigger name	Specifies the conventions for naming triggers based on the template.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- *Body* - Contains a field for entering the trigger code for the template. You can use trigger template items, PDM variables and macros and other tools available from the toolbar (see [Writing SQL Code in PowerDesigner \[page 288\]](#)).
- *Template Items* - Lists the template items (see [Trigger Template Items \[page 140\]](#)) that are defined in the trigger template and that will be generated when a trigger is generated from the template.

i Note

If you delete a template item from this list, it is not deleted from the template definition, but is excluded from generation when rebuilding triggers. PowerDesigner-provided template items listed on this tab are generated in a trigger if they match the trigger implemented referential integrity defined for a reference attached to the table. User-created template items are always generated regardless of trigger referential integrity constraints.

1.3.6.11 Trigger Template Items

Trigger template items are named reusable blocks of script that can be inserted into triggers or trigger templates. In a generated trigger script, a template item calls a macro that implements a trigger referential integrity constraint or does any other updating work on tables in the database.

To insert a trigger template item into your trigger or template definition, click the *Add Trigger Item from Model* or *Add Trigger Item from DBMS* tool, select the items from the list and click *OK*. The item is inserted with a dot followed by its name, and is also added to the list on the *Template Items* tab. For example, the following script contains two template items `InsertChildParentExist` and `InsertTooManyChildren`:

```
/* Before insert trigger "%TRIGGER%" for table "[%QUALIFIER%]%TABLE%" */
create trigger %TRIGGER% before insert order %ORDER% on [%QUALIFIER%]%TABLE%
referencing new as new_ins for each row
begin
  declare user_defined_exception exception for SQLSTATE '99999';
  declare found integer;
  .InsertChildParentExist
  .InsertTooManyChildren
end
/
```

Note

Certain DBMSs require that a cursor and variables are declared for each template item before the template item name is used in the script. You can use the following format to declare a template item:

```
.Decl<template item name>
```

For example, the trigger definition for Oracle 8 declares and then inserts the `.InsertChildParentExist` template item:

```
-- Before insert trigger "[%QUALIFIER%]%TRIGGER%" for table "[%QUALIFIER%]%TABLE%"
create trigger [%QUALIFIER%]%TRIGGER% before insert
on [%QUALIFIER%]%TABLE% for each row
declare
    integrity_error exception;
    errno    integer;
    errmsg   char(200);
    dummy    integer;
    found    boolean;
    .DeclInsertChildParentExist
begin
    .InsertChildParentExist
    -- Errors handling
exception
    when integrity_error then
        raise_application_error(errno, errmsg);
end;
/
```

To review or modify the provided trigger template items, select  [Database](#)  [Edit Current DBMS](#), and then click the [Trigger Template Items](#) tab. You cannot delete or rename these items.

Caution

The resource files provided with PowerDesigner inside the `Program Files` folder cannot be modified directly. To create a copy for editing, use the [New](#) tool on the resource file list, and save it in another location. To include resource files from different locations for use in your models, use the [Path](#) tool on the resource file list.

To create a new template item, click the [Create from DBMS Trigger Item](#) tool (to copy the code of an existing item to your new item) or the [Add a Row](#) tool (to start from scratch).

Note

You can, alternatively, create trigger template items in your model by selecting  [Model](#)  [Triggers](#)  [Trigger Template Items](#), but these templates will not be accessible from other models.

Trigger Template Item Properties

The *General* tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
DBMS	Specifies the parent DBMS.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- *Definition* - Contains a field for entering the trigger code for the item. You can use PDM variables and macros and other tools available from the toolbar (see [Writing SQL Code in PowerDesigner \[page 288\]](#)).
- *Declaration* - Contains a field for entering the declaration for the item in trigger scripts.

1.3.6.11.1 PowerDesigner Pre-Defined Trigger Template Items

PowerDesigner provides pre-defined template items for the trigger templates defined in each DBMS. The Rebuild Triggers function uses both pre-defined and user-defined trigger templates to automatically create triggers for selected tables.

In the pre-defined trigger templates, each pre-defined template item corresponds to a referential integrity constraint. Although a pre-defined template item is defined in a trigger template, it is only generated in a trigger script if it implements the trigger referential integrity defined for a reference. The item is available for generation if it is present on the *Template Items* tab of a trigger property sheet and will be generated if it is present on the *Template Items* tab of a trigger template property sheet.

Insert Constraints

The template items below implement referential integrity in insert trigger templates.

Template item	Integrity constraint	Description
DeclInsertChildParentExist InsertChildParentExist	Mandatory parent	Parent must exist when inserting a child

Template item	Integrity constraint	Description
DeclInsertTooManyChildren InsertTooManyChildren	Cannot exceed maximum cardinality constraint	Cannot insert a child if maximum cardinality has been reached
DeclInsertSequenceColumn InsertSequenceColumn	Select value in sequence list for column	Select a value for the column from a list of sequences

Update Constraints

The template items below implement referential integrity in update trigger templates.

Template item	Integrity constraint	Description
DeclUpdateChildParentExist UpdateChildParentExist	Mandatory parent	Parent must exist when updating a child
DeclUpdateChildChangeParent UpdateChildChangeParent	Change parent not allowed	Cannot modify parent code in child
DeclUpdateParentRestrict UpdateParentRestrict	Restrict on update	Cannot modify parent if child exists
DeclUpdateParentCascade UpdateParentCascade	Cascade on update	Modify parent code in all children
DeclUpdateChangeColumn UpdateChangeColumn	Non-modifiable column	Cannot modify column
DeclUpdateParentSetNull UpdateParentSetNull	Set null on update	Set parent code to null in all children
DeclUpdateParentSetDefault UpdateParentSetDefault	Set default on update	Set parent code to default in all children
DeclUpdateTooManyChildren UpdateTooManyChildren	Cannot exceed maximum cardinality constraint	Cannot update a child if maximum cardinality has been reached

Delete Constraints

The template items below implement referential integrity in delete trigger templates.

Template item	Integrity constraint	Description
DeclDeleteParentRestrict DeleteParentRestrict	Restrict on delete	Cannot delete parent if child exists
DeclDeleteParentCascade DeleteParentCascade	Cascade on delete	Delete parent code in all children
DeclDeleteParentSetNull DeleteParentSetNull	Set null on delete	Delete in parent sets child to null
DeclDeleteParentSetDefault DeleteParentSetDefault	Set default on delete	Delete in parent sets child to default

Constraint Messages

You can insert the following template items in any trigger template. They generate error messages that indicate the violation of an integrity constraint.

Template item	Description
UseErrorMsgText	Error handling without a message table
UseErrorMsgTable	Error handling with a message table

1.3.6.12 Generating Triggers and Procedures

You can create or modify database triggers to a script or to a live database connection.

Procedure

1. Select  **Database**  **Generate Database** to open the Database Generation window, and specify the standard options, including whether you want to generate to a script or to a live database connection.

For detailed information about using this window, see the [Generating a Database from a PDM \[page 298\]](#).

2. Select "Triggers & Procedures (with Permissions)" from the *Settings set* list in the Quick Launch groupbox at the bottom of the window. This settings set specifies standard options for generating triggers and procedures.

or:

Click the *Options* tab and click on Trigger in the left-hand pane to display the trigger generation options. Change the default options as appropriate.

For detailed information about settings sets, see [Quick Launch Selection and Settings Sets \[page 308\]](#).

3. [optional] Click the *Selection* tab and select the *Table* or *Procedure* subtab at the bottom of the tab. Select the tables or procedures that you want to generate for. Note that if you want to generate a trigger script for tables owned by a particular owner, you can select an owner from the *Owner* list.
4. Click *OK* to begin the generation.

1.3.6.12.1 Defining a Generation Order for Stored Procedures

You can define the order of the generation of stored procedures by using traceability links with a type of **DBCreateAfter**. The procedure from which you start the traceability link is dependent on the procedure you link it to, and this influent procedure will be generated before the dependent procedure.

Context


For example, a publisher may decide to sell certain books at a reduced rate (15%) when a customer's order is above 10 000\$. The **GENERAL CHECK** stored procedure verifies orders globally by checking availability, the order amount, if a discount rate is required, and so on. This procedure calls the **DISCOUNT CALC** procedure to calculate the 15% discount rate. Consequently, **DISCOUNT CALC** must be generated before **GENERAL CHECK**, and you can enforce this by creating a traceability link of type **DBCreateAfter** from **GENERAL CHECK** to **DISCOUNT CALC**.

i Note

There is a model check to warn you if you create a reflexive or circular set of traceability links of type **DBCreateAfter**. If generate without correcting this error, procedures will be generated in alphabetical order, without taking into account the generation order.

Procedure

1. Open the property sheet of the dependent stored procedure and click the *Traceability Links* tab.
2. Click the *Add Objects* tool, click the *Procedure* sub-tab in the Add Object selection dialog, select the influent stored procedure, and click *OK*.
3. Click in the *Link Type* column, click the down arrow and select **DBCreateAfter**.



4. Click **OK** to close the property sheet and return to your model.

i Note

You can also create **DBCCreateAfter** traceability links using the *Traceability Links* tool (see [Defining a Generation Order for Views \[page 129\]](#)). For detailed information about traceability links, see [Core Features Guide > Modeling with PowerDesigner > Objects > Traceability Links](#).

1.3.6.12.2 Creating User-Defined Error Messages

You can create a message table in your database to store user-defined error messages. When you select trigger generation parameters, you can choose to generate an error message from this table.

Procedure

1. Create a table with columns to store the following information:

Column to store...	Description
Error number	Number of the error message that is referenced in the trigger script
Message text	Text of message

2. Generate the table in your database.
 3. Select .
 4. Select a data source, fill in connection parameters, and click *Connect*.
- An SQL query editor box is displayed.
5. Enter an SQL statement to insert a message number and text in the appropriate columns. For example:

```
insert into table values (error number,'error message')
insert into ERR_MSG values (1004,'The value that you are trying to insert does
not exist in the referenced table')
```


6. Click *Execute*.
- A message box tells you that the command has been successfully executed.
7. Click *OK* to return to the SQL query dialog.
 8. Click *Close*.

1.3.6.12.2.1 Generating a User-Defined Error Message

You can choose to generate a user-defined error message from the trigger generation parameters box.

Procedure

1. Select .
2. Click the *Error Messages* tab, and select the *User-defined* radio button.
3. Enter the name of the table that contains the error message, the name of the column that contains the error number, and the name of the column that contains the error message text.



4. Click the *General* tab and select the mode and triggers to create.
5. Click the *Selection* tab and select the tables for which you want to create triggers.

For more information on rebuilding triggers, see [Rebuilding Triggers \[page 137\]](#).

6. Click *OK*.

The trigger rebuilding process is shown in the Output window.

7. Select **Database > Generate Database**, select generation parameters as required (see [Generating Triggers and Procedures \[page 144\]](#)), and click *OK*.

1.3.7 Stored Procedures and Functions (PDM)

You can define stored procedures and functions for any DBMS that supports them.

A stored procedure is a precompiled collection of SQL statements stored under a name and processed as a unit. Stored procedures are stored within a database; can be executed with one call from an application; and allow user-declared variables, conditional execution, and other programming features.

The use of stored procedures can be helpful in controlling access to data (end-users may enter or change data but do not write procedures), preserving data integrity (information is entered in a consistent manner), and improving productivity (statements in a stored procedure only need to be written one time).

A user-defined function is a form of procedure that returns a value to the calling environment for use in queries and other SQL statements.

1.3.7.1 Creating a Stored Procedure or Function

You can create a stored procedure or function from a table property sheet or from the Toolbox, Browser, or *Model* menu.

Context


- Use the Procedure tool in the diagram Toolbox.
- Open the Procedures tab in the property sheet of a table, and click the *Add a Row* tool.
- Select **Model > Procedures** to access the List of Procedures, and click the *Add a Row* tool.
- Right-click the model or package in the Browser, and select **New > Procedure**.

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

You can create a procedure based on one of the PowerDesigner templates or on a template of your own.

Procedure

1. Double-click a table symbol to open its property sheet, and then click the *Procedures* tab.
2. Click the *Add a Row* tool to create a new procedure, and type a name and code.
3. Click *Apply* to commit the creation of the new procedure, and then click the *Properties* tool to open its property sheet.
4. Click the *Body* tab:



5. [optional] Select a procedure template from the *Template* list (see [Procedure Templates \(PDM\) \[page 158\]](#)).
6. Modify the procedure code. You can use PDM variables and macros and various other tools available from the toolbar (see [Writing SQL Code in PowerDesigner \[page 288\]](#)).
7. You can also modify the procedure's other properties. For a full list of the properties available, see [Procedure Properties \[page 150\]](#).
8. Click **OK** in each of the dialog boxes.

Results

Note

When using the PowerDesigner Eclipse plug-in, you can right-click a procedure in the Browser or diagram and select **Edit in SQL Editor** from the contextual menu to open it in the Eclipse SQL Editor. You can optionally connect to your database in order to obtain auto-completion for table names. The procedure is added to the Generated SQL Files list in the Workspace Navigator.

1.3.7.2 Procedure Properties

To view or edit a procedure's properties, double-click its diagram symbol or Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The **General** tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the Code field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Owner	Specifies the name of the procedure owner.
Table	Specifies the table to which the procedure is attached. Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object.

Property	Description
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.


The following tabs are also available:

- *Body* - Specifies the SQL code for the procedure. For information about the tools available, see [Writing SQL Code in PowerDesigner \[page 288\]](#).
- *Parameters* - Specifies the parameter list for the procedure. This tab may be read-only if your procedure is based on a template that does not allow the editing of parameters (see [Procedure Templates \(PDM\) \[page 158\]](#)).
- *Script* - Specifies Begin and End scripts for the procedure (see [Customizing Creation Statements \[page 310\]](#)).
- *Permissions* - Specifies user permissions in the database for the procedure (see [Granting Object Permissions \[page 169\]](#)).
- *Preview* - Displays the SQL code associated with the procedure (see [Previewing SQL Statements \[page 292\]](#)).


1.3.7.3 Tracing Trigger and Procedure Dependencies

When you write a trigger or procedure, PowerDesigner automatically creates dependencies to any table, view, procedure, or database package referenced in the code. These dependencies are taken into account when performing an impact analysis prior to deleting the trigger or procedure or objects on which they depend. For procedures, if the procedure has a symbol in your diagram, then any dependencies will be shown graphically by way of arrows linking the procedure to these objects.


The diagram below shows a procedure, **ProcChangeLocation**, which is dependent on a number of other objects:



Its *Traceability Links* tab lists the objects upon which it depends, and the link type of **DBCreateAfter (computed)** shows that PowerDesigner has determined that it can only be created after these objects:




The **Employee** table *Dependencies* tab shows that **ProcChangeLocation** is dependent upon it, and if you were to perform an impact analysis prior to deleting the **Employee** table, you would be warned of the procedure's dependency on it.




1.3.7.3.1 Creating Procedure Dependencies Manually

Since procedures have diagram symbols, you can manually add dependencies for them using the Traceability Links tool in the toolbox.

In the diagram below, **ProcChangeLocation** has a dependency on a new procedure, **ProcOccupancy**:



Since **ProcOccupancy** is not directly referenced in **ProcChangeLocation**, you must manually set the type of the link to **DBCreateAfter** on the *Traceability Links* tab of the **ProcChangeLocation** property sheet:



1.3.7.3.2 Rebuilding Trigger and Procedure Dependencies

Trigger and procedure dependencies are rebuilt automatically after the following actions:


Context

- Importing a PDM created with a former version of PowerDesigner
- Reverse engineering a database into a PDM
- Merging PDMs

You can also manually rebuild trigger and procedure dependencies at any time.

Procedure

1. Select **Tools > Rebuild Objects > Rebuild Triggers and Procedures Dependencies** to open the Procedures Dependencies window.
2. Specify a rebuild mode for each of Procedures and Triggers. You can choose between the following options:
 - **Delete and Rebuild** – all triggers and/or procedures attached to templates are deleted and rebuilt, including those to which you have made modifications
 - **Preserve** – only those triggers and/or procedures attached to templates that have not been modified are deleted and rebuilt. Any triggers and/or procedures that you have modified are preserved.



3. [optional] Click the *Selection* tab and specify the tables, views, procedures, and (for Oracle only) database packages for which you want to rebuild dependencies. By default all are selected.
4. Click *OK* to begin the rebuild process.

1.3.7.4 Attaching a Stored Procedure to a Table

You can attach a stored procedure to a table when your current DBMS supports stored procedures. This feature lets you update the table or retrieve information from this table.

Context

For example, the stored procedure TABLE_ADDROW can be attached to a table in which you need to insert rows.

When you generate an OOM from a PDM, the procedures attached to a table become operations with the <>procedure>> stereotype in the generated class. By attaching procedures to tables, you are able to define class operations in the generated OOM.


When you generate a PDM from an OOM, class operations with the <>procedure>> stereotype become stored procedures attached to the generated table. The operation body is generated as a comment in the procedure definition.

You can attach a table to a procedure from the property sheet of a procedure or the property sheet of a table.

Procedure

1. Open the table property sheet and click the *Procedures* tab.
2. Click the *Add Objects* tool to open a selection box, choose the the stored procedure you want to attach to the table and click *OK*.

The stored procedure is displayed in the list of stored procedures.




3. Click **OK**.

1.3.7.4.1 Rebuilding Procedures Attached to Tables

You can rebuild procedures attached to tables at any time.

Procedure

1. Select **Tools** **Rebuild Objects** **Rebuild Table Stored Procedures** to open the Rebuild Table Stored Procedures window.



2. Specify a rebuild mode. You can choose between the following options:
 - *Delete and Rebuild* – all procedures attached to tables are deleted and rebuilt
 - *Add missing table stored procedures* – adds procedures to any selected tables that do not presently have them.
3. [optional] Click the *Selection* tab to specify for which tables you want to rebuild stored procedures.
4. Click *OK* to begin the rebuild process.

1.3.7.5 Procedure Templates (PDM)

PowerDesigner procedure templates allow you to write table procedures in a modular reusable fashion. We provide basic templates for `insert`, `select`, `update`, and `delete` procedures. You can modify the code specified in these templates or create your own templates in the DBMS definition file.

To apply a procedure template to your procedure definition, select the template from the list on the procedure property sheet *Body* tab (see [Procedure Properties \[page 150\]](#)).

To review or modify the provided procedure templates, select **Database > Edit Current DBMS**, and then click the *Procedure Templates* tab. You cannot delete or rename these templates.

Caution

The resource files provided with PowerDesigner inside the `Program Files` folder cannot be modified directly. To create a copy for editing, use the *New* tool on the resource file list, and save it in another location. To include resource files from different locations for use in your models, use the *Path* tool on the resource file list.

To create a new template, click the *Add a Row* tool.

Procedure Template Properties

The *General* tab contains the following properties:

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
DBMS	Specifies the parent DBMS.
Function	Specifies whether the template defines procedures or functions.
Procedure Name	Specifies the conventions for naming procedures based on the template.
Linked to table	Specifies whether the resulting procedure will be linked to a table.
Allow editing of parameters	Specifies that the parameters of the procedure can be edited when the template is applied. If this option is not selected, the <i>Parameters</i> tab of the procedure property sheet will be read-only.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- *Body* - Contains a field for entering the procedure code for the template. You can use PDM variables and macros and other tools available from the toolbar (see [Writing SQL Code in PowerDesigner \[page 288\]](#)).

1.3.7.6 Creating SQL/XML Queries with the Wizard

You can use the SQL/XML Wizard to insert a SQL/XML query in the definition of the body of a trigger, stored procedure, or function to store or retrieve data, in an XML format, from relational databases supporting SQL/XML. The wizard, allows you to select tables and views from a PDM to build a mapped XML model. This XML model (which does not appear in the workspace) is used to generate SQL/XML queries from global elements.

Procedure

1. Open the trigger property sheet, click the *Body* tab and position the cursor where you want to insert the SQL/XML query:

Trigger Properties - tdb_employee (TDB_EMPLOYEE)

General Definition Template Items Preview Notes Rules Dependencies Version Info

<None> before delete ... 1


create trigger %TRIGGER% before delete order %ORDER% on [%QUALIFIER%]%TABLE% referencing old as old_del for each row begin declare user_defined_exception exception for SQLSTATE '99999'; declare found integer; .DeleteParentRestrict end;

OK Cancel Apply Help


This screenshot shows the 'Trigger Properties' dialog for a trigger named 'tdb_employee' on the table 'TDB_EMPLOYEE'. The 'Definition' tab is selected. The trigger is defined as 'before delete' on the 'old' table. The code is as follows:

```
create trigger %TRIGGER% before delete order %ORDER% on [%QUALIFIER%]%TABLE% referencing old as old_del for each row begin
    declare user_defined_exception exception for SQLSTATE '99999';
    declare found integer;
    .DeleteParentRestrict
end;
```

2. Click the *SQL/XML Wizard* tool to launch the wizard at the *Tables and Views Selection* page:



3. Select the tables and views that you want to include in your query and click **Next** to go to the **XML Hierarchy Design** page:



On this tab, you construct the XML hierarchy that you want to generate:

- The left-hand pane lists the tables and views that you have selected
 - The right-hand pane displays the XML hierarchy to be generated, containing a default root element.
4. You can build your XML hierarchy using the following techniques:
- Specify whether columns will be generated as elements or attributes by using the radio buttons above the panes.
 - Drag and drop a table, view, or column onto a node in the XML hierarchy. You must respect the PDM hierarchy: You cannot create an XML hierarchy between two elements if there is no reference between their corresponding tables, and a parent table cannot be placed beneath one of its children.
 - Right-click a table, view, or column and select **Add** from the contextual menu to add it to the last selected node in the XML hierarchy.
 - Rename an element or attribute by clicking its node and typing a new name.
 - Create new elements and attributes not in the PDM, and Sequence, Choice and All group particles, by right-clicking an XML node and selecting **New** > **<object>** from the contextual menu.
 - Delete an XML node by right-clicking it and selecting **Delete** from the contextual menu.
5. When you have finished building your hierarchy, click **Next** to go to the **Query** tab:

SQL/XML Wizard : Query

```
Ln 1, Col 1
```

```
select '<?xml version="1.0" encoding="UTF-8" ?>' ||  
XMLEMENT( NAME "Root",  
(select XMLAGG ( XMLEMENT( NAME "EMPLOYEE",XMLCONCAT(  
XMLEMENT( NAME "EMPNUM",EMPLOYEE.EMPNUM),  
XMLEMENT( NAME "EMP_EMPNUM",EMPLOYEE.EMP_EMPNUM),  
XMLEMENT( NAME "DIVNUM",EMPLOYEE.DIVNUM),  
XMLEMENT( NAME "EMPFNAM",EMPLOYEE.EMPFNAM),  
XMLEMENT( NAME "EMPLNAM",EMPLOYEE.EMPLNAM),  
XMLEMENT( NAME "EMPFUNC",EMPLOYEE.EMPFUNC),  
XMLEMENT( NAME "EMPSAL",EMPLOYEE.EMPSAL))) )  
from EMPLOYEE))
```

< Back Next > Finish Cancel Help

6. Review your query and click *Back*, if necessary, to make revisions in your hierarchy. When you are satisfied, click *Finish* to close the wizard and insert the SQL/XML query in the code.

Trigger Properties - tdb_employee (TDB_EMPLOYEE)

General Definition Template Items Preview Notes Rules Dependencies Version Info


<None> before delete ... 1

Ln 19, Col 17


```
create trigger %TRIGGER% before delete order %ORDER% on [%QUALIFIER%]*TABLE%
referencing old as old_del for each row
begin
    declare user_defined_exception exception for SQLSTATE '99999';
    declare found integer;
    .DeleteParentRestrict

    select '<?xml version="1.0" encoding="UTF-8" ?>' ||
XMLELEMENT( NAME "Root",
(select XMLAGG ( XMLELEMENT( NAME "EMPLOYEE",XMLCONCAT(
    XMLELEMENT( NAME "EMPNUM",EMPLOYEE.EMPNUM),
    XMLELEMENT( NAME "EMP_EMPLNUM",EMPLOYEE.EMP_EMPLNUM),
    XMLELEMENT( NAME "DIVNUM",EMPLOYEE.DIVNUM),
    XMLELEMENT( NAME "EMPFNAM",EMPLOYEE.EmpFNAM),
    XMLELEMENT( NAME "EMPLNAM",EMPLOYEE.EMPLNAM),
    XMLELEMENT( NAME "EMPFUNC",EMPLOYEE.EmpFUNC),
    XMLELEMENT( NAME "EMPSAL",EMPLOYEE.EMPSAL))) )
from EMPLOYEE))
end;
```

OK Cancel Apply Help

A screenshot of the Oracle SQL Developer Trigger Properties dialog for the 'tdb_employee' table. The 'Definition' tab is selected. The trigger type is set to 'before' and the event is 'delete'. The code editor contains an SQL/PLSQL script that generates XML from the 'EMPLOYEE' table. The script uses XMLAGG to aggregate rows into an XML document with a root element 'Root'. Each row is represented by an 'EMPLOYEE' element containing child elements for 'EMPNUM', 'EMP_EMPLNUM', 'DIVNUM', 'EMPFNAM', 'EMPLNAM', 'EMPFUNC', and 'EMPSAL'. The 'Ln 19, Col 17' status bar indicates the current cursor position.

7. [optional] Add code to complete the SQL/XML query:



- Click **OK** to close the trigger property sheet:

1.3.8 Users, Groups, and Roles (PDM)

A user is a database object that identifies a person who can login or connect to the database. Groups and roles are used to simplify the granting of rights to users, as privileges and permissions granted to a group or role are inherited by users who belong to that group or incarnate that role.

Not all DBMSs support each of the concepts of user, role, and group.

i Note

For many DBMSs, users can have an implicit schema, and PowerDesigner can reverse-engineer create statements contained within a schema. For SQL Server 2005 and higher, where users can have multiple schemas, PowerDesigner reverse-engineers schemas as separate objects (see [Schemas \(SQL Server\) \[page 463\]](#)).

1.3.8.1 Creating a User, Group, or Role

You can create a user, group, or role from the Browser or *Model* menu. You can also create a user from the *Owner* field of various objects.

- Select *Model* *Users and Roles* <Type> to access the appropriate model object list, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select *New* <Type>.
- [users] Click the *Create* tool to the right of the *Owner* field on the *General* tab of a table (see [Table Properties \[page 84\]](#)) or other object that allows you to specify an owner.

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.3.8.2 User, Group, and Role Properties

To view or edit a user, group, or role's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Password	[users and groups] Password used for database connection.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- Privileges - lists the system privileges granted to the user (see [Granting System Privileges \[page 166\]](#)).
- Permissions - lists the operations that the user is permitted to perform on various database objects (see [Granting Object Permissions \[page 169\]](#)).
- Users - [groups and roles] Lists the users belonging to the group or role.
- Groups - [groups and roles] Lists the groups belonging to the group or role.
- Roles - [roles] Lists the roles belonging to the role.

1.3.8.3 Assigning an Owner to an Object

The database user who creates an object (table, view, stored procedure, etc) is the owner of the object and is automatically granted all permissions on it. In a PDM, you can specify the owner of an object by attaching a user to it. Each object can have only one owner. Where other users must access the object, you can restrict object modifications to the owner and grant **Select** or other permissions for the other users.

Context

i Note

To automatically assign a default owner for any type of object that supports the concept of ownership, select **Tools** ▶ **Model Options** [], choose the appropriate object type in the left-hand pane, and select the appropriate user in the *Default owner* field (see [Other Object Model Options \[page 21\]](#)).

Procedure

1. Open the property sheet of the object to the *General* tab.
2. Select a user in the *Owner* field. To create a new user, click the *Create* tool to the right of this field.
3. Click *OK* to return to your model.

i Note

When generating to your database (see [Generating a Database from a PDM \[page 298\]](#)), you can restrict the tables and other objects generated to only those belonging to a particular owner, by selecting the owner on the Database Generation dialog *Selection* tab.

1.3.8.4 Granting System Privileges

System privileges are granted to users, groups, and roles to give them the right to perform particular types of action in the database. By default, a user belonging to a group or having a role inherits the group or role privileges and these inherited privileges are identified as such in the *Privileges* tab of the user property sheet. A user with an administrative profile is also allowed to revoke a privilege.

Context

System privileges are used in association with object permissions (see [Granting Object Permissions \[page 169\]](#)) to evaluate the rights of a user, group, or role. For example, even if a user has the **Modify** privilege, he cannot modify an object on which he has no **Update** permission.

Note

In some DBMSs, system privileges are called permissions. In PowerDesigner, the term privilege is reserved for any right granted to a user, a group, or a role. Permissions are defined for objects.

Procedure


1. Open the property sheet of a user, role, or group, and click the *Privileges* tab.
2. [optional] Click the *Show/Hide All Inherited Privileges* tool to show privileges that have been inherited from a group. Inherited privileges are red, while privileges directly granted to the user are blue.
3. Click the *Add Objects* tool to choose one or more of the privileges available in the DBMS, and click *OK* to grant them to the user, role, or group:

System privileges are defined in the DBMS definition file. To review and edit the list of available privileges, select  *Edit Current DBMS*, select the item  *Script*  *Objects*  *Privilege*  *System*, and edit the list as appropriate. The *Privilege* category also contains entries that define the syntax for the necessary SQL statements for granting and revoking privileges. For more information, see *Customizing and Extending PowerDesigner > DBMS Definition Files > Script/Objects Category*.

4. [optional] To change the state of a privilege (whether granted directly, or inherited from a group), click in the *State* column to cycle through the available states, or click on the appropriate tools in the *Privilege state* group box at the bottom of the tab:

Privilege	Description
	<i>Grant</i> – [default] Assigns the privilege to the user.
	<i>Inherited/None</i> - Reverts the cell to the inherited state.
	<i>Revoke</i> – Revokes the privilege inherited from a group or role for the current user or group.

Privilege	Description
 	<i>Grant with admin option</i> - Assigns the privilege to the user, and allows the recipient to pass on the privilege to other users, groups, or roles. For example, you assign the CREATE TABLE privilege for user Designer_1 and then click the Grant With Admin Option button to permit Designer_1 to grant this privilege to other users.



- When the privileges are correct, click **OK** to return to the model.

1.3.8.4.1 Generating Privileges

You can generate privileges to a script or to a live database connection.

Procedure

- Select **Database > Generate Database** to open the Database Generation window, and specify the standard options, including whether you want to generate to a script or to a live database connection.

For detailed information about using this window, see [Generating a Database from a PDM \[page 298\]](#).

2. Select "Users & Groups (with privileges)" from the *Settings set* list in the Quick Launch groupbox at the bottom of the window. This settings set specifies standard options for generating privileges.

or:

Click the *Options* tab and click on User in the left-hand pane to display the user generation options. Change the default options as appropriate.

For detailed information about settings sets, see [Quick Launch Selection and Settings Sets \[page 308\]](#).

3. [optional] Click the *Selection* tab and select the *Users* sub-tab at the bottom of the tab. Select the users that you want to generate for.
4. Click *OK* to begin the generation.

1.3.8.5 Granting Object Permissions

Object permissions are granted to users, groups, and roles to give them the right to perform operations on particular database objects. PowerDesigner allows you to define permissions on tables, views, columns, procedures, packages, and other objects depending on your DBMS.

Context

System privileges are used in association with object permissions (see [Granting System Privileges \[page 166\]](#)) to evaluate the rights of a user, group, or role.

Note

The owner of an object (see [Assigning an Owner to an Object \[page 166\]](#)) automatically has permission to carry out any operation on that object. These permissions do not appear in the *Permissions* tab of the object property sheet but they are implemented during generation and reverse engineering.

Procedure

1. Open the property sheet of a user, role, or group, and click the *Permissions* tab. A sub-tab is displayed for each type of object supporting permissions. The columns in the list on each tab show the permissions available for a given type of object in the current DBMS (for example, Select, Insert, Alter, Delete, Update, etc).


The permissions available for each type of object are defined in the DBMS definition file. To review and edit the list of available permissions, select **Database** **Edit Current DBMS**, select the item **Script** **Objects** **<object_type>** **Permission**, and edit the list as appropriate. The syntax for inserting permissions in your scripts is defined in the **Script** **Objects** **Permission** category. For more information, see *Customizing and Extending PowerDesigner > DBMS Definition Files > Script/Objects Category*.

Note

You can assign permissions for multiple users, groups, and roles to an object on the *Permissions* tab of its property sheet.

2. Click the *Add Objects* tool to choose one or more objects of the present type, and click *OK* to add them to the list to assign permissions. If the user belongs to a group with permissions on the added objects, these permissions appear in red in the list.
3. [optional] Click the *Show All Inherited Permissions* or *Hide Inherited Permissions* tool to show or hide permissions that have been inherited from a group. Inherited permissions are red, while permissions directly granted to the user are blue.
4. [optional] To change the state of a permission (whether granted directly, or inherited from a group), click in the appropriate column to cycle through the available states, or click on the appropriate tools in the *Permission state* group box at the bottom of the tab:

Permission	Description
	<i>Grant</i> – Assigns the permission to the user.
	<i>Inherited/None</i> - Reverts the cell to the inherited state.
	<i>Revoke</i> – Revokes the permission inherited from a group or role for the current user or group.
	<i>Grant with admin option</i> - Assigns the permission to the user, and allows the recipient to pass on the permission to other users, groups, or roles.
	<i>Revoke with cascade</i> – Revokes the permission inherited from a group or role for the current user or group and revokes any permission granted by the user.




5. [optional] For tables, you can specify permissions on individual columns (see [Defining Column Permissions \[page 171\]](#)).
6. When the permissions are correct, click **OK** to return to the model.

1.3.8.5.1 Defining Column Permissions


You can fine tune the permissions on a table by specifying permissions on a column-by-column basis. The available column permissions are specified in the DBMS resource file. Note that any new or modified permission may not be supported during generation or reverse-engineering.

Procedure

1. Open the property sheet of a table, user, role, or group, and click the **Permissions** tab. For a table, select a user, group or role in the list to whom you want to grant column permissions. For a user, group or role, select a table in the list for which you want to specify permissions.
2. Click the ellipsis button to the right of the **Columns** field to open the Column Permissions dialog. The columns in the list show the permissions available for each of the table's columns.



3. To change the state of a permission (whether granted directly, or inherited from a group), click in the appropriate column to cycle through the available states, or click on the appropriate tools in the *Permission state* group box at the bottom of the tab.
4. Click **OK** to close the dialog and return to the property sheet. The cells for which specific permissions have been set for columns now contain ellipsis symbols. Click on one of these symbols to display the associated column permissions information in the *Columns* field:




5. Click **OK** to close the property sheet and return to the model.

1.3.8.6 Assigning a User to a Group or Role

Once you have created a group or role, you can assign users to it.

Procedure

1. Select or to open the appropriate list.
 2. Select a group or role in the list, click the *Properties* tool to open its property sheet and then click the *Users* tab.
 3. Click the *Add Objects* tool to open a selection box listing the users available in the model.
 4. Select one or more users and click *OK* to insert them into the group.



5. Click **OK** to return to the model.

1.3.9 Synonyms (PDM)

Synonyms are alternative names for various types of database object, which can be used to mask the name and owner of the object, provide location transparency for remote objects of a distributed database, and simplify SQL statements for database users.

For example, if the table `SALES_DATA` is owned by the user `JWARD`, you could define a synonym `Sales` for it to hide the ownership and simplify the required SQL select statement:

Standard Statement	Statement with Synonym
<code>SELECT * FROM jward.sales_data</code>	<code>SELECT * FROM sales</code>

You can create multiple synonyms for a base object (table, view, etc.), but each synonym can have only one base object. You can view the synonyms defined for a particular base object on the *Dependencies* tab of its property sheet. If you delete the base object of a synonym, the synonym is deleted as well.

i Note

PowerDesigner supports the generation and reverse-engineering of synonyms. When you reverse-engineer synonyms, the link with the base object is preserved if both objects are reverse engineered and if the base object is displayed before the synonym in the script. You can reverse a synonym without its base object, but then you should define a base object for it in your model.

1.3.9.1 Creating a Synonym

You can create synonyms from the *Model* menu.

Procedure

1. Select   to open the List of Synonyms.
2. Click the *Create Synonyms* tool to open a selection box listing all the available objects in the model on various sub-tabs, select one or more objects, and click *OK* to create synonyms for them in the list.

i Note

By default, synonyms are created with the same name as their base objects.

3. Click in the *Name* column and enter a new name for the synonym. Alternatively, click the *Properties* tool to open the property sheet of the synonym and edit its name and other properties there.
4. Click *OK* to return to your model.

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.3.9.2 Synonym Properties

To view or edit a synonym's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Owner	Specifies the user who is the owner of the object. This is usually its creator. Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object.
Base Object	Specifies the name of the object that is aliased by the synonym. Click the <i>Select</i> tool to the right of the field to select an object from among the PDMs of the same DBMS family open in the workspace.
Visibility	Specifies whether the synonym is public (accessible to all users) or private (available only to its owner).
Type	[if your DBMS supports synonyms and aliases] Specifies whether to create a synonym or an alias, both of which are modeled in the same way in PowerDesigner.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

1.3.9.3 Creating a View from a Synonym

You can create views from synonyms in the same way as for tables. The view query displays the content of the object aliased by the synonym.

Procedure


1. Ensure that no objects are selected in the diagram and select *Tools* *Create View* to open a selection box listing all the available objects in the model.
2. Click the *Synonyms* tab and select one or more synonyms to add to the view.

3. Click **OK**. The view is created in the diagram.

For example, the **ORDERS_PROD_DEPT** table has a synonym **ORDERS**:

ORDERS_PROD_DEPT	
Order_ID	<pk>
Dpt_ID	
Order_Amount	
Order_Delivery	

If you create a view for the **ORDERS** synonym, the view query displays the select order of the table content:



For more information about views, see [Views \(PDM\) \[page 123\]](#).

1.3.10 Defaults (PDM)

Default objects are named values that can be assigned to columns or domains. Defaults are available for selection from the **Default** list on the **Check Parameters** tab of column and domain property sheets. Defaults are not supported by all DBMSs.

For example, if you must set a default value for all columns of type **city**, you can create a default object **citydflt** to assign the value **London** to it. To review how the default will be generated to your database, click the **Preview** tab:

```
create default CITYDFLT as 'London'
```

1.3.10.1 Creating a Default

You can create a default from the Browser or *Model* menu.

- Select **Model** **Defaults** to access the List of Defaults, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select **New** **Default** .

Note

You can also convert default values assigned to column and domains into default objects for reuse through rebuilding (see [Rebuilding Defaults \[page 178\]](#)).

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.3.10.2 Default Properties

To view or edit a default's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Owner	Specifies the user who is the owner of the object. This is usually its creator. Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object.
Value	Specifies the value that will be generated for the default object.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- *Preview* - Displays the SQL code associated with the default (see [Previewing SQL Statements \[page 292\]](#)).

1.3.10.3 Assigning a Default to a Column or a Domain

You can select a default from the *Default* list on the *Check Parameters* tab of a column or domain property sheet.

Procedure

1. Open the property sheet of a column or a domain, and click the *Standard Checks* tab (see [Setting Data Profiling Constraints \[page 102\]](#)).
2. Select a default in the *Default* list in the *Value* groupbox.

You can, alternatively, enter a default value in the listbox. The value entered is assigned as a default value for the column or domain, but a default object is not created in the model, and the default cannot be reused elsewhere. If you enter a name that is already in the list, the relevant default object is attached to the column or domain.

i Note

You can create default objects for reuse from default values, through the *Rebuild Default* command (see [Rebuilding Defaults \[page 178\]](#)).

3. Click *OK* to return to your model.

1.3.10.4 Rebuilding Defaults

You can generate default objects from default values entered into the *Default* list on the *Check Parameters* tab of a column or domain property sheet. The new default objects replace the previously entered values, and can be reused with other columns and domains.

Context

i Note

If your model's DBMS does not support default objects and you have assigned default values to domains then, if you change to a DBMS that does support default objects, an object will be created for each value. Default values assigned to columns will not be converted into objects. When changing from a DBMS that supports default objects to one that does not, default objects are converted into default values.

Procedure

1. Select **Tools** **Rebuild Objects** **Rebuild Defaults**, and enter the appropriate options:

Option	Description
Domains / Columns	Specifies the naming conventions for defaults applied to domains and columns respectively, which are both, by default, D_% . U:VALUE%. You can specify different names for each type of default, and use the following variables: <ul style="list-style-type: none">○ %DOMAIN%, %COLUMN%, %TABLE% - Code of the domain, column, or table using the default.
Mode	Specifies the type of rebuild. You can select either or both of: <ul style="list-style-type: none">○ <i>Reuse default with identical value</i> – Creates a single default for each value, even if the value is found in multiple columns and domains. If you deselect this option, multiple defaults may be created with the same value.○ <i>Delete and rebuild</i> – Delete and rebuild all existing default objects.

2. [optional] Click the **Selection** tab to specify which domains and tables to search for defaults to rebuild.
3. Click **OK**. If you selected the Delete and Rebuild mode, a confirmation box asks you to confirm your choice. Click **Yes** to confirm the deletion and rebuild of the selected defaults.

1.3.11 Domains (CDM/LDM/PDM)

Domains allow you to group together a data type, length, precision, mandatoriness, check parameters, and business rules to standardize their application to a set of columns and entity attributes. You can define domains for columns of type ID, name, address, or any other kind of data whose use you want to standardize across multiples columns or attributes in your model.

1.3.11.1 Creating a Domain

You can create a domain from the Browser or **Model** menu.

- Select **Model** **Domains** to access the List of Domains, and click the **Add a Row** tool
- Right-click the model (or a package) in the Browser, and select **New** **Domain**

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.3.11.2 Domain Properties

To view or edit a domain's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:


Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Owner	[PDM] Specifies the user who is the owner of the object. This is usually its creator. Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object.
Data type/ Length/ Precision	Specifies the form of data to be stored, such as numeric, alphanumeric, or Boolean, and, where appropriate, the maximum number of characters or numerals that can be stored, and the maximum number of places after the decimal point. Click the ellipsis button to choose from the list of standard data types (see PowerDesigner Standard Data Types [page 181]). To review the data types permitted by your DBMS, select <i>Database</i> <i>Edit Current DBMS</i> and navigate to <i>Script</i> <i>DataType</i> <i>PhysDataType</i> . The following variables specify length and precision requirements: <ul style="list-style-type: none">• %n - length• %s - length with precision• %p - decimal precision For example, the data type <code>char(%n)</code> , requires you to specify a length.
Mandatory	[if supported by your DBMS] Specifies that a non-null value must be assigned.
Identity	[if supported by your DBMS] Specifies that the column is populated with values generated by the database. Identity columns are often used as primary keys.
With default	[PDM] [if supported by your DBMS] Specifies that the column is populated with values generated by the database. Identity columns are often used as primary keys.
Profile	[PDM] Specifies a test data profile to use to generate test data (see Populating Columns with Test Data [page 107]). Use the tools to the right of this field to create or browse to a profile, or to open the property sheet of the selected profile.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- *Standard Checks* - Specifies constraints to control the range and format of permitted data (see [Setting Data Profiling Constraints \[page 102\]](#))
- *Additional Checks* - Displays an editable SQL statement, initialized with the standard checks, which can be used to generate more complex constraints (see [Specifying Advanced Constraints \[page 106\]](#)).
- *Rules* - Lists the business rules associated with the object (see [Business Rules \(CDM/LDM/PDM\) \[page 202\]](#)).

1.3.11.2.1 PowerDesigner Standard Data Types

To open the list of Standard Data Types, click the ellipsis button to the right of the *Data Types* field on the *General* tab of a column, entity attribute, data item, or domain property sheet.



Numeric Data Types

The following numeric data types are available:

Standard data type	DBMS-specific physical data type	Content	Length
Integer	int / INTEGER	32-bit integer	—
Short Integer	smallint / SMALLINT	16-bit integer	—
Long Integer	int / INTEGER	32-bit integer	—
Byte	tinyint / SMALLINT	256 values	—
Number	numeric / NUMBER	Numbers with a fixed decimal point	Fixed
Decimal	decimal / NUMBER	Numbers with a fixed decimal point	Fixed
Float	float / FLOAT	32-bit floating point numbers	Fixed
Short Float	real / FLOAT	Less than 32-bit point decimal number	—
Long Float	double precision / BINARY DOUBLE	64-bit floating point numbers	—
Money	money / NUMBER	Numbers with a fixed decimal point	Fixed
Serial	numeric / NUMBER	Automatically incremented numbers	Fixed
Boolean	bit / SMALLINT	Two opposing values (true/false; yes/no; 1/0)	—

Character Data Types

The following character data types are available:

Standard data type	DBMS-specific physical data type	Content	Length
Characters	char / CHAR	Character strings	Fixed
Variable Characters	varchar / VARCHAR2	Character strings	Maximum
Long Characters	varchar / CLOB	Character strings	Maximum
Long Var Characters	text / CLOB	Character strings	Maximum

Standard data type	DBMS-specific physical data type	Content	Length
Text	text / CLOB	Character strings	Maximum
Multibyte	nchar / NCHAR	Multibyte character strings	Fixed
Variable Multibyte	nvarchar / NVARCHAR2	Multibyte character strings	Maximum

Time Data Types

The following time data types are available:

Standard data type	DBMS-specific physical data type	Content	Length
Date	date / DATE	Day, month, year	—
Time	time / DATE	Hour, minute, and second	—
Date & Time	datetime / DATE	Date and time	—
Timestamp	timestamp / TIMESTAMP	System date and time	—

Other Data Types

The following other data types are available:

Standard data type	DBMS-specific physical data type	Content	Length
Binary	binary / RAW	Binary strings	Maximum
Long Binary	image / BLOB	Binary strings	Maximum
Bitmap	image / BLOB	Images in bitmap format (BMP)	Maximum
Image	image / BLOB	Images	Maximum
OLE	image / BLOB	OLE links	Maximum
Other	—	User-defined data type	—


Standard data type	DBMS-specific physical data type	Content	Length
Undefined	undefined	Undefined. Replaced by the default data type at generation.	—

1.3.11.3 Controlling Non-Divergence from a Domain

You can specify which of the properties of your domains must be applied to the columns or entity attributes associated with the domain, and which properties are permitted to diverge.

Procedure


1. Select **Tools > Model Options** to open the Model Options dialog box. In a PDM, click the *Column and Domain* sub-category in the left-hand Category pan:



2. Select the checkboxes of the column or entity attribute properties that you want to prevent from diverging from those defined in the domain:
 - *Data type* - Data type, length, and precision.
 - *Check* (see [Setting Data Profiling Constraints \[page 102\]](#)).
 - *Rules* (see [Business Rules \(CDM/LDM/PDM\) \[page 202\]](#)).
 - *Mandatory* – Mandatory property of the column or attribute.
 - [PDM] *Profile* (see [Populating Columns with Test Data \[page 107\]](#)).
3. Click **OK** to close the dialog and return to your model.

You are prompted to apply domain properties to columns or attributes currently attached to the domain. If you click **OK**, the properties of these objects are modified in order to be consistent with the properties of their domain.

If you subsequently modify properties of the domain that are not selected for enforcement, you will be prompted to apply your changes to the columns or attributes attached to the domain. To choose not to apply your changes, deselect the appropriate checkbox. Properties that are enforced may not be deselected and if you only modify enforced properties, then this dialog will not be displayed.



i Note

Properties specified as non-divergent are read-only in lists and property sheets for associated columns and attributes. If you want to modify a non-divergent column or attribute property, you must detach the column or attribute from its domain.

1.3.12 Sequences (PDM)

Sequences are auto-incremented columns that allow you to define complex increments. Sequences are available for selection from the *Sequence* list on the *General* tab of column property sheets. Sequences are not supported by all DBMSs.

i Note

If you generate a CDM or OOM from your PDM, then the data types of table columns attached to sequences are converted to serial numerical data types for entity properties or class attributes with the format NO%<n>, where <n> indicates the length of the data type.

1.3.12.1 Creating a Sequence

You can create a sequence from the Browser or *Model* menu.

Context


i Note

If your model's DBMS does not support sequences and contains auto-incremented columns then, if you change to a DBMS that does support sequences, one will be created for each auto-incremented column. When changing from a DBMS that supports sequences to one that does not, sequences are converted into auto-incremented columns.

Procedure

1. Select to open the List of Sequences, and click the *Add a Row* tool. Then click the *Properties* tool to open the property sheet of the new sequence.
Alternatively, you can create a sequence by right-clicking the model (or a package), and selecting .
2. Enter an appropriate name for the sequence and then click the *Physical Options* or *Physical Options (Common)* tab and enter any DBMS-specific options.

The following example shows a sequence created in SQL Anywhere to represent the months in a year when quarterly reports are published.



For information about working with physical options, see [Physical Options \(PDM\) \[page 96\]](#).

3. Click **OK** to save the sequence and return to your model.

1.3.12.2 Assigning a Sequence to a Column

You can select a sequence from the **Sequence** list on the **General** tab of a column property sheet. You must enable sequences with the **Rebuild Triggers** command.

Procedure

1. Open the property sheet of a column with a numeric data type, and select a sequence in the **Sequence** list on the **General** tab.
2. Click **OK** to save the change and return to your model.
3. Select **Tools** **Rebuild Objects** **Rebuild Triggers** to open the Rebuild Triggers dialog (see [Rebuilding Triggers \[page 137\]](#)).
4. Click the **Selection** tab and select the tables containing the column to which you have assigned the sequence.
5. Click **OK** to rebuild the triggers and enable the sequence on the column.

1.3.12.3 Sequence Properties

To view or edit a sequence's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Owner	Specifies the user who is the owner of the object. This is usually its creator. Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- *Physical Options / Physical Options (Common)* - lists the physical options (see [Physical Options \(PDM\) \[page 96\]](#)) that control the incrementation of the sequence. For information about these options, see your DBMS documentation.

1.3.13 Abstract Data Types (PDM)

An abstract data type (ADT) is a user-defined data type which can encapsulate a data set and functions that can be performed on the data. Abstract data types are not supported by all DBMSs.

For example you could create an abstract data type for the Gregorian calendar to read and write roman numerals and convert dates between the Julian and Gregorian calendars.

If your model contains abstract data types of type JAVA, you can link them to Java classes in an OOM to model and review the Java class properties (see [Linking an Abstract Data Type to a Java Class \[page 191\]](#)).

1.3.13.1 Creating an Abstract Data Type

You can create an abstract data type from the Browser or *Model* menu.

Procedure

1. Select to open the List of Abstract Data Types, and click the *Add a Row* tool. Then click the *Properties* tool to open the property sheet of the new type.
Alternatively, you can create an abstract data type by right-clicking the model (or a package), and selecting .
2. Select the type for the ADT in the *Type* list on the *General* tab. Depending on your DBMS, you can choose from:
 - Array - Fixed length collection of elements. For example, VARRAY (Oracle 8 and higher).
 - List - Open collection of objects. For example, TABLE (Oracle 8 and higher).
 - Java - Java class. For example, JAVA (SAP® SQL Anywhere® and SAP® Adaptive Server® Enterprise).
 - Object - Contains lists of attributes and procedures. For example, OBJECT or SQLJ OBJECT (Oracle 8 and higher).
 - Structured - Contains a list of attributes. For example, NAMED ROW TYPE (Informix 9.x and higher).
3. [for object and structured types] Click the *Attributes* tab and create any appropriate attributes.
4. [for object types] Click the *Procedures* tab and create any appropriate procedures.
5. Click *OK* to return to your model.

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.3.13.2 Abstract Data Type Properties

To view or edit an abstract data type's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.

Property	Description
Type	Specifies the kind of the abstract data type (see Creating an Abstract Data Type [page 189]), which will change the other properties that are available.
Owner	Specifies the user who is the owner of the object. This is usually its creator. Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object.
Authorization	[objects] Specifies the Invoker Right attribute used for DDL generation.
Supertype	[objects] Specifies the parent type from which the type is derived, and from which it can inherit the procedures.
Final/Abstract	[objects] Mutually exclusive. If <i>Final</i> , the abstract data type cannot be used as supertype by another abstract data type. If <i>Abstract</i> , the abstract data type cannot be instantiated.
Data type/ Length/Precision	[tables, varrays] Specify the data type of the abstract data type.
Size	[arrays] Specifies the size of the abstract data type array.
Java class/Java data	[SQLJ objects] Specify the name of an external Java class to which the SQLJ object points (see Linking an Abstract Data Type to a Java Class [page 191]) and the mapping interface (CustomDatum, OraData or SQLData).
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- **Attributes** - [object and structured types] Use the *Add a Row* tool to create appropriate attributes, specifying a *Name*, *Code*, *Data Type*, and, if appropriate, select the *Mandatory (M)* check box.
- **Procedures** - [object types] Use the *Add a Row* tool to create appropriate procedures, specifying a *Name* and *Code*, and, if appropriate, selecting the *Final (F)*, *Static (S)* and/or *Abstract (A)* check boxes.

i Note

An object abstract data type with a supertype can inherit non-final procedures. Use the *Inherit Procedure* tool to select a non-final procedure from a parent abstract data type.

1.3.13.3 Linking an Abstract Data Type to a Java Class

You can link an abstract data type in a PDM to a Java class in an OOM open in the Workspace to access the properties of the Java class within the PDM.

Context

Note

If you reverse engineer Java classes from a database into an OOM (see *Object-Oriented Architecture*) before reverse-engineering the tables and other database objects into a PDM, then the Java classes that are reverse engineered into the PDM are created as abstract data types of type JAVA and linked to the appropriate classes in the OOM (if it remains open in the Workspace).


Procedure

1. Create an abstract data type and select *Java* from the *Type* list.
2. Click the *Select* tool to the right of the *Class* field to open a selection dialog listing all the Java classes that are available for linking.
3. Select a Java class and click *OK* to link it to the abstract data type. The class name is displayed in the abstract data type property sheet *Class* field. Click the *Properties* tool to the right of this field to open the Java class property sheet.

1.3.14 References (PDM)

A reference is a link between a parent table and a child table, which defines a referential integrity constraint between column pairs for a primary or alternate key and a foreign key, or between user-specified columns. Each column pair is linked by a join, and each reference can contain one or more joins. Each value in the child table column is equal to the value in the parent table column.

In the following example, the **STORE** parent table is linked to the **SALE** child table by a reference containing a join which links the primary key column **STORE_ID** (the referenced column) to the foreign key column **STOR_ID** (the referencing column).



1.3.14.1 Creating a Reference

You can create a reference that links a primary key, or alternate key, to a foreign key, or user-specified columns in both parent and child tables.

You can create a reference in any of the following ways:

- Use the *Reference* tool in the Toolbox.
- Select ► *Model* ► *References* ▾ to access the List of References, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select ► *New* ► *Reference* ▾.

i Note

You can control whether the creation of a reference automatically creates a join between a primary key in the parent table to a foreign key in the parent table (default) or whether the join columns are left undefined with the *Default link on creation* model option (see [Automatic Reuse and Migration of Columns \[page 195\]](#)).

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.3.14.2 Reference Properties

To view or edit a reference's properties, double-click its diagram symbol or Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Parent table/ Child table	Specify the parent table (which contains the primary or alternate key or a user-selected column) and the child table (which contains the foreign key or a user-selected column) linked by the reference. Use the tools to the right of the Parent table field to create, browse for, or view the properties of the currently selected table.

Property	Description
Parent role/ Child role	Specify the roles of the parent and child tables in the reference (for example Contains and Is contained by).
Generate	Specifies to generate the reference in the database.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

Joins Tab

The *Joins* tab lists the joins defined between parent and child table columns. Joins can link primary or alternate and foreign keys, or any user-specified columns.

i Note

You can control the default joins created using the *Default link on creation* and *Auto-migrate columns* model options (see [Automatic Reuse and Migration of Columns \[page 195\]](#)).

On this tab, you can either:

- Select a key from the parent table in the *Parent key* field on which to base the join to autopopulate the list with its associated parent and child columns. If necessary, you can modify the specified child columns.
- Specify **<None>** in the *Parent key* field and specify your own column pairs on which to base the join using the following tools:

Tool	Description
	Reuse Columns - Create a join by matching parent and child columns that share the same code and data type.
	Migrate Columns - First specify columns in the <i>Parent Table Column</i> column and then click this tool to migrate them to foreign key columns in the child table. If the columns do not exist in the child table, they are created.
	Cancel Migration - Remove any columns migrated to the child table.
	Insert/Add a Row - Inserts a row before the selected row in the list or at the end of the list to specify another column to join on.

i Note

Select the *Auto arrange join order* check box to sort the list by the key column order or deselect it to re-arrange the columns using the arrow buttons. If this option is not available, to enable it, add the **EnableChangeJoinOrder** item to the Reference category in the DBMS definition file and set the value to YES (see *Customizing and Extending PowerDesigner > DBMS Definition Files*).

Integrity Tab

Referential integrity governs data consistency between primary or alternate keys and foreign keys by dictating what happens when you update or delete a value or delete a row in the parent table. The Integrity tab contains the following properties:

Property	Description
Constraint name	Specifies the name of the referential integrity constraint. Maximum length is 254 characters. If you edit this name, the <i>User-defined</i> button will be depressed. To return to the default name, click to release this button.
Implementation	Specifies how referential integrity will be implemented. You can choose between: <ul style="list-style-type: none">• Declarative- Referential integrity constraints are defined for particular references. When the reference is generated the target DBMS evaluates the reference validity and generates appropriate error messages.• Trigger - Referential integrity constraints are implemented by triggers based on the integrity constraints defined in the reference property sheet. The trigger evaluates reference validity and generates appropriate user-defined error messages.
Cardinality	Indicates the minimum and maximum number of instances in a child table permitted for each corresponding instance in the parent table. The following values are available by default: <ul style="list-style-type: none">• 0..* - A parent can have zero or more children.• 0..1 - A parent can have zero or one children.• 1..* - A parent can have one or more children.• 1..1 – A parent must have exactly one child Alternately, you can enter your own integer values in one of the following formats (using * or n to represent no limit): <ul style="list-style-type: none">• x..y - A parent can have between x and y children. For example: 2..n – There must be at least 2 children.• x - A parent can have exactly x children. For example: 10 - There must be exactly 10 children.• x..y, a..b - A parent can have between x and y or between a and b children. For example: 1..2, 4..n – There must be one, two, four or more children.
Update/Delete constraint	Specifies how updating a key value in the parent table will affect the foreign key value in the child table. Depending on the implementation and DBMS, you can choose between: <ul style="list-style-type: none">• None - No effect on the child table.• Restrict - Values in the parent table cannot be updated or deleted if one or more matching child values exists.• Cascade - Updates or deletions of parent table values are cascaded to matching values in the child table.• Set null - Updates or deletions of parent table values set matching values in the child table to NULL.• Set default - Updates or deletions of parent table values set matching values in the child table to the default value.

Property	Description
Mandatory parent	Specifies that each foreign key value in the child table must have a corresponding key value, in the parent table.
Change parent allowed	Specifies that a foreign key value can change to select another value in the referenced key in the parent table.
Check on commit	[SQL Anywhere® only] Verifies referential integrity only on commit, instead of after row insertion. You can use this feature to control circular dependencies.
Cluster	Specifies that the reference constraint is a clustered constraint (for those DBMSs that support clustered indexes).

1.3.14.3 Automatic Reuse and Migration of Columns

When you create a reference, PowerDesigner can automatically reuse an appropriate existing column in the child table as the foreign key column and migrate the primary key column in the parent table to create a foreign key column in the child table.

Procedure

1. Select  **Tools**  to open the Model Options dialog box and select the *Reference* sub-category in the left-hand *Category* pane.
2. Select the following options as appropriate:











Option	Function
Auto-reuse columns	Enables the reuse of columns in a child table as foreign key columns when creating references if the following conditions are satisfied: <ul style="list-style-type: none"> ○ The child column has the same code as the migrating primary key column. ○ The child column is not already a foreign key column. If you want to reuse a child table column that is already a foreign key column, you must do this manually from the <i>Joins</i> tab of the reference property sheet. ○ Data types are compatible.

Option	Function
Auto-migrate columns	<p>Enables the automatic migration of primary key columns from the parent table as foreign key columns to the child table when creating references.</p> <p>i Note</p> <p>Foreign key columns created in this way will be deleted if the reference is deleted, while those created manually will be retained. To review which foreign key columns in a table were created through auto-migration, click the <i>Customize Columns and Filter</i> tool on the <i>Columns</i> tab and select to display the AutoMigrated property.</p> <p>Select the following column property checkboxes as appropriate to specify parent column properties to migrate:</p> <ul style="list-style-type: none"> ○ <i>Domains</i> (see Domains (CDM/LDM/PDM) [page 179]) ○ <i>Check</i> (see Setting Data Profiling Constraints [page 102]). ○ <i>Rules</i> (see Business Rules (CDM/LDM/PDM) [page 202]). ○ <i>Last position</i> - Adds migrated columns at the end of the table column list. If this option is not selected, migrated columns are inserted between key columns and other columns which implies that a child table must be dropped and recreated each time you add a reference and modify an existing database. <p>i Note</p> <p>During intermodel generation, whether or not this option is selected, any selected column property is migrated from the PK to the FK.</p>
Default link on creation	<p>Specifies whether reference joins are automatically created:</p> <ul style="list-style-type: none"> ○ <i>Primary key</i> – Automatically create joins between the parent table primary key and a child table foreign key. If the <i>Auto-migrate columns</i> option is not selected then you must manually specify foreign key columns on the reference <i>Joins</i> tab. ○ <i>User-defined</i> – Does not create joins. You must manually select columns on the reference <i>Joins</i> tab.

3. Click **OK** to close the dialog and return to your model.

Results

The following table shows the results of migrating and reusing primary key columns to a child table that contains a matching child table column, and where that child table column is already a foreign key column for another table:

Options Selected	Matching Child Table Column Exists	Matching Child Table Column Is Already a FK Column
[Original tables before migration]	The child table contains a matching column for one of the primary key columns: 	The child table contains a matching column that is already a foreign key column for another table: 
[default] Auto-reuse and Auto-migrate	Col_1 is reused and Col_2 is created: 	T1_Col_1 and Col_2 are created: 
Auto-migrate only	T1_Col_1 and Col_2 are created: 	T1_Col_1 and Col_2 are created: 
Auto-reuse only	Col_1 is reused but Col_2 is not created: 	No columns are reused or created: 
Neither	No column is reused or created 	No columns are reused or created: 

i Note

- By default, only the properties of the primary key column are migrated to the foreign key. If the primary key column is attached to a domain, the domain will not be migrated to the new foreign key column unless the *Enforce non-divergence* model option is selected (see [Controlling Non-Divergence from a Domain \[page 184\]](#)).
- If you have selected the *Auto-migrate columns* model option and you modify a reference attach point then you will migrate primary keys in the parent table to foreign keys in the child table, delete unused foreign key

columns, and modify the reference join. If you delete the parent primary key column then you will delete the corresponding foreign key and reference join.

For more information about other reference model options, see [Reference Model Options \[page 20\]](#).

1.3.14.4 Rebuilding References

You can rebuild references at any time to create default references between PK columns in one table and columns with identical code and data type in another table. Rebuilding is not possible between two tables with PK columns. Rebuilding references can be useful following the reverse engineering of a database in which not all the references could be reverse engineered.

Procedure

1. Select [Tools](#) [Rebuild Objects](#) [Rebuild References](#), and specify a mode.
 - Delete and Rebuild - All existing references are deleted, and new references built based on matching key columns.
 - Preserve - All existing references are kept, and new references are built based on new matching key columns.
2. [optional] Click the [Selection](#) tab to specify which tables you want to rebuild references for. By default, all tables are selected.

To rebuild references between tables in a package, select the package from the list at the top of the tab. To rebuild references between tables in a sub-package, select the [Include Sub-Packages](#) tool next to the list, and then select a sub-package from the dropdown list.
3. Click [OK](#). If you selected the Delete and Rebuild mode, a confirmation box asks you to confirm your choice. Click [Yes](#) to confirm the deletion and rebuild of the selected references.

1.3.14.5 Displaying Information on Reference Symbols

You can display the cardinality, referential integrity, join, table roles and other properties on the source and destination ends and in the center of a reference. To set display preferences for references, select [Tools](#) [Display Preferences](#), and select the Reference sub-category in the left-hand Category pane.


The notation for referential integrity and constraints on reference symbols is as follows:

Referential integrity	Constraint Types
<ul style="list-style-type: none"> upd(<constraint>) - Update del(<constraint>) - Delete cpa - Change Parent Allowed 	<ul style="list-style-type: none"> () - None (R) - Restrict (C) - Cascade (N) - Set null (D) - Set default

The *Cardinality* attribute displays the minimum and maximum number of instances in a child table that can appear for each corresponding instance in the parent table as follows:

<min> .. <max>

In this example, the source of the reference symbol shows a cardinality of **1..n** (one or more children is acceptable), and the child table role (**Does**) and the destination of the reference shows the parent table role (**Is Done By**). The center of the symbol shows the two primary keys that form the join, as well as the referential integrity (updates and deletions are restricted and change parent is allowed):




For information about changing the notation of references, see [Setting PDM Model Options \[page 18\]](#). For detailed information about working with display preferences, see *Core Features Guide > Modeling with PowerDesigner > Diagrams, Matrices, and Symbols > Display Preferences*.

1.3.15 View References (PDM)


A view reference is a link between a parent table or view and a child table or view, which defines the joins between the parent and child columns. View references are not generated to the database.

If you create a new view from existing views, the joins defined on these views influence the WHERE statement in the SQL query of the new view.

In this example, **French_Store** is a view of the **Store** table with a view reference defining a join between **Store_ID** in the table and **STORE_STORE_ID** in the view. **Customer_Orders** is a view of the **Orders** table with a view reference defining a join between **Order_No** in the table and **ORDER_ORDER_N** in the view:



You can create a view reference between the two views to define a join between `Customer_Order.ORDER_ORDER_STORE` and `French_Store.STORE_STORE_ID`:



If you were then to create a view from the **French_Store** and **Customer_Order** views, the **SELECT** order of the new view will take into account the join defined between the views to retrieve only those orders sent to French stores.

1.3.15.1 Creating a View Reference

You can create a view reference between two views or between a table and a view. A view reference cannot link two tables.

You can create a view reference in any of the following ways:

- Use the **Reference** tool in the Toolbox.
- Select **Model** to access the List of View References, and click the **Add a Row** tool.
- Right-click the model (or a package) in the Browser, and select **New** .

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.3.15.2 View Reference Properties

To view or edit a view reference's properties, double-click its diagram symbol or Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The **General** tab contains the following properties:

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the Code field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Parent/ Child	Specify the parent and child tables or views linked by the reference. Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object.
Parent role	Specify the roles of the parent and child tables or views in the reference.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

Joins Tab

The **Joins** tab lists the joins defined between parent and child table or views columns. You can specify column pairs on which to base the join using the following tools:

Tool	Description
	Reuse Columns - Create a join by matching parent and child columns that share the same code and data type.
	Insert/Add a Row - Inserts a row before the selected row in the list or at the end of the list to specify another column to join on.

1.3.16 Business Rules (CDM/LDM/PDM)

A business rule can represent a government-imposed law, a customer requirement, or an internal guideline. They may start as simple observations, such as "customers call toll-free numbers to place orders", and develop into more detailed expressions during the design process such as what information a customer supplies when placing an order or how much a customer can spend based on a credit limit.

Business rules complement your diagrams with information that is not easily represented graphically, and can help guide the creation of a model. For example, the rule "an employee belongs to only one division" can help you define the link between an employee and a division. Business rules are generated as part of intermodel generation and can be further specified in the generated model.

There are three ways to use business rules in a data model:

- Apply a business rule to a model object as part of its definition (see [Attaching a Business Rule to a Model Object \[page 204\]](#)).
- [PDM only] Create a server expression that can be generated to a database (see [Creating and Attaching a Constraint Rule \[page 204\]](#)).
- [PDM only] Insert a business rule expression in a trigger or stored procedure using the `.CLIENTEXPRESSION` or `.SERVEREXPRESSION` macros (see [Customizing and Extending PowerDesigner > DBMS Definition Files > PDM Variables and Macros](#)).

When creating business rules, you may find it helpful to ask the following kinds of question:

- Do any mandatory regulations impact my system?
- How can I clearly and concisely define the specifications for my project?
- Do any constraints limit my options?
- Is this rule a definition, fact, formula, or validation rule?

1.3.16.1 Creating a Business Rule

You can create a business rule from the Browser or **Model** menu, or from the **Rules** tab of an object property sheet.

- Select  **Model**  to access the List of Business Rules, and click the **Add a Row** tool.

- Right-click the model (or a package) in the Browser, and select **New** **Business Rule**.
- Open the property sheet of the object to which you want to apply the rule, click the **Rules** tab, and click the [Create an Object](#) tool.

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.3.16.2 Business Rule Properties

To view or edit a business rule's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The [General](#) tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the Code field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Type	Specifies the nature of the business rule. You can choose between: <ul style="list-style-type: none"> Constraint – a check constraint on a value. For example, "The start date should be inferior to the end date of a project." In a PDM, constraint rules attached to tables or columns are generated. If the DBMS supports multiple constraints, constraint rules are generated as separate constraint statements with the name of the rule. Definition – a property of the element in the system. For example; "A customer is a person identified by a name and an address". Fact – a certainty in the system. For example, "A client may place one or more orders". Formula – a calculation. For example, "The total order is the sum of all the order line costs". Requirement – a functional specification. For example, "The model is designed so that total losses do not exceed 10% of total sales". Validation – a constraint on a value. For example, "The sum of all orders for a client must not be greater than that client's allowance". In a PDM, validation rules attached to tables or columns are generated as part of the primary constraint for the table or column.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- [Expression](#) - As you develop your model and analyze your business problem, you can complete the rule by adding a technical expression. The syntax of expressions depends on the target database, and each rule can include two types of expression:

- *Server* - Can be generated to a database. You can generate server expressions as check parameters if they are attached to tables, domains, or columns
- *Client* - Used mainly for documentation purposes. However, you can insert both types of expression into a trigger or a stored procedure

1.3.16.3 Attaching a Business Rule to a Model Object

You can attach a business rule to a model object from the object's property sheet.

Procedure

1. Open the object's property sheet and click the *Rules* tab.
2. Click the *Add Objects* tool to open a list of available business rules.
3. Select one or more business rules and click *OK*.

The business rules are attached to the object and appear on the list of business rules for the object.

i Note

When you attach a business rule to an object, it is marked as used in the model. You can review which rules are used by opening the List of Business Rules and consulting the *U* (Used) column.

4. Click *OK* to return to the model diagram.

1.3.16.4 Creating and Attaching a Constraint Rule

Validate and constraint business rules have their expressions generated as constraints for DBMSs where this is supported. Validate rules can be reused by multiple objects, but constraint rules can only be used once, and will be generated as a separate constraint for DBMSs that support multiple constraints.

Context

Support for the generation of constraint rules to your database is controlled by the following items in the *General* category of your DBMS definition file:

- *EnableCheck* - Permits the generation of constraints to the database.
- *EnableMultiCheck* - Permits the generation of check parameters (see [Setting Data Profiling Constraints \[page 102\]](#)) and validation business rules as a single constraint, followed by the generation of each constraint business rule as a separate constraint in the order in which they are attached to the table. If this option is not enabled, then check parameters and all constraint and validation rules are concatenated into a single constraint expression.


- *UniqueConstName* - Requires that all validate and constraint rules have unique codes.

You can preview the constraints that will be generated on the *Preview* tab of the table property sheet.

When reverse engineering, the constraint order is respected, with the first constraint retrieved to the *Check* tab of the table property sheet, and each subsequent constraint retrieved as a constraint business rule attached to the table

Procedure

1. Create a business rule, enter a name and code, select *Constraint* in the *Type* list, and then click the *Expression* tab
2. Enter an expression on the *Server* sub-tab:



3. Click *OK* to save your changes and return to the model.
4. Open a table or column property sheet and click the *Rules* tab.
5. Click the *Add Objects* tool to open a list of available business rules, select your constraint business rule from the selection list and click *OK* to attach it.
6. [optional] Click *Apply* to confirm the attachment of the rule and then click the table property sheet *Preview* tab to verify that the constraint has been created in the script.

In the following example, multiple constraints are defined on the Project table:

- Check parameter (in the *Check* tab of the table) - Verifies that the customer number is different from the employee number.

- Validation business rules - **PROJ_NUM** to check that the column project number is not null and **EMP_NUM** to check that the employee number is not null.
- Constraint business rule - **DATE_CONSTY** to check that the start date of the project is inferior to the end date of the project.

The screenshot shows the SAP Studio interface with the title "Table Properties - Project (PROJECT)". The "Script" tab is selected, displaying the following SQL code:

```

/*
 * Table : PROJECT
 */

create table PROJ.PROJECT (
    PRONUM          ID,
    CUSNUM          ID,
    EMPNUM          ID,
    ACTBEG          DATE,
    ACTEND          DATE,
    PRONAME         NAME,
    PROLABEL        SHORT_TEXT,
    constraint PK_PROJECT primary key (PRONUM),
    constraint FK_PROJECT_SUBCONTRA_CUSTOMER foreign key (CUSNUM)
        references PROJ.CUSTOMER (CUSNUM),
    constraint FK_PROJECT_IS_RESPON_EMPLOYEE foreign key (EMPNUM)
        references PROJ.EMPLOYEE (EMPNUM),
    constraint CKT_PROJECT check ((PROJ_NUM>1) and (EMP_NUM>1)),
    constraint DATE_CONSTY check (ACTBEG is null or ACTEND is null or ACTBEG <= ACTEND)
)

```

1.3.17 Lifecycles (PDM)

A lifecycle allows you to model the movement of data from expensive, rapid storage, through various forms of cheaper slower storage as the data ages and access requirements diminish. The period during which data remain in each kind of storage are modeled as phases, which are associated with tablespaces.

i Note

Data lifecycle modeling is supported for SAP® IQ v15.0 and higher.


You can attach any number of tables to a lifecycle, and create multiple lifecycles to provide different speeds and/or methods for data aging. Each table can only be associated with one lifecycle. A lifecycle can be:

- **Age-based** - Data moves through the lifecycle in named partitions, remaining in each phase only for the specified retention period. The partitions move through the lifecycle in a predictable fashion and will become candidates for purging at the end of the lifecycle's total retention period.
- **Access-based** - Tables (and any associated indexes) move through the lifecycle based on the permitted idle time for each phase, which specifies how long a table can remain in the phase without being accessed. Tables must remain in the lifecycle for (as a minimum) the total retention period, and their movement to the end of the lifecycle can be delayed indefinitely if the data they contain continue to be accessed.

The following diagram illustrates an age-based lifecycle covering a period of five years, which is divided into three phases:

- Phase 1 (3 months) - high performance (tier-1) storage for new data that is frequently accessed.
- Phase 2 (9 months) - nearline (tier-2) storage for data from the last year.
- Phase 3 (48 months) - historical (tier-3) storage for data that is infrequently accessed but which must be retained.

The data is packaged in partitions (P1, P2, and P3), which each contain one month of data:



PowerDesigner can generate all the necessary scripts to automate all this data movement. In the example above, scripts will be generated for every month of the lifecycle. At the point illustrated in the picture, the scripts will:

- Move partition P1 from the tablespace associated with Phase 1 to the tablespace associated with Phase 2.
- Create a new partition, P4, to begin collecting new table rows in the tablespace associated with Phase 1.

As the data ages, scripts will additionally treat the movement of data aged more than one year from the tablespace associated with Phase 2 to the tablespace associated with Phase 3.

Once a lifecycle is put in place, you can generate scripts to perform data movement indefinitely. Additional scripts are generated to regularly purge data that arrive at the end of their lifecycle.

1.3.17.1 Modeling a Lifecycle

To correctly model a lifecycle you must define the lifecycle and its phases, and then associate your tables to it.

Procedure

1. Create a lifecycle in any of the following ways:
 - Select **Model > Lifecycles** (or **Database > Information Lifecycle Management > List of Lifecycles**) to access the List of Lifecycles, and click the **Add a Row** tool.
 - Right-click the model in the Browser, and select **New > Lifecycle**. Note that lifecycles can only be created at the model level and not within packages.
2. Click the **Properties** tool to open the lifecycle property sheet and specify a name for the lifecycle.
3. Click the **Detail** tab, and select the policy type:
 - **Age-based** - Data moves through the lifecycle in named partitions, based on the time since the data was created. Specify a **Start date** and the **Total retention** period (the length of time covered by the lifecycle).

- **Access-based** - Tables move through the lifecycle based on the time since the table was last accessed. Specify a *Total retention* period, which is treated as the minimum total period of time that a table's data must remain in the lifecycle.
4. Click the *Create Phase* tool to create as many phases as you need. Lifecycles often contain three phases to manage the movement of data from high performance, through nearline, to historical storage.

i Note

Your phase will display a yellow warning overlay until it is completely defined.

5. Click on each phase in turn to open its property sheet (see [Phases \(PDM\) \[page 212\]](#)). Specify a name, retention period (or, for access-based lifecycles, idle period) and tablespace to represent the physical storage in which the data is stored during this phase.

For age-based lifecycles, you can assign data from an external database to the first phase of your lifecycle and have that data loaded to your warehouse database for the second phase (see [Linking an External Database via the Data Source Wizard \[page 215\]](#)).

6. Open the property sheet for each of your tablespaces (see [Tablespace and Storage Properties \[page 217\]](#)) and enter any appropriate properties, including a value for the cost per GB to be used when calculating cost savings.

When you have completed the definition of your phases and tablespaces, return to the lifecycle property sheet and verify that the warning overlays on the phase buttons are no longer present.

7. [age-based lifecycles] Enter a partition range to specify the length of time covered by each table partition governed by the lifecycle. For example, a partition range of one month means that each partition will contain one month's data.
8. In the *Managed tables* groupbox, select the tables you want to associate with the lifecycle. For each table, specify the start date on which you want it to become subject to the lifecycle, and enter an estimate for the initial number of rows and a percentage growth rate to permit the calculation of cost savings.
9. [age-based lifecycles] You must, for each table, specify a column with a date datatype as the partition key used to determine to which partition a row must be assigned. The partition key can alternately be assigned on the *SAP IQ* tab of the table property sheets.
10. [optional] Select the *Cost savings analysis* checkbox and then click the *Refresh Cost Savings Analysis* tool to display a summary of the cost savings to be obtained by managing your data with the lifecycle.

You can also view the detail of the cost savings by year for a single table on the *Lifecycle* tab of the table property sheet (see [Table Properties \[page 84\]](#)).

i Note

If you intend to model multiple lifecycles, and/or want to confirm that all of your tables are associated with a lifecycle, you may find it useful to visualize these associations in the form of a dependency matrix. To view the Lifecycle/Table Matrix, select ► *Database* ► *Information Lifecycle Management* ► *View Lifecycle/Table Matrix* ▶.

1.3.17.1.1 Generating Data Archiving Scripts to Implement your Lifecycle

Once you have modeled your lifecycles, you can instruct PowerDesigner to generate scripts to automate the creation, movement, and purging of data through your lifecycle phases.

Context

Before you generate your data movement scripts, ensure that you have completed all the steps listed in [Modeling a Lifecycle \[page 207\]](#).

Procedure

1. Select to open the Generate dialog.
2. Specify a directory in which to generate the scripts, and, optionally, select to check your model before generation.
3. Click the *Selection* tab, and select the tables for which you want to generate data archiving scripts.
4. [for age-based lifecycles] Click the *Options* tab, specify the start and end date for the period for which you want to generate scripts. You can generate scripts for all or part of the period covered by your lifecycle, and also to cleanup data created before the start date of your lifecycle.

Note

For age-based lifecycles used to archive data from an external database, if you specify a generation start date before the start date of a table associated with the lifecycle, additional scripts will be generated to advance immediately older data created between the generation start date and the table lifecycle start date to the appropriate stages of the lifecycle.

5. [for age-based lifecycles] On the *Options* tab, specify the method for creating partitions. You can choose between creating partitions:
 - Individually, when the previous partition ends
 - All at the beginning (default)
6. Click *OK* to begin the generation.

The scripts are generated in the specified directory and listed in the *Results* pane.

The following scripts are generated for age-based lifecycles, and should be run on the date specified in the order specified by their numerical prefix. You can run the scripts manually or use SAP Control Center to automate this process:

- `IQ.CreateRemoteServerAndLogin.date.sql` - if you are archiving data stored in an external database.
- One or more folders named `yyyymmdd` for each date on which scripts must be run containing one or more of the following scripts:

- 01.IQ.CreateAndMovePartition.date.sql - one script per date on which a data movement action is required between the start and end dates you specify. For example, if you specify a start date of 01/01/2009 and an end date of 12/31/2009, a partition range of one month, and to create the partitions individually, then twelve scripts will be generated. The scripts should be run on the dates included in their filenames.
- 02.IQ.PurgePartition.date.sql - one script per date on which a data purge action is required for partitions arriving at the end of the lifecycle.
- 03.DB.DeleteSourceData.date.sql - if there is data to be purged in an external database.
- OldData - if you have specified a generation start date earlier than your table start dates, this folder will be created and will contain dated subfolders containing scripts to create, move, and purge older data.

The following scripts are generated for access-based lifecycles:

- CreateProcedures.sql - creates procedures to test the idle time during which tables have not been accessed and to move and/or delete them on demand. This script should be run immediately to prepare the database for data movements called for by an access-based lifecycle
- MoveData.sql - calls the procedures to test for and implement data movement based upon the specified idle times using the current date on the IQ server. This script should be scheduled to run regularly.
- DeleteData.sql - calls the procedure to test for and implement data purging based upon the specified idle times and the specified minimum retention period using the current date on the IQ server. You can schedule this script to run regularly or run it by hand as needed.

1.3.17.2 Lifecycle Properties

To view or edit a lifecycle's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

Detail Tab

This tab contains all the properties necessary to define your lifecycle. The *Policy* group box contains the following properties:

Property	Description
Policy type	Specifies the criteria used to advance data through the lifecycle. You can choose between: <ul style="list-style-type: none">• Age-based - where data are moved from phase to phase in named partitions depending on the time since their creation.• Access-base - where tables are moved from phase to phase depending on the time since the data in the tables were last accessed.
Start date	[age-based lifecycles only] Specifies the date from which you want the lifecycle to manage data movement.
Total retention	Specifies the total length of time during which data is controlled by the lifecycle. For example, if you specify a total retention of 5 years, the lifecycle will manage the movement of each record from the moment of its creation until it has existed for 5 years. For age-based lifecycles, the total retention time must be equal to the sum of all the retention times of all the phases contained within the lifecycle. For access-based lifecycles, the total retention time is used as the minimum total time that the data must remain in the lifecycle.
Phases	Lists the phases (see Phases (PDM) [page 212]) associated with the lifecycle. You can create phases using the Create a New Phase tool. Click on a phase to open its property sheet. i Note Your phase will display a yellow warning overlay until it is completely defined.
Partition range	[age-based lifecycles only] Specifies the period of data to be contained in partitions for tables governed by the lifecycle. For example, a partition range of one month means that each partition will contain one month's data.

The *Managed Tables* group box lists the tables whose data are managed by the lifecycle. Use the [Add Objects](#) and [Create an Object](#) tools to populate the list. If the lifecycle is used to archive data in an external database, the choice of tables to attach is limited to the tables in the external database, and the selected tables are generated to the warehouse PDM if they were not already present.

The following properties must be completed for each table in order to correctly generate data archiving scripts:

- *Name* and *Code* - to identify the table.
- *Start Date* - [optional] Specifies the start date from which to generate the first partition.
- *Initial Rows* and *Growth Rate* - Specifies the number of rows that the table will start with, and the percentage growth per year
- *Partition Key* - [age-based lifecycles] Specifies the column to use to determine to which partition a row is assigned.

Click the *Generate Data Archiving Script* button to generate scripts to implement your lifecycle (see [Generating Data Archiving Scripts to Implement your Lifecycle \[page 209\]](#)).

Select the *Cost Saving Analysis* checkbox and then click the *Refresh Cost Savings Analysis* tool to display a list of the cost savings to be obtained by managing data with the lifecycle. Use the tools above the list to export the cost savings data to Excel or to print it.

1.3.17.3 Phases (PDM)

A phase defines the period of time that data governed by a lifecycle will be retained by a particular tablespace.

Creating a Phase

You create phases on the *Detail* tab of a lifecycle using the *Create Phase* tool.

Phase Properties

To view or edit a phase's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator. The *General* tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Retention/Time unit	[age-based] Specifies the length of time that data will be retained in this phase.
Idle period/ Time unit	[access-based] Specifies the minimum length of time that the table must remain unaccessed before it is moved to the next phase.
Source	Specifies where the data to populate the phase is located. The default is the current (warehouse) database. For the first phase only in an age-based lifecycle, you can specify instead an external database (see Archiving Data From External Databases [page 213]), in which case you must also specify a data source to link to the PDM that models the external database.
Tablespace	[Current database only] Specifies the tablespace with which the phase is associated. Select a tablespace from the list or click the tools to the right of this field to create a new tablespace or open the property sheet of the currently selected one.

Property	Description
Data Source	[External database only] Specifies the data source used to connect to the external database. Click the <i>Create</i> tool to the right of this field to launch the Data Source Wizard (see Linking an External Database via the Data Source Wizard [page 215]) to create a data source and apply the appropriate tables to the lifecycle.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

1.3.17.4 Archiving Data From External Databases

When developing an age-based lifecycle policy, you can assign data from an external database modeled in another PDM to the first phase. At the end of the first phase the data will be loaded from the external database to your warehouse.

In order to model external database data archiving, you must:

1. Create a PDM to model the external database.
2. Create a PDM to model the data warehouse.
3. Link the second PDM to the first through a data source.
4. Specify access parameters for the warehouse database and the external database on the *Database Connection* and *Data Movement (Lifecycle)* tabs of the data source.
5. Create mappings between the external tables that contain the data to be archived and the warehouse tables to which this data will be loaded.
6. Create a lifecycle in the warehouse PDM and create the first phase.
7. Set the *Source* of the first phase to *External Database* and specify the data source through which you have connected the external database PDM.
8. Select the tables to attach to the lifecycle.

PowerDesigner provides various tools to help you create parts of this archiving environment:

- PDM-PDM model generation - can create the data warehouse PDM, the data source and mappings (see [Linking an External Database by Generation \[page 214\]](#))
- The Mapping Editor - can help you create (or modify) the mappings between the external database and warehouse PDM tables (see [Linking an External Database through the Mapping Editor \[page 214\]](#))
- The Data Source Wizard - can create the data source and table mapping, set the lifecycle source for the first phase and attach tables to the lifecycle (see [Linking an External Database via the Data Source Wizard \[page 215\]](#))

1.3.17.4.1 Linking an External Database by Generation

You can use the model generation mechanism to generate tables from your external database to your warehouse PDM and create the required data source and mappings in your warehouse PDM.

Procedure

1. Create a PDM to model the external database containing the tables to be archived by the lifecycle.
2. Select **Tools** ➤ **Generate Physical Data Model** to open the PDM Generation Options dialog.
3. On the *General* tab, choose whether you will create a new PDM to represent your warehouse database or add the tables to be generated to an existing warehouse PDM.
4. On the *Detail* tab, ensure that the *Generate mappings* option is selected.

These mappings are used in the subsequent generation of the lifecycle to route the data to be archived in the warehouse.

5. On the *Selection* tab, select the tables that contain the data you want to archive via the lifecycle.
6. Click **OK** to begin the generation.

If you are adding the tables to an existing warehouse PDM, the Merge Models dialog will open, allowing you to review the changes that will be made to it before clicking OK to continue with the generation.

The selected tables are generated to the warehouse PDM, along with a data source object and the appropriate mappings.

Note

For detailed information about model generation, see [Generating Other Models from a Data Model \[page 337\]](#). For information about using the Merge Models dialog, see *Core Features Guide > Linking and Synchronizing Models > Generating Models and Model Objects*.

1.3.17.4.2 Linking an External Database through the Mapping Editor

You can use the Mapping Editor to manually create (or modify) mappings between the external database and warehouse tables that will be used to archive the data governed by the lifecycle. This method can be useful when

you have PDMs to represent your external and warehouse databases and will be using non-standard mappings to load your data.

Context

To open the Mapping Editor from your warehouse PDM, select **Tools** **Mapping Editor**. If you have no data sources defined in the model, the Data Source Wizard will open, and you should use it to define a data source pointing to the external database PDM, which will then be opened in the Mapping Editor.

Note

For detailed information about using the Mapping Editor (and the Data Source Wizard) see *Core Features Guide > Linking and Synchronizing Models > Object Mappings*.

1.3.17.4.3 Linking an External Database via the Data Source Wizard

The Data Source Wizard guides you through creating an external database data source in your model, and to attach it and the tables to be managed to the first phase of your lifecycle

Procedure

1. Create an age-based lifecycle policy (see [Modeling a Lifecycle \[page 207\]](#)), add a first phase to it, and open the property sheet for this phase.
2. Set the retention period for the phase and set the *Location* property to *External database*.
3. Click the *Create* tool to the right of the data source field to open the Data Source Creation Wizard.
4. On the first page, select the PDM that represents your external database and then click *Next*.
5. On the second page, select the tables that you want to associate with the lifecycle.
6. Click *Finish* to associate the selected tables with the lifecycle.

The wizard creates a data source in the warehouse PDM and associates it with the first phase of the lifecycle. The selected tables are generated to the warehouse PDM if they were not already present, and appropriate mappings are created between the tables in the external database and those in the warehouse PDM.

1.3.18 Tablespaces and Storages (PDM)

Tablespaces and storages are generic objects used to represent physical locations (in named partitions) of tables and indexes in a database or storage device. A tablespace is a partition in a database. A storage is a partition on a storage device. Some DBMSs, allow a tablespace to use a specified storage in its definition.

The following table lists the DBMSs that use concepts that are represented by tablespaces and storages in PowerDesigner:

DBMS	Tablespace represents...	Storage represents...
ADABAS	NA	NA
IBM DB2 UDB Common Server	tablespace	buffer pool
	create tablespace	create bufferpool
IBM DB2 UDB for OS/390	table space	storage group
	create tablespace	create stogroup
Informix	NA	NA
Ingres	NA	NA
InterBase	NA	NA
Microsoft Access	NA	NA
Microsoft SQL Server	NA	filegroup alter database add filegroup...
MySQL	NA	NA
Oracle	tablespace	storage structure (not physical storage)
	create tablespace	
PostgreSQL	NA	NA
SAP® SQL Anywhere®	database space	NA
SAP® Adaptive Server® Enterprise	create dbspace	
	NA	segment sp-addsegment

DBMS	Tablespace represents...	Storage represents...
SAP® IQ	database space <code>create dbspace</code>	NA
Teradata	NA	NA

i Note

When tablespace or storage options are not applicable for a DBMS, the corresponding model menu item is not available.

1.3.18.1 Creating a Tablespace or Storage

You can create a tablespace or storage from the Browser or *Model* menu.

- Select ► *Model* ► *Tablespaces* (or ► *Storage*) to access the appropriate list, and click the *Add a Row* tool
- Right-click the model (or a package) in the Browser, and select ► *New* ► *Tablespace* (or ► *Storage*)

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.3.18.2 Tablespace and Storage Properties

To view or edit a tablespace or storage's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

Cost tab

The *Cost* tab is available if data lifecycle modeling (see [Lifecycles \(PDM\) \[page 206\]](#)) is supported by your DBMS.

Property	Description
Cost (per GB)	Specifies the cost per GB of the storage represented by the tablespace
Currency	Displays the currency to use for the cost per GB of storage. You can change the currency by selecting and choosing a currency from the list on the Model Settings page.

Other tabs

The following tabs are also available:

- *Physical Options* - lists all the physical options that can be applied to the tablespace or storage (see [Physical Options \(PDM\) \[page 96\]](#)).
- *Physical Options (Common)* - lists the most commonly used physical options that can be applied to the tablespace or storage.


Note

For detailed information about tablespace and storage options for a particular DBMS, see its reference manual.

1.3.19 Web Services (PDM)

Web services are applications stored on web servers that are accessed through standard web protocols (HTTP, SOAP) and data formats (HTML, XML...), whatever the systems and programming languages. PowerDesigner supports modeling for both the SOAP protocol, in which queries are encapsulated into services, and HTTP, where operations are invoked directly.

If you use web services to query databases, you no longer need database drivers. The following example shows the result of an HTTP request for a database web service:



/Customers>List

Customer custid	Customer custname	Customer custaddr
1	Finley	Chicago
2	Takashi	Tokyo
3	Smith	London
4	Dupont	Paris

AdaptiveServerAnywhere/9.0.0.1108

Web services comprise a set of operations, each of which contains a SQL query for retrieving data from a database. Web parameters are the parameters which appear in the SQL statements, and result columns display the results. These objects have no symbols, and appear only in the Browser. Web services can be modeled for the following DBMSs:

- SAP® SQL Anywhere® v9 and over.
- SAP® Adaptive Server® Enterprise v15 and over.
- SAP® IQ v12.6 and over.
- IBM DB2 v8.1 and over - Document Access Definition Extension (DADX) files specify Web services through a set of operations defined by SQL statements or Document Access Definition (DAD) files, which specify the mapping between XML elements and DB2 tables (see [Generating Web Services for IBM DB2 \[page 227\]](#) and [XML Architecture > Working with XML and Databases > Generating a DAD File for IBM DB2](#)).

You can test a Web service of type DISH or SOAP from within your model by right-clicking its Browser entry and selecting [Show WSDL](#). You can test a web service operation belonging to a Web service of another type by right-clicking the operation and selecting [Test Web Service Operation](#). Review the generated URL and then click [OK](#) to display the WSDL file (for SOAP) or results (for RAW) in your Web browser.

You can import a Web service as a service provider into a Business Process Model (BPM) to define the links between a concrete implementation of service interfaces and operations and their abstract definition (see [Business Process Architecture > Service Oriented Architecture \(SOA\) > Service Providers \(BPM\)](#)).

1.3.19.1 Creating a Web Service

You can create a web service from the Browser or *Model* menu.

- Select ► *Model* ► *Web Services* ▾ to access the List of Web Services, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select ► *New* ▶ *Web Service* ▾.

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.3.19.2 Web Service Properties

To view or edit a web service's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/Comment	<p>Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.</p> <p>In URLs, the name of the web service is used to access the web service, and should not start with a slash nor contain two consecutive slashes.</p>
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Local path	Specifies the name prefixing the web service, which is by default, the name of the web service. When several web services concern the same table, their local path usually starts with the name of the table, followed by a slash and a specific name identifying the query (e.g. Customer/List, Customer/Name). PowerDesigner treats HTTP web operations which share a local path as belonging to the web service with that local path name. If you enter a path, the <i>User-Defined</i> tool is depressed. Click the tool to release it and recover the original path.

Property	Description
Service type	[ASA, ASE, and IQ only] Specifies the type of web service. A web service invoked via an HTTP request can have a RAW, HTML or XML type. A web service invoked in a SOAP request can have a SOAP or a DISH type: <ul style="list-style-type: none"> DISH - [ASA and IQ only] acts as a proxy for a group of SOAP services and generates a WSDL (Web Services Description Language) file for each of its SOAP services. When you create a DISH service, you must specify a Name prefix on the Sybase tab (see SAP SQL Anywhere [page 603]) for all the SOAP services to which the DISH service applies. PowerDesigner treats SOAP web services as Web operations (see Web Operations (PDM) [page 222]) of DISH web services. HTML – [ASA and IQ only] the result of the SQL statement or procedure is formatted as an HTML document (with a table containing rows and columns). RAW - the result of the SQL statement or procedure is sent without any additional formatting. SOAP - [ASE only] generates a WSDL file. XML - the result of the SQL statement or procedure is sent in XML. By default, the result is converted into XML RAW format.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

Security Tab

This tab is available for ASA/SQL Anywhere and IQ only, and displays the following properties:

Property	Description
Secured connection	If selected, only HTTPS connections are accepted. If cleared, both HTTP and HTTPS connections are accepted
Required authorization	If selected, all users must provide a name and a password. When cleared, a single user must be identified
Connection User	When authorization is required, you can select <None> or a list of user names. When authorization is not required, you must select a user name. Default value is <None>, which means all users are granted access

The following tabs are also available:

- Operations - Lists the Web operations associated with the Web service (see [Web Operations \(PDM\) \[page 222\]](#)).
- Sybase - [ASA/SQL Anywhere, ASE, and IQ] Includes DBMS-specific properties (see [SAP SQL Anywhere \[page 603\]](#))
- Namespaces - [IBM DB2] Lists the namespaces associated with the Web service, including their prefix, URI and a comment. An XML Schema can be specified where elements and data types used in web parameters and result columns are defined.

1.3.19.3 Web Operations (PDM)

A web operation allows you to define the SQL statement of a web service and to display its parameters and result columns.

Creating a Web Operation

You can create a Web operation in the following ways:

- Open the *Operations* tab in the property sheet of a web service, and click the *Add a Row* tool.
- Right-click a web service in the Browser, and select ► *New* ► *Web Operation* ▾.

Web Operation Properties


To view or edit a web operation's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator. The *General* tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field. In URLs, the name of the web operation comes after the name of the web service followed by a slash, and should not start with a slash nor contain two consecutive slashes.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Web Service	Code of the web service containing the web operation. Click the <i>Properties</i> tool to open the web service property sheet
Owner	[ASE 15 only] Specifies the owner of the operation.

Property	Description
Operation Type	[IBM DB2 only] Specifies the type of operation. You can choose from the following: <ul style="list-style-type: none"> call - invokes a stored procedure with parameters and result columns for the web operation query - retrieves relational data using the SQL select statement in the <i>Implementation</i> tab retrieveXML - retrieves an XML document from relational data. The mapping of relational data to XML data is defined by a DAD file with SQL or RDB as MappingType storeXML - stores an XML document as relational data. The mapping of XML data to relational data is defined by a DAD file, with RDB as MappingType update - executes the SQL update statement with optional parameters. Parameters can be created from the <i>Parameters</i> tab in the web operation property sheet
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- Implementation* - Contains the SQL statement of the Web operation to select which data you want to retrieve from the database. For DISH web services, SQL statements are defined in the SOAP web services bearing their prefix name. For information about the tools on this tab, see [Writing SQL Code in PowerDesigner \[page 288\]](#).



- Security* - [SQL Anywhere/IQ] Displays the following properties:

Property	Description
Secured connection	Requires an HTTPS connection.
Required authorization	Requires users to provide a name and a password.
Connection User	When authorization is required, you can select the default <None> (all users are granted access), or a list of user names. When authorization is not required, you must select a user name.

- **Parameters** - Lists the parameters associated with the Web operation, which are part of the SQL statement defined on the *Implementation* tab (see [Web Parameters \(PDM\) \[page 224\]](#)).
- **Result Columns** - Lists the result columns associated with the Web operation (see [Web Result Columns \(PDM\) \[page 225\]](#)).
- **Sybase** - [ASE] Displays ASE-specific options (see [SAP Adaptive Server Enterprise \[page 564\]](#)).

1.3.19.4 Web Parameters (PDM)

Web parameters are part of the SQL statement defined in the *Implementation* tab of a web operation property sheet, and are listed on its *Parameters* tab.

Creating a Web Parameter

You can create a Web parameter in the following ways:

- Open the *Parameters* tab in the property sheet of a Web operation, and click the *Add a Row* tool. Alternatively, use the *Add Parameters from SQL Implementation* tool (ASA, ASE, and IQ only) to display the parameters resulting from the reverse engineering of the web service.
- Right-click a web operation in the Browser, and select *New* *Web Parameter*.

Web Parameter Properties

To view or edit a web parameter's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator. The *General* tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Web operation	Name of the web operation containing the web parameter.
Parameter type	Select in if you want the web parameter to be an input parameter. Select in/out if you want the web parameter to be both an input and output parameter. Select out if you want the web parameter to be an output parameter.
Default value	[ASE only] Specifies a default value for the parameter.
Data type	[For IBM DB2] Select an XML schema data type from the list, or click the Select Object tool to open a selection dialog box where you select a global element in an XML model open in the workspace. [For ASE] Select a datatype from the list.
Is element	[IBM DB2 only] Checked and greyed when a global element is attached to a web parameter.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

1.3.19.5 Web Result Columns (PDM)

Result columns are part of the SQL statement defined in the *Implementation* tab of a web operation property sheet, and are listed on its *Result Columns* tab. They belong to a table in the target database.

Creating a Web Result Column

You can create a Web result column in the following ways:

- Open the *Result Columns* tab in the property sheet of a Web operation, and click the *Add a Row* tool. Alternatively, use the *Add Result Columns from Executing SQL Statement* tool to display the result columns resulting from the execution of the SQL statement in the database.
- Right-click a web operation in the Browser, and select ► *New* ► *Result Column* ▾.

Web Result Column Properties

To view or edit a result column's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator. The *General* tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Data Type	[IBM DB2] Select an XML schema data type from the list, or click the <i>Select Object</i> tool to select a global element in an XML model open in the workspace.
Is element	[IBM DB2] Checked and greyed when a global element is attached to a result column.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

1.3.19.6 Generating Web Services for SQL Anywhere, ASE, and IQ

You can generate database web services to a script or to a live database connection.

Procedure

1. Select **Database** **Generate Database** to open the Database Generation dialog, and specify the standard options, including whether you want to generate to a script or to a live database connection (see [Generating a Database from a PDM \[page 298\]](#)).
2. [optional] Click the *Options* tab and click *Web Service* in the left-hand pane to display the web service generation options. Change the default options as appropriate.
3. [optional] Click the *Selection* tab and select the *Web Services* subtab at the bottom of the tab. Select the web services that you want to generate.
4. Click *OK* to begin the generation.

Note

For web services generated to a live database connection, you may have to refresh the Web Services folder before they appear.

1.3.19.7 Generating Web Services for IBM DB2


For IBM DB2 Web services, PowerDesigner can generate Document Access Definition Extension (DADX) files.

Context


To enable the DADX generation extensions in your model, select **Model > Extensions**, click the *Attach an Extension* tool, select the DADX file (on the *General Purpose* tab), and click **OK** to attach it.

Procedure

1. Select **Tools > Extended Generation** to open the Generation dialog with DADX selected in the *Targets* tab.




2. Click the *Select a Path* tool to the right of the *Directory* field, and specify a path for the DADX files.
3. Click the *Selection* tab, and select the web services for which you want to generate a DADX file.



4. Click **OK** to begin generation.

When generation is complete, the Result dialog displays the paths of the DADX files.



5. [optional] Select the path of a DADX file and click **Edit** to display the DADX file in the editor window.

```

<?xml version="1.0" encoding="UTF-8"?>
<DADX
>

    <result_set_metadata name="CUSTOMER" rowName="CUSTOMER">
        <column name="custid" type="" />
        <column name="custname" type="" />
        <column name="custaddr" type="" />
    </result_set_metadata>

    <operation name="CUSTOMER">
        <call>
            <SQL_call>
                select * from Customer where custid=:CustomerID
            </SQL_call>
            <parameter name="CUSTOMERID" kind="in"/>
            <result_set name="rs_CUSTID" metadata="CUSTOMER"/>
            <result_set name="rs_CUSTNAME" metadata="CUSTOMER"/>
            <result_set name="rs_CUSTADDR" metadata="CUSTOMER"/>
        </call>
    </operation>

    <operation name="LIST">
        <query>
            <SQL_query>
                select * from Customer
            </SQL_query>
            <XML_result name="CUSTID"/>
            <XML_result name="CUSTNAME"/>
            <XML_result name="CUSTADDR"/>
        </query>
    </operation>

    <operation name="NAME">
        <query>
            <SQL_query>
                select * from Customer where custname=:CustomerName
            </SQL_query>
            <XML_result name="CUSTID"/>
            <XML_result name="CUSTNAME"/>
            <XML_result name="CUSTADDR"/>
            <parameter name="CUSTOMERNAME" kind="in"/>
        </query>
    </operation>
</DADX>

```

6. Click **Close** in the Result dialog box.

You can now use the DADX files for SOAP requests in IBM DB2 UDB web services Object Runtime Framework (WORF).

1.3.19.8 Reverse Engineering Web Services

You can reverse engineer Web services from a SQL Anywhere, ASE, and IQ database to a PDM. You can reverse engineer web services into a new or existing PDM from a script or live database connection via the Database Reverse Engineering dialog box.

For general information about database reverse engineering, see [Reverse Engineering a Database into a PDM \[page 323\]](#). The following list shows how Web service objects in these databases are treated in PowerDesigner:

- Database HTTP web services with a common local path are grouped as PowerDesigner web operations of an HTTP web service with the specified local path:

Software	Web service name	Type	Web operation name
Database	Customers/Name	HTML	—
PowerDesigner	Customers	HTML	Name

- Database HTTP web services without a common local path are grouped as PowerDesigner web operations of an HTTP web service named raw, xml or html:

Software	Web service name	Type	Web operation name
Database	Customers	HTML	—
PowerDesigner	html	HTML	Customers

- Database SOAP web services with a prefix name are considered as PowerDesigner web operations of a DISH web service with the prefix name:

Software	Web service name	Type	Web operation name
Database	DishPrefix/Name	SOAP	—
PowerDesigner	Customers (with DishPrefix as prefix)	DISH	Name

- Database SOAP web services without a prefix name are considered as PowerDesigner web operations of a DISH web service without a prefix name:


Software	Web service name	Type	Web operation name
Database	Customers	SOAP	—
PowerDesigner	WEBSERVICE_1	DISH	Customers

- Database DISH web services with or without a prefix name are considered identically in PowerDesigner:

Software	Web service name	Type	Web operation name
Database	Customers	DISH	—
PowerDesigner	Customers (with or without DishPrefix as prefix)	DISH	—

1.4 Multidimensional Diagrams

A multidimensional data diagram provides a graphical view of your datamart or data warehouse database, and helps you identify the facts and dimensions that will be used to build its cubes.




Note

Multi-dimensional diagrams are generally generated from a physical diagram (see [Generating Cubes \[page 233\]](#)). To manually create a multidimensional diagram in an existing PDM, right-click the model in the Browser and select **New > Multidimensional Diagram**. To create a new model, select **File > New Model**, choose Physical Data Model as the model type and **Multidimensional Diagram** as the first diagram, and then click **OK**.

Numeric values or measures such as sales total, budget, and cost, are the facts of the business, while the areas covered by the business, in terms of geography, time, people and products, are the dimensions of the business. A multidimensional diagram shows the facts, surrounded by their dimensions, which will be used to populate cubes.

for enterprise information management, query and analysis tool and enterprise reporting. In the following example, the Sales fact is surrounded by the Product, Time, Customer, and Store dimensions to allow sales data to be analyzed by any of these criteria:



PowerDesigner maps facts and dimensions to their original operational database tables to enable population of the cubes (see [Operational to Warehouse Data Mappings \[page 243\]](#)).

The following objects can be created in a multidimensional diagram:

Tool	Description
	Fact - A group of measures related to aspects of the business and used to carry out a decision support investigation. See Facts (PDM) [page 235] .
	Dimension - An axis of investigation of a cube (time, product, geography). See Dimensions (PDM) [page 238] .
[none]	Attribute - Used to qualify a dimension. For example, attribute Year qualifies the Date dimension. See Fact and Dimension Attributes (PDM) [page 239] .
[none]	Measure - A variable linked to a fact, used as the focus of a decision support investigation. See Measures (PDM) [page 236] .
[none]	Hierarchy - An organizational structure that describes a traversal pattern through a dimension. See Hierarchies (PDM) [page 241] .
	Association - A link that relates a fact to a dimension. See Associations (PDM) [page 242] .

1.4.1 Identifying Fact and Dimension Tables

When designing a data warehouse, you will need to identify which of your tables and views represent facts (containing numerical values such as sales, revenue, or budget figures), and which dimensions (providing ways of

aggregating these figures, such as by region, date, customer, or product). PowerDesigner can retrieve the multidimensional type of a table by analyzing the references attached to it, where child tables or views are identified as candidate facts and parent tables or views are identified as candidate dimensions.

Procedure

1. Select **Tools** **Multidimension** **RetrieveMultidimensional Objects** to open the Multidimensional Objects Retrieval Wizard.
2. Specify the objects to be retrieved. By default both Facts and Dimensions will be retrieved.

Note

If you are working with SAP® IQ v12.0 or higher, you can also select to automatically rebuild join indexes after retrieving multidimensional objects. For more information, see [Join Indexes \(IQ/Oracle\) \[page 597\]](#).

3. [optional] Click the *Selection* tab to specify which tables to consider as candidates for fact or dimension tables. By default, all tables except those that have their *Dimensional type* set to **Exclude** are selected (see [Table Properties \[page 84\]](#)).
4. Click **OK** to retrieve the multidimensional objects.

The selected tables are assigned a multidimensional type, and a type icon is displayed in the upper left corner of each table's symbol:

Fact table	Dimension table

5. [optional] Review the types identified by PowerDesigner and, if necessary, modify them by changing the value of the *Dimensional type* field on the *General* tab of the table or view property sheet.

1.4.2 Generating Cubes

PowerDesigner can generate facts and dimensions from your operational tables to create a multidimensional diagram representing a cube. The generation will create mappings between your operational and warehouse objects as the basis for extraction scripts or in preparation for generating a BusinessObjects universe.

Context


You can prepare and preview the multidimensional types of your operational tables and views before launching this wizard either manually by setting the *Dimensional type* value (see [Table Properties \[page 84\]](#)) or have

PowerDesigner retrieve them (see [Identifying Fact and Dimension Tables \[page 232\]](#)). You can generate a BusinessObjects universe at any time (see [Generating an SAP BusinessObjects Universe \[page 311\]](#)).

Procedure

1. Select **Tools** **Multidimensional Objects** to open the wizard.
2. Select the package where you want to create the multidimensional diagram, and then click **Next**. For DBMSs, such as SAP HANA®, which require that you create your multidimensional objects in a package, PowerDesigner will force the creation of a new package if none exist.
3. Select the operational tables from which to build your facts and dimensions, and then click **Next**. By default, PowerDesigner selects all the tables in your model.
4. Select the operational tables from which to build your facts, and then click **Next**. By default, PowerDesigner selects tables with only outgoing references as facts.
5. Select the operational tables from which to build dimensions around each of your facts, and then click **Next**. By default, PowerDesigner selects all the tables with direct or indirect references from your fact tables and will merge second and higher order references into the dimensions created from first order references.
6. Select fact table columns as measures or attributes of your facts, and then click **Next**. By default, PowerDesigner selects non-key numeric columns as measures and all other columns as attributes. You can drag and drop columns between the Candidates, Measures, and Attributes trees as necessary.
7. Review the list of facts that will be generated, and click **Finish** to begin the generation.

The Generate Cubes Wizard creates a multidimensional object containing facts and dimensions to represent your cubes:



1.4.2.1 Modifying Cubes

PowerDesigner can update your facts and dimensions in a multidimensional diagram representing a cube to reflect changes made to your operational tables or simply to add or remove dimensions, measures, or attributes.

Procedure

1. Select the cube fact in the multidimensional diagram you want to update, and then select **Tools > Modify Cube** to open the wizard.
2. Select the operational tables from which to build dimensions around your facts, and then click **Next**. By default, PowerDesigner selects only those tables that you have previously selected as dimensions.
3. Select fact table columns as measures or attributes of your facts, and then click **Next**. By default, PowerDesigner reproduces your previous choices and you can drag and drop columns between the Candidates, Measures, and Attributes trees as necessary.
4. Review the objects that will be generated, and click **Finish** to begin the generation.

The wizard updates your multidimensional diagram to reflect your new choices.

1.4.3 Facts (PDM)

Facts define the focus of the data to be analyzed and how it is calculated. Examples of facts are sales, costs, employee hours, revenue, budget. Facts contain a list of measures, which represent the actual numerical data, and are surrounded by dimensions, which control how that data will be analyzed.



1.4.3.1 Creating a Fact

Facts are generally generated from operational database tables or views. You can also manually create facts from the Toolbox, Browser, or **Model** menu.

- Use the **Fact** tool in the Toolbox.
- Select **Model > Facts** to access the List of Facts, and click the **Add a Row** tool.
- Right-click the model (or a package) in the Browser, and select **New > Fact**.

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.4.3.2 Fact Properties

To view or edit a fact's properties, double-click its diagram symbol or Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The [General](#) tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the Code field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Mapped to	Specifies the operational database table or view to which the fact is mapped. Click the Properties tool to open the source table property sheet. To map a manually-created fact to its source, open the Mapping Editor and drag and drop the table or view from the Source pane onto the fact in the Target pane (see Operational to Warehouse Data Mappings [page 243]).
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- [Attributes](#) - specifies attributes that are used by the fact for joins to dimensions or as the basis of calculated measures (see [Fact and Dimension Attributes \(PDM\) \[page 239\]](#)).
- [Measures](#) - lists the measures manipulated by the fact (see [Measures \(PDM\) \[page 236\]](#)).
- [Dimensions](#) - lists the dimensions linked to the fact in the cube (see [Dimensions \(PDM\) \[page 238\]](#)).
- [Mapping](#) - specifies the mapping between the fact and the source operational database table or view (see [Operational to Warehouse Data Mappings \[page 243\]](#)).

1.4.3.3 Measures (PDM)

Measures are mapped to numerical columns in fact tables and aggregate the values in the columns along the selected dimensions. For example, when a user chooses to view the sales in Texas in 2012 Q1, the calculation is performed via the Sales measure using a Sum aggregation. Measures can also be based on operations or calculations or derived from other measures.

Creating a Measure

Measures are generally generated from numerical columns in operational database tables. You can also manually create measures from the property sheet of, or in the Browser under, a fact.

- Open the [Measures](#) tab in the property sheet of a fact, and click the *Add a Row* tool.
- Right-click a fact in the Browser, and select  [New > Measure](#).

Measure Properties

To view or edit a measure's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The [General](#) tab contains the following properties:

Property	Description
Parent	Specifies the parent fact of the measure. Click the Properties tool to open the fact property sheet.
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the Code field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Type	Specifies how the value of the measure is determined. In each case, specify the aggregation function to be applied to values and then choose from: <ul style="list-style-type: none">• Standard - the measure is mapped to the operational table column specified in the Mapped to field. To map a manually-created measure to its source, open the Mapping Editor and drag and drop the column from the Source pane onto the measure in the Target pane (see Operational to Warehouse Data Mappings [page 243]).• Calculated - the measure is calculated from an expression specified in the Formula expression field. Enter the expression directly or click the Edit with SQL Editor tool (see Writing SQL Code in PowerDesigner [page 288]).• Restricted - the measure is derived from the measure specified in the Base measure field, and constrained by the values specified for each of the fact or dimension attributes added to the list.
Hidden	Specifies that the measure will not be visible to business users consulting the cube.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

1.4.4 Dimensions (PDM)

A dimension is an axis of analysis in a multidimensional structure. Typical dimensions for a sales database include time, region, department, and product.

A dimension is made of an ordered list of attributes that share a common semantic meaning in the domain being modeled. For example a Time dimension often contains attributes that allow you to analyze data by year, quarter, month, and week:

Time
Year
Quarter
Month
Week
Year_time <Default> <h>

A dimension may have one or more hierarchies representing different ways of traversing the list of attributes.

1.4.4.1 Creating a Dimension

Dimensions are generally generated from operational database tables or views. You can also manually create a dimension from the Toolbox, Browser, or *Model* menu.

- Use the *Dimension* tool in the Toolbox.
- Select to access the List of Dimensions, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select .

For general information about creating objects, see *Core Features Guide > Modeling with PowerDesigner > Objects*.

1.4.4.2 Dimension Properties

To view or edit a dimension's properties, double-click its diagram symbol or Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Mapped to	Specifies the operational database table or view to which the dimension is mapped. Click the <i>Properties</i> tool to open the source table property sheet. To map a manually-created dimension to its source, open the Mapping Editor and drag and drop the table or view from the <i>Source</i> pane onto the dimension in the <i>Target</i> pane (see Operational to Warehouse Data Mappings [page 243]).
Default Hierarchy	Specifies the dimension hierarchy used by default for a cube to perform its consolidation calculations. The hierarchy used by the cube is defined on the cube dimension association
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- Attributes - lists the attributes that qualify the dimension (see [Fact and Dimension Attributes \(PDM\) \[page 239\]](#)).
- Hierarchies - lists the hierarchies used to organize the dimension attributes (see [Hierarchies \(PDM\) \[page 241\]](#)).
- Mapping - defines the mapping between the current dimension and a table or a view in a data source.

1.4.4.3 Fact and Dimension Attributes (PDM)

Fact attributes are used by the fact for joins to dimensions or as the basis of calculated measures. Dimension attributes provide data points around which the data in a fact can be interrogated.

Creating an Attribute

Fact and dimension attributes are generally generated from operational database table columns. You can also manually create attributes as follows:

- Open the *Attributes* tab in the property sheet of a fact or dimension, and click the *Add a Row* or *Insert a Row* tool. The *Add Attributes* tool allows you to reuse an attribute from another fact or dimension.
- Right-click a fact or dimension in the Browser, and select *New > Attribute*.

Attribute Properties


To view or edit an attribute's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Parent	Specifies the parent fact or dimension of the attribute.
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Type	Specifies how the value of the attribute is determined: <ul style="list-style-type: none">• Standard - the attribute is mapped to the operational table column specified in the <i>Mapped to</i> field. To map a manually-created attribute to its source, open the Mapping Editor and drag and drop the column from the <i>Source</i> pane onto the attribute in the <i>Target</i> pane (see Operational to Warehouse Data Mappings [page 243]).• Calculated - the attribute is calculated from an expression specified in the <i>Formula expression</i> field. Enter the expression directly or click the <i>Edit with SQL Editor</i> tool (see Writing SQL Code in PowerDesigner [page 288]).
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

Dimension attributes include the following tab:

- **Detail Attributes** - Lists other dimension attributes that are used to further define the attribute. Click the *Add Detail Attributes* tool to select attributes defined on the current dimension to further define the attribute.
In the following example, attributes **Cust_Name** and **Cust_Address** are used as detail attributes for **Cust_ID**:



1.4.4.4 Hierarchies (PDM)

A hierarchy defines a path for navigating through the attributes in a dimension when drilling down or rolling up through the data. For example, a time dimension with the attributes Year, Quarter, Month, Week, Day may have a default hierarchy listing all these periods in order and a second hierarchy which includes only Year, Month, and Week.

Creating a Hierarchy

You can create a hierarchy from the property sheet of, or in the Browser under, a dimension.

- Open the *Attributes* tab in the property sheet of a dimension, select the attributes you want to include in your dimension and then click the *Create Hierarchy* tool.
 - Open the *Hierarchies* tab in the property sheet of a dimension, click the *Add a Row* tool, then click the *Properties* tool and add your attributes manually.
 - Right-click a dimension in the Browser, and select  *New > Hierarchy*.

Hierarchy Properties

To view or edit a hierarchy's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Dimension	Specifies the parent dimension of the hierarchy.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.


The following tabs are also available:

- *Attributes* - lists the attributes associated with the hierarchy in ascending order of specificity (see [Fact and Dimension Attributes \(PDM\) \[page 239\]](#)).

1.4.5 Associations (PDM)

An association connects a fact to the dimension that defines it.

For example, the **Sale** fact is linked to the **Time** dimension by the **Sale - Time** association to analyze sales through the time dimension.



There can be only one association between a fact and a dimension.

Creating an Association

Associations are generally generated from operational database references. You can manually create associations from the Toolbox, Browser, or *Model* menu.

- Use the *Association* tool in the Toolbox.
- Select ► *Model* ► *Associations* ▾ to access the List of Associations, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select ► *New* ► *Association* ▾.

Association Properties

To view or edit an association's properties, double-click its diagram symbol or Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Fact	Specifies the fact at the origin of the association. Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object.
Dimension	Specifies the destination dimension of the association. Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Reference	Specifies the reference upon which the association is based. Click the <i>Properties</i> tool to view the properties of the selected reference.
Hierarchy	Specifies the default hierarchy used by the cube for the consolidation calculation. Click the <i>Properties</i> tool to view the properties of the selected hierarchy.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.


1.4.6 Operational to Warehouse Data Mappings

Data warehousing requires the extraction, transformation, and loading of data from operational systems to a data warehouse database. You can create mappings between operational and data warehouse data and from the data warehouse data and OLAP cubes. To review or edit these mappings, open your multidimensional diagram, and then select ► *Tools* ► *Mapping Editor* ▾.

You can model operational and data warehouse data structures in PDMs, and specify mappings between the operational data sources and the data warehouse to generate extraction scripts to populate the data warehouse

with operational data. In this kind of relational-to-relational mapping, operational tables are mapped to data warehouse tables with a type of fact or dimension, and operational columns are mapped to warehouse columns.

The Generate Cube wizard automatically creates mappings between source tables and facts and dimensions and you can modify these or manually create mappings between these objects:



The **Select** sub-tab displays the SQL statement used to select data in the data source. The Generate Cube Data wizard uses this SQL statement to fill the text files used to populate cubes in an OLAP database.

1.4.7 Generating Data Warehouse Extraction Scripts


You can model operational and data warehouse data structures in PDMs, and specify mappings between the operational data sources and the data warehouse to generate extraction scripts to populate the data warehouse with operational data.

Context

In this kind of relational-to-relational mapping, operational tables are mapped to data warehouse tables with a type of fact or dimension, and operational columns are mapped to warehouse columns. You can generate a script file for each data source, you can also select the tables in the data source which `select` orders will be generated in the script file. The extraction scripts list all the `select` orders defined in the table mappings.

Procedure

1. In the Physical Diagram, select :



2. Specify a destination directory for the generated file, and select the *Check Model* option if you want to verify the PDM syntax before generation.

3. [optional] Click the *Options* tab and specify any appropriate options:

Option	Description
Title	Specifies to insert the database header and the name of the tables before each select query.
Encoding	Specifies the encoding format. You should select the format that supports the language used in your model and the database encoding format.
Character Case	Specifies the case to use in the generated file.
No Accent	Specifies to remove any accents from generated characters.

4. [optional] Click the *Selection* tab, and select the tables for which you want to generate extraction scripts.
5. Click *OK* to generate the script files in the specified directory. The name of the script is identical to the name of the data source.

1.4.8 Generating Cube Data


You can map physical tables (including those of type dimension or fact) to cube dimensions or cube measures in OLAP databases, and use these mappings to generate cube data in text files to be loaded by OLAP engines. When you use the Rebuild Cubes command to create cubes and dimensions from fact and dimension tables, mappings between source tables and OLAP objects are automatically created.

Context

In a PDM multidimensional diagram, each fact is associated with a query. There is one fact per mapping and per data source. The query defined on a fact is used to extract data from a data warehouse or operational database to populate the cubes in the OLAP database. The link between the data warehouse database and the OLAP database is a relational to multidimensional mapping.

Procedure

1. In the multidimensional diagram, select *Tools* *Generate Cube Data*.



2. Specify a destination directory for the generated file, and select any appropriate options in the *Options* tab:

Option	Description
Header	Specifies to include the name of the attribute at the beginning of the generated text file
Extension	Specifies the extension of the generated text file. You can choose either .txt and .csv.
Separator	Specifies the separator to use between columns. The default is , (comma).
Delimiter	Specifies the character to delimit string values. The default is " (double-quote).
Encoding	Specifies the encoding format. You should select the format that supports the language used in your model and the database encoding format.
Character Case	Specifies the case to use in the generated file.
No Accent	Specifies to remove any accents from generated characters.

3. Select the facts and data sources for which you want to generate a file from the sub-tabs in the *Selection* tab.
 4. Click *OK*.

The generated files are stored in the destination directory you have defined. PowerDesigner produces one file for each selected fact and each selected data source, named by concatenating the names of the fact and the data source, and containing the following fields:

Field	Details
Dimension	Lists the attributes of the cube
Member	Lists the attribute values
Data fields	Contains the values stored in the fact measures

1.5 Checking a Data Model

The data model is a very flexible tool, which allows you quickly to develop your model without constraints. You can check the validity of your Data Model at any time.

A valid Data Model conforms to the following kinds of rules:

- Each object name in a data model must be unique
- Each entity in a CDM must have at least one attribute
- Each relationship in a LDM must be attached to at least one entity
- Each index in a PDM must have a column

i Note

We recommend that you check your data model before generating another model or a database from it . If the check encounters errors, generation will be stopped. The *Check model* option is enabled by default in the Generation dialog box.

You can check your model in any of the following ways:

- Press F4, or
- Select  **Tools**  **Check Model**, or
- Right-click the diagram background and select Check Model from the contextual menu

The Check Model Parameters dialog opens, allowing you to specify the kinds of checks to perform, and the objects to apply them to. The following sections document the Data Model-specific checks available by default. For information about checks made on generic objects available in all model types and for detailed information about using the Check Model Parameters dialog, see *Core Features Guide > Modeling with PowerDesigner > Objects > Checking Models* .

1.5.1 Abstract Data Type Checks (PDM)

PowerDesigner provides default model checks to verify the validity of abstract data types.

Check	Description and Correction
Name/Code contains terms not in glossary	[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: None.
Name/Code contains synonyms of glossary terms	[if glossary enabled] Names and codes must not contain synonyms of glossary terms. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	Object names must be unique in the namespace. <ul style="list-style-type: none">• Manual correction: Modify the duplicate name or code.• Automatic correction: Appends a number to the duplicate name or code.
Abstract Data Type code maximum length	The code of the ADT is longer than the maximum allowed by the DBMS. <ul style="list-style-type: none">• Manual correction: Reduce the length of the code• Automatic correction: Reduces the code to a permissible length
Instantiable object type must have attributes and no abstract procedures	If an abstract data type of type Object (or SQLJ Object) is instantiable (Abstract option not checked), then it must have attributes and no abstract procedure. <ul style="list-style-type: none">• Manual correction: Define at least one attribute in the ADT Attributes tab and clear the Abstract option in the procedures property sheet• Automatic correction: None
Abstract object type must not have tables based on it	If an abstract data type of type Object (or SQLJ Object) is not instantiable (Abstract option checked), then it must not have tables based on it. <ul style="list-style-type: none">• Manual correction: Set the Based on property to <None> in the tables property sheet• Automatic correction: None

1.5.2 Abstract Data Type Procedure Checks (PDM)

PowerDesigner provides default model checks to verify the validity of abstract data type procedures.

Check	Description and Correction
Name/Code contains terms not in glossary	[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: None.

Check	Description and Correction
Name/Code contains synonyms of glossary terms	<p>[if glossary enabled] Names and codes must not contain synonyms of glossary terms.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	<p>Object names must be unique in the namespace.</p> <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.
Abstract Data Type procedure code maximum length	<p>The code of the ADT procedure is longer than the maximum allowed by the DBMS.</p> <ul style="list-style-type: none"> Manual correction: Reduce the length of the code Automatic correction: Reduces the code to a permissible length
Procedure cannot have the same name as an attribute	<p>An abstract data type procedure cannot have the same name as an attribute.</p> <ul style="list-style-type: none"> Manual correction: Change the name of the ADT procedure Automatic correction: None
Abstract data type procedure definition empty	<p>An abstract data type procedure must have a body defined.</p> <ul style="list-style-type: none"> Manual correction: Create an ADT procedure definition in the Body tab of the ADT procedure property sheet Automatic correction: None
Inconsistent return type	<p>If the abstract data type procedure is a function, a map or an order, you should define a return data type for the function, map or order.</p> <ul style="list-style-type: none"> Manual correction: Select a return data type in the Return data type list Automatic correction: None

1.5.3 Association Checks (CDM)

PowerDesigner provides default model checks to verify the validity of associations.

Check	Description and Correction
Name/Code contains terms not in glossary	<p>[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: None.
Name/Code contains synonyms of glossary terms	<p>[if glossary enabled] Names and codes must not contain synonyms of glossary terms.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: Replaces synonyms with their associated glossary terms.

Check	Description and Correction
Name/Code uniqueness	<p>Object names must be unique in the namespace.</p> <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.
Number of links ≥ 2	<p>An association is isolated and therefore does not define a relationship between entities.</p> <ul style="list-style-type: none"> Manual correction: Define at least two links between the isolated association and one or several entities. Automatic correction: None.
Number of links = 2 with an identifier link	<p>An identifier link introduces a dependency between two entities. An association with this type of link must be binary.</p> <ul style="list-style-type: none"> Manual correction: Delete the unnecessary links or clear the Identifier check box for a link. Automatic correction: None.
Number of identifier links ≤ 1	<p>An identifier link introduces a dependency between two entities. There can only be one identifier link between two entities otherwise a circular dependency is created.</p> <ul style="list-style-type: none"> Manual correction: Clear the Identifier check box for one of the links. Automatic correction: None.
Absence of properties with identifier links	<p>An association with an identifier link cannot have any properties.</p> <ul style="list-style-type: none"> Manual correction: Move the association properties into the dependent entity (the one linked to the association with an identifier link). Automatic correction: None.
Bijective association between two entities	<p>There are bijective associations between two entities when a two-way one to one association between the entities exist. This is equivalent to a merge of two entities.</p> <ul style="list-style-type: none"> Manual correction: Merge the entities or modify the cardinality links. Automatic correction: None.
Maximal cardinality links	<p>An association with more than two links can only have links with a maximum cardinality greater than one.</p> <ul style="list-style-type: none"> Manual correction: Change the maximum cardinality of such links to be greater than 1. Automatic correction: None.
Reflexive identifier links	<p>An identifier link introduces a dependency between two entities. An association with this type of link cannot therefore be reflexive.</p> <ul style="list-style-type: none"> Manual correction: Change the relationship between the entities or clear the Identifier check box for a link. Automatic correction: None.

Check	Description and Correction
Name uniqueness constraint between many-to-many associations and entities	<p>A many-to-many association and an entity cannot have the same name or code.</p> <ul style="list-style-type: none"> Manual correction: Change the name or code of the many-to-many association or the name or code of the entity. If you do not, PDM generation will rename the generated table. Automatic correction: None.

1.5.4 Association Checks (PDM)

PowerDesigner provides default model checks to verify the validity of associations.

Check	Description and Correction
Existence of hierarchy	<p>An association must have a hierarchy specified in order to perform the consolidation calculation.</p> <ul style="list-style-type: none"> Manual correction: Select a hierarchy in the Hierarchy list in the association property sheet Automatic correction: None

1.5.5 Column Checks (PDM)

PowerDesigner provides default model checks to verify the validity of columns.

Check	Description and Correction
Name/Code contains terms not in glossary	<p>[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: None.
Name/Code contains synonyms of glossary terms	<p>[if glossary enabled] Names and codes must not contain synonyms of glossary terms.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	<p>Object names must be unique in the namespace.</p> <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.

Check	Description and Correction
Column code maximum length	<p>The column code length is limited by the maximum length specified in the DBMS definition (MaxLen entry, in the <i>Objects</i> <i>Column</i> category) or in the naming conventions of the model options.</p> <ul style="list-style-type: none"> Manual correction: Modify the column code length to meet this requirement Automatic correction: Truncates the code length to the maximum length specified in the DBMS definition
Domain divergence	<p>Divergence is verified between columns, domains, and data types. Various checks and attributes are also examined. One or more of the Enforce non divergence model options must be selected.</p> <ul style="list-style-type: none"> Manual correction: Select one or more of the Enforce non divergence model options to enforce non divergence Automatic correction: Restores divergent attributes from domain to column (domain values overwrite column values)
Column mandatory	<p>In some DBMS, the columns included in a key or a unique index should be mandatory.</p> <ul style="list-style-type: none"> Manual correction: Select the Mandatory check box in the column property sheet Automatic correction: Makes the column mandatory
Detect inconsistencies between check parameters	<p>The values entered in the check parameters tab are inconsistent for numeric and string data types: default does not respect minimum and maximum values, or default does not belong to list of values, or values in list are not included in minimum and maximum values, or minimum is greater than maximum value. Check parameters must be defined consistently.</p> <ul style="list-style-type: none"> Manual correction: Modify default, minimum, maximum or list of values in the check parameters tab Automatic correction: None
Precision > Maximum length	<p>The data type precision should not be greater than the length. Note that some DBMS accept a precision higher than the length.</p> <ul style="list-style-type: none"> Manual correction: Make the data type length greater than the precision Automatic correction: None
Undefined data type	<p>A model should not contain columns with undefined data type, all columns should have a defined data type.</p> <ul style="list-style-type: none"> Manual correction: Select a data type in the column property sheet Automatic correction: None
Foreign key column data type and constraint parameters divergence	<p>Primary/alternate and foreign key columns involved in a join should have consistent data types and constraint parameters.</p> <ul style="list-style-type: none"> Manual correction: Modify foreign key data types and constraint parameters to make them consistent Automatic correction: Parent column overwrites existing data type and constraint parameters in the foreign key column

Check	Description and Correction
Column with sequence not in a key	<p>Since a sequence is used to initialize a key, it should be attached to a column that is part of a key. This applies to those DBMS that support sequences.</p> <ul style="list-style-type: none"> Manual correction: Attach the sequence to a column that is part of a key Automatic correction: None
Auto-incremented column with data type not numeric	<p>An auto-incremented column must have a numeric data type.</p> <ul style="list-style-type: none"> Manual correction: Change the column data type Automatic correction: Changes data type to numeric data type
Auto-incremented column is foreign key	<p>A foreign key column should not be auto-incremented.</p> <ul style="list-style-type: none"> Manual correction: Deselect the Identity check box in the column property sheet Automatic correction: None
Missing computed column expression	<p>A computed column should have a computed expression defined.</p> <ul style="list-style-type: none"> Manual correction: Add a computed expression to the column in the Details tab of the column property sheet Automatic correction: None
Invalid mapping from source column	<p>A column in a table managed by a lifecycle policy in which the first phase is associated with an external database must not be mapped to more than one column in the corresponding table in the external database.</p> <ul style="list-style-type: none"> Manual correction: Remove the additional mappings. Automatic correction: None
Data type compatibility of mapped columns	<p>A column in a table managed by a lifecycle policy in which the first phase is associated with an external database must be mapped to a column with the same data type in the corresponding table in the external database.</p> <ul style="list-style-type: none"> Manual correction: Harmonize the data types in the source and target columns. Automatic correction: None
Existence of mapping for mandatory columns	<p>A mandatory column in a table managed by a lifecycle policy in which the first phase is associated with an external database must be mapped to a column in the corresponding table in the external database.</p> <ul style="list-style-type: none"> Manual correction: Map the mandatory column to a column in the external database. Automatic correction: None

1.5.6 Cube Checks (PDM)

PowerDesigner provides default model checks to verify the validity of cubes.

Check	Description and Correction
Name/Code contains terms not in glossary	[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: None.
Name/Code contains synonyms of glossary terms	[if glossary enabled] Names and codes must not contain synonyms of glossary terms. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	Object names must be unique in the namespace. <ul style="list-style-type: none">• Manual correction: Modify the duplicate name or code.• Automatic correction: Appends a number to the duplicate name or code.
Existence of association	A cube must have at least one association with a dimension. <ul style="list-style-type: none">• Manual correction: Create an association between the cube and a dimension• Automatic correction: None
Existence of fact	A cube must be associated to a fact. <ul style="list-style-type: none">• Manual correction: Click the Ellipsis button beside the Fact box in the cube property sheet, and select a fact from the List of Facts• Automatic correction: None
Duplicated association with the same dimension	A cube cannot have more than one association with the same dimension. <ul style="list-style-type: none">• Manual correction: Delete one of the associations• Automatic correction: None

1.5.7 Database Checks (PDM)

PowerDesigner provides default model checks to verify the validity of databases.

Check	Description and Correction
Name/Code contains terms not in glossary	[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: None.

Check	Description and Correction
Name/Code contains synonyms of glossary terms	[if glossary enabled] Names and codes must not contain synonyms of glossary terms. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	Object names must be unique in the namespace. <ul style="list-style-type: none">• Manual correction: Modify the duplicate name or code.• Automatic correction: Appends a number to the duplicate name or code.
Database code maximum length	The code of the database is longer than the maximum allowed by the DBMS. <ul style="list-style-type: none">• Manual correction: Reduce the length of the code• Automatic correction: Reduces the code to a permissible length
Database not used	The database you have created is not used in the model. <ul style="list-style-type: none">• Manual correction: Delete the database or apply the database as a physical option to a table, an index, a key, a column, a storage, a tablespace or a view (Options tab of the object property sheet)• Automatic correction: None

1.5.8 Database Package Checks (PDM)

PowerDesigner provides default model checks to verify the validity of database packages.

Check	Description and Correction
Name/Code contains terms not in glossary	[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: None.
Name/Code contains synonyms of glossary terms	[if glossary enabled] Names and codes must not contain synonyms of glossary terms. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	Object names must be unique in the namespace. <ul style="list-style-type: none">• Manual correction: Modify the duplicate name or code.• Automatic correction: Appends a number to the duplicate name or code.

Check	Description and Correction
Database package name and code maximum length	<p>The database package name and code length is limited by the maximum length specified in the DBMS definition and in the naming conventions of the model options.</p> <ul style="list-style-type: none"> Manual correction: Modify the name/code length to meet this requirement Automatic correction: Truncates the name/code length to the maximum length specified in the DBMS definition (at  <i>Objects</i>  <i>DB Package</i> 
Existence of package <i><sub-object></i>	<p>A database package must have a number of sub-objects defined in order to be correctly modeled.</p> <ul style="list-style-type: none"> Manual correction: Create one or more of the relevant object on the appropriate tab of the database package property sheet: <ul style="list-style-type: none"> Procedures (or use existing stored procedures and duplicate them in the database package) Cursors Variables Types Exceptions Automatic correction: None

1.5.9 Database Package Sub-Object Checks (PDM)

PowerDesigner provides default model checks to verify the validity of database package cursors, exceptions, procedures, types, and variables.

Check	Description and Correction
Name/Code contains terms not in glossary	<p>[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: None.
Name/Code contains synonyms of glossary terms	<p>[if glossary enabled] Names and codes must not contain synonyms of glossary terms.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	<p>Object names must be unique in the namespace.</p> <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.
Package <i><sub-object></i> definition empty	<p>[cursors, procedures, types] These sub-objects must have a body defined.</p> <ul style="list-style-type: none"> Manual correction: Create the definition in the <i>Body</i> tab of the sub-object's property sheet Automatic correction: None

Check	Description and Correction
Check for undefined return types	[cursors, procedures] These sub-objects must have a return data type. <ul style="list-style-type: none">• Manual correction: Select a return data type in the subobject's property sheet• Automatic correction: None
Existence of parameter	[cursors, procedures] These sub-objects must contain parameters for input values. <ul style="list-style-type: none">• Manual correction: Create one or several parameters in the <i>Parameters</i> tab of the sub-object's property sheet• Automatic correction: None
Undefined data type	[variables] Variables must have a data type. <ul style="list-style-type: none">• Manual correction: Select a data type in the variable property sheet• Automatic correction: None

1.5.10 Data Format Checks (CDM/LDM/PDM)

PowerDesigner provides default model checks to verify the validity of data formats.

Check	Description and Correction
Empty expression	Data formats must have a value entered in the <i>Expression</i> field. <ul style="list-style-type: none">• Manual correction: Specify an expression for the data format.• Automatic correction: None

1.5.11 Data Item Checks (CDM)

PowerDesigner provides default model checks to verify the validity of data items.

Check	Description and Correction
Name/Code contains terms not in glossary	[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: None.
Name/Code contains synonyms of glossary terms	[if glossary enabled] Names and codes must not contain synonyms of glossary terms. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: Replaces synonyms with their associated glossary terms.

Check	Description and Correction
Name/Code uniqueness	<p>Object names must be unique in the namespace.</p> <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.
Data item not used	<p>There are unused data items. These are useless for PDM generation.</p> <ul style="list-style-type: none"> Manual correction: To use a data item, add it to an entity. If you do not need an unused data item, delete it to allow PDM generation. Automatic correction: None.
Data item used multiple times	<p>There are entities using the same data items. This can be tolerated if you defined this check as a warning.</p> <ul style="list-style-type: none"> Manual correction: Take care to ensure consistency when defining data item properties. Automatic correction: None.
Detect differences between data item and associated domain	<p>There is a divergence between data items and associated domains. This can be tolerated if you defined this check as a warning.</p> <ul style="list-style-type: none"> Manual correction: Ensure consistency when defining data item properties Automatic correction: Restores divergent attributes from domain to data items (domain values overwrite data item values).
Detect inconsistencies between check parameters	<p>The values entered in the check parameters page are inconsistent for numeric and string data types: default does not respect minimum and maximum values, or default does not belong to list of values, or values in list are not included in minimum and maximum values, or minimum is greater than maximum value. Check parameters must be defined consistently.</p> <ul style="list-style-type: none"> Manual correction: Modify default, minimum, maximum or list of values in the check parameters page Automatic correction: None.
Precision > maximum length	<p>The data type precision should not be greater than or equal to the length.</p> <ul style="list-style-type: none"> Manual correction: Make the data type length greater than or equal to the precision. Automatic correction: None.
Undefined data type	<p>Undefined data types for data items exist. To be complete, a model should have all its data items data types defined.</p> <ul style="list-style-type: none"> Manual correction: While undefined data types are tolerated, you must select data types for currently undefined data types before you can generate a PDM. Automatic correction: None.
Invalid data type	<p>Invalid data types for data items exist. To be complete, a model should have all its data types for data items correctly defined.</p> <ul style="list-style-type: none"> Manual correction: While tolerated, you must select valid data types for currently non-valid data types to generate the PDM. Automatic correction: None.

1.5.12 Data Source Checks (PDM)

PowerDesigner provides default model checks to verify the validity of data sources.

Check	Description and Correction
Name/Code contains terms not in glossary	[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: None.
Name/Code contains synonyms of glossary terms	[if glossary enabled] Names and codes must not contain synonyms of glossary terms. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	Object names must be unique in the namespace. <ul style="list-style-type: none">• Manual correction: Modify the duplicate name or code.• Automatic correction: Appends a number to the duplicate name or code.
Existence of physical data model	A data source must contain at least one physical data model in its definition. <ul style="list-style-type: none">• Manual correction: Add a physical data model from the Models tab of the property sheet of the data source.• Automatic correction: Deletes data source without physical data model.
Data source containing models differing DBMS types	The models in a data source should share the same DBMS since they represent a single database. <ul style="list-style-type: none">• Manual correction: Delete models with different DBMS or modify the DBMS of models in the data source.• Automatic correction: None
Unsupported source models	Each lifecycle policy can only manage one external database, so any data sources defined (and the models they reference) must all point to the same database. <ul style="list-style-type: none">• Manual correction: Remove any data sources pointing to other databases.• Automatic correction: None

1.5.13 Default Checks (PDM)

PowerDesigner provides default model checks to verify the validity of defaults.

Check	Description and Correction
Name/Code contains terms not in glossary	[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: None.

Check	Description and Correction
Name/Code contains synonyms of glossary terms	<p>[if glossary enabled] Names and codes must not contain synonyms of glossary terms.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	<p>Object names must be unique in the namespace.</p> <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.
Default code maximum length	<p>The default code length is limited by the maximum length specified in the DBMS definition (MaxLen entry, in the  Objects  category).</p> <ul style="list-style-type: none"> Manual correction: Modify the default code length to meet this requirement Automatic correction: Truncates the default code length to the maximum length specified in the DBMS definition
Default value empty	<p>You must type a value for the default, this value is used during generation.</p> <ul style="list-style-type: none"> Manual correction: Type a value in the Value box of the default property sheet Automatic correction: None
Several defaults with same value	<p>A model should not contain several defaults with identical value.</p> <ul style="list-style-type: none"> Manual correction: Modify default value or delete defaults with identical value Automatic correction: None

1.5.14 Dimension Checks (PDM)

PowerDesigner provides default model checks to verify the validity of dimensions.

Check	Description and Correction
Name/Code contains terms not in glossary	<p>[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: None.
Name/Code contains synonyms of glossary terms	<p>[if glossary enabled] Names and codes must not contain synonyms of glossary terms.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	<p>Object names must be unique in the namespace.</p> <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.

Check	Description and Correction
Existence of attribute	<p>A dimension must have at least one attribute.</p> <ul style="list-style-type: none"> Manual correction: Create an attribute in the Attributes tab of the dimension property sheet Automatic correction: None
Existence of hierarchy	<p>A dimension must use at least one hierarchy.</p> <ul style="list-style-type: none"> Manual correction: Create a hierarchy in the Hierarchies tab of the dimension property sheet Automatic correction: None
Dimension have duplicated hierarchies	<p>Dimensions should not have duplicated hierarchies, that is to say hierarchies organizing identical attributes.</p> <ul style="list-style-type: none"> Manual correction: Remove one of the duplicated hierarchies Automatic correction: None
Dimension without a default hierarchy	<p>A dimension should have a default hierarchy.</p> <ul style="list-style-type: none"> Manual correction: Select a hierarchy in the Default Hierarchy list of the dimension property sheet Automatic correction: None
Dimension mapping not defined	<p>A dimension should be mapped to tables or views in an operational model in order to be populated by data from this model.</p> <ul style="list-style-type: none"> Manual correction: Map the dimension to a table or a view. You may need to create a data source before you can create the mapping Automatic correction: Destroys the mapping for the dimension. This removes the data source from the Mapping list in the dimension Mapping tab
Attribute mapping not defined	<p>Attributes must be mapped to columns in the data source tables or views.</p> <ul style="list-style-type: none"> Manual correction: Map the attributes to columns in the data source Automatic correction: None
Incomplete dimension mapping for multidimensional generation	<p>All attributes, detail attributes and hierarchies of the dimension must be mapped to tables and columns. You must map the dimension objects before generation.</p> <ul style="list-style-type: none"> Manual correction: Map dimension objects to tables and columns Automatic correction: None

1.5.15 Domain Checks (CDM/LDM/PDM)

PowerDesigner provides default model checks to verify the validity of domains.

Check	Description and Correction
Name/Code contains terms not in glossary	[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: None.
Name/Code contains synonyms of glossary terms	[if glossary enabled] Names and codes must not contain synonyms of glossary terms. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	Object names must be unique in the namespace. <ul style="list-style-type: none">• Manual correction: Modify the duplicate name or code.• Automatic correction: Appends a number to the duplicate name or code.
Domain code maximum length	[PDM only] The domain code length is limited by the maximum length specified in the DBMS definition (MaxLen entry, in the category) or in the naming conventions of the model options. <ul style="list-style-type: none">• Manual correction: Modify the domain code length to meet this requirement• Automatic correction: Truncates the domain code length to the maximum length specified in the DBMS definition
Detect Inconsistencies between check parameters	The values entered in the Check Parameters tab are inconsistent for numeric and string data types. Default does not respect minimum and maximum values, or default does not belong to list of values, or values in list are not included in minimum and maximum values, or minimum is greater than maximum value. Check parameters must be defined consistently. <ul style="list-style-type: none">• Manual correction: Modify default, minimum, maximum or list of values in the check parameters tab• Automatic correction: None
Precision > maximum length	The data type precision should not be greater than the length. <ul style="list-style-type: none">• Manual correction: Make the data type length greater than the precision• Automatic correction: None
Undefined data type	A model should not contain domains with undefined data type, all domains should have a defined data type. <ul style="list-style-type: none">• Manual correction: Select a data type from the domain property sheet• Automatic correction: None

Check	Description and Correction
Invalid data type	[CDM/LDM only] Invalid data types for domains exist. To be complete, a model should have all its domain data types correctly defined. <ul style="list-style-type: none"> Manual correction: While tolerated, you must select valid data types for currently non-valid data types to generate the PDM. Automatic correction: None.

1.5.16 Entity Attribute Checks (CDM/LDM)

PowerDesigner provides default model checks to verify the validity of entity attributes.

Check	Description and Correction
Name/Code contains terms not in glossary	[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary. <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: None.
Name/Code contains synonyms of glossary terms	[if glossary enabled] Names and codes must not contain synonyms of glossary terms. <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	Object names must be unique in the namespace. <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.
Detect differences between attribute and associated domain	[LDM only] There is a divergence between attributes and associated domains. This can be tolerated if you defined this check as a warning. <ul style="list-style-type: none"> Manual correction: Ensure consistency when defining attribute properties Automatic correction: Restores divergent attributes from domain to attributes (domain values overwrite attribute values).
Detect inconsistencies between check parameters	[LDM only] The values entered in the Check Parameters page are inconsistent for numeric and string data types. Default does not respect minimum and maximum values, or default does not belong to list of values, or values in list are not included in minimum and maximum values, or minimum is greater than maximum value. Check parameters must be defined consistently. <ul style="list-style-type: none"> Manual correction: Modify default, minimum, maximum or list of values in the check parameters page Automatic correction: None.

Check	Description and Correction
Precision > maximum length	<p>[LDM only] The data type precision should not be greater than or equal to the length.</p> <ul style="list-style-type: none"> Manual correction: Make the data type length greater than or equal to the precision. Automatic correction: None.
Undefined data type	<p>[LDM only] Undefined data types for attributes exist. To be complete, a model should have all its attributes data types defined.</p> <ul style="list-style-type: none"> Manual correction: While undefined data types are tolerated, you must select data types for currently undefined data types before you can generate a PDM. Automatic correction: None.
Invalid data type	<p>[LDM only] Invalid data types for attributes exist. To be complete, a model should have all its data types for attributes correctly defined.</p> <ul style="list-style-type: none"> Manual correction: While tolerated, you must select valid data types for currently non-valid data types to generate the PDM. Automatic correction: None.

1.5.17 Entity Identifier Checks (CDM/LDM)

PowerDesigner provides default model checks to verify the validity of entity identifiers.

Check	Description and Correction
Name/Code contains terms not in glossary	<p>[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: None.
Name/Code contains synonyms of glossary terms	<p>[if glossary enabled] Names and codes must not contain synonyms of glossary terms.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	<p>Object names must be unique in the namespace.</p> <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.
Existence of entity attribute	<p>At least one attribute must exist for an entity identifier.</p> <ul style="list-style-type: none"> Manual correction: Add an attribute to the entity identifier or delete the identifier. Automatic correction: None.

Check	Description and Correction
Identifier inclusion	An identifier cannot include another one. <ul style="list-style-type: none"> • Manual correction: Delete the identifier that includes an existing identifier. • Automatic correction: None.
Primary identifier in child entity	[Barker notation] Primary identifiers are not permitted in child entities <ul style="list-style-type: none"> • Manual correction: Move the primary identifier to the parent entity. • Automatic correction: None

1.5.18 Entity Checks (CDM/LDM)

PowerDesigner provides default model checks to verify the validity of entities.

Check	Description and Correction
Name/Code contains terms not in glossary	[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary. <ul style="list-style-type: none"> • Manual correction: Modify the name or code to contain only glossary terms. • Automatic correction: None.
Name/Code contains synonyms of glossary terms	[if glossary enabled] Names and codes must not contain synonyms of glossary terms. <ul style="list-style-type: none"> • Manual correction: Modify the name or code to contain only glossary terms. • Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	Object names must be unique in the namespace. <ul style="list-style-type: none"> • Manual correction: Modify the duplicate name or code. • Automatic correction: Appends a number to the duplicate name or code.
Entity name and code maximum length	The entity name and code length is limited to a maximum length of 254 characters specified in the naming conventions of the model options. <ul style="list-style-type: none"> • Manual correction: Modify the entity name/code length to meet this requirement. • Automatic correction: Truncates the entity name/code length to the maximum length specified in the naming conventions.
Existence of attributes	An entity must always contain at least one attribute. <ul style="list-style-type: none"> • Manual correction: Add an attribute to the entity or delete the entity. • Automatic correction: None.

Check	Description and Correction
Number of serial types > 1	<p>An entity cannot have more than one serial type attribute. Serial types are automatically calculated values.</p> <ul style="list-style-type: none"> Manual correction: Change the types of the appropriate entity attributes to have only one serial type attribute. Automatic correction: None.
Existence of identifiers	<p>An entity must contain at least one identifier.</p> <ul style="list-style-type: none"> Manual correction: Add an identifier to the entity or delete the entity. Automatic correction: None.
Existence of relationship or association link	<p>An entity must have at least one relationship or association link.</p> <ul style="list-style-type: none"> Manual correction: Add a relationship or an association link to the entity or delete the entity. Automatic correction: None.
Redundant inheritance	<p>An entity inherits from another entity more than once. This is redundant and adds nothing to the model.</p> <ul style="list-style-type: none"> Manual correction: Delete redundant inheritances Automatic correction: None.
Multiple inheritance	<p>An entity has multiple inheritance. This is unusual but can be tolerated if you defined this check as a warning.</p> <ul style="list-style-type: none"> Manual correction: Make sure that the multiple inheritance is necessary in your model. Automatic correction: None.
Parent of several inheritances	<p>An entity is the parent of multiple inheritances. This is unusual but can be tolerated if you defined this check as a warning.</p> <ul style="list-style-type: none"> Manual correction: Verify if the multiple inheritances could not be merged. Automatic correction: None.
Redefined primary identifier	<p>Primary identifiers in child entities must be the same as those in their parents.</p> <ul style="list-style-type: none"> Manual correction: Delete those primary identifiers in the child entities that are not in the parent entity. Automatic correction: None.

1.5.19 Fact Checks (PDM)

PowerDesigner provides default model checks to verify the validity of facts.

Check	Description and Correction
Name/Code contains terms not in glossary	[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: None.
Name/Code contains synonyms of glossary terms	[if glossary enabled] Names and codes must not contain synonyms of glossary terms. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	Object names must be unique in the namespace. <ul style="list-style-type: none">• Manual correction: Modify the duplicate name or code.• Automatic correction: Appends a number to the duplicate name or code.
Existence of measure	A fact must have at least one measure. <ul style="list-style-type: none">• Manual correction: Create a measure in the Measures tab of the fact property sheet• Automatic correction: None
Fact mapping not defined	A fact must be mapped to tables or views in an operational model in order to be populated by data from this model. <ul style="list-style-type: none">• Manual correction: Map the fact to tables or views. You may need to create a data source before you can create the mapping• Automatic correction: Destroys the mapping for the fact. This removes the data source from the Mapping list in the fact Mapping tab
Measure mapping not defined	Fact measures must be mapped to columns in the data source tables or views. <ul style="list-style-type: none">• Manual correction: Map the fact measure to columns in the data source• Automatic correction: Destroys the mapping for the measure. This removes the measures that are not mapped to any object in the Measures Mapping tab of the fact Mapping tab

1.5.20 Fact Measure, Dimension Hierarchy, and Attribute Checks (PDM)

PowerDesigner provides default model checks to verify the validity of fact measures, dimension hierarchies, and fact and dimension attributes.

Check	Description and Correction
Name/Code contains terms not in glossary	[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: None.
Name/Code contains synonyms of glossary terms	[if glossary enabled] Names and codes must not contain synonyms of glossary terms. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	Object names must be unique in the namespace. <ul style="list-style-type: none">• Manual correction: Modify the duplicate name or code.• Automatic correction: Appends a number to the duplicate name or code.
Existence of attribute	[hierarchies only] A dimension hierarchy must have at least one attribute. <ul style="list-style-type: none">• Manual correction: Add an attribute to the hierarchy from the Attributes tab of the hierarchy property sheet• Automatic correction: None

1.5.21 Horizontal and Vertical Partitioning and Table Collapsing Checks (PDM)

PowerDesigner provides default model checks to verify the validity of horizontal and vertical partitioning and table collapsing objects.

Check	Description and Correction
Name/Code contains terms not in glossary	[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: None.
Name/Code contains synonyms of glossary terms	[if glossary enabled] Names and codes must not contain synonyms of glossary terms. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: Replaces synonyms with their associated glossary terms.

Check	Description and Correction
Name/Code uniqueness	<p>Object names must be unique in the namespace.</p> <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.
Existence of partition	<p>[horizontal and vertical partitionings] A partitioning object cannot be empty, it must contain at least one partition.</p> <ul style="list-style-type: none"> Manual correction: Delete the partitioning object or create at least one partition in its property sheet Automatic correction: Deletes empty horizontal partitioning object
Existence of target table	<p>[collapsings] A table collapsing must have a table as result of the collapsing.</p> <ul style="list-style-type: none"> Manual correction: Delete the table collapsing object Automatic correction: None
Unavailable target table	<p>A partition or collapsing object requires a table to act upon.</p> <ul style="list-style-type: none"> Manual correction: Delete the partitioning or collapsing with no corresponding table Automatic correction: Deletes the partitioning or collapsing with no corresponding table

1.5.22 Index and View Index Checks (PDM)

PowerDesigner provides default model checks to verify the validity of indexes and view indexes.

Check	Description and Correction
Name/Code contains terms not in glossary	<p>[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: None.
Name/Code contains synonyms of glossary terms	<p>[if glossary enabled] Names and codes must not contain synonyms of glossary terms.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	<p>Object names must be unique in the namespace.</p> <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.

Check	Description and Correction
Index code maximum length	<p>The index code length is limited by the maximum length specified in the DBMS definition (MaxLen entry, in the Objects Index category) or in the naming conventions of the model options.</p> <ul style="list-style-type: none"> Manual correction: Modify the index code length to meet this requirement Automatic correction: Truncates the index code length to the maximum length specified in the DBMS definition
Existence of index column	<p>An index must have at least one index column.</p> <ul style="list-style-type: none"> Manual correction: Add an index column from the Column tab of the index property sheet or delete the index Automatic correction: Deletes the index without column
Undefined index type	<p>[indexes] An index type must be specified.</p> <ul style="list-style-type: none"> Manual correction: Specify a type in the index property sheet or delete the index with no type Automatic correction: None
Index column count	<p>The current DBMS does not support more than the number of index columns specified in the MaxColIndex entry of the current DBMS.</p> <ul style="list-style-type: none"> Manual correction: Delete one or more columns in the index property sheet. You can create additional indexes for these columns Automatic correction: None
Uniqueness forbidden for HNG index type	<p>[indexes] An index of HNG (HighNonGroup) type cannot be unique.</p> <ul style="list-style-type: none"> Manual correction: Change the index type or set the index as non unique Automatic correction: None
Index inclusion	<p>An index should not include another index.</p> <ul style="list-style-type: none"> Manual correction: Delete the index that includes an existing index Automatic correction: None

1.5.23 Inheritance Checks (CDM/LDM)

PowerDesigner provides default model checks to verify the validity of inheritances.

Check	Description and Correction
Name/Code contains terms not in glossary	<p>[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: None.

Check	Description and Correction
Name/Code contains synonyms of glossary terms	[if glossary enabled] Names and codes must not contain synonyms of glossary terms. <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	Object names must be unique in the namespace. <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.
Existence of inheritance link	An inheritance must have at least one inheritance link, from the inheritance to the parent entity. <ul style="list-style-type: none"> Manual correction: Define the inheritance link or delete the inheritance. Automatic correction: None.
Incomplete inheritance with ungenerated ancestor	[LDM only] If an inheritance is incomplete, the parent should be generated because you can lose information. <ul style="list-style-type: none"> Manual correction: Generate parent entity or define the inheritance as complete. Automatic correction: None.

1.5.24 Join Index Checks (PDM)

PowerDesigner provides default model checks to verify the validity of join indexes and bitmap join indexes.

Check	Description and Correction
Name/Code contains terms not in glossary	[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary. <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: None.
Name/Code contains synonyms of glossary terms	[if glossary enabled] Names and codes must not contain synonyms of glossary terms. <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	Object names must be unique in the namespace. <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.
Existence of base table	Join index must have a base table. <ul style="list-style-type: none"> Manual correction: Select a base table in the join index property sheet Automatic correction: None

Check	Description and Correction
Reference without parent key	<p>Each reference associated with a join index must have a parent key.</p> <ul style="list-style-type: none"> Manual correction: Set the parent key on the Joins tab of the reference property sheet. Automatic correction: None
Join Index tables owners	<p>The tables associated to a join index must have the same owner.</p> <ul style="list-style-type: none"> Manual correction: Modify the join index owner or the table owner Automatic correction: None
Join index references connection	<p>Join index references must be connected to selected table on a linear axis.</p> <ul style="list-style-type: none"> Manual correction: Delete or replace references in the join index Automatic correction: None
Duplicated join indexes	<p>Join indexes cannot have the same set of references.</p> <ul style="list-style-type: none"> Manual correction: Delete one of the duplicated join indexes Automatic correction: None

1.5.25 Key Checks (PDM)

PowerDesigner provides default model checks to verify the validity of keys.

Check	Description and Correction
Name/Code contains terms not in glossary	<p>[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: None.
Name/Code contains synonyms of glossary terms	<p>[if glossary enabled] Names and codes must not contain synonyms of glossary terms.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	<p>Object names must be unique in the namespace.</p> <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.
Key code length	<p>The key code length is limited by the maximum length specified in the DBMS definition (MaxCons-tLen entry, in the category).</p> <ul style="list-style-type: none"> Manual correction: Modify the key code length to meet this requirement Automatic correction: Truncates the key code length to the maximum length specified in the DBMS definition

Check	Description and Correction
Key column exists	<p>Each key must have at least one column.</p> <ul style="list-style-type: none"> Manual correction: Add a column to the key from the Column tab of the key property sheet Automatic correction: Deletes key without column
Key inclusion	<p>A key cannot include another key (on some columns, regardless of their order).</p> <ul style="list-style-type: none"> Manual correction: Delete the key that includes an existing key Automatic correction: None
Multi-column key has sequence column	<p>Since the column initialized by a sequence is already a key, it should not be included in a multi-column key.</p> <ul style="list-style-type: none"> Manual correction: Detach the sequence from a column that is already part of a multi-column key Automatic correction: None

1.5.26 Lifecycle and Lifecycle Phase Checks (PDM)

PowerDesigner provides default model checks to verify the validity of lifecycles and phases.

Check	Description and Correction
Name/Code contains terms not in glossary	<p>[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: None.
Name/Code contains synonyms of glossary terms	<p>[if glossary enabled] Names and codes must not contain synonyms of glossary terms.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	<p>Object names must be unique in the namespace.</p> <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.
Existence of phases	<p>[lifecycle] A lifecycle must contain phases.</p> <ul style="list-style-type: none"> Manual correction: Add phases to the lifecycle (on the Phases tab) Automatic correction: None
Incorrect total retention setting	<p>[lifecycle] The total retention for the lifecycle must equal the retentions of all the phases.</p> <ul style="list-style-type: none"> Manual correction: Adjust the total retention or the retentions of individual phases as appropriate. Automatic correction: Adjust the total retention to equal the retentions of all the phases.

Check	Description and Correction
Invalid partition range setting	<p>[lifecycle] The partition range must be no longer than the shortest phase retention.</p> <ul style="list-style-type: none"> Manual correction: Reduce the partition range so that it is equal to the shortest phase retention. Automatic correction: Reduces the partition range so that it is equal to the shortest phase retention.
Existence of tablespace	<p>[phase] Specified tablespace does not exist.</p> <ul style="list-style-type: none"> Manual correction: Specify another tablespace. Automatic correction: None
Invalid tablespace setting	<p>[phase] The tablespace cannot be a catalog store.</p> <ul style="list-style-type: none"> Manual correction: Deselect the catalog store property on the tablespace property sheet. Automatic correction: Deselects the catalog store property.
Phase tablespace uniqueness	<p>[phase] Each phase must be associated with a different tablespace.</p> <ul style="list-style-type: none"> Manual correction: Move one or more phases to another tablespace. Automatic correction: None
Consistency of cost currency setting	<p>[phase] The same currency must be used for all tablespaces.</p> <ul style="list-style-type: none"> Manual correction: Harmonize the currency settings. Automatic correction: Applies the currency specified in the model options to all tablespaces.
Invalid retention setting	<p>[phase] Age-based lifecycle phases must have a retention period greater than 0.</p> <ul style="list-style-type: none"> Manual correction: Set the retention period to greater than 0. Automatic correction: Sets the retention period to 1.
Invalid idle period setting	<p>[phase] Access-based lifecycle phases must have an idle period greater than 0.</p> <ul style="list-style-type: none"> Manual correction: Set the idle period to greater than 0. Automatic correction: Sets the idle period to 1.
Existence of data source	<p>[phase] A lifecycle phase associated with an external database must have a data source specified.</p> <ul style="list-style-type: none"> Manual correction: Specify a data source for the phase. Automatic correction: None
Invalid lifecycle management scope	<p>[phase] Only the first phase in a lifecycle can have an external source. Subsequent phases must have the source set to the current database.</p> <ul style="list-style-type: none"> Manual correction: Set the phase source to the current database. Automatic correction: None

1.5.27 Package Checks (CDM/LDM/PDM)

PowerDesigner provides default model checks to verify the validity of packages.

Check	Description and Correction
Name/Code contains terms not in glossary	[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: None.
Name/Code contains synonyms of glossary terms	[if glossary enabled] Names and codes must not contain synonyms of glossary terms. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: Replaces synonyms with their associated glossary terms.
Circular references	[PDM only] A circular reference occurs when a table refers to another table, and so on until a loop is created between tables. A package cannot contain circular references. <ul style="list-style-type: none">• Manual correction: Resolve the circular reference by correcting the reference, deleting its source, or clearing the <i>Mandatory parent</i> or <i>Check on commit</i> option• Automatic correction: None
Constraint name uniqueness	[PDM only] A constraint name is a unique identifier for the constraint definition of tables, columns, primary and foreign keys in the database. You define the constraint name in the following tabs: <ul style="list-style-type: none">• <i>Check</i> tab of the table property sheet• <i>Additional Check</i> tab of the column property sheet• <i>General</i> tab of the key property sheet A constraint name must be unique in a model. <ul style="list-style-type: none">• Manual correction: Modify the duplicated constraint name in the corresponding tab• Automatic correction: Modifies the duplicated constraint name of a selected object by appending a number to its current name
Constraint name maximum length	[PDM only] The constraint name length cannot be longer than the length specified in the DBMS definition: either in the MaxConstLen entry, in the Object category, or in each object category. <ul style="list-style-type: none">• Manual correction: Modify the constraint name to meet this requirement• Automatic correction: Truncates the constraint name to the maximum length specified in the DBMS definition
Circular dependencies	[PDM only] Traceability links of type <<DBCreateAfter>> can be used to define a generation order for stored procedures and views. These links should not introduce circular dependencies in the model. <ul style="list-style-type: none">• Manual correction: Remove the link.• Automatic correction: None

Check	Description and Correction
Circular dependency	<p>[CDM/LDM only] A circular dependency occurs when an entity depends on another and so on until a dependency loop is created between entities. A package cannot contain circular dependencies.</p> <ul style="list-style-type: none"> Manual correction: Clear the Dependent check box for the link or delete an inheritance link. Automatic correction: None.
Circularity with mandatory links	<p>[CDM/LDM only] A circular dependency occurs when an entity depends on another and so on until a dependency loop is created between entities through mandatory links.</p> <ul style="list-style-type: none"> Manual correction: Clear the <i>Mandatory parent</i> check box or delete a dependency on a relationship. Automatic correction: None.
Shortcut code uniqueness	<p>Shortcuts codes must be unique in a namespace.</p> <ul style="list-style-type: none"> Manual correction: Change the code of one of the shortcuts Automatic correction: None
Shortcut potentially generated as child table of a reference	<p>[CDM/LDM only] The package should not contain associations or relationships with an external shortcut as child entity. Although this can be tolerated in the CDM, the association or relationship will not be generated in a PDM if the external shortcut is generated as a shortcut.</p> <ul style="list-style-type: none"> Manual correction: Modify the design of your model in order to create the association or relationship in the package where the child entity is defined. Automatic correction: None.

1.5.28 Procedure Checks (PDM)

PowerDesigner provides default model checks to verify the validity of procedures.

Check	Description and Correction
Name/Code contains terms not in glossary	<p>[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: None.
Name/Code contains synonyms of glossary terms	<p>[if glossary enabled] Names and codes must not contain synonyms of glossary terms.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	<p>Object names must be unique in the namespace.</p> <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.

Check	Description and Correction
Procedure code maximum length	<p>The procedure code length is limited by the maximum length specified in the DBMS definition (MaxLen entry, in the  Objects  category).</p> <ul style="list-style-type: none"> Manual correction: Modify the procedure code length to meet this requirement Automatic correction: Truncates the procedure code length to the maximum length specified in the DBMS definition
Procedure definition body empty	<p>A procedure definition should have a body to specify its functionality.</p> <ul style="list-style-type: none"> Manual correction: Specify the procedure body on the Body tab of its property sheet Automatic correction: None
Existence of permission	<p>Permissions are usage restrictions set on a procedure for a particular user, group or role.</p> <ul style="list-style-type: none"> Manual correction: Define permissions on the procedure for users, groups and roles Automatic correction: None

1.5.29 Reference and View Reference Checks (PDM)

PowerDesigner provides default model checks to verify the validity of references and view references.

Check	Description and Correction
Name/Code contains terms not in glossary	<p>[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: None.
Name/Code contains synonyms of glossary terms	<p>[if glossary enabled] Names and codes must not contain synonyms of glossary terms.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	<p>Object names must be unique in the namespace.</p> <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.
Reflexive and mandatory reference	<p>[references only] A reflexive reference exists should not have a mandatory parent which could lead to inconsistent joins.</p> <ul style="list-style-type: none"> Manual correction: Correct the reference by clearing the Mandatory parent check box Automatic correction: None

Check	Description and Correction
Existence of reference join	<p>A reference must have at least one reference join.</p> <ul style="list-style-type: none"> Manual correction: Create a reference join for the reference or delete the reference Automatic correction: Deletes reference without join
Reference code maximum length	<p>[references only] The reference code length is limited by the maximum length specified in the DBMS definition (MaxConstLen entry, in the category) or in the naming conventions of the model options.</p> <ul style="list-style-type: none"> Manual correction: Modify the reference code length to meet this requirement Automatic correction: Truncates the reference code length to the maximum length specified in the DBMS definition
Incomplete join	<p>[references only] Joins must be complete.</p> <ul style="list-style-type: none"> Manual correction: Select a foreign key column or activate the primary key column migration Automatic correction: None
Join order	<p>[references only] The join order must be the same as the key column order for some DBMS.</p> <ul style="list-style-type: none"> Manual correction: If required, change the join order to reflect the key column order Automatic correction: The join order is changed to match the key column order

1.5.30 Relationship Checks (CDM/LDM)

PowerDesigner provides default model checks to verify the validity of relationships.

Check	Description and Correction
Name/Code contains terms not in glossary	<p>[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: None.
Name/Code contains synonyms of glossary terms	<p>[if glossary enabled] Names and codes must not contain synonyms of glossary terms.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	<p>Object names must be unique in the namespace.</p> <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.

Check	Description and Correction
Reflexive dependency	<p>A dependency means that one entity is defined through a relationship with another. A dependent relationship cannot therefore be reflexive.</p> <ul style="list-style-type: none"> Manual correction: Change or delete the reflexive dependency. Automatic correction: None.
Reflexive mandatory	<p>A reflexive mandatory relationship exists.</p> <ul style="list-style-type: none"> Manual correction: Deselect the Mandatory check boxes for the relationship to be non-mandatory. Automatic correction: None.
Bijective relationship between two entities	<p>There is a bijective relationship between two entities when there is a two-way one to one relationship between the entities. This is equivalent to a merge of two entities.</p> <ul style="list-style-type: none"> Manual correction: Merge the entities or modify the relationship. Automatic correction: None.
Name uniqueness constraint between many-to-many relationships and entities	<p>A many-to-many relationship and an entity cannot have the same name or code.</p> <ul style="list-style-type: none"> Manual correction: Change the name or code of the many-to-many relationship or the name or code of the entity. If you do not, PDM generation will rename the generated table. Automatic correction: None.
Consistency between dominant and dependent relationships	<p>A dependent relationship between entities cannot also be a dominant relationship.</p> <ul style="list-style-type: none"> Manual correction: Select the Dominant check box on the other (correct) side of the relationship. Automatic correction: None.
Identifier link from child entity	<p>[Barker notation CDM only] A child entity may not be dependant on any entity other than its parents.</p> <ul style="list-style-type: none"> Manual correction: Remove the dependant relationship with the non-parent. Automatic correction: None
'Many-many' relationships	<p>[LDM only] 'Many-to-many' relationships are not permitted.</p> <ul style="list-style-type: none"> Manual correction: Create an intermediary entity, which contains the primary identifiers of the previous 'many-to-many' entities. Automatic correction: None.

1.5.31 Sequence Checks (PDM)

PowerDesigner provides default model checks to verify the validity of sequences.

Check	Description and Correction
Name/Code contains terms not in glossary	[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: None.
Name/Code contains synonyms of glossary terms	[if glossary enabled] Names and codes must not contain synonyms of glossary terms. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	Object names must be unique in the namespace. <ul style="list-style-type: none">• Manual correction: Modify the duplicate name or code.• Automatic correction: Appends a number to the duplicate name or code.
Sequence code maximum length	The code of the sequence is longer than the maximum allowed by the DBMS. <ul style="list-style-type: none">• Manual correction: Reduce the length of the code• Automatic correction: Reduces the code to a permissible length

1.5.32 Synonym Checks (PDM)

PowerDesigner provides default model checks to verify the validity of synonyms.

Check	Description and Correction
Name/Code contains terms not in glossary	[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: None.
Name/Code contains synonyms of glossary terms	[if glossary enabled] Names and codes must not contain synonyms of glossary terms. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	Object names must be unique in the namespace. <ul style="list-style-type: none">• Manual correction: Modify the duplicate name or code.• Automatic correction: Appends a number to the duplicate name or code.

Check	Description and Correction
Synonym name and code maximum length	<p>The synonym name and code length is limited by the maximum length specified in the DBMS definition (MaxLen entry, in the Objects Synonym category) and in the naming conventions of the model options.</p> <ul style="list-style-type: none"> Manual correction: Modify the name/code length to meet this requirement Automatic correction: Truncates the name/code length to the maximum length specified in the DBMS definition
Existence of the base object	<p>A synonym must correspond to a model object. By default, when you create synonyms from the List of Synonyms using the <i>Add a Row</i> tool, they are not attached to any base object.</p> <ul style="list-style-type: none"> Manual correction: Select a base object from the synonym property sheet Automatic correction: Deletes the synonym

1.5.33 Table and View Checks (PDM)

PowerDesigner provides default model checks to verify the validity of tables and views.

Check	Description and Correction
Name/Code contains terms not in glossary	<p>[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: None.
Name/Code contains synonyms of glossary terms	<p>[if glossary enabled] Names and codes must not contain synonyms of glossary terms.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	<p>Object names must be unique in the namespace.</p> <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.
Name and code length	<p>The table and view name and code length is limited by the maximum length specified in the DBMS definition (MaxLen entry, in the Objects Table and View categories) and in the naming conventions of the model options.</p> <ul style="list-style-type: none"> Manual correction: Modify the name/code length to meet this requirement Automatic correction: Truncates the name/code length to the maximum length specified in the DBMS definition

Check	Description and Correction
Constraint name conflicts with index name	<p>[tables only] A constraint name of the table cannot be the same as an index name.</p> <ul style="list-style-type: none"> Manual correction: Change the name of the table constraint Automatic correction: None
Existence of column, reference, index, key	<p>[tables only] A table should contain at least one column, one index, one key, and one reference.</p> <ul style="list-style-type: none"> Manual correction: Add missing item to the definition of the table Automatic correction: None
Number of auto-incremented columns	<p>[tables only] Auto-incremented columns contain automatically calculated values. A table cannot contain more than one auto-incremented column.</p> <ul style="list-style-type: none"> Manual correction: Delete all but one auto-incremented column Automatic correction: None
Table index definition uniqueness	<p>[tables only] Identical indexes are indexes with the same columns, order and type. A table cannot have identical indexes.</p> <ul style="list-style-type: none"> Manual correction: Delete index or change its properties Automatic correction: None
Table mapping not defined	<p>[tables only] When a table belongs to a model containing one or several data sources, it must be mapped to tables or views in the data source in order to establish a relational to relational mapping.</p> <ul style="list-style-type: none"> Manual correction: Map the current table to one or several tables or views in the model belonging to the data source Automatic correction: Destroys the mapping for the table. This removes the data source from the Mapping list in the table Mapping tab
Column mapping not defined	<p>[tables only] When a column belong to a table in a model containing one or several data sources, it should be mapped to columns in the data source in order to establish a relational to relational mapping.</p> <ul style="list-style-type: none"> Manual correction: Map the current column to one or several columns in the models belonging to the data source Automatic correction: Destroys the mapping for the column. This removes the columns that are not mapped to any object in the Columns Mapping tab of the table Mapping tab
Existence of permission	<p>Permissions are usage restrictions set on a table or view for a particular user, group or role.</p> <ul style="list-style-type: none"> Manual correction: Define permissions on the table or view for users, groups and roles Automatic correction: None
Existence of partition key	<p>[tables only] A table managed by an age-based lifecycle policy must have a column specified as its partition key.</p> <ul style="list-style-type: none"> Manual correction: Specify a column as the partition key. Automatic correction: None

Check	Description and Correction
Invalid start date setting	<p>[tables only] A table managed by an age-based lifecycle policy must not have a start date earlier than the start date of the lifecycle.</p> <ul style="list-style-type: none"> Manual correction: Change one or other date so that the table start date is equal to or later than the lifecycle start date. Automatic correction: Changes the table start date to the lifecycle start date.
Missing lifecycle policy	<p>[tables only] A table managed by a lifecycle must not reference tables not managed by a lifecycle.</p> <ul style="list-style-type: none"> Manual correction: Add the referenced tables to the lifecycle. Automatic correction: None
Invalid mapping from source table	<p>[tables only] In a lifecycle where the first phase references an external database, each archive table must be mapped to exactly one external table.</p> <ul style="list-style-type: none"> Manual correction: Remove the additional mappings. Automatic correction: None
Partial column mapping of source table	<p>[tables only] In a lifecycle where the first phase references an external database, all columns in each source table must be mapped to columns in the same archive table.</p> <ul style="list-style-type: none"> Manual correction: Create the missing mappings. Automatic correction: None
Existence of partition key mapping	<p>[tables only] In a lifecycle where the first phase references an external database, the partition key column in the archive table must be mapped to a column in the source table.</p> <ul style="list-style-type: none"> Manual correction: Create the missing mapping. Automatic correction: None
Tablespace outside lifecycle	<p>[tables only] A table managed by a lifecycle must be assigned to a tablespace associated with the lifecycle.</p> <ul style="list-style-type: none"> Manual correction: Assign the table to a tablespace associated with the lifecycle. Automatic correction: If the table is not assigned to any tablespace it will be assigned to the tablespace associated with the first phase of the lifecycle.

1.5.34 Tablespace and Storage Checks (PDM)

PowerDesigner provides default model checks to verify the validity of tablespaces and storages.

Check	Description and Correction
Name/Code contains terms not in glossary	<p>[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: None.

Check	Description and Correction
Name/Code contains synonyms of glossary terms	[if glossary enabled] Names and codes must not contain synonyms of glossary terms. <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	Object names must be unique in the namespace. <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.
Code maximum length	The code of the tablespace or storage is longer than the maximum allowed by the DBMS. <ul style="list-style-type: none"> Manual correction: Reduce the length of the code Automatic correction: Reduces the code to a permissible length
Not used	The tablespace or storage you have created is not used in the model. <ul style="list-style-type: none"> Manual correction: Delete the tablespace or storage or apply it as a physical option to a table, an index, a key, a column, a storage or a view (Options tab of the object property sheet) Automatic correction: None

1.5.35 Trigger and DBMS Trigger Checks (PDM)

PowerDesigner provides default model checks to verify the validity of triggers and DBMS triggers.

Check	Description and Correction
Name/Code uniqueness	Object names must be unique in the namespace. <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.
Trigger code maximum length	The trigger code length is limited by the maximum length specified in the DBMS definition (MaxLen). <ul style="list-style-type: none"> Manual correction: Modify the trigger code length to meet this requirement Automatic correction: Truncates the trigger code length to the maximum length specified in the DBMS definition
Invalid event	The event specified in the DBMS trigger definition must be available in its chosen scope. <ul style="list-style-type: none"> Manual correction: Modify the trigger code to reference an event in the chosen scope. Automatic correction: None

1.5.36 User, Group, and Role Checks (PDM)

PowerDesigner provides default model checks to verify the validity of users, groups, and roles.

Check	Description and Correction
Name/Code contains terms not in glossary	[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: None.
Name/Code contains synonyms of glossary terms	[if glossary enabled] Names and codes must not contain synonyms of glossary terms. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	Object names must be unique in the namespace. <ul style="list-style-type: none">• Manual correction: Modify the duplicate name or code.• Automatic correction: Appends a number to the duplicate name or code.
Code maximum length	The code length is limited by the maximum length specified in the DBMS definition (MaxLen entry, in the  Objects  and  categories). <ul style="list-style-type: none">• Manual correction: Modify the code length to meet this requirement• Automatic correction: Truncates the code length to the maximum length specified in the DBMS definition
Existence of user	[groups, roles] A group is created to factorize privilege and permission granting to users. A group without user members is useless. <ul style="list-style-type: none">• Manual correction: Add users to group or delete group• Automatic correction: Deletes unassigned group
Password empty	[users, groups] Users and groups must have a password to be able to connect to the database. <ul style="list-style-type: none">• Manual correction: Define a password for the user or group• Automatic correction: None

1.5.37 View Checks (PDM)

PowerDesigner provides default model checks to verify the validity of views.

Check	Description and Correction
Name/Code contains terms not in glossary	[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary. <ul style="list-style-type: none">• Manual correction: Modify the name or code to contain only glossary terms.• Automatic correction: None.

Check	Description and Correction
Name/Code contains synonyms of glossary terms	<p>[if glossary enabled] Names and codes must not contain synonyms of glossary terms.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	<p>Object names must be unique in the namespace.</p> <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.
View code maximum length	<p>The view code length is limited by the maximum length specified for the table code length.</p> <ul style="list-style-type: none"> Manual correction: Modify the view code length to meet this requirement Automatic correction: Truncates the view code length to the maximum length specified in the DBMS definition
Existence of permission	<p>Permissions are usage restrictions set on a view for a particular user, group or role.</p> <ul style="list-style-type: none"> Manual correction: Define permissions on the view for users, groups and roles Automatic correction: None

1.5.38 Web Service and Web Operation Checks (PDM)

PowerDesigner provides default model checks to verify the validity of Web services and Web operations.

Check	Description and Correction
Name/Code contains terms not in glossary	<p>[if glossary enabled] Names and codes must contain only approved terms drawn from the glossary.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: None.
Name/Code contains synonyms of glossary terms	<p>[if glossary enabled] Names and codes must not contain synonyms of glossary terms.</p> <ul style="list-style-type: none"> Manual correction: Modify the name or code to contain only glossary terms. Automatic correction: Replaces synonyms with their associated glossary terms.
Name/Code uniqueness	<p>Object names must be unique in the namespace.</p> <ul style="list-style-type: none"> Manual correction: Modify the duplicate name or code. Automatic correction: Appends a number to the duplicate name or code.

Check	Description and Correction
Code maximum length	<p>Web service and Web operation code lengths are limited by the maximum length specified in the DBMS definition (Maxlen entry, in the Objects Web Service and Web Operation categories).</p> <ul style="list-style-type: none"> • Manual correction: Modify the code length to meet this requirement • Automatic correction: Truncates the code length to the maximum length specified in the DBMS definition

1.6 Generating and Reverse-Engineering Databases

PowerDesigner provides full support for round trip generation and reverse-engineering between a PDM and a database.

1.6.1 Writing SQL Code in PowerDesigner

The objects that you create in your model display the SQL code that will be generated for them on the [Preview](#) tab of their property sheets. Certain objects provide editors on other tabs to allow you to modify the SQL statements.

For example, you may need to write SQL code in order to:


- Specify a view query (see [View Queries \[page 125\]](#)).
- Write a trigger (see [Triggers \(PDM\) \[page 130\]](#)) or procedure (see [Stored Procedures and Functions \(PDM\) \[page 148\]](#)).
- Define a computed column (see [Creating a Computed Column \[page 112\]](#)).
- Insert scripts at the beginning and/or end of database or table creation (see [Customizing Creation Statements \[page 310\]](#)).

The following tools are available in the PowerDesigner SQL editors:

Tool	Description
	<i>Add Trigger Item From Model / DBMS</i> - [triggers and trigger templates only] Opens a dialog box to list trigger template items defined in the model or in the DBMS definition file for insertion in the trigger body (see Trigger Template Items [page 140]).
	<i>Operators / Functions</i> - List logical operators and group, number, string, date, conversion and other functions for insertion in the SQL code. Operators and functions are DBMS-specific and these lists are populated from entries in the <i>Script\Sql\Keywords</i> category (see Customizing and Extending PowerDesigner > DBMS Definition Files > Script/Sql Category).


Tool	Description
	<i>Macros / Variables</i> - List PDM macros and variables for insertion in the SQL code (see Customizing and Extending PowerDesigner > DBMS Definition Files > PDM Variables and Macros). You can also use formatting variables to force values to lower-case or upper-case or to truncate the length of values characters.
	<i>Edit with SQL Editor</i> - Opens the full SQL Editor dialog which gives access to model objects for insertion in the SQL code.
	<i>SQL/XML Wizard</i> - [procedures only] Opens the SQL/XML Wizard to build a SQL/XML query from a table or a view for insertion in the SQL code (see Creating SQL/XML Queries with the Wizard [page 159]).
	<i>Insert SQL/XML Macro</i> - Opens a dialog box to select a global element from an XML model open in the workspace (and which must have the SQL/XML extension file attached) for insertion in the SQL code.

In addition to these tools, the pop-out SQL Editor lists PDM object types in the upper left pane and the available objects of the selected type in the upper right pane. Double-click an object to insert it into your code in the lower pane:




You can use the PowerDesigner Generation Template Language (GTL) and PDM variables and macros to reference objects and object properties and iterate over collections when writing SQL statements. While you can perform many tasks using the PDM variables and macros, GTL is more powerful, as it allows you to access any information about any object in the model.


In the following example, a trigger is written using the PDM variables and macros and attached to the Example table, to write the contents of any insertion to HistoryTable.



The same trigger can be written using GTL:




In each case, the trigger code to be generated is the same, and can be viewed by clicking the *Preview* tab:



For detailed information about working with GTL, see *Customizing and Extending PowerDesigner > Customizing Generation with GTL*. For lists of the available variables and macros, see *Customizing and Extending PowerDesigner > DBMS Definition Files > PDM Variables and Macros*.

1.6.2 Previewing SQL Statements

Click the *Preview* tab in the property sheet of the model, packages, tables, and various other model objects in order to view the code that will be generated for it.



The text in the script preview is color coded as follows:

Text color	Represents
Blue	SQL reserved word
Black	Statement body
Red	Variable
Green	Comment

The following tools are available on the *Preview* tab toolbar:

Tools	Description
	<p><i>Editor Menu</i> (<code>Shift</code> + <code>F11</code>) - Contains the following commands:</p> <ul style="list-style-type: none"> • <i>New</i> (<code>Ctrl</code> + <code>N</code>) - Reinitializes the field by removing all the existing content. • <i>Open...</i> (<code>Ctrl</code> + <code>O</code>) - Replaces the content of the field with the content of the selected file. • <i>Insert...</i> (<code>Ctrl</code> + <code>I</code>) - Inserts the content of the selected file at the cursor. • <i>Save</i> (<code>Ctrl</code> + <code>S</code>) - Saves the content of the field to the specified file. • <i>Save As...</i> - Saves the content of the field to a new file. • <i>Select All</i> (<code>Ctrl</code> + <code>A</code>) - Selects all the content of the field. • <i>Find...</i> (<code>Ctrl</code> + <code>F</code>) - Opens a dialog to search for text in the field. • <i>Find Next...</i> (<code>F3</code>) - Finds the next occurrence of the searched for text. • <i>Find Previous...</i> (<code>Shift</code> + <code>F3</code>) - Finds the previous occurrence of the searched for text. • <i>Replace...</i> (<code>Ctrl</code> + <code>H</code>) - Opens a dialog to replace text in the field. • <i>Go To Line...</i> (<code>Ctrl</code> + <code>G</code>) - Opens a dialog to go to the specified line. • <i>Toggle Bookmark</i> (<code>Ctrl</code> + <code>F2</code>) - Inserts or removes a bookmark (a blue box) at the cursor position. Note that bookmarks are not printable and are lost if you refresh the tab, or use the <i>Show Generation Options</i> tool • <i>Next Bookmark</i> (<code>F2</code>) - Jumps to the next bookmark. • <i>Previous Bookmark</i> (<code>Shift</code> + <code>F2</code>) - Jumps to the previous bookmark.
	<p><i>Edit With</i> (<code>Ctrl</code> + <code>E</code>) - Opens the previewed code in an external editor. Click the down arrow to select a particular editor or <i>Choose Program</i> to specify a new editor. Editors specified here are added to the list of editors available at ► <i>Tools</i> > <i>General Options</i> > <i>Editors</i> ▾</p>
	<i>Save</i> (<code>Ctrl</code> + <code>S</code>) - Saves the content of the field to the specified file.
	<i>Print</i> (<code>Ctrl</code> + <code>P</code>) - Prints the content of the field.
	<i>Find</i> (<code>Ctrl</code> + <code>F</code>) - Opens a dialog to search for text.
	<i>Cut</i> (<code>Ctrl</code> + <code>X</code>), <i>Copy</i> (<code>Ctrl</code> + <code>C</code>), and <i>Paste</i> (<code>Ctrl</code> + <code>V</code>) - Perform the standard clipboard actions.
	<i>Undo</i> (<code>Ctrl</code> + <code>Z</code>) and <i>Redo</i> (<code>Ctrl</code> + <code>Y</code>) - Move backward or forward through edits.
	<p><i>Refresh</i> (<code>F5</code>) - Refreshes the Preview tab.</p> <p>You can debug the GTL templates that generate the code shown in the Preview tab. To do so, open the target or extension resource file, select the <i>Enable Trace Mode</i> option, and click <i>OK</i> to return to your model. You may need to click the <i>Refresh</i> tool to display the templates.</p>
	<p><i>Select Generation Targets</i> (<code>Ctrl</code> + <code>F6</code>) - Lets you select additional generation targets (defined in extensions), and adds a sub-tab for each selected target. For information about generation targets, see <i>Customizing and Extending PowerDesigner</i> > <i>Extension Files</i> > <i>Generated Files (Profile)</i> > <i>Generating Your Files in a Standard or Extended Generation</i>.</p>

Tools	Description
	<i>Show Generation Options</i> (Ctrl + W) - Opens the Generation Options dialog, allowing you to modify the generation options and to see the impact on the code.
	<i>Ignore Generation Options</i> (Ctrl + D) - Ignores changes to the generation options made with the <i>Show Generation Options</i> tool.

Ignore Generation Options

If you click the Ignore Generation Options tool, the preview ignores generation options selected by using the Change generation options tool but uses a predefined set of options.

Selected tool	Effect on generation options	Effect on preview
Change generation options	You can select generation options	Visible in Preview if options are applicable
Ignore generation options	Generation options currently selected are overridden by predefined set of options	Only predefined options are visible in Preview
Change generation options + Ignore generation options	You can select generation options	Changes ignored in Preview

The predefined set of generation options selects these items:

Generation Option Tab	Selected items
Tables and Views	All items except drop options
Keys and Indexes	All items except options represented differently in some DBMS. For example, if a database is auto indexed, the index options corresponding to the keys are not selected
Database	All items except drop options
Options	All user-defined options are used

1.6.3 Connecting to a Database

PowerDesigner allows you to define data connections to access information in different database management systems (DBMSs) using Structured Query Language (SQL).

Context


Before connecting to your database for the first time, you will have to configure a PowerDesigner connection profile. Your choice will depend on the interface that you have installed:

You have	Configure a connection of type:
ODBC driver	ODBC machine or file data source
JDBC driver	JDBC connection profile

For detailed information about creating, configuring, and using connection profiles, see *Core Features Guide > Modeling with PowerDesigner > Getting Started with PowerDesigner > Connecting to a Database*.

Procedure

1. Select to open the Connect to a Data Source window:



2. Select one of the following radio buttons, depending on your chosen method for connecting to your database:

- ODBC machine data source
- ODBC file data source
- Connection profile (for JDBC connections)

You can use the tools to the right of the data source field to browse to a new connection profile file or directory, and the *Modify* and *Configure* buttons to modify or configure your data source connection.

3. Enter your user ID and password, and then click *Connect*. If prompted by your database, you may need to enter additional connection parameters.

You stay connected until you disconnect or terminate the shell session.

You can display information about your connection at any time by selecting *Database* *Connection Information*. The amount of information available depends on your DBMS and your connection profile.

To disconnect from a database, select *Database* *Disconnect*.

1.6.3.1 Executing SQL Queries

You can send SQL queries to a database and display the results.

Procedure

1. Select *Database* *Execute SQL*.

If you are not already connected to a database, the Connect to Data Source window will open. Choose your connection profile and click *Connect* to proceed to the Execute SQL Query dialog.

2. Type one or more SQL statements in the window, and click *Run* to apply them to the database.

The screenshot shows the SAP PowerDesigner 'Execute SQL Query' dialog box with the title 'Execute SQL Query - crebas.sql'. The query editor contains the following SQL script:

```
alter table PROJ.EMPLOYEE
    delete foreign key FK_EMPLOYEE_CHIEF_EMPLOYEE;

alter table PROJ.COMPOSE
    delete foreign key FK_COMPOSE_COMPOSED_MATERIAL;

alter table PROJ.COMPOSE
    delete foreign key FK_COMPOSE_COMPOSES_MATERIAL;

alter table PROJ.PARTICIPATE
    delete foreign key FK_PARTICIP_IS_DONE_B_TASK;

alter table PROJ.MEMBER
    delete foreign key FK_MEMBER_IS_MEMBER_EMPLOYEE;

alter table PROJ.PROJECT
```

The status bar at the top right indicates 'Ln 25, Col 1'. At the bottom of the dialog are buttons for 'Run', 'Close', and 'Help'.

The query results are displayed in the Results window.

1.6.4 Generating a Database from a PDM

PowerDesigner can generate sophisticated SQL scripts as files or for direct execution via a live database connection.


Context

i Note

To generate to a SAP HANA® 1.0 database, use the HANA wizard (see [Exporting Objects to the HANA Repository \[page 535\]](#)).

Procedure

1. Select **Database > Generate Database** to open the Database Generation dialog box.



Note


To load a pre-configured selection or settings set (see [Quick Launch Selection and Settings Sets \[page 308\]](#)), select it in the appropriate list in the **Quick launch** group box.

2. Enter a destination **Directory** and **File Name** for the script file.
3. Specify the type of generation (script or live database connection) to perform:
 - Script generation - generate a script to be executed on a DBMS at a later time. Optionally select **One file only** to create the generation script as a single file. By default, a separate script file is created for each table.
 - Direct generation – generate a script and execute it on a live database connection. Optionally select **Edit generation script** to open the script in an editor for review or editing before execution.
4. [optional] Select the following options as appropriate:

Option	Description
Check model	Specifies that a model check is performed before script generation.
Automatic archive	Creates an archive version of the PDM after generation to use to determine changes during your next database modification (see Archive PDMs [page 337]).


5. [optional] To change the default generation options, click the **Options** tab (see [Database Generation Dialog Options Tab \[page 303\]](#)).

- [optional] To change the format of your script, click the *Format* tab (see [Database Generation Dialog Format Tab \[page 306\]](#)).
- [optional] To control which database objects will be generated, click the *Selection* tab:




You can save your selection via the Selection bar at the bottom of the tab (see [Quick Launch Selection and Settings Sets \[page 308\]](#)).

- [optional] Click the *Summary* tab to view the summary of your settings and selections. The summary is not editable, but you can search, save, print, and copy its contents.



9. [optional] Click the [Preview](#) tab to preview the SQL script to be generated. The script is not editable, but you can search, save, print, and copy its contents.



10. Click **OK** to begin the generation.

If you are generating a database script, the *Output* window shows the progress of the generation process, and gives instructions for running the script. When generation is complete, the Generated Files dialog opens listing the paths to the generated script files. Click *Edit* to open the script in a text editor or *Close* to close the Result box.

i Note

For information about the additional steps required to generate for MS Access, see [Generating a Microsoft Access Database \[page 633\]](#).

If you are generating a database directly, and are not currently connected to a database, a dialog box asks you to identify a data source and connection parameters (see [Connecting to a Database \[page 296\]](#)).

Results


i Note

Advanced users can further customize database generation by, for example, changing the order in which objects are generated, adding scripts to run before or after generation, and generating additional objects. For information about these and other advanced topics, see *Customizing and Extending PowerDesigner > DBMS Definition Files*.

1.6.4.1 Database Generation Dialog Options Tab

The Options tab allows you to specify what script elements to generate for each object type.

By default, there is an entry in the left-hand pane under the meta-category "All Objects" for each object type present in your model, and all the possible options are displayed in the right-hand pane. If you click on an object type in the left-hand pane, then the options are restricted to that object type.



Depending on the objects present in your model, some or all of the following options will be available.

Parameter	Description
Create <object>	<p>Generates the object.</p> <p>When generating primary, alternate, or foreign keys or indexes, you can choose between:</p> <ul style="list-style-type: none">Inside Table – keys or indexes are generated during table creationOutside - keys or indexes are generated with a separate SQL command, generally using an ALTER command after the creation of the table <p>The generation of keys or indexes outside the table is possible only if the Create entry exists in the Pkey, Key, Reference, and/or Index categories of your DBMS.</p>

Parameter	Description
Drop <object>	<p>Deletes an existing object, before recreating it.</p> <p>Note that when generating defaults, if the Create and Drop check boxes are selected, the default objects will be created/dropped before domains and tables. For more information on the default generation statement, see <i>Customizing and Extending PowerDesigner > DBMS Definition Files</i>.</p>
Begin script	Inserts a customized script before creation of the object.
End script	Inserts a customized script after creation of the object.
Physical options	Generates physical options for the object.
Comment	Generates a comment for the object.
Privilege	[users, groups, and roles] Generates privileges for the user, group, or role.
Permission	Generates the permission statement for a given user during creation of the object.
Check	<p>[domains, tables, and columns] Generates check parameters and validation rules for domains, tables, and columns.</p> <p>For table and columns, if this option is selected you can choose between:</p> <ul style="list-style-type: none"> • Inside Table - checks are generated during table creation • Outside - checks are generated with a separate SQL command, generally using an ALTER command after the creation of the table <p>The generation of checks outside the table is possible only if the AddTableCheck entry exists in the Table category of your DBMS.</p>
Open database	[databases] Opens the database.
Close database	[databases] Closes the database.
Default value	[domains and columns] Specifies a default value for the domain or column.
Install JAVA class	[abstract data types] Installs a Java class, which is stored on a server.
Remove JAVA class	[abstract data types] Deletes an existing Java class, before installing a new Java class.
User-defined type	[columns] Generates a user-defined data type for the column.


Parameter	Description
Decl. Integrity	[foreign keys] Generates declarative referential integrity for references specified to be Declarative in their property sheets. You can specify any or all of the following: <ul style="list-style-type: none"> • Update constraint restrict • Update constraint cascade • Update constraint set null • Update constraint set default • Delete constraint restrict • Delete constraint cascade • Delete constraint set null • Delete constraint set default
Index Filter	[indexes] You can specify from none to all of: <ul style="list-style-type: none"> • Primary key - Generates primary key indexes • Foreign key - Generates foreign key indexes • Alternate key - Generates alternate key indexes • Cluster - Generates cluster indexes • Others - Generates indexes for all key columns with a defined index
Trigger Filter	[triggers] You can specify the creation of triggers: <ul style="list-style-type: none"> • For insert • For update • For delete
Synonym Filter	[synonyms] You can specify from none to all of: <ul style="list-style-type: none"> • Table - Generates table synonyms • View - Generates view synonyms • Procedure - Generates procedure synonyms • Synonym - Generates synonym synonyms • Database Package - Generates database package synonyms • Sequence - Generates sequence synonyms

Parameter	Description
Force column list	<p>[views] Generates a view with a list of columns, even if this list is identical to the corresponding columns in the SQL order. Allows you to generate the list of view columns with the view creation order. By default, the list of view columns is generated only if it is different from the list of columns of the view query. For example, in the following view query:</p> <pre>select a, b from Table1</pre> <p>columns a and b are view columns by default. The default generation statement is:</p> <pre>create view V1 as select a, b from Table1</pre> <p>If you select the <i>Force column list</i> option, the generation statement will become:</p> <pre>create view V1(a,b) as select a, b from Table1</pre>

You can save your option settings via the *Settings set* bar at the bottom of the tab. For more information, see [Quick Launch Selection and Settings Sets \[page 308\]](#).

1.6.4.2 Database Generation Dialog Format Tab

The options on the Format tab allow you to control the format of database generation scripts.



Some of the following options may not be available, depending on your target database.

You can save your format settings via the Settings set bar at the bottom of the tab. For more information, see [Quick Launch Selection and Settings Sets \[page 308\]](#).

Option	Result of selection
Database prefix	Table and view names in the script are prefixed by the database name.
Identifier delimiter	Specifies the characters used to delimit identifiers (for example, table and view names). Most DBMSs require a double-quote character ("), but some permit other forms of delimiter.
Owner prefix	Table and view names in the script are prefixed by their owner names. For those DBMSs that support sequence owners, this option will also prefix sequence names by their owner names.
Title	Each section of the script includes commentary in the form of titles (for example, Database Name: TUTORIAL).
Generate name in empty comment	For those DBMSs that support comments, this option allows to generate the name in the comment when the comment box is empty. This option applies to tables, columns, and views. The comment generated using the object name will be reversed as a comment.

Option	Result of selection
Encoding	Specifies an encoding format. You should select a format that supports the language used in your model and the database encoding format.
Character case	Specifies the case to use in the script. You can choose between: <ul style="list-style-type: none"> • Upper - all uppercase characters • Lower - all lowercase characters • Mixed - lowercase and uppercase characters
No accent	Non-accented characters replace accented characters in script


1.6.4.3 Quick Launch Selection and Settings Sets

The Quick Launch groupbox at the bottom of the Database Generation dialog [General](#) tab allows you to load pre-configured selections and settings sets for use when generating the database.

- Selection - the ensemble of selections of database objects made on the [Selection](#) tab. To save a selection, enter a name in the Selection bar at the bottom of the [Selection](#) tab and then click the [Save](#) tool. The selection is saved as part of the model file.
- Settings Set - the ensemble of generation options (see [Database Generation Dialog Options Tab \[page 303\]](#)) and format options (see [Database Generation Dialog Format Tab \[page 306\]](#))

To save a settings set, enter a name in the Settings set bar at the bottom of the [Options](#) or [Format](#) tab and then click the [Save](#) tool, specify whether you want to save the settings set inside the model or as an external file, and click [OK](#).

To review your settings sets, click the [Settings Set Manager](#) tool to the right of the field on the [Options](#) or [Format](#) tab:



The following tools are available:

Icon	Use
	Browse to the settings set directory.
	Delete the selected settings set. Only available when an internally-saved settings set is selected. You can only delete a settings set saved to an external file through Windows Explorer.
	Export the selected settings sets to an external file. Only available when an internally-saved settings set is selected.

Icon	Use
	Import the selected settings sets to inside the model. Only available when an externally-saved settings set is selected.

i Note

Settings sets should not be copied and renamed outside of PowerDesigner. If you want to create a variant of an existing settings set, then you should load it, make the necessary changes, and then save it under a different name.

1.6.4.4 Customizing Creation Statements

You can insert custom scripts at the beginning and end of database, table, tablespace and other objects' creation statements directly from their property sheets. For example, access rights can be added under a table creation script. You can modify the standard creation statements for these and other objects by editing the DBMS definition file.

Context

Open the property sheet of the object for which you want to specify a script, and click the *Script* tab. To open the script in your preferred editor (see *Core Features Guide > Modeling with PowerDesigner > Customizing Your Modeling Environment > General Options > Text Editors*), press **Ctrl** + **E** or click the *Edit With* tool.

The following variables are commonly used in begin and end scripts:

Variable	Description
%DATABASE%, %DBMSNAME%	Name of the database and of the DBMS definition file.
%NAMESCRIPT%, %PATHSCRIPT% %	Filename or path of script file
%STARTCMD%	Command that runs the script
%AUTHOR%, %DATE%	Author of the current model, and date of script generation.
%TABLESPACE%	Code of the tablespace.
%TABLE%	Name or code of table (based on display preferences).
%TNAME%, %TCODE%, %TLABL%	Name, code, or label of the table.

Variable	Description
%OWNER%, %OWNERPREFIX%	Owner or owner prefix of the table or tablespace.
%COLNLIST%	List of the table's columns.
%OPTIONS%	Physical options defined on the object.

The begin and end scripts are placed directly before and after the `create` statement. The SQL snippet below shows where the `BeforeCreate`, `Header`, `Footer`, and `AfterCreate` scripts that you can define in the DBMS file for these and other objects are placed around the `create` statement:

```
This is my BeforeCreate script.
/*=====
/* Table: TABLE_1
/*=====
This is my Header script.
This is my Begin script
create table TABLE_1
(
    COLUMN_1          CHAR(10),
    COLUMN_2          CHAR(10),
    COLUMN_3          CHAR(10),
    constraint PK_TABLE_1 primary key ()
);
This is my End script
This is my Footer script.
This is my AfterCreate script.
```

For detailed information about editing DBMS definition files, including using the PDM variables, see *Customizing and Extending PowerDesigner > DBMS Definition Files*.

1.6.5 Generating an SAP BusinessObjects Universe

PowerDesigner can generate an SAP® BusinessObjects™ universe from your PDM for editing in the BusinessObjects Universe Design or Information Design tools, or for direct consumption by the Web Intelligence rich client. Generating a universe from your PDM gives you access to table, view, and column names and comments and more reliable cardinality information than if you create a universe directly from your database.

Context


i Note

To generate universes, you must have SAP® BusinessObjects™ SBOP BI Platform Clients 4.0 SP04 Patch 3 (v14.0.4.819) or higher installed on your workstation. On Windows Vista or Windows 7 machines, if PowerDesigner fails to recognize a valid BusinessObjects installation, it may be necessary separately to launch the Universe Design tool one time with administrator privileges to enable the BusinessObjects SDK.


For information about reverse-engineering universes, see [Reverse-Engineering an SAP BusinessObjects Universe \[page 335\]](#).

Procedure

- [optional] Optimize your PDM for generation of a universe in the following ways:
 - Specify auto-incrementing primary keys (see [Creating Primary Keys \[page 116\]](#)) together with one or more human-readable alternative keys (see [Creating Alternate Keys \[page 117\]](#)) to uniquely identify dimension rows.
 - Identify fact and dimension tables either manually or by retrieval (see [Identifying Fact and Dimension Tables \[page 232\]](#)) and review the choices that PowerDesigner has made:



- [optional] To completely control the format of your multidimensional objects, retrieve facts and dimensions in a multidimensional diagram (see [Generating Cubes \[page 233\]](#)), and edit them as necessary:



- Select Tools > SAP BusinessObjects > Generate BusinessObjects Universe .
- [optional] Click the *Connect* button to connect to the BusinessObjects CMS.
- Select a data connection to allow BusinessObjects to connect to your database. If you have not connected to the CMS, you can use an existing local connection from the BusinessObjects connection list; otherwise choose from the list of secured connections. You can, alternatively, click the *Create* button to create a new connection with the BusinessObjects New Connection wizard.

i Note

The user that you specify in this connection must have sufficient privileges and permissions to read all of the database objects contained in the PDM you are creating your universe from.

5. Click **Next** to select the objects to generate from your model. PowerDesigner will propose objects to generate as follows:
 - If facts and dimensions are present in your model, the facts are proposed for generation.
 - If no facts are present, but one or more tables have been specified as fact tables, then these will be proposed for generation.
 - If no facts or fact tables are present, then PowerDesigner will evaluate all the tables in the model and propose those which could serve as fact tables for generation.

i Note

By default, tables that have no links to other tables are excluded from the list. Select the *Include isolated tables* option to add them for selection.

6. [when facts are not present] Click **Next** to select any appropriate generation options:

Option	Description
Expand fact date columns as time dimensions	[selected by default] Creates a time dimension with the standard Year, Quarter, and Month attributes for each date column in each fact table.
Add Large Object dimension details	[deselected by default] Specifies that dimension attributes are created for columns of type blob (which commonly contain images, audio, or other binary data). If this option is deselected, these columns will still appear in the data foundation, but will not be visible in the business layer.
Use primary keys as dimension identifiers	Specifies whether dimension identifiers can or must be generated from the primary keys of their source tables. You can choose from the following settings: <ul style="list-style-type: none">○ Force - Dimension identifiers must be generated from the primary keys of their source tables.○ Allow - [default] PowerDesigner chooses the first available columns in the following list to use as dimension identifiers:<ul style="list-style-type: none">○ The first alternative key (all associated columns concatenated).○ The first unique index not identified as a primary key.○ The first column with a string data type, including primary keys with a string data type.○ The first non-key column.○ The first key column.○ Disallow - Same as allow, but dimension identifiers cannot be generated from primary keys even if they have a string data type (for example a primary key containing a GUID).


7. Click **Next** to review your choices and then click **Finish** to begin the universe generation.

When the universe is generated, you can:

- Open it in the Universe Design tool or import it into the Information Design tool (select  **File**  **Convert UNV Universe** ) for further editing.


PowerDesigner generates a universe comprising a connection, data foundation, and business layer. The business layer has one folder for each fact containing:

- A dimension for each dimension associated with the fact in PowerDesigner. Dimension series, such as the Product dimension in our example are grouped within their own subfolder. Dimensions with more than one attribute list each attribute beneath them.
- A measure for every numeric column in the fact.



After the import is complete, open the data foundation view and select **Actions > Refresh Structure** to obtain access to the richer selection of data types available in the Information Design tool.

- [if you are connected to the CMS] Import it into the CMS for editing or consumption.
- Consume it directly in the Web Intelligence rich client:



1.6.6 Generating Test Data to a Database

PowerDesigner can generate sample data to your database tables to verify performance or to help in estimating the amount of memory that the database will require. You can generate test data for some or all of the tables in your PDM to an empty or existing database.

Context

i Note

The following objects are not taken into account when you generate test data:

- Alternate keys
- Foreign keys
- Business and validation rules
- Binary, sequential, OLE, text or image data types
- Trigger contents

Procedure

1. [optional] Specify one or more test data profiles to define the range of data to be generated or to draw data from a file or other database (see [Populating Columns with Test Data \[page 107\]](#)). If you do not define profiles, PowerDesigner will generate random data that is appropriate to each data type.

i Note

The format in which date and time data is generated with or without profiles can be controlled by DBMS items in the Script/Sql/Format category (see *Customizing and Extending PowerDesigner > DBMS Definition Files > Script/Sql Category*).

2. Select to open the Test Data Generation dialog.
3. On the *General* tab, enter or select the appropriate parameters:

Option	Description
Directory	Specifies the directory in which the file will be saved.
File name	Specifies the name of the test data file to generate. Select the <i>One file only</i> checkbox to specify that a single file should be generated.

Option	Description
Generation type	<p>Specifies how the test data will be generated:</p> <ul style="list-style-type: none"> ○ Script generation ○ Direct generation – to a live database connection. <div style="background-color: #ffffcc; padding: 10px; margin-top: 10px;"> <p>i Note</p> <p>As triggers are not needed in this context and can block insertions and considerably increase the time required to generate the database, we recommend that you do not implement triggers or remove them from your test database.</p> </div> <ul style="list-style-type: none"> ○ Data file – as a set of values in a file.
Commit mode	<p>Specifies when the data will be committed:</p> <ul style="list-style-type: none"> ○ Auto - during script generation ○ At end - after script generation ○ By packet - at defined intervals during script generation
Data file format	<p>Specifies the format when generating a data file:</p> <ul style="list-style-type: none"> ○ CSV – comma-separated values ○ Custom delimiter – specify a custom delimiter
Delete old data	Deletes existing data before generating new data.
Check model	Checks the PDM before generating the test database or script, and stops generation if an error is found.
Automatic archive	Creates an archive of any previous test data.
Default number of rows	Specifies the default number of rows to generate for tables. This number can be overridden for individual tables on the Number of Rows tab.
Default number/ character/ date profile	Specifies the default test data profiles (see Populating Columns with Test Data [page 107]) to use to generate data. We recommend that you create test data profiles to accurately model your data and associate them with each of your columns and domains as appropriate, but if you have not done so, then these default profiles are used.

4. [optional] Click the [Number of Rows](#) tab to change the number of rows to be generated for each table.

By default, PowerDesigner generates the number of rows that is specified in the [Number](#) property in the table property sheet (see [Table Properties \[page 84\]](#)) or, if no number is specified, the default number specified on the [General](#) tab of this Test Data Generation dialog.

5. [optional] Click the [Format](#) tab and modify the script formatting options as appropriate:

Option	Result of selection
Owner prefix	Specifies that an owner prefix is added.
Titles	Specifies that each section of the script includes commentary in the form of titles.

Option	Result of selection
Encoding	Specifies the encoding format to use for test data generation. You should select the encoding format that supports the language used in your model and the database encoding format.
Character case	Specifies the character case to use. The following settings are available: <ul style="list-style-type: none"> ○ Upper - all uppercase characters ○ Lower - all lowercase characters ○ Mixed - both uppercase and lowercase characters
No accent	Non-accented characters replace accented characters in script.

6. [optional] Click the [Selection](#) tab and select which tables you want to generate test data for. By default all tables are selected.
7. Click [OK](#) to start the generation.

If you are generating test data to a live database connection, then the Connect to a Data Source dialog box opens. Select a data source, and then click [Connect](#). If you are generating a test data script, then a Result dialog box asks you if you want to Edit or Close the newly generated file.

A message in the Output window indicates that the test data generation is completed.

1.6.7 Estimating Database Size

You can estimate the size of a database for all or some of the tables and other objects in your model. You can estimate the initial size of the database or project its growth over a number of years.

Context

The estimate is based on the following elements:

- Estimated number of records in tables - Specify the number of rows (and their annual projected growth rate) in a table in the [Number](#) and [Row growth rate](#) fields on the [General](#) tab of its property sheet (see [Table Properties \[page 84\]](#)).
- Table columns and their sizes - Specify the average size for variable length columns in the [Average length](#) field on the [Detail](#) tab of its property sheet (see [Column Properties \[page 100\]](#)). If you do not specify an average length for variable length columns, then the maximum length is used. It is particularly important to specify an average length for strings or long binary data types, as a Binary Long OBject (BLOB), such as a picture, can represent the largest portion of the space actually taken by a table.

Note

To specify values for multiple tables or columns, select  [Model](#)  [Tables](#) or  [Model](#)  [Columns](#). If you do not see the appropriate property column, then add it using the [Customize Columns and Filter](#) tool.

- Indexes in the model - including primary, alternate, and foreign key indexes (if supported) and database-specific indexes such as IQ join indexes.


- Tablespaces in the model - the size of a tablespace is estimated as a total of all the tables and all the indexes in the tablespace.
- DBMS and its storage options.

Note

The default estimation algorithms can be overridden in the DBMS definition file (see *Customizing and Extending PowerDesigner > DBMS Definition Files > Profile Category > Modifying the Estimate Database Size Mechanism*).

Procedure

1. Select  **Database**  to open the Database Size Estimation dialog.
2. Select the tables for which you want to estimate the size.



3. [optional] Click the *Options* tab and specify the number of years of growth that you want to include in your estimate. By default, only the initial size of the database is calculated, without allowing for any growth.
4. Click **OK** to begin the estimation.

Size estimates are generated to both the Result List and Output windows. The *Database Size* tab of the Result List provides a list of objects which can be double-clicked to open their property sheets, while the *Database Size* tab of the Output window prints a textual list of objects with sizes and a total for the database:

Estimate of the size of the Database "Project Management"...		
Number	Estimated size	Object
1,000,000	136,224 KB	Table 'Customer'

```

      Index 'Primary' (4,880 KB)
1,000          48 KB  Table 'Division'
10,000         696 KB Table 'Employee'
                           Index 'Primary' (48 KB)
5,000          312 KB Table 'Material'
10,000         96 KB  Table 'Member'
10,000         392 KB Table 'Participate'
10,000         640 KB Table 'Project'
                           Index 'Primary' (48 KB)
10,000         464 KB Table 'Task'
1,000          80 KB  Table 'Team'
10,000         96 KB  Table 'Used'
-----
139,048 KB   Total estimated space
Database size estimation completed.
The number of records was not defined for 1 table(s).

```

A warning is given if any tables in the model do not have a number of records defined.

1.6.8 Modifying a Database

You can modify an existing database schema to reflect changes in your model. The PDM (source model) and the existing database schema (target model) are merged using a database synchronization window, which allows you to choose which objects are added, deleted, or updated in the target.


Context

Note

To update a HANA 1.0 database, use the HANA wizard (see [Exporting Objects to the HANA Repository \[page 535\]](#)).

Procedure

1. Select  *Database*  *Apply Model Changes to Database*



i Note

To load a pre-configured settings set (see [Quick Launch Selection and Settings Sets \[page 308\]](#)), select it in the list at the bottom of the dialog.


2. Enter a destination *Directory* and *File Name* for the script file.
3. Specify the type of generation (script or live database connection) to perform:
 - o Script generation - generate a script to be executed on a DBMS at a later time. Optionally select *One file only* to create the generation script as a single file. By default, a separate script file is created for each table.
 - o Direct generation – generate a script and execute it on a live database connection. Optionally select *Edit generation script* to open the script in an editor for review or editing before execution.
4. Specify how PowerDesigner will determine the changes to apply. You can choose to compare your model against:

- *Archive model* – Click the button to the right to browse to the archived model (see [Archive PDMs \[page 337\]](#)).
 - *Data source* – Click the button to the right to connect to your data source.
 - *Script file* – Select a script from the list or click the button to the right to browse to the script.
 - *Model from repository* – Browse the repository from the list. You can optionally select a version earlier than the latest by clicking the button to the right.
5. [optional] Select the following options as appropriate:

Option	Description
Always use create statements/ Use alter statements when possible	Specify whether create statements should always be used to modify database tables, or whether alter statements should be used where possible.
Backup tables	Specifies that any existing table will be copied to a temporary backup during the modification, and then restored to the updated tables. If this option is not selected, then all existing data will be erased. If you select this option then you can also specify to : <ul style="list-style-type: none"> ○ <i>Drop temporary tables</i> - Specifies that the temporary backup tables are removed after script execution. ○ <i>Use physical options for temporary tables</i> - Specifies that the temporary backup tables are generated with their physical options.
Check model	Specifies that a model check is performed before script generation.
Automatic archive	Creates an archive version of the PDM after generation to use to determine changes during your next database modification (see Archive PDMs [page 337]).

6. [optional] To change the default generation options, click the *Options* tab (see [Database Generation Dialog Options Tab \[page 303\]](#)).
7. [optional] To change the format of your script, click the *Format* tab (see [Database Generation Dialog Format Tab \[page 306\]](#)).
8. [optional] To control which database objects will be modified, click the *Selection* tab.
 You can save your selection via the Selection bar at the bottom of the tab (see [Quick Launch Selection and Settings Sets \[page 308\]](#)).
9. Click *OK* to begin the update. If you are using a live database connection, then the Reverse Engineering window will open, allowing you to select or clear check boxes in the target model for objects that you want to include or remove from the source model. Make your selections and then click *OK* to continue.
10. The Database Synchronization window will open. Select or clear check boxes in the target model for objects that you want to include or remove from the model, and then click *OK* to continue.

For more information about comparing and merging models, see [Core Features Guide > Modeling with PowerDesigner > Comparing and Merging Models](#).



- If you are generating a script, a result box opens listing the file path of the generated file. To open the script in a text editor, select the file in the result box and click the *Edit* button.
- If you are generating a database directly, a Data Source connection box is displayed. Type your connection details and click the *Connect* button. A message box shows the progress of the generation process. At the end of generation click *OK* to close the box.

1.6.9 Displaying Data from a Database

You can connect to a database and display the data that corresponds to a PDM table, view, or reference.

Procedure

1. Right-click a table, view, or reference and select *View Data*.

If you are not already connected to a database, the Connect to Data Source window will open. Choose your connection profile and click *Connect* to proceed.

-
2. A Query Results windows list all the database records corresponding to the selected table, view, or reference.

1.6.10 Reverse Engineering a Database into a PDM

Reverse engineering is the process of generating a PDM (or certain PDM objects) from an existing database schema. You can reverse engineer into a new PDM or an existing PDM from one or more script files or from a live database.

Context

 Note

The database user that PowerDesigner uses to connect to the database must have public access to catalog views, which is generally granted by default when creating users.

 Note

To reverse-engineer from a HANA 1.0 database, use the HANA wizard (see [Importing Objects from the HANA Repository \[page 539\]](#)).

1.6.10.1 Reverse Engineering from Scripts

PowerDesigner can reverse engineer a PDM for one or more SQL script files. The script will normally be the script used to generate the database but can also include other scripts.

Context

 Caution

In general, only statements that create objects are reverse-engineered and `alter` statements, except for those that add columns to a table, are not supported.

Procedure

1. To reverse engineer a script into an existing PDM, select  .

or

To reverse engineer a script and create a new PDM, select **File > Reverse Engineer > Database** to open the New Physical Data Model dialog. Specify a model name, choose a DBMS from the list, and then click **OK**.


or

When working with the PowerDesigner Eclipse plug-in, select any SQL file in the Navigator, right-click it and select *Reverse Engineer from SQL File*. You are given the option to reverse into an existing or new PDM.

i Note

To reverse-engineer an MS Access database, you must first prepare a .dat file (see [Reverse Engineering a Microsoft Access Database \[page 633\]](#)).

- When the Database Reverse Engineering Options dialog opens, select *Using script files*:



The following tools are provided to help with script selection:

Tool	Description
	<i>Add Files</i> – Opens a dialog box to allow you to browse for scripts files. You can add as many files as necessary.
	<i>Move Up</i> – Moves the selected file(s) up one row. This tool is grayed if the selected file(s) are at the top of the list.
	<i>Move Down</i> - Moves the selected file(s) down one row. This tool is grayed if the selected file(s) are at the bottom of the list.
	<i>Clear All</i> - Deletes all files from the list.

 **Note**

You can add as many script files as necessary to the list. If you are reversing more than one script file, the order in which the files are reversed must respect any dependencies among objects (for example, trigger creation scripts must come after table creation scripts, and grant permission scripts must come after both table and user creation scripts).

3. [optional] Click the *Options* tab to specify any reverse engineering options (see [Reverse Engineering Options Tab \[page 328\]](#)).

 **Note**

References and primary keys are not rebuilt by default. To enable rebuilding, select the appropriate options on the *Options* tab.

4. [optional] Click the *Target Models* tab to specify any external shortcuts (see [Reverse Engineering Target Models Tab \[page 331\]](#)).
5. Click **OK** to begin reverse engineering.

If you are reverse engineering to an existing PDM, then the Merge Models dialog box opens to allow you to control the merging of the new objects into your PDM (see *Core Features Guide > Modeling with PowerDesigner > Comparing and Merging Models*). When the process is complete, a confirmation message is given in the Output window.

1.6.10.2 Reverse Engineering from a Live Database

PowerDesigner can reverse engineer a PDM from a live database connection. You must specify a data source and connection information. You can select to use administrator permissions in order to be able to select the system tables that are reserved to a database administrator.


Procedure

1. To reverse engineer from a live database connection into an existing PDM, select **Database > Update Model from Database**.

or

To reverse engineer from a live database connection and create a new PDM, select **File > Reverse Engineer > Database** to open the New Physical Data Model dialog. Specify a model name, choose a DBMS from the list, and then click **OK**.

2. In the Database Reverse Engineering Options dialog, select *Using a data source*:



i Note

A data source might be predefined, or you can enter the name of an existing data source. In both cases, if you need to specify additional connection parameters, a database connection dialog box opens when you


click **OK**. Enter the necessary parameters and click **Connect** to open the Database Reverse Engineering dialog.

3. Select your data source. You can either accept the selected data source (if one is present) or click the [Connect to a Data Source](#) tool to select or define one. For detailed information about working with data sources, see [Core Features Guide > Modeling with PowerDesigner > Getting Started with PowerDesigner > Connecting to a Database](#).
4. [optional] To reverse engineer tables reserved to the database administrator, select [Reverse using administrator's permissions](#).
5. [optional] Click the [Options](#) tab to specify any reverse engineering options (see [Reverse Engineering Options Tab \[page 328\]](#)).

i Note

References and primary keys are not rebuilt by default. To enable rebuilding, select the appropriate options on the [Options](#) tab.

6. [optional] Click the [Target Models](#) tab to specify any external shortcuts (see [Reverse Engineering Target Models Tab \[page 331\]](#)).
7. Click **OK** to open the Database Reverse Engineering dialog, which allows you to specify the objects to reverse engineer (see [Database Reverse Engineering Selection Window \[page 330\]](#)). Only tables and triggers are selected by default.



8. Click **OK** to begin reverse engineering.

If you are reverse engineering to an existing PDM, then the Merge Models dialog box opens to allow you to control the merging of the new objects into your PDM (see [Core Features Guide > Modeling with PowerDesigner > Comparing and Merging Models](#)). When the process is complete, a confirmation message is given in the Output window.

1.6.10.3 Reverse Engineering Options Tab

When you reverse engineer a database schema using script files or a data source, you can define rebuild options after reverse engineering.


The rebuild options automatically perform the following tasks after reverse engineering:

Option	Description
Automatically rebuild references when no reference is reversed	Rebuilds references (see Rebuilding References [page 198]) when no references are reverse engineered. A reference is created between each column belonging to a primary key and a column, with identical name and data type, that does not belong to a primary or a foreign key in another table.
Automatically rebuild primary keys from unique indexes when tables have no key and only one unique index	Rebuilds primary keys (see Rebuilding Primary Keys [page 116]) using unique indexes when tables have no key and only one unique index.
Automatically reverse tables referenced by selected tables	Reverse engineers the parents of the selected child tables in order to complement the definition of these child tables.
Create symbols	Creates a symbol for each reversed object in the diagram. If this option is not selected, reversed objects are visible only in the browser. Where there are a large number of objects with complex interactions, PowerDesigner may create synonyms of objects to improve diagram readability. For example, if a table has a large number of references, PowerDesigner may create a synonym of the table in another location in the diagram to reduce the length required for references.
Apply code to name conversion to reversed objects	Applies the code to name conversion script specified in the model options (see Core Features Guide > Modeling with PowerDesigner > Objects > Naming Conventions).
File encoding	Specifies the default file encoding of the files to reverse engineer. Click the ellipsis to the right of the option to change the encoding (see Reverse Engineering Encoding Format [page 329]).
Block/ Command terminator	Specify the end of block and end of command characters for the reversed script. By default, these values are defined in the DBMS definition file at <code>Script\SQL\Syntax</code> , and modifications made here are saved in the Registry for reuse in other models. To restore the DBMS value, click the Restore from DBMS tool.
Case sensitive database	Specifies that the database is case sensitive and enables the case sensitive option in the model.

1.6.10.3.1 Reverse Engineering Encoding Format

If the code you want to reverse engineer is written with Unicode or MBCS (Multibyte character set), you should use the encoding parameters provided to you in the File Encoding box.

If you want to change these parameters because you know which encoding is used within the sources, you can select the appropriate encoding parameter by clicking the Ellipsis button beside the File Encoding box. This opens the Text Input Encoding Format dialog box in which you can select the encoding format of your choice.



The Text Input Encoding Format dialog box includes the following options:


Option	Description
Encoding hint	Encoding format to be used as hint when reversing the file.
Detection mode	Indicates whether text encoding detection is to be attempted and specifies how much of each file should be analyzed. When enabled, PowerDesigner analyzes a portion of the text, and uses an heuristic based on illegal bytes sequences and/or the presence of encoding-specific tags in order to detect the appropriate encoding that should be used for reading the text. The following settings are available: <ul style="list-style-type: none">• No detection - for use when you know what the encoding format is• Quick detection - analyzes a small part of the file. For use when you think that the encoding format will be easy to detect• Full detection – analyzes the whole file. For use when you think that the number of characters that determine the encoding format is very small
On ambiguous detection	Specifies what action should be taken in case of ambiguity. The following settings are available: <ul style="list-style-type: none">• Use encoding hint and display warning - the encoding hint format is used and a warning message is displayed.• Use encoding hint - the encoding hint format is used but no warning message is displayed.• Use detected encoding - the encoding format detected by PowerDesigner is used
Abort on character loss	Allows you to stop reverse engineering if characters cannot be identified and are to be lost in current encoding

Here is an example on how to read encoding formats from the list:

ASCII	
DOS	
UTF-8	→ No Byte-Order-Mark in the header
UTF-8 (with signature)	
Unicode	
Unicode (with signature)	→ There must be a Byte-Order-Mark in the header for the file to be valid
Unicode big endian	
Unicode big endian (with signature)	
ANSI (Active Code Page)	

1.6.10.4 Database Reverse Engineering Selection Window

When you reverse engineer a database from a live database connection, you can choose to populate your PDM with a subset of the available objects by selecting them in the Database Reverse Engineering Selection window.




Click the subtabs to view the different types of objects. Certain object types have attributes, or options, that appear below the object lists. Options that are not available for the selected object type or DBMS are grayed. When you select tables containing triggers on the *Table* tab, the triggers are selected on the *Trigger* tab.

You can restrict database objects to reverse engineer in the top area of the window by selecting to filter by:

- Qualifier - such as a database or a partition that contains one or more tables. For example, the DB2 DBMS authorizes the use of the qualifier field to select which databases are to be reverse engineered from a list.
- Owner - normally the creator of a database object. To reverse engineer objects from multiple owners, select All users. Only users that have creation rights are reverse engineered.

i Note

If the selected qualifier contains a large number of table owners, it may be faster to click the [Select Qualifier and Owner](#) tool and enter a qualifier and/or owner in the dialog box, as opening the Owner list may take a very long time.



You can save your selections for re-use by entering a selection name in the list at the bottom of the window and clicking the [Save](#) tool to the right of the list. Selections are saved with a .sel file extension, and are added to the list for subsequent use. You can change the folder in which the files are saved by clicking the folder tool to the right of the list.

1.6.10.5 Reverse Engineering Target Models Tab

External shortcuts depend on their corresponding target objects located in different models. When you need several models to design a single database, you can use shortcuts to share objects between models. The Target Models tab displays the list of detected target models containing target objects for shortcuts in the current model to reverse.


This tab is always visible, even if the model does not contain shortcuts, so that you can add target models and create shortcuts instead of duplicating objects.

The following tools are available on this tab:

Tool	Description
	Change Target Model - Displays a standard Open dialog box to let you select another file as target model
	Open Model - Opens selected target model in current workspace
	Add Models - Opens a selection list with the models opened in the current workspace. This tool is particularly useful when you reverse engineer into a new model where the target models are not defined

Tool	Description
	Delete - Deletes the target model and the shortcuts in the current model that reference the deleted target model

When you reverse engineer a model, any target models should be open in your workspace. If not, the following confirmation dialog box is displayed to let you open the target models:



If you are reverse engineering from a:

- Script - All the create statements in the script create objects, provided the script contains a full definition of the object. When the script only uses an object and does not define it, this object is sought among the target objects in the target models and an external shortcut is created in the reversed model.
- Live data source - External shortcuts are created for all selected objects that already exist in another target model. These existing objects are deselected by default in the *Selection* tab of the Reverse Engineering dialog box, except for target objects corresponding to shortcuts already existing in the reversed model.

1.6.10.6 Optimizing Live Database Reverse Engineering Queries

Live database reverse engineering has been optimized in order to improve performance. All queries run according to an optimization process rule.

This process uses the following registry keys:

- RevOdbcMinCount defines a number of selected objects for reverse engineering. The default number is 100
- RevOdbcMinPerct defines a percentage of selected objects for reverse engineering. The default percentage is 10

These keys do not exist by default, you have to create and edit them in the Registry under:

```
Current User \Software\Sybase\PowerDesigner <version>\FolderOptions\Physical Objects
```

During reverse engineering, PowerDesigner compares the total number of current objects for reverse engineering to the value of RevOdbcMinCount, and if the total number of listed items is:

- lower than RevOdbcMinCount - then a global reverse query is executed.

- higher than `RevOdbcMinCount` - then the process uses key `RevOdbcMinPerct`, and if the percentage of reversed items is :
 - lower than `RevOdbcMinPerct` - then the same query is executed for each object.
 - higher than `RevOdbcMinPerct` - then a global query is executed.

1.6.10.7 Reverse Engineering Database Statistics


You can reverse engineer statistics for an existing database, such as the number of distinct or null values in a column or the average length of a character field. These can provide helpful information when optimizing a design.

Context


You can reverse engineer the statistics as part of the general reverse engineering process by selecting the Statistics checkbox in the Database Reverse Engineering window (see [Reverse Engineering from a Live Database \[page 326\]](#)), or update them at any other time, using the dedicated Update Statistics window.

Procedure

1. Select  **Tools**  to open the Update Statistics window (if PowerDesigner is not presently connected to a database via a live database connection, you will be required to connect):



2. On the **General** tab, select or clear the checkboxes to specify whether you want to update statistics for tables and/or columns.
3. [optional] Click the **Selection** tab and select or clear checkboxes to specify for which tables you want to update statistics:



- Click **OK** to begin the update. Progress appears in the Output window. For large updates, a progress dialog box opens, allowing you to cancel the update at any time.

When the process is complete, you can view the updated statistics in the property sheets of your tables and columns.

1.6.11 Reverse-Engineering an SAP BusinessObjects Universe

PowerDesigner can reverse-engineer a SAP® BusinessObjects™ universe to a PDM for analysis and editing.

Context

i Note

To reverse-engineer universes, you must have SAP® BusinessObjects™ Business Intelligence platform 4.1 Support Package 2 Client Tools or higher installed on your workstation, and you must have selected to install the SAP BusinessObjects Semantic Layer Java SDK.

For information about generating universes, see [Generating an SAP BusinessObjects Universe \[page 311\]](#).

Procedure

1. To prepare your universe for reverse-engineering, connect to your BusinessObjects server, right-click the universe in the Repository Resources browser, select [Retrieve Universe](#), and specify a local project to retrieve it to.
2. To reverse-engineer the universe into an existing PDM, select [Tools](#) [SAP BusinessObjects](#) [Reverse BusinessObjects Universe](#).

or

To reverse-engineer the universe and create a new PDM, select [File](#) [Reverse Engineer](#) [SAP BusinessObjects Universe](#) to open the New Physical Data Model dialog. Specify a model name, choose a DBMS from the list, and then click [OK](#).

3. Navigate to and select the universe file in your BusinessObjects workspace, and then select from the following options as appropriate:

Option	Description
Reverse universe business layer	Deselect this option to reverse only the data foundation to produce a physical diagram. If this option is selected, you can select the following: <ul style="list-style-type: none">○ Allow the creation of multiple facts - Instructs PowerDesigner to create multiple facts, each in its own multidimensional diagram if the universe contains various measures based on different table,○ Name columns from universe attributes - Instructs PowerDesigner to modify the names of database table columns if their associated dimension attributes are more human-readable. Column codes are not changed.○ Create dimensions from folder structure - Instructs PowerDesigner to build a dimension for each folder in the universe and add every item under it in this dimension.
Enrich data foundation from source database	Reverse-engineers the tables, indexes and references that are selected in the data foundation from its associated database in order to obtain more information such as physical data type, additional columns, missing references, and physical options, to augment the information contained in the universe. Selecting this option will open a database connection dialog to allow you to connect to the database.
Show Merge Dialog	[when reversing into an existing PDM] Specifies to display the Merge dialog even if there are no conflicts between the model and the server. By default the Merge dialog is displayed only if one or more objects contains conflicting changes on the BusinessObjects server and in the model.

4. Click [Finish](#). PowerDesigner requests your BusinessObjects server username and password to open the universe for reverse-engineering.

PowerDesigner creates tables, references, facts, and dimensions as appropriate in your model. Tables and references are displayed in a physical diagram, and each cube is displayed in its own multidimensional diagram, surrounded by its associated dimensions.

1.6.12 Archive PDMs

Archive PDMs provide a snapshot of the structure of your database at a point in time to allow you to determine model changes since that time when updating your database. When comparing your model directly with a database or script (and not with an archive PDM), some differences (particularly around renamed objects) can be lost, leading to more drop/creates in place of alter statements.

Archives are created by default when you generate or update your database (using the *Automatic Archive* option), and can be created manually at any time by clicking *File* *Save As*, and selecting Archived PDM (bin) or Archived PDM (xml) in the Save As Type list.

1.7 Generating Other Models from a Data Model

You can generate various types of PowerDesigner models from CDMs, LDMs, and PDMs.

Context

Data Model	CDM	LDM	PDM	OOM	XSM
CDM	X	X	X	X	
LDM	X	X	X		
PDM	X	X	X	X	X

Procedure

1. Select Tools, and then one of the following to open the appropriate Model Generation Options Window:
 - Generate Conceptual Data Model... + +
 - Generate Logical Data Model... + +
 - Generate Physical Data Model... + +
 - Generate Object-Oriented Model... + +
 - Generate XML Model... + +
2. On the *General* tab, select a radio button to generate a new or update an existing model, and complete the appropriate options.
3. [optional – PDM-PDM generation only] Click the *DBMS Preserve Options* tab and set any appropriate options.

i Note

For detailed information about the options available on the various tabs of the Generation window, see *Core Features Guide > Linking and Synchronizing Models > Generating Models and Model Objects*.

4. [optional] Click the *Detail* tab and set any appropriate options. We recommend that you select the Check model checkbox to check the model for errors and warnings before generation.
5. [optional] Click the *Target Models* tab and specify the target models for any generated shortcuts.
6. [optional] Click the *Selection* tab and select objects to generate.
7. Click *OK* to begin generation.

Results

1.7.1 Generating Other Models from a CDM

You can generate CDM objects to other model objects.

CDM	OOD	PDM
Entity	Class - All entities with the <i>Generate</i> property selected are generated as persistent classes with the Generate table persistence mode. If an entity's <i>Generate</i> property is not selected, the generated class has the Migrate columns persistence mode.	Table - If the entity is involved in an inheritance, the inheritance <i>Generation Mode</i> setting (see Inheritance Properties [page 72]) affects whether parents and children are generated.
Entity attribute	Attribute	Table column i Note Two columns in the same table cannot have the same name. If column names conflict due to foreign key migration, PowerDesigner automatically renames the migrated columns to the first three letters of the original entity name followed by the code of the attribute.
Primary identifier	-	Primary or foreign key depending on independent or dependent relationship
Identifier	-	Alternate key

CDM	OOM	PDM
Association	Relationship or association	-
Binary association with attributes	Association class	-
Inheritance	Generalization	-
Relationship	-	Reference

1.7.1.1 Generating PDM Table Keys from CDM Entity Identifiers

The type of key that is generated in the PDM depends on the cardinality and type of dependency defined for a relationship in the CDM. Primary identifiers generate primary and foreign keys. Other identifiers that are not primary identifiers generate alternate keys:


- A primary key is a column or columns whose values uniquely identify a row in a table.
- A foreign key is a column or columns that depend on and migrate from a primary key column in another table.
- An alternate key is a column or columns whose values uniquely identify a row in a table, and is not a primary key.

Independent One-to-many Relationships

In independent one-to-many relationships, the primary identifier of the entity on the one side of the relationship is generated as a:

- Primary key in the table generated by the entity on the one side of the relationship
- Foreign key in the table generated by the entity on the many side of the relationship

The following CDM shows an independent relationship. Each division contains one or more employees:



The following PDM will be generated:





Table	Primary key	Foreign key
Division	Division number	—
Employee	Employee number	Division number

Dependent One-to-many Relationships

In dependent relationships, the primary identifier of the nondependent entity is generated as a primary/foreign key in the table generated by the dependent entity. The migrated column is integrated into the primary key if it already exists.

The following CDM shows a dependent relationship. Each task must have a project number.



The following PDM will be generated:





Table	Primary key	Foreign key
Project	Project number	—
Task	Project number/Task number	Project number

Independent Many-to-many Relationships

In independent many-to-many relationships, the primary identifiers of both entities migrate to a join table as primary/foreign keys. The CDM below shows an independent relationship. Each employee can be a member of one or more teams, and each team can have one or more employees as members.



The following PDM will be generated:




Table	Primary key	Foreign key
Team	Team number	—
Employee	Employee number	—
Member	Team number/Employee number	Team number/Employee number

Independent One-to-one Relationships

In independent one-to-one relationships, the primary identifier of one entity migrates to the other generated table as a foreign key.

1.7.2 Generating Other Models from an LDM

You can generate LDM objects to other model objects.

LDM	CDM	PDM
Business rule	Business rule	Business rule
Domain	Domain	Domain
Entity	Entity	Table
Identifier	Identifier	Key
Entity attribute	Entity attribute	Column table
Inheritance	Inheritance	References
Relationship	Relationship	Reference

1.7.3 Generating Other Models from a PDM

You can generate PDM objects to other model objects.

PDM	CDM	LDM	OOD	XSM
Domain	Domain	Domain	Domain	Simple Type
Table	Entity	Entity	Class	Element
Table column	Entity attribute	Entity attribute	Attribute	Attribute or element
Primary key	Primary identifier	Primary identifier	Primary identifier	-
Alternate key	Identifier	Identifier	Identifier	-
Foreign key	-	-	-	Keyref constraint
Stored-Procedures	-	-	Operation	-
View	-	-	-	Element
View column	-	-	-	Attribute
Index	-	-	-	Unique
Abstract data type	-	-	-	Complex type

PDM	CDM	LDM	OOM	XSM
Reference	Relationship	Relationship	Association	-

i Note

If the code of the generated XML model objects does not correspond to the target language naming conventions, you can define a code naming convention script to convert object names into codes. For more information on conversion scripts, see *Core Features Guide > Modeling with PowerDesigner > Objects > Naming Conventions*.

XML Specifics

Generation of column as attribute or element is controlled by generation option

Foreign keys - When a foreign key is not a composition, it is generated as a KeyRef constraint

Oracle 8 and Interbase Sequence Translation

When a CDM is generated from a PDM, the data type of the table column attached to a sequence is translated to a serial data type in the CDM with the format NO%*n*, where %*n* is the length of the data type (see [Sequences \(PDM\) \[page 186\]](#)).

OOM Specifics

All tables are generated as persistent classes with the "Generate table" persistence mode.

All abstract data types are generated as persistent classes with the "Generate ADT" persistence mode.

Table - Class. The cardinality of a class is translated from the number of estimated records in a table

Table with migrated keys from only two other tables - Class linked with an association class between the two classes generated by the two parent tables

Stored-Procedures and stored functions attached to selected table - If the parent table is generated as a class, the stored procedure or the stored function is generated as an operation attached to the class

i Note


If the code of the generated OOM objects does not correspond to the target language naming conventions, you can define a code naming convention script to convert object names into codes. For more information, see *Core Features Guide > Modeling with PowerDesigner > Objects > Naming Conventions*.

1.7.3.1 Customizing Data Type Mappings

When generating another PDM from your PDM, PowerDesigner maps the existing column datatypes to appropriate data types in the new model. If the standard mappings are not sufficient for you, you can use the `Enhance Data Type Mapping` extension to specify alternative mappings, including on a column-by-column basis.


Context

To review the conversions that PowerDesigner makes by default between the data types of a database or other modeling target and its standard conceptual types (which are also used in the CDM), select `Tools > Resources > <Type>`, select the appropriate file in the list and click the `Properties` tool. Expand the `Script > DataType` (for DBMSs) or `Settings > DataType` (for other resource files), and review each of the entries (which are described in their `Comment` field):



Procedure

1. Select **Tools > Generate Physical Data Model**, enter the appropriate generation options (see Core Features Guide > Linking and Synchronizing Models > Generating Models and Model Objects).
2. On the **Detail** tab, click the **Enable Transformations** button to display the **Extensions** tab, and select the **Enhance Data Type Mapping** extension.
3. Click **OK** to start the generation. The Data Type Mappings dialog appears, with the existing data types present in the model listed in the **Original type** column, and those that PowerDesigner proposes in the new DBMS in the **Target data type** column:



4. You can change data type mappings in two ways:
 - To change the mapping for all columns of a certain data type, select the desired new data type from the list in the **Target data type** column.
 - To change the mapping for one column only, click the **Add Specific Column Mapping** button, select the column from the tree, click **OK**, choose the new data type for the column, and click **OK** to add this mapping to the list.
5. When you have modified all the necessary data types, click **Close** and the generation will continue, using your custom mappings where appropriate.

i Note

You can also customize data type mappings when changing the DBMS of your model with the **Database > Change Current DBMS** command. To do so, you must first attach the Enhance Data Type Mapping extension, by selecting **Model > Extensions**, clicking the *Attach an Extension* tool, select the extension, and clicking **OK** to attach it to your model.

For more information about data types, see *Customizing and Extending PowerDesigner > DBMS Definition Files > Script/Data Type Category* and *Customizing and Extending PowerDesigner > Object, Process, and XML Language Definition Files > Settings Category: Object Language*.

1.7.3.2 Customizing XSM Generation for Individual Objects

When generating an XSM from a PDM or OOM, you can specify global generation options to generate tables/classes as elements with or without complex types and columns/attributes as elements or attributes. You can override these options for individual objects by attaching the **PDM XML Generation** or **OOM XML Generation** extension to your source model and selecting from their XML generation options.

Context

i Note

The extension provides new property sheet tabs for setting generation options for individual objects, but you can also set these options with or without the extension by selecting **Model > <objects>** to open the appropriate object list, clicking the *Customize Columns and Filter* tool, and selecting to display the **XML Generation Mode** column.

For example, if you want to generate the majority of your table columns to an XSM as XML attributes, but want to generate certain columns as elements, you should:

- Modify the XML generation options for those columns that you want to generate as elements.
- Select to generate columns as attributes on the Model Generation Options *Detail* tab.

Procedure

1. Select **Model > Extensions** to open the List of Extensions, and click the *Attach an Extension* tool.
2. On the *General Purpose* tab, select **PDM XML Generation** or **OOM XML Generation** and click **OK** to attach the extension to your model and **OK** to close the List of Extensions.

These extension files enable the display of the **XML** tab in all table and column or class and attribute property sheets.

3. Open the property sheet of the table, column, class, or attribute whose generation you want to customize, and click the *XML* tab.
 4. Use the radio buttons to specify how you want to generate the object in an XSM.
 - For tables and classes, you can specify to generate them as:
 - Elements - the table/class is generated as an untyped element directly linked to its columns/attributes generated as attributes or sub-elements.
 - Elements with complex types - the table/class is generated as an element typed by a complex type, generated in parallel, to contain the columns/attributes.
 - Default - generation of the table/class is controlled by the option selected in the *XML Generation* group box on the Model Generation Options *Detail* tab.
 - For tables, you can additionally specify to generate keys as:
 - Key - [default] The primary key columns are generated and also KEY and KEYREF wherever the table is referenced.
 - ID attribute - The primary key columns are not generated and an ID attribute, **id**, is generated to replace them.

Wherever the table is referenced, an IDREF attribute is generated to reference the appropriate element. If the reference role name is assigned, this attribute is given this name. Otherwise, the referenced table name is used and the standard renaming mechanism is enforced.
 - Key and ID attribute - In many cases the primary key columns have significant data and you may want to generate them, as well as an ID attribute. In this case an ID attribute is generated for the element and IDREF is used systematically for any reference to the table:
- The following rules apply to the generation of keys:
- If a Table generates an ID, all its child tables will generate an ID attribute.
 - If a Table generates Key columns, all its child tables will generate Key columns.
 - If a child table is flagged to generate PK only, ID Attribute will be automatically generated.
 - If a table generates ID attribute, No Key nor KeyRef will be generated, and ALL references will generate IDREF attribute.. (Even if the table generates also Key Columns)
 - If a table generates ID attribute ONLY, All Foreign Key Columns referencing its Key columns will be systematically removed and replaced by an IDREF attribute
- For columns and attributes, you can specify to generate them as:
 - Elements - [default] the column/attribute is generated as an sub-element of its table/class element or complex type.
 - Attributes - the column/attribute is generated as an attribute of its table/class element or complex type.
 - Default - generation of the column/attribute is controlled by the option selected in the *XML Generation* group box on the Model Generation Options *Detail* tab.
5. Modify the XML generation options for any other objects that you want to generate in a different manner.
 6. Select  **Tools**  **Generate XML Model**, ensure that the appropriate options are set in the *XML Generation* group box on the Model Generation Options *Detail* tab, and start your generation.

1.7.3.3 Configuring the Generated Model Options

When you configure the options of a CDM to generate, you may define options diverging from the PDM options.

To avoid conflicts, PowerDesigner applies the following rule for default values of CDM options: an option defined for the generated CDM should respect the equivalent option of the PDM.

Equivalent Enforce non-divergence model options are available in both the PDM and CDM.

PDM option	CDM option	Result in generated CDM
Enforce non-divergence	—	Enforce non-divergence in model according to PDM options. Data items and attributes attached to the domain cannot have divergent definitions
—	Enforce non-divergence	Enforce non-divergence in model according to CDM options defined using the Configure Model Options feature

Relationships Unique Code

(CDM) Unique Code for relationships is not selected by default in the CDM options. However, if you select Unique Code for relationships in the CDM options, relationships are renamed during the generation of a PDM to a CDM.

Options with no equivalent, like Enforce Profile in the PDM without any corresponding option in a CDM, are generated using default values found in the registry.

Options with No Equivalent in the Models

(OOM) Options with no equivalent, like Enforce Profile in the PDM without any corresponding option in an OOM, are generated using default values found in the registry.

1.8 Migrating from ERwin to PowerDesigner

You can easily import a model built with ERwin into PowerDesigner with no loss of metadata. PowerDesigner allows complete flexibility through reliable linking and synchronization between conceptual, physical and object-oriented model approaches, providing outstanding model clarity and flexibility.

PowerDesigner supports the import of the following ERwin v3.x and higher model files, though v4.x or higher files are recommended, as they contain more metadata:

- ERwin v3.x (.erx)
- ERwin v4.x (.xml)
- ERwin v7.x, v8.x, v9.x (.xml) – the ERwin model must be saved as Standard XML Format, and you must uncheck *Only save minimum amount of information* in the ERwin Save as XML File dialog box.

Note

Before importing, we recommend that you review your ERwin model to see if any model object names are duplicated. It is good practice to avoid using duplicate names, and PowerDesigner will automatically attach a suffix to any duplicate objects that it encounters during the import process.

An ERwin logical model can be imported into either a PowerDesigner conceptual or logical model (CDM or LDM), while an ERwin Physical Model is imported into a PowerDesigner physical data model (PDM).

PowerDesigner cannot import the following ERwin objects:

- ERwin triggers and stored procedures (not directly possible, but see the process in [Post-Import \[page 352\]](#))
- ERwin reports
- ER1 files
- ERwin data sources
- ERwin target clients

While PowerDesigner can import all your object display preferences and will retain color and font information, it does not support multiple colors for columns in a single table. The default column color will be used during the import.


1.8.1 Importing Individual ERwin Files

PowerDesigner provides a wizard to help you import individual ERwin files.

Procedure

1. Select   .
2. Browse to the directory that contains the ERwin file, select it, and then click [Open](#).
3. If the ERwin file contains only a physical model, you will be prompted to choose whether to import references as triggers. Select [Yes](#) or [No](#) to begin the import.

Alternatively, if the ERwin file contains a logical model or a combined logical and physical model, the ERwin model import dialog box opens:



The options available depend on the type of ERwin model that you are importing. PowerDesigner supports data modeling at the conceptual, logical, and physical levels. The full set of options is as follows:

- A conceptual data model can be created when you are importing an ERwin logical model. It provides a platform-independent representation of a system, giving an abstract view of its static data structures, and permitting real normalized data structures with many-to-many and inheritance relationships.
- A logical data model can be created when you are importing an ERwin logical model. It allows you to resolve many-to-many and super/sub-type relationships, de-normalize your data structures, and define indexes, without specifying a particular RDBMS.
- A physical data model can be created when you are importing an ERwin physical model. It is a representation of a real database and associated objects running on a server with complete information on the structure of the physical objects, such as tables, columns, references, triggers, stored procedures, views, and indexes.

Select the checkbox for each type of model that you want to create.

4. If your ERwin model contains a logical model, and you want to create a conceptual data model, then you can choose to merge identical data items. This is a powerful metadata management technique that is not available in the ERwin environment.

For example, your ERwin logical model may contain multiple entities that contain an attribute "address". By default, PowerDesigner will create a separate data item for each of these entity attributes. However if you select the *Merge identical data items* checkbox, then a single data item will be created, and adjustments to it will automatically cascade down to all the associated entity attributes.


5. If your ERwin model contains a physical model, then you can choose whether to *Implement referential integrity by triggers*.
6. Click **OK** to begin the import. When the process is complete, the imported models will appear in the Browser.

1.8.2 Importing Multiple ERwin Files

PowerDesigner provides a wizard to help you import multiple ERwin files.

Procedure

1. Select **File** > **Import** > **Multiple ERwin Files** to open the ERwin model import dialog:



2. Use the *Add Directory* or *Open Files* tools to add .xml or .erx files to import to the list.
 3. Use the following checkbox columns (or the equivalent options at the bottom of the dialog) to specify import options for the files.
 - *[C]onceptual Data Model* - import the file as a CDM
 - *[M]erge identical data items* - [CDMs only] create a single data item for all entity attributes with the same name (eg "address")
 - *[L]ogical Data Model* - import the file as an LDM
 - *[P]hysical Data Model* - import the file as a PDM
 - *[I]mplement referential integrity by triggers* - [PDMs only]

You can select to import a single ERwin file as multiple model types. To select multiple files and set the same options for them, click and hold while dragging your cursor over the far-left numbered column.

4. Specify a *Destination Folder* in which to create the PowerDesigner models.
5. Click *OK* to begin the import.

PowerDesigner will import each model and add it to your workspace. Note that to avoid problems of memory allocation when importing many models, the PowerDesigner models are closed by default. To open a model, simply double-click it.

1.8.3 Post-Import

You should perform a certain number of checks after import, and also be prepared for certain differences in your models.

We recommend that you perform the following post-import checks:

- Import triggers - Triggers cannot be directly imported from ERwin. There are, however, two methods for transferring your constraint trigger information to PowerDesigner:
 - Automatically generate triggers - Select ► *Tools* ► *Rebuild Objects* ► *Rebuild Triggers* . Creating triggers in this way ensures that they will be synchronized automatically by PowerDesigner, but the actual code may be different from that which you are used to in ERwin.
 - Reverse engineer triggers - Generate the triggers from ERwin, and then reverse engineer them into PowerDesigner. Creating triggers in this way ensures that they use exactly the same code as before, but they will not be automatically synchronized by PowerDesigner.
- Import procedures: Procedures cannot be directly imported from ERwin. You can, however transfer them by generating the triggers from ERwin, and then reverse engineering them into PowerDesigner.
- Set up object naming conventions - Select ► *Tools* ► *Model Options* , expand the Naming Convention category and select the object entry (see *Core Features Guide > Modeling with PowerDesigner > Objects > Naming Conventions*).
- Select other model options - Select ► *Tools* ► *Model Options* , and select the Model Settings category or one of its children (see [Setting CDM/LDM Model Options \[page 15\]](#) and [Setting PDM Model Options \[page 18\]](#))

The following are some differences that are commonly encountered when working with a newly imported ERwin model:

- Why do I see errors in Check Model when my ERwin model was clean? - PowerDesigner performs stricter checks than ERwin. For example, duplicate objects are not permitted in PowerDesigner, and the existence of orphaned items will generate a warning.
- Why do some of my object symbols appear with numeric suffixes? - If an object is required to appear more than once in a diagram (for, example, to improve readability), PowerDesigner will create a graphical synonym to represent it. Thus, if the table "Purchase" is displayed twice in a diagram, the two symbols will be labeled as "Purchase: 1" and "Purchase: 2".

1.8.4 PowerDesigner vs ERwin Terminology

PowerDesigner and ERwin use different terms to describe certain model objects.

The import process converts general model objects as follows:

ERwin	PowerDesigner
Model	Model
Stored display, subject area	Diagram
Business rule	Business rule
Domain	Domain
Symbols (including symbol size and position)	Symbols (including symbol size and position)
Description	Description
Notes	Annotation
Text block	Text symbol
IE notation	Entity/Relationship notation
IDEF1X notation	IDEF1X notation
User-defined properties	Imported as extended attributes stored in an extension file called Imported Attributes and embedded in the model. For information about working with extension files, see <i>Customizing and Extending PowerDesigner > Extension Files</i> .

The import process converts ERwin logical model objects into conceptual data model (CDM) objects as follows:

ERwin logical model	PowerDesigner CDM
Attribute	Data item, entity attribute
Key group	Identifier
Entity	Entity
Relationship	Relationship
Subtype relationship	Inheritance link
Subtype category	Inheritance

The import process translates ERwin physical model objects into physical data model (PDM) objects as follows:

ERwin physical model	PowerDesigner PDM
Column	Column
Key	Key
Table	Table
Relationship	Reference
Index	Index
View table	View
Fact, dimension, outrigger	Table
Target database	Current DBMS
Valid value	Check parameter
Tablespace	Tablespace
Segment	Storage

1.8.5 Getting Started Using PowerDesigner for Former ERwin Users

This section lists some common tasks that former ERwin users will want to perform with PowerDesigner.

Objects

How do I find objects? All the objects in the model are listed, organized by type, in the Browser. PowerDesigner provides various methods for locating your objects:

- To find the symbol for an object in the Browser: Right-click the object in the Browser and select *Find in Diagram*.
- To find the browser entry for an object symbol: Right-click the symbol in the diagram and select *Find in Browser*.
- To search for an object: Type `Ctrl` + `F` to open the Find Objects dialog box. Enter the text to search for (you can use the asterisk as a wild card) and click *Find Now*. Right-click any of the results choose whether to find it in the Browser or Diagram.

How do I edit objects? You can edit the name of an object by selecting its symbol in the diagram and typing `F2`. To edit other object properties, double-click the symbol or the object entry in the Browser and enter the necessary information in its property sheet.

How do I share objects? You can share objects between packages and models using shortcuts and replications (see *Core Features Guide > Linking and Synchronizing Models > Shortcuts and Replicas*).

Packages/Subject Areas

How do I create subject areas? In PowerDesigner, you can create multiple views of your model by adding additional diagrams. You can also divide your model into smaller subdivisions using packages.

- To add a diagram to your model: Right-click the diagram background and select ► *Diagram* ► *New Diagram* ► *[Diagram Type]*.
- To convert a diagram into a package: Right-click the diagram background and select ► *Diagram* ► *Convert to Package*. The Convert Diagram to Package wizard will open, permitting you to name the package and select objects to move into it. The package will appear in the Browser with its own diagram and associated objects. For more information about packages, see *Core Features Guide > Modeling with PowerDesigner > Objects > Packages*.

Reports

How do I create a report? PowerDesigner provides wizards to create two different types of report:

- To create a report about a specific type of object: Select ► *Report* ► *List Report Wizard* and follow the wizard instructions.
- To create a report about multiple object types or the whole model: Select ► *Report* ► *Report Wizard* and follow the wizard instructions.

For more information about PowerDesigner reports, see *Core Features Guide > Modeling with PowerDesigner > Reports*

Databases

How do I create or update a model from a database? Select ► *File* ► *Reverse Engineer* ► *Database* and complete the dialog. When updating a model, a Merge dialog will open to allow you to verify the changes to be made before committing them. For more information, see [Reverse Engineering a Database into a PDM \[page 323\]](#).

How do I generate a database from my model? Select ► *Database* ► *Generate Database* and complete the dialog. For more information, see [Generating a Database from a PDM \[page 298\]](#).

How do I update a database from my model? Select ► *Database* ► *Apply Model Changes to Database* and complete the dialog. A Database Synchronization window will open to allow you to verify the changes to be made before committing them. For more information, see [Modifying a Database \[page 319\]](#).

Models

How do I compare or merge models? Select  [Tools](#)  [Compare Models](#) or  [Tools](#)  [Merge Model](#). For more information, see *Core Features Guide > Modeling with PowerDesigner > Comparing and Merging Models*.

2 DBMS Definition Reference

The chapters in this part provide information specific to the DBMSs supported by PowerDesigner.

2.1 Amazon Redshift

To create a PDM with support for features specific to the Amazon Redshift DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select  *Database*  *Edit Current DBMS*  and expand the *Profile* node.

Tables

The following extensions are available on the *General* tab:

Name	Description
Temporary	Specifies that the table is visible only within the current session. Scripting name: <code>Temporary</code>

Columns

The following extensions are available on the *General* tab:

Name	Description
Encoding	Specifies the type of compression encoding to apply to the column. Scripting name: <code>Encoding</code>
Distribution key	Specifies that the column is part of the table distribution key. Scripting name: <code>DistKey</code>
Sort key	Specifies that the column is part of the table sort key. Scripting name: <code>SortKey</code>

Name	Description
Seed	[identity] Specifies the identity seed value. Scripting name: <code>IdtSeed</code>
Increment	[identity] Specifies the identity increment value. Scripting name: <code>IdtIncr</code>

Views

The following extensions are available on the *General* tab:

Name	Description
Schema Binding	Specifies that the view is not bound to the underlying database objects, such as tables and user-defined functions. Scripting name: <code>SchemaBinding</code>

Users

The following extensions are available on the *General* tab:

Name	Description
Create DB	Allows the user to create databases. Scripting name: <code>CreateDB</code>
Create User	Gives the user all database privileges, including <code>CREATE USER</code> . Scripting name: <code>CreateUser</code>
Groups	Specifies the name of an existing group that the user belongs to. Scripting name: <code>Groups</code>
Password	Specifies the user password. Scripting name: <code>OPassword</code>
Valid Until	Specifies an absolute time after which the user account password is no longer valid. Scripting name: <code>ValidUntil</code>

Name	Description
Connection Limit	Specifies the maximum number of database connections the user is permitted to have open concurrently. Scripting name: ConnectionLimit

2.1.1 Schemas (Redshift)

PowerDesigner models Redshift schemas as users with a stereotype of <<Schema>>.

Creating a Schema

You can create a schema in any of the following ways:

- Select to access the List of Schemas, and click the *Add a Row* tool.
- Right-click the model or package in the Browser, and select .

Schema Properties

You can modify an object's properties from its property sheet. To open a schema property sheet, double-click its Browser entry in the Schemas folder.

The following extended attributes are available on the *General* tab:

Name	Description
Implicit	Specifies that the schema will be named after the authorization user name. Scripting name: Implicit
Authorization	Specifies the user owning the schema. Scripting name: Authorization

2.1.2 External Schemas (Redshift)

PowerDesigner models Redshift external schemas as extended objects with a stereotype of <<ExternalSchema>>.

Creating an External Schema

You can create an external schema in any of the following ways:

- Select to access the List of External Schemas, and click the *Add a Row* tool.
- Right-click the model or package in the Browser, and select .

External Schema Properties

You can modify an object's properties from its property sheet. To open an external schema property sheet, double-click its Browser entry in the External Schemas folder.

The following extended attributes are available on the *General* tab:

Name	Description
Source	Specifies the location of the external database. Scripting name: ESSource
Region	For external databases defined in an Athena data catalog, the region in which the database is located. Scripting name: ESRegion
Database	Specifies the database to be used. Scripting name: ESDatabase
Create External Database	Specifies to create an external database with the name specified by the <i>Database</i> property. Scripting name: ESCreateExternalDatabase
IAM Role	Specifies the Amazon Resource Name (ARN) for an IAM role that your cluster uses for authentication and authorization. Scripting name: ESIAMRole
URI / Port	Specify the URI and port number of the database in a Hive metastore. Scripting name: ESURI, ESURIPort

2.2 Hadoop Hive

To create a PDM with support for features specific to the Hadoop Hive DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select  *Database*  *Edit Current DBMS* and expand the *Profile* node.

Note

When working with PowerDesigner and Hadoop Hive, please bear in mind the following limitations:

- Since Hadoop Hive is not a relational database, and does not support such concepts as primary and foreign keys, many of PowerDesigner's typical modeling features have no relevance when modeling Hive databases.
- Hive has no system catalog, which limits PowerDesigner's reverse-engineering possibilities to the capabilities of your ODBC driver, and round-trip reverse-engineering and generation may not be possible.

Abstract Data Types

The following extensions are available on the *General* tab when you select *Map* in the *Type* box:

Name	Description
Value Data Type	Specifies the data type of the mapped value. Scripting name: MappedDttpAttr

Columns

The following extensions are available on the *General* tab:

Name	Description
Partitioning column	Specifies if the column defines a partition. Scripting name: PartitionColumn

Users (Databases)

The following extensions are available on the *General* tab:

Name	Description
HdfsPath	Specifies the path of database files. Scripting name: HdfsPath
Database properties	Specifies the database properties. Scripting name: DatabaseOptions

Views

The following extensions are available on the *General* tab:

Name	Description
Scope	Specifies if the view is available for all or only local session. Note: The local and global keywords are present for SQL standard compatibility, but have no effect in the database. Scripting name: TemporaryScope
View properties	[N/A for Table As view] Specifies the view properties. Scripting name: VTblProperties

The following extensions are available on the *Options* tab if you select the <>Table As>> stereotype on the *General* tab:

Name	Description
Block size	Specifies the size, in bytes, for each block in a table. The value must be between 8192 and 2097152 bytes, and be a multiple of 8192. Scripting name: BlockSize
Append only	Specifies if the table must be created as an append-only table (TRUE) or as a regular heap-storage table (FALSE). Scripting name: AppendOnly
OIDs	Specifies whether to assign object identifiers to rows. This box is unchecked by default. Scripting name: OIDs

Name	Description
Fill factor	Specifies the percentage that determines how full the index method will try to pack index pages. Scripting name: <code>FillFactor</code>
Compression type	Specifies ZLIB (default) or QUICKLZ compression type. Scripting name: <code>CompressType</code>
Level	For zlib compression of append-only tables, specifies a value between 1 (fastest compression) to 9 (highest compression ratio). Scripting name: <code>CompressLevel</code>
Orientation	Set to <code>column</code> for column-oriented storage, or <code>row</code> (the default) for row-oriented storage. Scripting name: <code>Orientation</code>
On commit	Specifies the behavior of temporary tables at the end of a transaction block. Scripting name: <code>OnCommit</code>
Distributed by	Specifies the distribution policy for a table. Scripting name: <code>DistributedByColumns</code>

2.2.1 Partitions and Partition Values (Hadoop Hive)

PowerDesigner supports Hadoop Hive partitions and partition values as extended sub-objects with stereotypes of <>Partition<> and <>PartitionValues<> respectively.

To create a partition, use the tools on the *Partitions* tab of the table property sheet. To create a partition value, use the tools on the *General* tab of the partition property sheet.

Partition Properties

You can modify an object's properties from its property sheet. To open a partition property sheet, double-click its Browser entry in the Partitions folder.

The following extended attributes are available on the *General* tab:

Name	Description
Set	Specifies if the partition has its column collection correctly filled and fixes it if possible. Scripting name: <code>IsOK</code>

Name	Description
Location	Specifies the directory where the data files for the partition reside. Scripting name: PartLocation
Specification	Specifies the partition definition. Scripting name: PartitionSpec

Partition Value Properties

The following extended attributes are available on the *General* tab:

Name	Description
Column	Specifies the column which value will be compared with the threshold. Scripting name: Column
Value	Specifies the value that determines if row can be stored in this partition. Scripting name: Value

2.3 HP Neoview

To create a PDM with support for features specific to the HP Neoview DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select   and expand the *Profile* node.

The following sections list the extensions provided for HP Neoview.

Note

We do not provide documentation for the properties on the *Physical Options* and certain other tabs, though minimal information is available for them in the Resource Editor. For information about these properties, consult your DBMS reference documentation.

Tables

The following extensions are available on the *General* tab:

Name	Description
Set	Specifies that the table is a SET table, and thus discards duplicate rows. Scripting name: Set
Volatile	Specifies that indexes associated with the table have lifespans limited to the SQL session in which the index is created and are dropped when the session ends. Scripting name: Volatile

Columns

The following extensions are available on the *Neoview* tab:

Name	Description
Identity	Specifies that the column is an identity column. Scripting name: Identity
Type	Specifies the type of identity column. You can choose between: <ul style="list-style-type: none">• by default - allows both user-supplied and system-generated column values for the identity column• always - provides system-generated unique values and does not allow user-supplied identity column values. Scripting name: IdentityType
Start with	Specifies the start value of the cycle range for the identity column. Scripting name: StartWith
Increment	Specifies the value by which each value is incremented to obtain the next value. Scripting name: Increment
Minimum	Specifies the minimum value of the data type of the identity column starting the cycle range. Scripting name: MinValue
Maximum	Specifies the maximum value of the data type of the identity column starting the cycle range. Scripting name: MaxValue

Name	Description
Cycle	Specifies that when the maximum value is reached for the identity column, the values are restarted from the minimum. If this option is not selected, an error will be raised. Scripting name: Cycle
Unsigned	Specify that the column is unsigned. By default, columns are signed. Scripting name: Unsigned
Character set	[character columns] Specifies the character set to use. Scripting name: Charset
Upshift	[character columns] Specifies that the contents are stored as uppercase. Scripting name: Upshift
Mandatory	Specifies that the column must not contain a null value. Scripting name: Mandatory
Constraint name	Specifies the name of the not null column constraint. Scripting name: MandConstName

Indexes

The following extensions are available on the *General* tab:

Name	Description
Volatile	Specifies that the index has a lifespan limited to the SQL session in which it is created and is dropped when the session ends. Scripting name: Volatile
Unique	Specifies that the index is a unique index. Scripting name: Unique
No populate	Specifies that the index is not to be populated when it is created. The indexes are created, but no data is written to the index, and it is marked offline. Scripting name: NoPopulate

Name	Description
Partition	<p>Specifies the partitioning columns. If you do not specify the partitioning columns, the default is the same partitioning column or columns as the base table for a non-unique index, and all the columns in the index for a unique index.</p> <p>Scripting name: HashPartitionColumns</p>

References

The following extensions are available on the [General](#) tab:

Name	Description
Enforced	<p>Specifies that the reference is checked.</p> <p>Scripting name: Enforced</p>

Materialized Views

The following extensions are available on the [Neoview](#) tab:

Name	Description
Refresh type	<p>Specifies the method that will be used to update the materialized view.</p> <p>Scripting name: RefreshType</p>
Ignore	<p>[on request only] Instructs the refresh operation of a materialized view over several base tables to ignore the changes to the listed base tables.</p> <p>Scripting name: IgnoreChangesOn</p>
Initialize	<p>Specifies when the materialized view gets its initial content, either upon creation or at the time of its first refresh.</p> <p>Scripting name: Initialize</p>
Clustering columns	<p>Specifies the order of rows within the physical file that holds the table, determines the physical organization of the table, and the ways you can partition the table.</p> <p>Scripting name: Clustering</p>

Name	Description
Partition	Specifies hash partitioning, which is the only partitioning scheme supported for materialized views. Scripting name: HashPartition
Partitioning keys	Specifies the the partitioning keys of the materialized view. Scripting name: PartitionColumnList
Commit each	Specifies the number of rows that refresh processes from the log before committing a transaction and starting another one. Scripting name: MVAttribute
Text	Provides a textual view of the materialized view options. This field auto-updates as you select options, and you edits you make here are reflected in the options. Scripting name: ViewOption

2.3.1 Materialized View Groups (Neoview)

Materialized view groups allow you to collect together materialized views (views with the *Type* property set to `Materialized view`) that should be refreshed together. PowerDesigner models materialized view groups as extended objects with a stereotype of `<<MVGroup>>`.

Creating a Materialized View Group

You can create a materialized view group in any of the following ways:

- Select to access the List of Materialized View Groups, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select .

Materialized View Group Properties

You can modify an object's properties from its property sheet. To open a materialized view group property sheet, double-click its diagram symbol or its Browser entry in the Materialized View Groups folder.

The following extended attributes are available on the [Neoview](#) tab:

Name	Description
Owner	Specifies the group's owner. Scripting name: Owner

The following tabs are also available:

- [Materialized Views](#) - lists the materialized views contained within the group.

2.4 IBM DB2 for z/OS (formerly OS/390)

To create a PDM with support for features specific to the IBM DB2 for z/OS DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select [Database](#) [Edit Current DBMS](#) and expand the [Profile](#) node.

Note

The DBMS definition file for IBM DB2 v8 for OS/390 is deprecated.

The following table lists DB2 objects and their equivalents in PowerDesigner:

DB2	PowerDesigner
Bufferpool	Storage
Database Partition Group	Extended Object <<DatabasePartitionGroup>>
Distinct Type	Domain
Function	Procedure of "Function" type
Index Extension	Extended Object <<IndexExtension>>
Method	Abstract Data Type Procedure
Type	Abstract Data Type
SuperView	SubView of a View

The following sections list the extensions provided for DB2 for z/OS.

Note

We do not provide documentation for the properties on the [Physical Options](#) and certain other tabs, though minimal information is available for them in the Resource Editor. For information about these properties, consult your DBMS reference documentation.

Columns

The following extensions are available on the [DB2](#) tab:

Name	Description
Field procedure name	Defines the procedure that will be used as generator/cryptor of values. Scripting name: ExtFieldProcName
Character subtype	[v6.x and higher] Specifies a subtype for a character string column. Scripting name: ExtSubtypeData [up to v6.x] Specifies a subtype for a character string column (column with a CHAR,VARCHAR,or LONG VARCHAR data type). The subtype can proceed from the list defined in extended attribute type T_For-Data. Scripting name: ExtData
Generated value	[v7.x and higher] Indicates that DB2 generates values for the column using the computed column function. If you select Always, the server will send an error message if you try to type a value in the column. If you select By Default, the server uses the computed column value or the value typed for the column. Scripting name: ExtGeneratedAs
Implicitly hidden	[v9.x and higher] Specifies that the column is not visible in the result for SQL statements unless you explicitly refer to the column by name. Scripting name: ImplicitlyHidden
As security label	[v8 and higher] Specifies that the column will contain security label values. This also indicates that the table is defined with multi-level security with row level granularity. Scripting name: SecurityLabel

The following extensions are available on the [Generated Column](#) tab for v12 and higher:

Name	Description
Generated as	Specifies how the column is generated. You can choose between: <ul style="list-style-type: none">• <None> [default]• As Identity• As row• As transaction start ID• As row change timestamp Complete other properties as appropriate for the selected type. Scripting name: GeneratedType

Domains

The following extensions are available on the *General* tab for v12 and higher:

Name	Description
Character Subtype	Specifies the type of the user-defined data type as distinct or array. Scripting name: ExtSubtypeData

The following extensions are available on the *DB2* tab:

Name	Description
Character Subtype	[v6.x and higher] Specifies a subtype for a character string column. Scripting name: ExtSubtypeData

References

The following extensions are available on the *DB2* tab:

Name	Description
Enforced	[v8 and higher] Indicates whether or not the referential constraint is enforced by the database manager during normal operations, such as insert, update, or delete. Scripting name: Enforced

Sequences

The following extensions are available on the *DB2* tab:

Name	Description
Datatype	Specifies a computed value for "As" option. Allows to select a data type in a list. Scripting name: AsDatatype
Length	Specifies the length of the data type Scripting name: AsDatatypeLength

Name	Description
Start with	Specifies the first value for the sequence. Scripting name: InitialStartWith
Increment by	Specifies the interval between consecutive values of the sequence. Scripting name: InitialIncrementBy
Cache	Specifies the numerical value of the cache option. Scripting name: CacheValue
No Cache	Specifies a computed boolean value for order option. Scripting name: NoCacheBool
Cycle	Specifies a computed boolean value for cycle option. Scripting name: CycleBool
Order	Specifies a computed boolean value for order option. Scripting name: OrderBool
Minimum value	Specifies the numerical value of the minvalue option. Scripting name: LimitsMinvalueValue
Maximum value	Specifies the numerical value of the maxvalue option. Scripting name: LimitsMaxvalueValue
No minimum	Specifies a computed boolean value for no minvalue option. Scripting name: NoMinLimit
No maximum	Specifies a computed boolean value for no maxvalue option. Scripting name: NoMaxLimit

2.4.1 Trusted Contexts (DB2)

Using a trusted context in an application can improve security by placing accountability at the middle-tier, reducing over granting of privileges, and auditing of end-user's activities.

Context

Trusted contexts are supported for DB2 for z/OS v9.x and higher and DB2 for Common Server v9.5 and higher. PowerDesigner models trusted contexts as extended objects with a stereotype of <<TrustedContext>>, and lists them under the *Model* menu and in the *Trusted Contexts* folder under the model in the Browser.

Procedure

1. Select to access the *List of Trusted Contexts*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *DB2* tab:

Name	Description
Enable	Specifies that the trusted context is created in the enabled state. Scripting name: Enable
Authorization	Specifies that the context is a connection that is established by the authorization ID that is specified by authorization-name. Scripting name: Authorization
Default role	Specifies the default role that is assigned to a user in a trusted connection when the user does not have a role in the trusted context. If empty, then a No Default Role is assumed. Scripting name: DefaultRole
As object owner	[DB2 for z/OS only] Specifies that the role is treated as the owner of the objects that are created using a trusted connection based on the trusted context. Scripting name: WithRoleAsObjectOwner
Default security label	[DB2 for z/OS only] Specifies the default security label for a trusted connection based on the trusted context. Scripting name: DefaultSecurityLabel

Name	Description
Attributes	Specifies one or more connection trust attributes that are used to define the trusted context. Scripting name: Attributes
With use for	Specifies who can use a trusted connection that is based on the trusted context. Scripting name: WithUseFor

2.4.2 Auxiliary Tables (DB2)

Auxiliary tables are used to store large object (LOB) data, such as graphics, video, etc, or to store rarely-accessed data in order to improve the performance of the base table.

Context

PowerDesigner models auxiliary tables as extended objects with a stereotype of <<AuxiliaryTable>>, and lists them under the [Model](#) menu and in the [Auxiliary Tables](#) folder under the model in the Browser.

Procedure

1. Select to access the [List of Auxiliary Tables](#), click the [Add a Row](#) tool, and then click the [Properties](#) tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the [DB2](#) tab:

Name	Description
Database	Specifies the database in which the LOB data will be stored. Scripting name: Database
Tablespace	Specifies the table space in which the auxiliary table is created. Scripting name: Tablespace
Table	Specifies the table that owns the LOB column. Scripting name: Table

Name	Description
Column	Specifies the name of the LOB column in the auxiliary table. Scripting name: Column
Partition	Specifies the partition of the base table for which the auxiliary table is to store the specified column. Scripting name: Partition

2.4.3 Tablespace Prefix (DB2)

In IBM databases for z/OS, the physical options for a table can specify the tablespace in which a table resides, as well as the database name.

You declare a tablespace in a database and assign a table to a tablespace on the *Physical Options (Common)* tabs of their property sheets.

If the tablespace is not declared in any database, then the tablespace is not prefixed by any database name.

When you preview your table creation code, you can verify that the tablespace is prefixed by the name of the database.

Propriétés de la table - Client (CLIENT)


Correspondances	Permissions	Partitions	Physical Options (Common)	Définition	Règles
Général	Colonnes	Index	Clés	Triggers	Procédures
Diagrammes associés	Attributs étendus	Aperçu	Dépendances	Liens de traçabilité	Version

Ln 18, Col 3

```
CLIADR          TEXTE_COURT,
CLIACT          TEXTE_COURT,
CLICON          NOM,
CLITEL          TELEPHONE,
CLIFAX          TELEPHONE,
constraint P_IDTF_14 primary key (CLINUM)
);
in MaBase.TBSP1;
```

SQL

<< Moins OK Annuler Appliquer Aide



2.4.4 Materialized Query Tables (DB2)

Materialized query tables are based upon the result of a query.

Context

Materialized query tables are supported for IBM DB2 for z/OS 10 and higher. PowerDesigner models materialized query tables as views with a stereotype of <<MaterializedView>>, and lists them under the *Model* menu and in the *Materialized Query Tables* folder under the model in the Browser.

Procedure

1. Select to access the *List of Materialized Query Tables*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *General* tab:

Name	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Owner	Specifies the user who is the owner of the object. This is usually its creator. Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object.
Usage	Specifies how the view will be used. You can choose between: <ul style="list-style-type: none">○ Query only - Consultation only. The view cannot update tables.○ Updatable - Consultation and update of underlying tables.○ With Check options - Implements controls on view insertions.
Dimensional type	Specifies the type of view table for purposes of creating star or snowflake schemas containing fact tables and dimensions. You can choose between: <ul style="list-style-type: none">○ Fact○ Dimension○ Exclude - Do not consider as a multidimensional object.
Generate	Selects the view for generation to the database.
User-defined	By default, the view query is updated to reflect changes to model objects on which it is based. Selecting this option freezes the view and protects your manual changes.
Result table	Specifies whether the materialized view is a query table or result table. Scripting name: <code>WithNoData</code>
Maintained by	[Query table] Specifies how the data in the materialized query table is maintained. Scripting name: <code>MaintainedBy</code>
Query optimization	[Query table] Specifies whether this materialized query table can be used for optimization. Scripting name: <code>QueryOptimization</code>
Column default	[Result table] Specifies whether or not to copy column defaults. Scripting name: <code>ColumnDefault</code>

Name	Description
Identity	[Result table] Specifies whether or not to copy identity column attributes. Scripting name: Identity

The following tabs are also available:

- *Partitions* - lists the partitions contained within the materialized query table.
3. Click the *Partitions* tab, to specify partitions for the materialized query table.

2.4.5 Masks (DB2)

A column mask specifies the rules for users to receive the masked values that are returned for the column.

Context

Masks are supported for IBM DB2 for z/OS 10 and higher. PowerDesigner models masks as extended objects with a stereotype of <>Mask<>, and lists them under the *Model* menu and in the *Masks* folder under the model in the Browser.

Procedure

1. Select to access the *List of Masks*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *General* tab:

Name	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Owner	Specifies the user who is the owner of the object. This is usually its creator. Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object.

Name	Description
Column	Specifies the column to which the mask applies. A mask must not already exist for the column. Scripting name: MaskColumn
Enabled	Specifies if the column mask is to be enabled for column access control. Scripting name: MaskEnabled

3. Enter the following properties in the *Expression* tab:

Name	Description
Table correlation name	Specifies a correlation name that can be used within CASE expression to designate the table. Scripting name: TableCorrelation
Case expression	Specifies a CASE expression that determines the value that is returned for the column. The result of the CASE expression is returned in place of the column value in a row. Scripting name: CaseExpression

2.4.6 Row Permissions (DB2)

A row permission is a database object that describes a specific row access control rule for a table.

Context

Row permissions are supported for IBM DB2 for z/OS 10 and higher. PowerDesigner models row permissions as extended objects with a stereotype of <<RowPermission>>, and lists them under the *Model* menu and in the *Row Permissions* folder under the model in the Browser.

Procedure

1. Select to access the *List of Row Permissions*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *General* tab:

Name	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <code>Code</code> field.
Owner	Specifies the user who is the owner of the object. This is usually its creator. Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object.
Table	Specifies the table on which the row permission is created. Scripting name: <code>Table</code>
Enabled	Specifies that the row permission is to be enabled for row access control. Scripting name: <code>RowPermissionEnabled</code>

3. Enter the following properties in the *Search Condition* tab:

Name	Description
Correlation name	Specifies a correlation name that can be used within search-condition to designate the table. Scripting name: <code>TableCorrelation</code>
Search condition	Specifies a condition that can be true, false, or unknown for a row of the table. Search condition follows the same rules used by the search condition in a WHERE clause of a subselect. Scripting name: <code>SearchCondition</code>

2.5 IBM DB2 for Common Server

To create a PDM with support for features specific to the IBM DB2 for Common Server DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select and expand the *Profile* node.

Note

The DBMS definition file for IBM DB2 v8.x Common Server is deprecated.

For a list of DB2 objects and their equivalents in PowerDesigner, see [IBM DB2 for z/OS \(formerly OS/390\) \[page 369\]](#).

The following sections list the extensions provided for DB2 for Common Server.

Note

We do not provide documentation for the properties on the *Physical Options* and certain other tabs, though minimal information is available for them in the Resource Editor. For information about these properties, consult your DBMS reference documentation.

Tables

The following extensions are available on the *DB2* tab:

Name	Description
Ptcfree	Indicates what percentage of each tab to leave as free space during load or reorganization. Scripting name: ExtTablePctFree
Data	Identifies the tablespace in which the table will be created. Scripting name: In
Cycle	Specifies whether or not the number of data partitions with no explicit tablespace can exceed the number of specified data partitions. Scripting name: DisplayCycle
Long	Identifies the table space in which the values of any long columns (LONG VARCHAR, LONG VARGRAPHIC, LOB data types, distinct types with any of these as source types, or any columns defined with user-defined structured types with values that cannot be stored inline) will be stored. Scripting name: InLongIn
Index	Identifies the tablespace in which any indexes on the table will be created. Scripting name: InIndexIn

Columns

The following extensions are available on the *DB2* tab:

Name	Description
Lob option	[up to v8.x] Specifies options for LOB data type columns. Scripting name: ExtLobOption

Name	Description
For bit data	<p>Specifies that the content of the column is to be treated as bit (binary) data. This is only applicable on columns with a character datatype.</p> <p>Scripting name: ExtForBitData</p>
Always Generate value	<p>When set to True (generated always), indicates that DB2 will always generate a value for the column when a row is inserted into the table or whenever the result value of the generation expression may change.</p> <p>When set to False (generated by default), indicates that DB2 will generate a value for the column when a row is inserted into the table, unless a value is specified.</p> <p>Scripting name: ExtGenAlways</p>
As row change timestamp	<p>[v9.5 and higher] Specifies that the column is a timestamp column for the table. A value is generated for the column in each row that is inserted, and for any row in which any column is updated.</p> <p>Scripting name: AsRowChangeTimestampClause</p>
Expression	<p>Specifies that the definition of the column is based on an expression.</p> <p>Scripting name: ExtGenExpr (up to v9.0: ExtGenExpr)</p>
Compact	<p>Specifies COMPACT options for LOB data type columns.</p> <p>Scripting name: Compact</p>
Logged	<p>Specifies LOGGED options for LOB data type columns.</p> <p>Scripting name: Logged</p>
Inline length	<p>This option is only valid for a column defined using a structured type and indicates the maximum byte size of an instance of a structured type to store inline with the rest of the values in the row.</p> <p>Scripting name: InlineLength</p>
Compress	<p>Specifies that system default values (that is, the default values used for the data types when no specific values are specified) are to be stored using minimal space. If the VALUE COMPRESSION clause is not specified, a warning is returned and system default values are not stored using minimal space.</p> <p>Scripting name: CompressSystemDefault</p>
Hidden	<p>Specifies whether or not the column is to be defined as hidden. The hidden attribute determines whether the column is included in an implicit reference to the table, or whether it can be explicitly referenced in SQL statements.</p> <p>Scripting name: HiddenBool</p>
Security label	<p>Identifies a security label that exists for the security policy that is associated with the table.</p> <p>Scripting name: SecurityLabel</p>

References

The following extensions are available on the *DB2* tab (v8.0 and higher):

Name	Description
Enforced	Indicates whether or not the referential constraint is enforced by the database manager during normal operations, such as insert, update, or delete. Scripting name: <code>Enforced</code>
Enable query optimization	Specifies whether the constraint can be used for query optimization under appropriate circumstances. Scripting name: <code>QueryOptimization</code>

Views

The following extensions are available on the *DB2* tab (v9.x and higher):

Name	Description
View is based on a type	Specifies that the columns of the view are based on the attributes of the structured type identified by type-name. Scripting name: <code>ADTView</code>
Structured type	Specifies the abstract data type that the view is based on. Scripting name: <code>ViewType</code>
Super view	Specifies the view that the current view is a subview of. The superview must be an existing view and must be defined using a structured type that is the immediate supertype of the current view type. Scripting name: <code>SuperView</code>
Identifier column	Defines the object identifier column for the typed view. Scripting name: <code>OIDColumn</code>
Unchecked	Defines the object identifier column of the typed view definition to assume uniqueness even though the system cannot prove this uniqueness. Scripting name: <code>Unchecked</code>
Additional options	Defines additional options that apply to columns of a typed view. Scripting name: <code>RootViewOptions</code>

Name	Description
With row movement	Specifies that an updated row is to be moved to the appropriate underlying table, even if it violates a check constraint on that table. Scripting name: WithRowMovement
Check option	Specifies the constraint that every row that is inserted or updated through the view must conform to the definition of the view. Scripting name: CheckOption

Tablespaces

The following extensions are available on the *General* tab:

Name	Description
Type	Specifies the tablespace type, as defined in the extended attribute type ExtTablespaceTypeList. Scripting name: ExtTablespaceType

Abstract Data Types

The following extensions are available on the *DB2* tab (v9.x and higher):

Name	Description
Inline length	Indicates the maximum size (in bytes) of a structured type column instance to store inline with the rest of the values in the row of a table. Instances of a structured type or its subtypes, that are larger than the specified inline length, are stored separately from the base table row, similar to the way that LOB values are handled. Scripting name: InlineLength
Without comparison	Indicates that there are no comparison functions supported for instances of the structured type. Scripting name: WithoutComparison
Cast (ref as source) function	Defines the name of the system-generated function that casts a reference type value for this structured type to the data type representation type. A schema name must not be specified as part of function name (SQLSTATE 42601). The cast function is created in the same schema as the structured type. If the clause is not specified, the default value for function name is the name of the representation type. Scripting name: RefAsSourceCastFunction

Name	Description
Cast (source as ref) function	Defines the name of the system-generated function that casts a value with the data type representation type to the reference type of this structured type. A schema name must not be specified as part of the function name (SQLSTATE 42601). The cast function is created in the same schema as the structured type. If the clause is not specified, the default value for function name is the structured type name. A matching function signature must not already exist in the same schema (SQLSTATE 42710). Scripting name: <code>SourceAsRefCastFunction</code>
With function access	Indicates that all methods of this type and its subtypes, including methods created in the future, can be accessed using functional notation. This clause can be specified only for the root type of a structured type hierarchy (the UNDER clause is not specified) (SQLSTATE 42613). This clause is provided to allow the use of functional notation for those applications that prefer this form of notation over method invocation notation. Scripting name: <code>WithFunctionAccess</code>
Ref using	Defines the built-in data type used as the representation (underlying data type) for the reference type of this structured type and all its subtypes. This clause can only be specified for the root type of a structured type hierarchy (UNDER clause is not specified) (SQLSTATE 42613). The type cannot be a LONG VARCHAR, LONG VARGRAPHIC, BLOB, CLOB, DBCLOB, DATALINK, or structured type, and must have a length less than or equal to 32 672 bytes (SQLSTATE 42613). If this clause is not specified for the root type of a structured type hierarchy, then REF USING VARCHAR(16) FOR BIT DATA is assumed. Scripting name: <code>RepType</code>
Length/ precision	Specifies the precision for representation type. Scripting name: <code>RepPrecision</code>

Abstract Data Type Attributes

The following extensions are available on the DB2 tab (v9.x and higher) with the LOB data type:

Name	Description
Compact	Specifies COMPACT options for LOB data type columns. Scripting name: <code>Compact</code>
Logged	Specifies LOGGED options for LOB data type columns. Scripting name: <code>Logged</code>

Abstract Data Type Procedures

The following extensions are available on the *DB2* tab (v9.x and higher):

Name	Description
Inherit isolation level	Specifies whether or not a lock request can be associated with the isolation-clause of the statement when the method inherits the isolation level of the statement that invokes the method. The default is INHERIT ISOLATION LEVEL WITHOUT LOCK REQUEST. Scripting name: <code>IsolationLevel</code>
Method is external	Indicates that the CREATE METHOD statement is being used to register a method, based on code written in an external programming language. Scripting name: <code>ExternalMethod</code>
External name	Identifies the name of the user-written code which implements the method being defined. Scripting name: <code>ExternalName</code>
Transform group	Indicates the transform group that is used for user-defined structured type transformations when invoking the method. A transform is required since the method definition includes a user-defined structured type. Scripting name: <code>TransformGroup</code>

2.5.1 Database Partition Groups (DB2)

Database partition groups are supported for DB2 for Common Server v9.x and higher.

A partition group is a logical layer that provides for the grouping of one or more database partitions. A partition can belong to more than one partition group. When a database is created, DB2 creates three default partition groups, which cannot be dropped.

Creating a Database Partition Group

You can create a database partition group in any of the following ways:

- Select to access the List of Database Partition Groups, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select .

Database Partition Group Properties

You can modify an object's properties from its property sheet. To open a database partition group property sheet, double-click its diagram symbol or its Browser entry in the Database Partition Groups folder.

The following extended attributes are available on the *DB2* tab:

Property	Description
Database partitions	<p>Specifies the database partitions that are in the partition group.</p> <p>When empty, the group includes all database partitions defined in the database at the time of its creation.</p> <p>Scripting name: DBPartitionNumList</p>

2.5.2 Index Extensions (DB2)

Index extensions are supported for DB2 for Common Server v9.x and higher, and are used with indexes on tables that have columns of a structured or distinct type.

The following options are available on the *DB2* tab:

Property	Description
Owner	<p>Specifies the index extension schema.</p> <p>Scripting name: Owner</p>
Parameters	<p>Specifies a list of parameters (with data types) that is passed to the index extension at CREATE INDEX time to define the actual behavior of this index extension.</p> <p>Scripting name: IndexExtensionParameters</p>
Source key parameters	<p>Specifies the parameter (and its data type) that is associated with the source key column.</p> <p>Scripting name: SourceKeyParameters</p>
Key generation function	<p>Specifies how the index key is generated using a user-defined table function. Multiple index entries may be generated for a single source key data value.</p> <p>Scripting name: KeyGenerationFunction</p>
Parameter	<p>Specifies parameters for the key generation function.</p> <p>Scripting name: KeyGenerationFunctionParameters</p>
Target key parameters	<p>Specifies the target key parameters that are the output of the key generation function specified on the GENERATE KEY USING clause.</p> <p>Scripting name: TargetKeyParameters</p>

Property	Description
Search methods	<p>Specifies the list of method details of the index search. Each detail consists of a method name, the search arguments, a range producing function, and an optional index filter function.</p> <p>Scripting name: SearchMethods</p>

2.5.3 Security Policies (DB2)

Security policies define criteria that determine who has write and/or read access to individual rows and columns of tables.

Every protected table must have exactly one security policy associated with it. Rows and columns in that table can only be protected with security labels that are part of that security policy and all access of protected data follows the rules of that policy. You can have multiple security policies in a single database but you cannot have more than one security policy protecting any given table.

Security policies are supported for DB2 for Common Server v9.5 and higher. PowerDesigner models security policies as extended objects with a stereotype of <>SecurityPolicy>>.

Creating a Security Policy

You can create a security policy in any of the following ways:

- Select  **Model**  to access the List of Security Policies, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select  **New** .

Security Policy Properties

You can modify an object's properties from its property sheet. To open a security policy property sheet, double-click its Browser entry in the Security Policies folder.

The following extended attributes are available on the *General* tab:

Property	Description
Use group authorization	<p>Specifies that security labels and exemptions granted directly or indirectly to groups are considered for any access attempt.</p> <p>Scripting name: GroupAuthorization</p>

Property	Description
Use role authorization	Specifies that security labels and exemptions granted directly or indirectly to roles are considered for any access attempt. Scripting name: RoleAuthorization
Restrict Not Authorized Write Security Label	Specifies the action that is to be taken when a user is not authorized to write the explicitly specified security label that is provided in the INSERT or UPDATE statement issued against a table that is protected with this security policy. A user's security label and exemption credentials determine the user's authorization to write an explicitly provided security label. Scripting name: Restrict

The following tabs are also available:

- *Components* - lists the security label components associated with the security policy

2.5.3.1 Security Labels (DB2)

Security labels are database objects that describe a set of security criteria, and which are granted to users to allow them to access protected data.

Every security label is part of exactly one security policy and includes one value for each component in that security policy.

Security labels are supported for DB2 for Common Server v9.5 and higher. PowerDesigner models security labels as extended objects with a stereotype of <<SecurityLabel>>.

Creating a Security Label

You can create a security label in any of the following ways:

- Select to access the List of Security Labels, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select .

Security Label Properties

You can modify an object's properties from its property sheet. To open a security label property sheet, double-click its Browser entry in the Security Labels folder.

The following extended attributes are available on the *DB2* tab:

Property	Description
Policy	Specifies the security policy with which the label is associated. Scripting name: Policy

The following tabs are also available:

- *Components* - lists the security label components associated with the security label.

2.5.3.2 Security Label Components (DB2)

Security label components are database objects that model your organization's security structure.

A security label component represents a criteria to decide if a user should have access to a given piece of data, such as how well trusted the user is, what department she is in, or whether she is involved in a particular project.

Security label components are supported for DB2 for Common Server v9.5 and higher. PowerDesigner models security label components as extended objects with a stereotype of <<SecurityLabelComponent>>.

Creating a Security Label Component

You can create a security label component in any of the following ways:

- Select to access the List of Security Label Components, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select .

Security Label Component Properties

You can modify an object's properties from its property sheet. To open a security label component property sheet, double-click its Browser entry in the Security Label Components folder.

The following extended attributes are available on the **DB2** tab:

Property	Description
Component type	Specifies the type of component. You can choose between: <ul style="list-style-type: none">• TREE: Each element represents a node in a tree structure• ARRAY: Each element represents a point on a linear scale• SET: Each element represents one member of a set Scripting name: Type
Constant list	Specifies one or more string constant values that make up the set of valid values for the component. The order in which the array elements appear is significant, with the first element ranking higher than the second element, and so on. Scripting name: List

2.5.4 Event Monitors (DB2)

Event monitors show activity from start to finish, and often consist of both a start and end event record. The most common uses for event monitors are for connections, locks, and statements. PowerDesigner models event monitors as extended objects with a stereotype of <>EventMonitor<>.

Creating an Event Monitor

You can create an event monitor in any of the following ways:

- Select  **Model**  to access the List of Event Monitors, and click the **Add a Row** tool.
- Right-click the model or package in the Browser, and select  **New** .

Event Monitor Properties

You can modify an object's properties from its property sheet. To open an event monitor property sheet, double-click its diagram symbol or its Browser entry in the Event Monitors folder.

The following extended attributes are available on the *General* tab:

Name	Description
Workload management event monitor	Specifies that the event monitor is used for workload management. Selecting this option affects the types that are available in the Type field. Scripting name: WlmEventMonitor
Type	Specifies the type of event to record. Click the button to the right of the field to select multiple types. Scripting name: Type
Event condition	[connections, transactions, or statements type] Defines a filter that determines which connections cause a CONNECTION, STATEMENT or TRANSACTION event to occur. Scripting name: EventCondition
Details	[deadlock type] Specifies that the event monitor is to generate a more detailed deadlock connection event for each application that is involved in a deadlock. Scripting name: DeadlocksDetails

The following extended attributes are available on the *DB2* tab:

Name	Description
Write to	Specifies the location where the event monitor will record its information. If you are writing to a table, you can additionally associate the event monitor with one or more event monitor groups on the EVMGroup tab. Event monitor groups identify the logical data group for which a target table is being defined, and PowerDesigner models them as extended sub-objects with a stereotype of <>EventMonitor<>. Scripting name: WriteToObject
Blocked	[table, file] Specifies that each agent that generates an event should wait for an event buffer to be written out to disk if the agent determines that both event buffers are full. This option should be selected to guarantee no event data loss. Scripting name: Blocked
Buffer size	[table, file] Specifies the size of the event monitor buffers (in units of 4K pages). All event monitor file I/O is buffered to improve the performance of the event monitors. Scripting name: BufferSize
Path	[file] The name of the directory in which the event monitor should write the event files data. The path must be known at the server. Scripting name: Path

Name	Description
Max files	[file] Specifies that there is a limit on the number of event monitor files that will exist for a particular event monitor at any time. Scripting name: MaxFiles
Maximum file size	[file] Specifies that there is a limit to the size of each event monitor file. Scripting name: MaxFileSize
Append	[file] Specifies that if event data files already exist when the event monitor is turned on, then the event monitor will append the new event data to the existing stream of data files. Scripting name: Append
Pipe name	[pipe] The name of the pipe to which the event monitor will write the data. The naming rules for pipes are platform specific. Scripting name: PipeName
Start	Specifies that the event monitor must be activated manually or is to be automatically activated whenever the database partition on which the event monitor runs is activated. Scripting name: Start
Scope	Either the event monitor reports on all database partitions (global) or only on the database partition that is running (local). Scripting name: Scope
Database partition	[pipe, file] Specifies the database partition on which the event monitor is to run. Scripting name: DBPartitionNum

Event Monitor Group Properties

You can create and manage event monitor groups from the EVMGroup tab of an event monitor. PowerDesigner models event monitor groups as extended sub-objects with a stereotype of <>EVMGroup<>.

The following extended attributes are available on the *General* tab:

Name	Description
Group	Identifies the logical data group for which a target table is being defined. Scripting name: Group
Table	Specifies the name of the target table. Scripting name: Table

Name	Description
PCTDeactivate	If a table is being created in a DMS table space, the PCTDEACTIVATE parameter specifies how full the table space must be before the event monitor automatically deactivates. Scripting name: PCTDeactivate
Tablespace	Defines the table space in which the table is to be created Scripting name: Tablespace
Trunc	Specifies that the STMT_TEXT and STMT_VALUE_DATA columns are defined as VARCHAR(n), where n is the largest size that can fit into the table row. Scripting name: Trunc
Inclusion criteria	Specifies which elements will be included in the table. Scripting name: Elements
Elements	Identifies a monitor element that will be included in or excluded from monitoring Scripting name: ElementList

2.5.5 Federated Systems (DB2)

A federated system consists of a DB2 instance that operates as a federated server, a database that acts as the federated database, one or more data sources, and clients (users and applications) that access the database and data sources. PowerDesigner provides support for federated servers for DB2 for Common Server v9.0 and higher through nicknames, servers, wrappers, and user mappings.

2.5.5.1 Nicknames (DB2)

A nickname is an identifier that an application uses to reference a data source object, such as a table or view. In a federated system, you use can nicknames to access data source objects and improve the performance of queries on remote data sources. Nicknames are supported for DB2 for Common Server v9.7 and higher.

Creating a Nickname

You can create a nickname in any of the following ways:

- Right-click the model node in the Browser and select *New Nickname for External Table*. In the dialog, select a table from a PDM open in the workspace and click *OK*. PowerDesigner will create a shortcut to the external table along with the necessary nickname and server objects.
- Select  *Model > Nicknames* to access the List of Nicknames, and click the *Add a Row* tool.

- Right-click the model (or a package) in the Browser, and select  [Nickname](#).

Nickname Properties

You can modify an object's properties from its property sheet. To open a nickname property sheet, double-click its Browser entry in the Nicknames folder.

The following extended attributes are available on the [General](#) tab:

Property	Description
Server	Specifies the server that contains the table the nickname is referring to (see Servers (DB2) [page 397]). Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object. Scripting name: Server
Remote schema	Specifies the schema to which the table or view belongs. If left empty, the server authorization name is used. Scripting name: RemoteSchema
Remote table	Specifies the remote table name. Scripting name: RemoteTable
Relational definition	Selecting Yes displays the Relational Definition tab, which contains a field to allow you to specify an appropriate definition in SQL. Scripting name: RemoteTable

The following extended attributes are available on the [Options](#) tab:

Property	Description
Code page	Specifies the code page of the file at the data source. This option is valid only for federated databases that use Unicode. Scripting name: CODEPAGE
Column delimiter	Specifies a single character to use as the delimiter that separates columns in the table-structured file. Scripting name: COLUMN_DELIMITER
Data source	Specifies the name of the script to invoke. Scripting name: DATASOURCE
File path	Specifies the fully qualified directory path and file name of the Excel spreadsheet to access. Scripting name: FILE_PATH

Property	Description
Key column	Specifies the name of the column on which the file is sorted. Scripting name: KEY_COLUMN
Namespaces	Specifies the namespaces that are associated with the namespace prefixes that are used in the XPATH and TEMPLATE options for each column. Scripting name: NAMESPACES
No empty string	Specifies whether the remote data source server can contain empty strings. Scripting name: NO_EMPTY_STRING
Numeric string	Specifies how to treat numeric strings. When set to Y for a column, the query optimizer recognizes that the column contains no blanks that could interfere with the sorting of the data in the column. Scripting name: NUMERIC_STRING
Range	Specifies the range of Excel cells to use. Scripting name: RANGE
Remote object	Specifies the name of the BioRS databank that is associated with the nickname. This name determines the schema and the BioRS databank for the nickname. Scripting name: REMOTE_OBJECT
SOAP action	Specifies the URI SOAPACTION attribute from the Web Services Description Language (WSDL) format. Scripting name: SOAPACTION
Sorted	Specifies whether the file at the data source is or is not sorted in ascending order. Scripting name: SORTED
Streaming	Specifies whether the source document should be separated into logical fragments for processing. Scripting name: STREAMING
Template	Specifies the nickname template fragment to use to construct a SOAP request. Scripting name: TEMPLATE
Timeout	Specifies the maximum time, in minutes, to wait for a response from the data source server. Scripting name: TIMEOUT
Validate	Specifies whether the source document is validated to ensure that it conforms to an XML schema or document type definition (DTD) before data is extracted from it. Scripting name: VALIDATE

Property	Description
Validate data file	For sorted files, this option specifies whether the wrapper verifies that the key column is sorted in ascending order and checks for null keys. Scripting name: VALIDATE_DATA_FILE
XPath	Specifies the XPath expression that identifies the XML elements that represent individual tuples. Scripting name: XPATH
XML root	Specifies the XML root element to add to the values of an XML column that references an XML sequence. Scripting name: XML_ROOT
Additional options	Can be used to specify any additional options. Scripting name: OtherOptions

2.5.5.2 Servers (DB2)

The instance owner supplies a name to identify the data source, along with the type and version of the data source, the database name for the data source (RDBMS only), and metadata that is specific to the data source. This information is called a server definition. Data sources answer requests for data and are servers in their own right. Servers are supported for DB2 for Common Server v9.7 and higher.

Creating a Server

i Note

A server can be created automatically when you create a nickname (see [Nicknames \(DB2\) \[page 394\]](#)) using the [New Nickname for External Table](#) command.

You can manually create a server in any of the following ways:

- Select to access the List of Servers, and click the [Add a Row](#) tool.
- Right-click the model (or a package) in the Browser, and select .
- Use the [Create](#) tool next to the [Server](#) field on the [General](#) tab of a nickname or user mapping property sheet (see [Servers \(DB2\) \[page 397\]](#)).

Server Properties

You can modify an object's properties from its property sheet. To open a server property sheet, double-click its Browser entry in the Servers folder.

The following extended attributes are available on the *General* tab:

Property	Description
Authorization / Password	Required only for DB2 family data sources. Specify the authorization ID and password under which any necessary actions are performed at the data source when the CREATE SERVER statement is processed. This authorization ID is not used when establishing subsequent connections to the server. Scripting name: Authorization, Password
Type / Version	Specify the type and version of the data source. Scripting name: Type, Version
Wrapper	Specifies the wrapper (see Wrappers (DB2) [page 400]) that the DB2 federated server uses to interact with the server object. Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object. Scripting name: Wrapper
Model	Specifies the PDM containing the structure of the database on the server being referenced. Use the tools to the right of the list to browse for an object or view the properties of the currently selected object. Scripting name: Model

The following extended attributes are available on the *Options* tab:

Property	Description
Fold login / Fold password	Specify the case of user IDs and passwords that the DB2 federated server sends to the data source server for authentication, and whether they can be null. Scripting name: FOLD_ID, FOLD_PW
Enable plan hints	Specifies whether plan hints, which are statement fragments that provide extra information for data source optimizers to help decide whether to use an index, which index to use, or which table join sequence to use. This information can, for certain query types, improve query performance. Scripting name: PLAN_HINTS
Ignore user data types	Specifies whether the DB2 federated server should determine the built-in type that underlies a UDT without strong typing. Scripting name: IGNORE_UDT
Push down	Specifies whether the DB2 federated server will consider letting the data source evaluate operations. Scripting name: PUSHDOWN
Collating sequence	Specifies whether the data source uses the same default collating sequence as the DB2 federated server, based on the NLS code set and the country information. Scripting name: COLLATING_SEQUENCE

Property	Description
Date compatibility	<p>Specifies whether the DATE compatibility semantics associated with the <code>TIMESTAMP(0)</code> data type are applied to the connected database.</p> <p>Scripting name: <code>DATE_COMPAT</code></p>
No trailing blanks	<p>Specifies whether data sources which have variable character data types pad the length with trailing blanks.</p> <p>Scripting name: <code>VARCHAR_NO_TRAILING_BLANKS</code></p>
Enforce savepoint	<p>Specifies whether the DB2 federated server should enforce detecting or building of application save-point statements.</p> <p>Scripting name: <code>IUD_APP_SVPT_ENFORCE</code></p>
CPU ratio / IO ratio	<p>Indicate how much faster or slower a data source's CPU and I/O system runs than those of the the DB2 federated server.</p> <p>Scripting name: <code>CPU_RATIO, IO_RATIO</code></p>
Packet size	<p>Specifies the packet size of the Sybase interface file in bytes. If the data source does not support the specified packet size, the connection will fail. Increasing the packet size when each record is very large (for example, when inserting rows into large tables) significantly increases performance.</p> <p>Scripting name: <code>PACKET_SIZE</code></p>
Timeout	<p>Specifies the number of seconds the DB2 federated server will wait for a response from Sybase Open Client for any SQL statement. The value of seconds is a positive whole number in DB2 Universal Database's integer range.The timeout value that you specify depends on which wrapper you are using. The default behavior of the <code>TIMEOUT</code> option for the Sybase wrappers is 0, which causes DB2 to wait indefinitely for a response.</p> <p>Scripting name: <code>TIMEOUT</code></p>
Login timeout	<p>Specifies the number of seconds for the DB2 federated server to wait for a response from Sybase Open Client to the login request.</p> <p>Scripting name: <code>LOGIN_TIMEOUT</code></p>
Communication rate	<p>Specifies the communication rate between the DB2 federated server and the data source server in megabytes per second.</p> <p>Scripting name: <code>COMM_RATE</code></p>
Database name	<p>Specifies the database that you want the the DB2 federated server to access on the data source. For DB2, this value corresponds to a specific database within an instance or, with DB2 for z/OS or OS/390, the database <code>LOCATION</code> value.</p> <p>Not required for Oracle instances, which contain only one database.</p> <p>Scripting name: <code>DBNAME</code></p>

Property	Description
Sybase OCI path	Specifies the path and name of the Sybase Open Client interfaces file. On Windows NT servers, the default is %DB2PATH%\interfaces. Scripting name: IFILE
Node	Specifies the name by which the data source is defined as an instance to its RDBMS. Scripting name: NODE
Additional options	Can be used to specify any additional options. Scripting name: OtherOptions

2.5.3 Wrappers (DB2)

Wrappers are mechanisms by which the federated server interacts with data sources. The federated server uses routines stored in a library called a wrapper module to implement a wrapper. Wrappers are supported for DB2 for Common Server v9.7 and higher.

Creating a Wrapper

You can create a wrapper in any of the following ways:

- Select to access the List of Wrappers, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select .
- Use the *Create* tool next to the *Wrapper* field on the *General* tab of a server property sheet (see [Servers \(DB2\) \[page 397\]](#)).

Wrapper Properties

You can modify an object's properties from its property sheet. To open a wrapper property sheet, double-click its Browser entry in the Wrappers folder. The following extended attributes are available on the *Options* tab:

Property	Description
Library	Specifies the name of the file that contains the wrapper library module. Scripting name: Library

Property	Description
Fenced	<p>Specifies that the wrapper is fenced or trusted by DB2. A fenced wrapper operates under some restrictions.</p> <p>Scripting name: DB2_FENCED</p>
Language / Class or library	<p>Specify the language and implementation of the user mapping plug-in. Valid languages are Java (default) and C.</p> <p>For a plug-in written in Java, you must specify a case-sensitive string for the class name that corresponds to the user mapping repository class. For example, UserMappingRepositoryLDAP.</p> <p>For a plug-in written in C, you must specify any valid C library name.</p> <p>Scripting name: DB2_UM_PLUGIN_LANG, DB2_UM_PLUGIN</p>
Additional options	<p>Can be used to specify any additional options.</p> <p>Scripting name: OtherOptions</p>

2.5.5.4 User Mappings (DB2)

A user mapping is an association between an authorization ID on the federated server and the information that is required to connect to the remote data source. User mappings are supported for DB2 for Common Server v9.7 and higher.

Creating a User Mapping

You can create a user mapping in any of the following ways:

- Select to access the List of User Mappings, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select .

User Mapping Properties

You can modify an object's properties from its property sheet. To open a user mapping property sheet, double-click its Browser entry in the User Mappings folder.

The following extended attribute is available on the *General* tab:

Property	Description
Server	Specifies the name of the server object (see Servers (DB2) [page 397]) for the data source that the authorization-name can access. The server name is the local name for the remote server that is registered with the federated database. Scripting name: Server

The following extended attributes are available on the *Options* tab:

Property	Description
Accounting string	Specifies a DRDA accounting string. Valid values include any string that has 255 characters or fewer. Scripting name: ACCOUNTING_STRING
Remote user ID / password	Specify the remote user ID to which the local user ID is mapped, and its password in the remote system. If you do not specify a password, the password used to connect to the federated database is used. Scripting name: REMOTE_AUTHID, REMOTE_PASSWORD
Use trusted context	Specifies whether the user mapping is trusted. Scripting name: USE_TRUSTED_CONTEXT
Additional options	Can be used to specify any additional options. Scripting name: OtherOptions

2.6 Greenplum

To create a PDM with support for features specific to the Greenplum DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select  *Database*  *Edit Current DBMS* and expand the *Profile* node.

Abstract Data Types

The following extensions are available on the *Parameters* tab:

Name	Description
Input function1	Specifies the name of a function that converts data from the type's external textual form to its internal form. Scripting name: <code>Input</code>
Receive function	Specifies the name of a function that converts data from the type's external binary form to its internal form. Scripting name: <code>Receive</code>
Compression type	Specifies the type of compression. Scripting name: <code>Compressstype</code>
Default	Specifies the default value for the data type. Scripting name: <code>Default</code>
Element	Specifies that the type being created is an array; this specifies the type of the array elements. Scripting name: <code>Element</code>
Block size	Specifies the size of block. The value must be a multiple of 8192. Scripting name: <code>Blocksize</code>
Passed by value	Specifies that values of this data type are passed by value, rather than by reference. Scripting name: <code>Passedbyvalue</code>
Output function	Specifies the name of a function that converts data from the type's internal form to its external textual form. Scripting name: <code>Output</code>

Name	Description
Send function	Specifies the name of a function that converts data from the type's internal form to its external binary form. Scripting name: Send
Compression level	Specifies the level of compression. Scripting name: Compresslevel
Delimiter	Specifies the delimiter character to be used between values in arrays made of this type. Scripting name: delimiter character to be used between values in arrays made of this type.
Internal length	Specifies a numeric constant that specifies the length in bytes of the new type's internal representation. The default assumption is that it is variable-length. Scripting name: Internallength
Alignment	Specifies the storage alignment requirement of the data type. Scripting name: Alignment
Storage strategy	Specifies the storage strategy for the data type. Scripting name: Storage

Databases

The following extensions are available on the *General* tab:

Name	Description
Owner	Specifies the name of the database user who will own the new database, or DEFAULT to use the default owner (the user executing the command). Scripting name: Owner

The following extensions are available on the *Greenplum* tab:

Name	Description
Tablespace	Specifies the name of the tablespace that will be associated with the new database, or DEFAULT to use the template database tablespace. This tablespace will be the default tablespace used for objects created in this database. Scripting name: Tablespace

Name	Description
Template	<p>Specifies the name of the template from which to create the new database, or <code>DEFAULT</code> to use the default template.</p> <p>Scripting name: <code>Template</code></p>
Encoding	<p>Specifies the character set encoding to use in the new database. Specify a string constant (e.g., '<code>SQL_ASCII</code>'), or an integer encoding number, or <code>DEFAULT</code> to use the default encoding.</p> <p>Scripting name: <code>Encoding</code></p>
Connection limit	<p>Specifies the maximum number of concurrent connections possible. The default of <code>-1</code> means there is no limitation</p> <p>Scripting name: <code>ConnectionLimit</code></p>
SQL	<p>Specifies an hidden attribute to bear object options.</p> <p>Scripting name: <code>DatabaseOptions</code></p>

Domains

The following extensions are available on the [Additional Checks](#) tab:

Name	Description
Constraint name	<p>Specifies the name of the domain constraint .</p> <p>Scripting name: <code>DomnConstName</code></p>
N/A	<p>In the Check expression preview subtab the domain code is replaced with the Greenplum keyword value.</p> <p>Scripting name: <code>ConstraintDefn</code></p>

Materialized Views

The following extensions are available on the [General](#) tab:

Name	Description
Scope	<p>Specify if the materialized view is available for all or only local session. Note: These keywords are present for SQL standard compatibility, but have no effect in Greenplum Database.</p> <p>Scripting name: <code>TemporaryScope</code></p>

The following extensions are available on the *Options* tab:

Name	Description
Block size	Specifies the size, in bytes, for each block in a table. The value must be between 8192 and 2097152 bytes, and be a multiple of 8192. Scripting name: <code>BlockSize</code>
Append only	Specifies if the table must be created as an append-only table (TRUE) or as a regular heap-storage table (FALSE). Scripting name: <code>AppendOnly</code>
OIDs	Specifies whether to assign object identifiers to rows. This box is unchecked by default. Greenplum strongly recommends that you do not enable OIDS when creating a table. Scripting name: <code>OIDs</code>
Orientation	Set to column for column-oriented storage, or row (the default) for row-oriented storage. Scripting name: <code>Orientation</code>
On commit	Specifies the behavior of temporary tables at the end of a transaction block. Scripting name: <code>OnCommit</code>
Fill factor	Specifies the percentage that determines how full the index method will try to pack index pages. Scripting name: <code>FillFactor</code>
Compression type	Specifies ZLIB (default) or QUICKLZ compression type. Scripting name: <code>CompressType</code>
Level	For zlib compression of append-only tables, specifies a value between 1 (fastest compression) to 9 (highest compression ratio). Scripting name: <code>CompressLevel</code>

References

The following extensions are available on the *Greenplum* tab:

Name	Description
Deferrable	Specifies whether the constraint can be deferred. A constraint that is not deferrable will be checked immediately after every command. Checking of constraints that are deferrable may be postponed until the end of the transaction. Only foreign key constraints currently accept this clause. All other constraint types are not deferrable. Scripting name: <code>Deferrable</code>
Foreign key constraint deferred	If a constraint is deferrable, specifies the default time to check the constraint. <code>False</code> means the constraint is <code>INITIALLY IMMEDIATE</code> , it is checked after each statement. This is the default. <code>True</code> means the constraint is <code>INITIALLY DEFERRED</code> , it is checked only at the end of the transaction. Scripting name: <code>ForeignKeyConstraintDeferred</code>

Sequences

The following extensions are available on the *General* tab:

Name	Description
Column	Causes the sequence to be associated with a specific table column, such that if that column (or its whole table) is dropped, the sequence will be automatically dropped as well. Scripting name: <code>Column</code>
Temporary	If specified, the sequence object is created only for this session, and is automatically dropped on session exit. Scripting name: <code>Temporary</code>

The following extensions are available on the *Options* tab:

Name	Description
Start value	Allows the sequence to begin anywhere. The default starting value is <code>Minvalue</code> for ascending sequences and <code>Maxvalue</code> for descending ones. Scripting name: <code>Startvalue</code>
Minimum value	Specifies the minimum value a sequence can generate. Scripting name: <code>Minvalue</code>

Name	Description
Maximum value	Specifies the the maximum value for the sequence. Scripting name: Maxvalue
Cache	Specifies how many sequence numbers are to be preallocated and stored in memory for faster access. The minimum (and default) value is 1 (no cache). Scripting name: Cache
Increment	Specifies which value is added to the current sequence value to create a new value. A positive value will make an ascending sequence, a negative one a descending sequence. The default value is 1. Scripting name: Increment
Cycle	Allows the sequence to wrap around when the Maxvalue (for ascending) or Minvalue (for descending) has been reached. Scripting name: Cycle
SQL	Specifies the SQL text of the sequence options. Scripting name: SqncOptions

Tables

The following extensions are available on the [General](#) tab:

Name	Description
Like table	The LIKE clause specifies a table from which the new table automatically copies all column names, their data types, and their not-null constraints. Scripting name: LikeTable
Writable	[External table type only] Specifies the type of external table, readable being the default. Readable external tables are used for loading data into Greenplum Database. Writable external tables are used for unloading data. Scripting name: Writable
Web	[External table type only] Creates a web external table definition in Greenplum Database. Scripting name: ExternalWeb

Name	Description
Scope	[Temporary table type only] Specifies if the table is available for all or only local session. Note: The local and global keywords are present for SQL standard compatibility, but have no effect in Greenplum Database. Scripting name: TemporaryScope

Tablespaces

The following extensions are available on the *General* tab:

Name	Description
Owner	Specifies the name of the user who will own the tablespace. If omitted, defaults to the user executing the command. Scripting name: Owner
Filespace	Specifies the name of a Greenplum Database filesystem that was defined using the file space management utility. Scripting name: Filespace

Triggers

The following extensions are available on the *Body* tab:

Name	Description
For each	Specifies whether the trigger procedure should be fired once for every row affected by the trigger event, or just once per SQL statement. Scripting name: ForEach

Users, Groups and Roles

The following extensions are available on the *General* tab:

Name	Description
Encrypted	Specifies whether the password is stored encrypted in the system catalogs. Scripting name: EncryptedPassword

The following extensions are available on the *Options* tab:

Name	Description
Super user	If SUPERUSER is specified, the role being defined will be a superuser, who can override all access restrictions within the database. Superuser status is dangerous and should be used only when really needed. Scripting name: SuperUser
Inherit	If specified, INHERIT (the default) allows the role to use whatever database privileges have been granted to all roles it is directly or indirectly a member of. With NOINHERIT, membership in another role only grants the ability to SET ROLE to that other role. Scripting name: Inherit
Login	If specified, LOGIN allows a role to log in to a database. A role having the LOGIN attribute can be thought of as a user. Roles with NOLOGIN (the default) are useful for managing database privileges, and can be thought of as groups. Scripting name: Login
Create DB	Specifies if the role being defined will be allowed to create new databases. NOCREATEDB (the default) will deny a role the ability to create databases. Scripting name: CreateDB
Create role	Specifies if the role being defined will be allowed to create new roles, alter other roles, and drop other roles. NOCREATEROLE (the default) will deny a role the ability to create roles or modify roles other than their own. Scripting name: CreateRole
Create user	If TRUE, the user is allowed to create new users. This option also turns the user into a superuser who can override all access restrictions. Scripting name: CreateUser
Create external table	[Roles only] Specifies if the role is allowed to create external tables. Scripting name: CreateExtTable

Name	Description
Connection limit	[Roles only] Specifies the maximum number of concurrent connections possible. The default of -1 means there is no limitation. Scripting name: ConnectionLimit
Resource queue	Specifies the resource queue. Scripting name: ResourceQueue
Valid until	Specifies a date and time after which the role's password is no longer valid. If this clause is omitted the password will never expire. Scripting name: ValidUntil
Deny point / to	[Roles only] Specifies time-based constraints that are enforced at login. Scripting name: DenyPointStart, DenyPointEnd
Options	Gets or sets user options. Scripting name: UserOptions

Views

The following extensions are available on the *General* tab if you select *Temporary* in the *Type* box:

Name	Description
Scope	Specifies if the view is available for all or only local session. Note: The <code>local</code> and <code>global</code> keywords are present for SQL standard compatibility, but have no effect in Greenplum Database. Scripting name: TemporaryScope

2.6.1 Conversions (Greenplum)

PowerDesigner models Greenplum conversions between character set encodings as extended objects with a stereotype of <<Conversion>>.

Creating a Conversion

You can create a conversion in any of the following ways:

- Select to access the List of Conversions, and click the *Add a Row* tool.
- Right-click the model or package in the Browser, and select .

Conversion Properties

You can modify an object's properties from its property sheet. To open an conversion property sheet, double-click its Browser entry in the Conversions folder.

The following extended attributes are available on the *Greenplum* tab:

Name	Description
Source encoding	Specifies the source encoding name. Scripting name: <i>For</i>
Destination encoding	Specifies the destination encoding name. Scripting name: <i>To</i>
Function name	Specifies the function used to perform the conversion. Scripting name: <i>From</i>
Options	Specifies the conversion options. Scripting name: <i>ConversionOptions</i>

2.6.2 Aggregates (Greenplum)

PowerDesigner models user-defined Greenplum aggregate functions as extended objects with a stereotype of <<Aggregate>>.

Creating an Aggregate

You can create an aggregate in any of the following ways:

- Select **Model** **Aggregates** to access the List of Aggregates, and click the *Add a Row* tool.
- Right-click the model or package in the Browser, and select **New** .

Aggregate Properties

You can modify an object's properties from its property sheet. To open an aggregate property sheet, double-click its Browser entry in the Aggregates folder.

The following extended attributes are available on the *General* tab:

Name	Description
Name	Specifies the name of the aggregate function. Scripting name: AggregateName
Input data types	Specifies the input data type on which this aggregate function operates. To create a zero-argument aggregate function, write * in place of the list of input data types. An example of such an aggregate is count (*). Scripting name: InputTypeList
Owner	Specifies the owner of the aggregate. Scripting name: Owner
Ordered	Specifies that the created aggregate function is ordered. Scripting name: Ordered

The following extensions are available on the [Greenplum](#) tab:

Name	Description
Final function	<p>Specifies the name of the final function called to compute the aggregate's result after all input rows have been traversed. The function must take a single argument of type <code>state_data_type</code>. The return data type of the aggregate is defined as the return type of this function. If a final function is not specified, then the ending state value is used as the aggregate's result, and the return type is <code>state_data_type</code>.</p> <p>Scripting name: <code>FinalFunc</code></p>
Initial condition	<p>Specifies the initial setting for the state value. This must be a string constant in the form accepted for the data type <code>state_data_type</code>. If not specified, the state value starts out null.</p> <p>Scripting name: <code>InitCond</code></p>
Preliminary aggregation function	<p>Specifies the name of a preliminary aggregation function. This is a function of two arguments, both of type <code>state_data_type</code>. It must return a value of <code>state_data_type</code>. A preliminary function takes two transition state values and returns a new transition state value representing the combined aggregation. In Greenplum, if the result of the aggregate function is computed in a segmented fashion, the preliminary aggregation function is invoked on the individual internal states in order to combine them into an ending internal state.</p> <p>Scripting name: <code>PreFunc</code></p>
State transition function	<p>Specifies the name of the state transition function to be called for each input row. For an N-argument aggregate function, the function must take N+1 arguments, the first being of type <code>state_data_type</code> and the rest matching the declared input data type(s) of the aggregate. The function must return a value of type <code>state_data_type</code>. This function takes the current state value and the current input data value(s), and returns the next state value.</p> <p>Scripting name: <code>SFunc</code></p>
Sort operator	<p>Specifies the associated sort operator for a MIN- or MAX-like aggregate. This is just an operator name (possibly schema-qualified). The operator is assumed to have the same input data types as the aggregate (which must be a single-argument aggregate).</p> <p>Scripting name: <code>SortOp</code></p>
State data type	<p>Specifies the data type for the aggregate's state value.</p> <p>Scripting name: <code>SType</code></p>

2.6.3 Rules (Greenplum)

PowerDesigner models Greenplum rules (which allow you to define alternate actions to be performed as well or instead of insertions, updates, or deletions), as extended objects with a stereotype of <>Rule<>.

Creating a Rule

You can create a rule in any of the following ways:

- Select **Model** **Rules** to access the List of Rules, and click the *Add a Row* tool.
- Right-click the model or package in the Browser, and select **New** **Rule**.

Rule Properties

You can modify an object's properties from its property sheet. To open an rule property sheet, double-click its Browser entry in the Rules folder.

The following extended attributes are available on the *General* tab:

Name	Description
Table	Specifies the table or view the rule applies to. Scripting name: RTable
Action	INSTEAD indicates that the commands should be executed instead of the original command. ALSO indicates that the commands should be executed in addition to the original command. Scripting name: RAction
Event	Specifies the event that raises the rule. Scripting name: REvent

The following extended attributes are available on the *Greenplum* tab:

Name	Description
Condition	Specifies any SQL conditional expression (returning boolean). The condition expression may not refer to any tables except NEW and OLD, and may not contain aggregate functions. Scripting name: RCondition

Name	Description
Command(s)	Specifies the command or commands that make up the rule action. Valid commands are SELECT, INSERT, UPDATE, or DELETE. Scripting name: RCommand

2.6.4 Resource Queues (Greenplum)

PowerDesigner models Greenplum resource queues as extended objects with a stereotype of <<ResourceQueue>>.

Creating a Resource Queue

You can create a resource queue in any of the following ways:

- Select   to access the List of Resource Queues, and click the *Add a Row* tool.
- Right-click the model or package in the Browser, and select  .

Resource Queue Properties

You can modify an object's properties from its property sheet. To open an resource queue property sheet, double-click its Browser entry in the Resource Queues folder.

The following extended attributes are available on the *Greenplum* tab:

Name	Description
Active statement	Specifies the number of active queries that are allowed to run at the same time. Scripting name: ActiveStatement
Max cost	Specifies the maximum limit on the total cost of queries that can be executed by roles assigned to that queue. Scripting name: MaxCost
Cost overcommit	Specifies if a query that exceeds the allowed cost threshold will be allowed to run but only when the system is idle. Scripting name: CostOverCommit

Name	Description
Memory limit	Specifies the total memory quota for all statements submitted from users in this resource queue. Scripting name: <code>MemoryLimit</code>
Min cost	Specifies the minimum query cost limit of what is considered a small query. Scripting name: <code>MinCost</code>
Priority	Specifies the priority of queries associated with a resource queue. Scripting name: <code>Priority</code>

2.7 JSON

To create a PDM with support for generating JSON select **JSON** in the **DBMS** field of the **New Model** dialog.

In a JSON PDM, the model represents a JSON document containing an array, `objects`, in which each table is a JSON object containing:

- A property, `id`, containing the table's code.
- An array, `fields`, containing the table's columns as objects with an `id` and `type`.
To change a column to type array containing an array `items`, open the column property sheet and select the **Array** property.
- An object for each reference to a child table.
To embed the child table inside the reference object, open the property sheet of the reference link and select the **Nested child** property.
- An array, `primary key`, containing the table's primary keys.
- An array `required` containing the table's columns that are set to **Mandatory**.

To preview the JSON to be generated for a table, open its property sheet, click the **Preview** tab, and select the **Schema** sub-tab.

To preview the JSON to be generated for the model, open its property sheet, click the **Preview** tab, and select the **Schema** sub-tab.

The following generation options are available on the model property sheet **Options** tab:

Option	Description
Label for ...	Specify the labels for the arrays of tables, columns, users, and rules.
Include title	Specifies to include a <code>title</code> property containing the object's Name on all objects.
Include description	Specifies to include a <code>description</code> property containing the object's Comment on all objects.

Option	Description
Include owner	Specifies to include an <code>owner</code> property containing the table's <i>Owner</i> on table objects. Selecting this option will also add an array, <code>schemas</code> at the document root.
Include creation date	Specifies to include a <code>date</code> property containing the object's <i>Creation Date</i> on all objects.
Include rules	Specifies to include a <code>rules</code> array containing the business rules associated with the table on table objects

To generate the model as a JSON document, select *Database* *Generate Database*, specify a filename, and click *OK*.

2.8 Microsoft SQL Server

To create a PDM with support for features specific to the MS SQL Server DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select *Database* *Edit Current DBMS* and expand the *Profile* node.

Note

The DBMS definition files for SQL Server v7.x and SQL Server 2000 are deprecated.

The following sections list the extensions provided for MS SQL Server.

Note

In addition to the extensions listed below, PowerDesigner supports the following features for SQL Server 2005 and higher:

- User Schemas – Use the `schema` stereotype to specify that a user is actually a schema, belonging to another user (the "principal").
- WithOption – Use the `withoptions` type to enable access to additional physical options when working with views.
- Support for multiple databases during live database reverse engineering.

Abstract Data Types

The following extensions are available on the *Microsoft* tab:

Name	Description
Assembly	Specifies the assembly to bind with the abstract data type. Scripting name: <code>Assembly</code>

Abstract Data Type Attributes

The following extensions are available on the *Microsoft* tab:

Name	Description
Nullable	Specifies that the type column allows null value. Scripting name: <code>Nullable</code>
Computed	Specifies that the type column is computed. Scripting name: Specifies that the type column is computed.
Identity	Specifies that the new column is an identity column. Scripting name: <code>Identity</code>
Expression	Specifies an expression that defines the value of a computed column. Scripting name: <code>Expression</code>
Persisted	Specifies that the SQL Server Database Engine will physically store the computed values in the table, and update the values when any other columns on which the computed column depends are updated. Scripting name: <code>Persisted</code>
Seed	Specifies the value used for the very first row loaded into the table. Scripting name: <code>Seed</code>
Increment	Specifies the incremental value added to the identity value of the previous row loaded. Scripting name: <code>Increment</code>
Default	Specifies the value provided for the column when a value is not explicitly supplied during an insert. Scripting name: <code>Default</code>

Name	Description
Row GUID	Specifies that the new column is a row GUID column Scripting name: RowGuidCol
Collation	Specifies the collation for the column. Scripting name: Collate

Columns

The following extensions are available on the *Microsoft* tab:

Name	Description
Row global unique identifier	Indicates that the new column is a row global unique identifier column. Only one unique identifier column per table can be designated as the ROWGUIDCOL column. Scripting name: ExtRowGuidCol
Sparse	[v2008 and higher] Specifies that the column is a sparse column. The storage of sparse columns is optimized for null values. Sparse columns cannot be designated as NOT NULL. Scripting name: Sparse
Filestream	[v2008 and higher] Specifies that when the FILESTREAM storage attribute is specified for a column, all values for that column are stored in a FILESTREAM data container on the file system Scripting name: Filestream
Do not validate check constraints during replication	Specifies that "NOT FOR REPLICATION" keywords are used to prevent the CHECK constraint from being enforced during the distribution process used by replication. Scripting name: ExtCkcNotForReplication
Default constraint name	Contains the name of the constraint that is used to apply a default value to the column. If empty, the "constraint" keyword is not generated. Scripting name: ExtDeftConstName
Not null constraint name	Contains the name of the constraint that is used to apply a mandatory property of the column. If empty, the "constraint" keyword is not generated. Scripting name: ExtNullConstName
Collation name	A single string that specifies the collation name for a SQL collation. Scripting name: ExtCollation

Name	Description
Identity seed and increment	<p>Is a string composed of two integer values separated by a comma.</p> <p>First value is the seed value of the identity column, meaning the value to be assigned to the first row in the table.</p> <p>Second value is the increment to add to the seed value for successive rows in the table.</p> <p>Scripting name: ExtIdentitySeedInc</p>
Identity value not replicated	<p>Indicates that the IDENTITY property should not be enforced when a replication login inserts data into the table.</p> <p>Scripting name: ExtIdtNotForReplication</p>
XML schema collection	<p>Applies only to the XML data type for associating an XML schema collection with the type.</p> <p>Scripting name: XMLSchemaCollection</p>
Content type	<p>- CONTENT:</p> <p>Specifies that each instance of the XML data type in column_name can contain multiple top-level elements. CONTENT applies only to the XML data type and can be specified only if xml_schema_collection is also specified. If not specified, CONTENT is the default behavior.</p> <p>- DOCUMENT:</p> <p>Specifies that each instance of the XML data type in column_name can contain only one top-level element. DOCUMENT applies only to the XML data type and can be specified only if xml_schema_collection is also specified.</p> <p>Scripting name: ContentType</p>

Facts

The following extensions are available on the [Microsoft](#) tab:

Name	Description
Storage mode	<p>Specifies the storage mode for the fact.</p> <p>Scripting name: StorageMode</p>
Visible	<p>Determines the visibility of the fact.</p> <p>Scripting name: Visible</p>

Dimensions

The following extensions are available on the *Microsoft* tab:

Name	Description
Type	Provides information about the contents of the dimension. Scripting name: Type
Storage mode	Determines the storage mode for the parent element. Scripting name: StorageMode
AttributeAllMemberName	Contains the caption, in the default language, for the All member of the dimension. Scripting name: AttributeAllMemberName
WriteEnabled	Indicates whether dimension writebacks are available (subject to security permissions). Scripting name: WriteEnabled

Dimension Attributes

The following extensions are available on the *Microsoft* tab:

Name	Description
Type	Identifies the specific type of level. You can choose between: <ul style="list-style-type: none">• ALL: Indicates the top (All) level of a dimension (the one that precalculates all the members of all lower levels).• YEAR: a level that refers to years (Time dimension only).• QUARTER: a level that refers to (calendar) quarters (Time dimension only).• MONTH: a level that refers to months (Time dimension only).• WEEK: a level that refers to weeks (Time dimension only).• DAY: a level that refers to days (Time dimension only).• DAYOFWEEK: a level that refers to days of the week (Time dimension only).• DATE: a level that refers to dates (Time dimension only).• HOUR: a level that refers to hours (Time dimension only).• MINUTE: a level that refers to minutes (Time dimension only).• SECOND: Indicates that a level refers to seconds (Time dimension only). Scripting name: Type

Name	Description
MembersWith-Data	Determines whether to display data members for non-leaf members in the parent attribute. Scripting name: MembersWithData
OrderBy	Describes how to order the members contained in the attribute. Scripting name: OrderBy
MemberName-sUnique	Determines whether member names under the parent element must be unique. Scripting name: MemberNamesUnique
IsAggregatable	Specifies whether the values of the DimensionAttribute element can be aggregated. Scripting name: IsAggregatable
AttributeHier-archyEnabled	Determines whether an attribute hierarchy is enabled for the attribute. Scripting name: AttributeHierarchyEnabled
AttributeHier-archyVisible	Determines whether the attribute hierarchy is visible to client applications. Scripting name: AttributeHierarchyVisible

Databases

The following extensions are available on the *Microsoft* tab:

Name	Description
Primary	Specifies that the associated file specification list defines the primary file. Scripting name: Primary
File	Gets or sets the file specification. Scripting name: FileListFileSpec
Filegroup	Gets or sets the first filegroup name. Scripting name: FilelistFilegroup
File (filegroup)	Gets or sets the Filegroup specification. Scripting name: FileGroupFileSpec
Log on	Gets or sets the log file specification. Scripting name: LogOnFileSpec

Name	Description
Collation name	<p>Specifies the default collation for the database. Collation name can be either a Windows collation name or a SQL collation name.</p> <p>Scripting name: <code>Collate</code></p>
Attach	<p>Specifies that a database is attached from an existing set of operating system files.</p> <p>Scripting name: <code>ForAttach</code></p>
With	<p>Controls Service Broker options on the database.</p> <p>Service Broker options can only be specified when the <code>FOR ATTACH</code> clause is used.</p> <ul style="list-style-type: none"> • <code>ENABLE_BROKER</code>: Specifies that Service Broker is enabled for the specified database. • <code>NEW_BROKER</code>: Creates a new <code>service_broker_guid</code> value in both <code>sys.databases</code> and the restored database and ends all conversation endpoints with clean up. The broker is enabled, but no message is sent to the remote conversation endpoints. • <code>ERROR_BROKER_CONVERSATIONS</code>: Ends all conversations with an error stating that the database is attached or restored. The broker is disabled until this operation is completed and then enabled. <p>Scripting name: <code>ForAttachWith</code></p>
Attach rebuild log	<p>Specifies that the database is created by attaching an existing set of operating system files.</p> <p>Scripting name: <code>ForAttachRebuildLog</code></p>
Database chaining	<p>When <code>ON</code> is specified, the database can be the source or target of a cross database ownership chain.</p> <p>When <code>OFF</code>, the database cannot participate in cross database ownership chaining. The default is <code>OFF</code>.</p> <p>Scripting name: <code>WithDbChaining</code></p>
Trust worthy	<p>When <code>ON</code> is specified, database modules (for example, views, user-defined functions, or stored procedures) that use an impersonation context can access resources outside the database.</p> <p>When <code>OFF</code>, database modules in an impersonation context cannot access resources outside the database. The default is <code>OFF</code>.</p> <p>Scripting name: <code>WithTrustworthy</code></p>
Snapshot of	<p>Specifies the name of the new database snapshot.</p> <p>Scripting name: <code>AsSnapshotOf</code></p>

For information about the extended attributes available on the *Mirroring* tab, see [Database Mirroring \(SQL Server\)](#) [page 449].

Data Sources

The following extensions are available on the *OLE DB* tab:

Name	Description
Data provider	<p>Specifies the data provider. You can choose between:</p> <ul style="list-style-type: none">• .NET Framework Data Provider for Microsoft SQL Server• .NET Framework Data Provider for Oracle• Native Data Provider for OLE DB <p>Scripting name: DataProvider</p>
Connection string	<p>Specifies the connection string.</p> <p>Scripting name: ConnectionString</p>

The following extensions are available on the *Configuration* tab:

Name	Description
Server name	<p>Specifies the server name.</p> <p>Scripting name: ServerName</p>
Authentication	<p>[only for SQL Server] Specifies the Windows Authentication and SQL Server Authentication types.</p> <p>Scripting name: AuthenticationType</p>
User name	<p>Specifies the user name.</p> <p>Scripting name: UserName</p>
Password	<p>Specifies the password.</p> <p>Scripting name: Password</p>
Initial catalog	<p>[only for SQL Server and OLE DB] Specifies the Initial catalog.</p> <p>Scripting name: InitialCatalog</p>
Database File	<p>[only for SQL Server] Specifies a Microsoft SQL Server database file if you select an MSSQL connection.</p> <p>Scripting name: MSSQLDatabaseFile</p>
Logical name	<p>[only for SQL Server] Specifies the logical name of the selected database file.</p> <p>Scripting name: LogicalName</p>
Data providers	<p>[only for OLE DB] Specifies the data provider.</p> <p>Scripting name: DataProvider</p>

Name	Description
Location	[only for OLE DB] Specifies the location for OLEDB. Scripting name: <code>Location</code>
Persist security info	[only for OLE DB] Specifies that security information be persistent. Scripting name: <code>PersistSecurityInfo</code>
Use Windows NT Integrated Security	[only for OLE DB] Specifies whether to use windows NT Integrated Security or not. Scripting name: <code>UseNTIntegratedSecurity</code>

Dimension Hierarchies

The following extensions are available on the [Microsoft](#) tab:

Name	Description
AllMemberName	Contains the caption in the default language for the All member of a Hierarchy element. Scripting name: <code>AllMemberName</code>
MemberNamesUnique	Determines whether member names under the parent element must be unique. Scripting name: <code>MemberNamesUnique</code>
AllowDuplicateNames	Determines whether duplicate names are allowed in a Hierarchy element. Scripting name: <code>AllowDuplicateNames</code>

Fact Measures

The following extensions are available on the [Microsoft](#) tab:

Name	Description
AggregateFunction	Defines the common prefix to be used for aggregation names throughout the associated parent element. Scripting name: <code>AggregateFunction</code>
BindingType	Defines the binding type for the measure. Scripting name: <code>BindingType</code>

Name	Description
Visible	Determines the visibility of the fact measure. Scripting name: <code>Visible</code>
FormatString	Describes the display format for a CalculationProperty or a Measure element. Scripting name: <code>FormatString</code>

Indexes

Note

For additional information about special SQL Server index types, see [XML Indexes \(SQL Server\) \[page 446\]](#) and [Spatial Indexes \(SQL Server\) \[page 444\]](#).

The following extensions are available on the *Microsoft* tab:

Name	Description
Filegroup	Specifies the name of the filegroup. Scripting name: <code>FileGroup</code>
Partition scheme	Specifies the name of the partition scheme. Scripting name: <code>PartitionScheme</code>
Column	Specifies the partitioned column. Scripting name: <code>PartitionSchemeColumn</code>
Fill factor	Specifies a percentage that indicates how full the Database Engine should make the leaf level of each index page during index creation or rebuild. Scripting name: <code>FillFactor</code>
Max degree of parallelism	Overrides the max degree of parallelism configuration option for the duration of the index operation. Use MAXDOP to limit the number of processors used in a parallel plan execution. The maximum is 64 processors. Scripting name: <code>MaxDop</code>
Index padding	Specifies index padding. Scripting name: <code>PadIndex</code>
Statistics no recompute	Specifies whether distribution statistics are recomputed. Scripting name: <code>StatisticsNoRecompute</code>

Name	Description
Drop existing	Specifies that the named, preexisting clustered, nonclustered, or XML index is dropped and rebuilt. Scripting name: DropExisting
Online	Specifies whether underlying tables and associated indexes are available for queries and data modification during the index operation. Scripting name: Online
Sort in temporary database	Specifies whether to store temporary sort results in tempdb. Scripting name: SortInTempDB
Allow row locks	Specifies whether row locks are allowed. Scripting name: AllowRowLocks
Allow page locks	Specifies whether page locks are allowed. Scripting name: AllowPageLocks
Ignore dup key	Specifies the error response to duplicate key values in a multiple row insert operation on a unique clustered or unique nonclustered index. Scripting name: IgnoreDupKey

If the index is not a cluster index, then the Include tab is displayed, allowing you to specify the columns with which it is associated.

Keys

The following extensions are available on the *Microsoft* tab:

Name	Description
Filegroup	Specifies the name of the filegroup. Scripting name: FileGroup
Fill Factor	Specifies how full SQL Server should make each index page used to store the index data. Scripting name: FillFactor

References

The following extensions are available on the *Microsoft* tab:

Name	Description
Do not validate foreign key constraint during replication	Specifies that "NOT FOR REPLICATION" keywords are used to prevent the FOREIGN KEY constraint from being enforced during the distribution process used by replication. Scripting name: ExtFkNotForReplication

Storages

The following extensions are available on the *Microsoft* tab:

Name	Description
Contains filestream	Specifies that the filegroup stores FILESTREAM binary large objects (BLOBs) in the file system. Scripting name: FileStream

Tables

The following extensions are available on the *Microsoft* tab:

Name	Description
Do not validate check constraints during replication	Specifies that "NOT FOR REPLICATION" keywords are used to prevent the TABLE CHECK constraint from being enforced during the distribution process used by replication. Scripting name: ExtCktNotForReplication
Table is partitioned	Specifies that the table is partitioned. Scripting name: PartitionedTable
Filegroup	[unpartitioned tables] Specifies the name of the filegroup. Scripting name: FileGroup
Text/Image	[unpartitioned tables] Specifies the name of the filegroup where text and image are stored. Scripting name: TextImageOn

Name	Description
Filestream	[unpartitioned tables] Specifies the name of the filegroup used for filestream. Scripting name: <code>FilestreamOnFilegroup</code>
Compression	[unpartitioned tables] Specifies the compression type of the table (none, row or page). Scripting name: <code>TableCompression</code>
Partition scheme	[partitioned tables, v2005 and higher] Specifies the name of the partition scheme. You must also specify the name of the partitioned column Scripting name: <code>PartitionScheme</code> , <code>PartitionSchemeColumn</code>
Filestream partition scheme	[partitioned tables, v2005 and higher] Specifies the name of the partition scheme. Scripting name: <code>FilestreamPartitionScheme</code> , <code>FilestreamPartitionSchemeColumn</code>
Compression	[partitioned tables] Specifies the partitions that use the compression. Scripting name: <code>DataCompression</code>

Triggers

The following extensions are available on the [Microsoft](#) tab:

Name	Description
Option	Is a concatenation of the WITH ENCRYPTION (which is illegal for CLR triggers, and which prevents the trigger from being published) and EXECUTE AS (which specifies the security context under which the trigger is executed) options. Scripting name: <code>Option</code>

An additional property is available for CLR triggers (see [CLR Procedures, Functions, and Triggers \(SQL Server\)](#) [page 437]).

Users

The following extensions are available on the *General* tab (v2005 and higher):

Name	Description
Implicit schema	Specifies that the stored procedure <code>sp_grantdbaccess</code> will be used instead of a create user statement during database generation. Scripting name: <code>ImplicitSchema</code>
Default schema	Specifies the first schema searched to resolve the names of objects for this user. If the Implicit schema option is selected, then the default schema is initialized to the name of the user. Scripting name: <code>DefaultSchema</code>

Views

The following extensions are available on the *Microsoft* tab:

Name	Description
Encryption option	Defines the encryption option of the view, respecting the view creation syntax. Scripting name: <code>WithOption</code>

2.8.1 Horizontal Partitioning (SQL Server)

SQL Server supports horizontal partitioning of tables and indexes, to make them more manageable by dividing them horizontally and spreading them across more than one filegroup in a database.

To partition a table or an index, specify a partition scheme and column on the *Microsoft* tab of its property sheet.

2.8.1.1 Partition Functions (SQL Server)

A partition function specifies how a table or index can be partitioned.

Context

PowerDesigner models partition functions as extended objects with a stereotype of <<PartitionFunction>>, and lists them under the *Model* menu and in the *Partition Functions* folder under the model in the Browser.

Procedure

1. Select to access the *List of Partition Functions*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *Microsoft* tab:

Name	Description
Input Parameter Type	Specifies the data type of the column used for partitioning. All data types are valid, except text, ntext, image, xml, timestamp, varchar(max), nvarchar(max), varbinary(max), alias data types, or CLR user-defined data types. Scripting name: InputParameterType
Length	Specifies the length of input parameter data type. Scripting name: InputParameterLength
Precision	Specifies the precision of input parameter data type Scripting name: InputParameterPrec
Interval Side	Specifies to which side of each boundary value interval the boundary_value [....n] belongs. You can choose between: <ul style="list-style-type: none">○ left [default]○ right Interval values are sorted by the database engine in ascending order from left to right. Scripting name: IntervalSide
Boundary Values	Specifies the boundary values for each partition of a partitioned table or index. All values must be separated by commas. Scripting name: BoundaryValues

2.8.1.2 Partition Schemes (SQL Server)

A partition scheme maps the partitions produced by a partition function to a set of user-defined filegroups.

Context

PowerDesigner models partition schemes as extended objects with a stereotype of <<PartitionScheme>>, and lists them under the *Model* menu and in the *Partition Schemes* folder under the model in the Browser.

Procedure

1. Select to access the *List of Partition Schemes*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *Microsoft* tab:

Name	Description
Partition Function	Specifies the partition function using the scheme. Partitions created by the partition function are mapped to the filegroups specified in the partition scheme. Scripting name: <code>PartitionFunction</code>
All Partitions	Specifies that all partitions map to the filegroup specified by the <i>File Groups</i> property. Scripting name: <code>AllPartitions</code>
File Groups	Specifies the names of the filegroups to hold the partitions specified by the partition function. If [PRIMARY] is specified, the partition is stored on the primary filegroup. If ALL is specified, only one filegroup name can be specified. Scripting name: <code>Filegroups</code>

2.8.2 Common Language Runtime (CLR) Integration (SQL Server)

CLR integration allows stored procedures, triggers, and user-defined types, functions, and aggregate functions to be written for SQL Server in any .NET language, such as VB .NET or C#.

2.8.2.1 CLR Assemblies (SQL Server)

An assembly is a DLL file used to deploy objects written in one of the managed code languages hosted by the Microsoft .NET Framework common language runtime (CLR), instead of in Transact-SQL.

Context

Assemblies are supported from v12 and higher. PowerDesigner models assemblies as extended objects with a stereotype of <>Assembly<>, and lists them under the *Model* menu and in the *Assemblies* folder under the model in the Browser.

Procedure

1. Select to access the *List of Assemblies*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *Microsoft* tab:

Name	Description
Authorization	Specifies the name of a user or role as the owner of the assembly. Scripting name: Authorization
File name	Specifies the local path or network location where the assembly that is being uploaded is located, and also the manifest file name that corresponds to the assembly. Can be entered as a fixed string or an expression evaluating to a fixed string. Scripting name: FileName
Permission set	Specifies a set of code access permissions that are granted to the assembly when it is accessed by SQL Server. You can choose between: <ul style="list-style-type: none"><input type="radio"/> SAFE<input type="radio"/> UNSAFE<input type="radio"/> EXTERNAL_ACCESS Scripting name: PermissionSet
Visibility	Specifies that the assembly is visible for creating common language runtime (CLR) functions, stored procedures, triggers, user-defined types, and user-defined aggregate functions against it. You can choose between: <ul style="list-style-type: none"><input type="radio"/> On<input type="radio"/> Off Scripting name: Visibility
Unchecked data	By default, ALTER ASSEMBLY fails if it must verify the consistency of individual table rows. This option allows postponing the checks until a later time by using DBCC CHECKTABLE. Scripting name: UncheckedData

2.8.2.2 CLR Aggregate Functions (SQL Server)

SQL Server allows developers to create custom aggregate functions in managed code, and to make these functions accessible to Transact-SQL or other managed code.

Context

PowerDesigner models aggregate functions as extended objects with a stereotype of <<Aggregate>>, and lists them under the *Model* menu and in the *Aggregates* folder under the model in the Browser.

Procedure

1. Select to access the *List of Aggregates*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *Microsoft* tab:

Name	Description
Owner	Specifies the name of a schema as the owner of the aggregate function. Scripting name: Owner
Assembly	Specifies the assembly to bind with the aggregate function. Scripting name: Assembly
Class name	Specifies the name of the class in the assembly that implements the aggregate function. If the class name is not specified, SQL Server assumes it is the same as the aggregate name. Scripting name: Class
Parameter name	[v2005] Specifies the name of the input parameter. Scripting name: InputParameterName
Type	[v2005] Specifies the type of the input parameter. All scalar data types or CLR user-defined types can be used, except text, ntext, and image. Scripting name: InputParameterType
Return type	Specifies the return type of the aggregate function. All scalar data types or CLR user-defined types can be used as return type, except text, ntext, and image. Scripting name: ReturnType

Name	Description
Length	Specifies the length of return data type. Scripting name: <code>ReturnTypeLength</code>
Precision	Specifies the precision of return data type. Scripting name: <code>ReturnTypePrec</code>

- For v2008 and higher, click the *Parameters* tab, create parameters as necessary, and specify their name, type, length, and precision.

2.8.2.3 CLR User-Defined Types (SQL Server)

User-defined types (UDTs) can contain multiple elements and have behaviors, differentiating them from the traditional alias data types which consist of a single SQL Server system data type. UDTs in SQL Server are well suited to date, time, currency, and extended numeric types, geospatial applications, and encoded or encrypted data.

Context

PowerDesigner models user-defined types as abstract data types, and lists them under the *Model* menu and in the *Abstract Data Types* folder under the model in the Browser.

Procedure

- Select to access the *List of Abstract Data Types*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select *Abstract Data Type*).
- Enter the following properties in the *General* tab:

Name	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.

Name	Description
Type	Select CLR .
Class	Click the <i>Select Object</i> tool to select a class from an object-oriented model open in the workspace as the supertype.

3. Click the *Microsoft* tab and enter the following properties:

Name	Description
Assembly	Specifies the assembly to bind with the abstract data type. Scripting name: <code>Assembly</code>
Mandatory	Specifies whether the type can hold a null value. Scripting name: <code>Mandatory</code>

2.8.2.4 CLR Procedures, Functions, and Triggers (SQL Server)

SQL Server supports writing user-defined procedures, functions, and triggers in any Microsoft .NET Framework programming language.

Context

PowerDesigner models user-defined types as standard procedures and triggers that use a CLR template and are linked to a method from an associated OOM, and lists them under the *Model* menu and in the standard folders under the model in the Browser.

Procedure

1. Create a standard procedure or function and, on the *Body* tab of its property sheet, select CLR Procedure, CLR Function, or CLR Trigger from the template list. A Class method field will be displayed to the right of the template list.
2. Click the *Select Method* tool to the right of the Class method field, in order to specify the associated method.
3. Click the *Microsoft* tab and select an assembly from the list to bind to the procedure or function.

Name	Description
Assembly	Specifies the assembly where the class method is defined. Scripting name: Assembly

2.8.3 Encryption (SQL Server)

SQL Server provides a security infrastructure to support hierarchical encryption and key management through certificates and asymmetric and symmetric keys

2.8.3.1 Certificates (SQL Server)

A public key certificate is a digitally-signed statement that binds the value of a public key to the identity of the person, device, or service that holds the corresponding private key.

Context

PowerDesigner models certificates as extended objects with a stereotype of <<Certificate>>, and lists them under the *Model* menu and in the *Certificates* folder under the model in the Browser.

Procedure

1. Select to access the *List of Certificates*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *Microsoft* tab:

Name	Description
Authorization	[v2005] Specifies the name of a user as the owner of the certificate. Scripting name: Authorization
Assembly	[v2005] Specifies a signed assembly that has already been loaded into the database. Scripting name: Assembly

Name	Description
Assembly File	[v2005] Specifies the complete path, including file name, to a DER encoded file that contains the certificate. The path name can be a local path or a UNC path to a network location. The file will be accessed in the security context of the SQL Server service account. This account must have the required file system permissions. Scripting name: <code>AssemblyFile</code>
Executable	[v2005] If the EXECUTABLE option is used, the file is a DLL that has been signed by the certificate. Scripting name: <code>Executable</code>
File	Specifies the complete path, including file name, to the private key. The private key path name can be a local path or a UNC path to a network location. The file will be accessed in the security context of the SQL Server service account. This account must have the necessary file system permissions. Scripting name: <code>PrivateKeyFile</code>
Encryption password (private key)	Specifies the password that will be used to encrypt the private key. Scripting name: <code>PrivateKeyEncryptionPassword</code>
Decryption password	Specifies the password required to decrypt a private key that is retrieved from a file. Scripting name: <code>PrivateKeyDecryptionPassword</code>
Subject	Specifies the value of the subject field in the metadata of the certificate as defined in the X.509 standard. Scripting name: <code>Subject</code>
Encryption password	[v2005] Use this option only if you want to encrypt the certificate with a password. Scripting name: <code>EncryptionPassword</code>
Start date	Specifies the date on which the certificate becomes valid. If not specified, <code>StartDate</code> will be set equal to the current date. Scripting name: <code>StartDate</code>
Expiry date	Specifies the date on which the certificate expires. If not specified, <code>ExpiryDate</code> will be set to a date one year after <code>StartDate</code> . Scripting name: <code>ExpiryDate</code>
Active for begin dialog	Specifies that the certificate is available to the initiator of a Service Broker dialog conversation. Scripting name: <code>ActiveForBeginDialog</code>

2.8.3.2 Asymmetric Keys (SQL Server)

An asymmetric key is made up of a private key and the corresponding public key. While asymmetric encryption is relatively resource-intensive, it is more secure than symmetric encryption.

Context

PowerDesigner models asymmetric keys as extended objects with a stereotype of <<AsymmetricKey>>, and lists them under the *Model* menu and in the *Asymmetric Keys* folder under the model in the Browser.

Procedure

1. Select to access the *List of Asymmetric Keys*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *Microsoft* tab:

Name	Description
Authorization	Specifies the name of a user as the owner of the asymmetric key. Scripting name: Authorization
Source type	[v2008 and higher] Specifies the type of source (File, Executable file, Assembly or Provider) Scripting name: Source
Assembly	Specifies the name of an assembly from which to load the public key. Scripting name: Assembly
Assembly file	Specifies the path of a file from which to load the key. Scripting name: AssemblyFile
Provider	[v2008 and higher] Specifies the name of the EKM (Extensible Key Management) provider. Scripting name: Provider
Executable	[v2005] If the EXECUTABLE option is used, the file attribute specifies an assembly file from which to load the public key, otherwise the file attribute specifies the path of a strong name file from which to load the key pair. Scripting name: Executable

Name	Description
Algorithm	Specifies the algorithm used to encrypt the key. Scripting name: Algorithm
Create disposition	[v2008 and higher] Creates a new key or use an existing one. Scripting name: CreateDisposition
Provider key name	[v2008 and higher] Specifies the key name from the external provider. Scripting name: ProviderKeyName
Encryption password	Specifies the password with which to encrypt the private key. If this clause is not present, the private key will be encrypted with the database master key. Scripting name: EncryptionPassword

2.8.3.3 Symmetric Keys (SQL Server)

A symmetric key is one key that is used for both encryption and decryption. Symmetric encryption is faster than asymmetric encryption, but not as secure.

Context

PowerDesigner models symmetric keys as extended objects with a stereotype of <<SymmetricKey>>, and lists them under the *Model* menu and in the *Symmetric Keys* folder under the model in the Browser.

Procedure

1. Select to access the *List of Symmetric Keys*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *Microsoft* tab:

Name	Description
Authorization	Specifies the name of a user or role as the owner of the key. Scripting name: Authorization

Name	Description
Certificate	Specifies the name of the certificate that will be used to encrypt the symmetric key. Scripting name: Certificate
Password	Specifies a password from which to derive a TRIPLE_DES key with which to secure the symmetric key. Password complexity will be checked. You should always use strong passwords. Scripting name: Password
Symmetric key	Specifies a symmetric key to be used to encrypt the key that is being created. Scripting name: SymmetricKey
Asymmetric key	Specifies an asymmetric key to be used to encrypt the key that is being created. Scripting name: AsymmetricKey
Key source	Specifies a pass phrase from which to derive the key. Scripting name: KeySource
Algorithm	Specifies the algorithm used to encrypt the key Scripting name: Algorithm
Identity value	Specifies an identity phrase from which to generate a GUID for tagging data that is encrypted with a temporary key. Scripting name: IdentityValue

2.8.4 Full Text Search (SQL Server)

SQL Server supports full-text queries against a table's plain character data.

PowerDesigner supports this feature through the full text catalog and full text index objects.

2.8.4.1 Full-Text Catalogs (SQL Server)

A full-text catalog is a virtual object that regroups full-text indexes.

Context

PowerDesigner models full-text catalogs as extended objects with a stereotype of <<FullTextCatalog>>, and lists them under the *Model* menu and in the *Full-Text Catalogs* folder under the model in the Browser.

Procedure

1. Select to access the *List of Full-Text Catalogs*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *Microsoft* tab:

Name	Description
Authorization	Specifies the name of a user or role as the owner of the full text catalog. Scripting name: Authorization
File group	Specifies the name of the SQL Server filegroup (or storage) of which the new catalog will be part. Scripting name: FileGroup
Path	Specifies the root directory for the catalog. Scripting name: Path
Accent sensitivity	Specifies whether the catalog is accent sensitive for full text indexing. Scripting name: AccentSensitivity
Default	Specifies that the catalog is the default catalog. Scripting name: Default

2.8.4.2 Full-Text Indexes (SQL Server)

A full-text index stores information about significant words and their location within a given column. This information is used to quickly compute full-text queries that search for rows with particular words or combinations of words.

Context

PowerDesigner models full-text indexes as table indexes with an index type set to **FULLTEXT**.

Procedure

1. Create a standard index and, on the *General* tab, select **FULLTEXT** in the *Type* field.

2. Enter the following properties in the *Microsoft* tab:

Name	Description
Catalog	Specifies the full text catalog where the full text index is defined. Scripting name: <code>FullTextCatalog</code>
Change tracking	Specifies whether or not SQL Server maintains a list of all changes to the indexed data. You can choose between: <ul style="list-style-type: none"> ○ manual ○ auto ○ off ○ off, no population Scripting name: <code>ChangeTracking</code>

2.8.5 Spatial Indexes (SQL Server)

SQL Server 2008 and higher supports spatial data types and indexes. PowerDesigner supports these new features through table indexes with the type set to SPATIAL.

Creating a Spatial Index

To create a spatial index:

1. Create a table containing a column of type `geography` or `geometry`.
2. Create a standard index and, on the *General* tab, select `SPATIAL` in the *Type* field. The *Columns* tab is renamed to *Spatial Options*.
3. Click the *Spatial Options* tab, select your spatial column in the *Indexed column* field, and complete the remaining properties.

Spatial Index Properties

You can modify an object's properties from its property sheet. To open a spatial index property sheet, double-click its Browser entry. The following extended attributes are available on the *Spatial Options* tab:

Name	Description
Indexed column	Specifies the spatial column on which the index is based Scripting name: <code>IndexedColumn</code>

Name	Description
Tessellation scheme	<p>Specifies the tessellation scheme for the spatial index.</p> <p>Scripting name: <code>TesselationType</code></p>
Bounding box	<p>Specifies a numeric four-tuple that defines the four coordinates of the bounding box: the x-min and y-min coordinates of the lower, left corner, and the x-max and y-max coordinates of the upper right corner.</p> <p>Scripting name: <code>BoundingBoxDefn</code></p>
Cells per object	<p>Specifies the number of tessellation cells (any integer between 1 and 8192, inclusive) per object that can be used for a single spatial object in the index by the tessellation process.</p> <p>Scripting name: <code>CellsPerObject</code></p>
Grids	<p>Specifies the density of the grid at each level of a tessellation scheme.</p> <p>Scripting name: <code>GridsDefn</code></p>
Fill factor	<p>Specifies a percentage that indicates how full the Database Engine should make the leaf level of each index page during index creation or rebuild.</p> <p>Scripting name: <code>FillFactor</code></p>
Index padding	<p>Specifies index padding.</p> <p>Scripting name: <code>PadIndex</code></p>
Max degree of parallelism	<p>Overrides the max degree of parallelism configuration option for the duration of the index operation. Use MAXDOP to limit the number of processors (up to 64) used in a parallel plan execution.</p> <p>Scripting name: <code>MaxDop</code></p>
Allow row locks	<p>Specifies whether row locks are allowed.</p> <p>Scripting name: <code>AllowRowLocks</code></p>
Allow page locks	<p>Specifies whether page locks are allowed.</p> <p>Scripting name: <code>AllowPageLocks</code></p>
Store sort result	<p>Specifies to store temporary sort results in tempdb.</p> <p>Scripting name: <code>SortInTempDB</code></p>
Do not recompute statistics	<p>Specifies to recompute distribution statistics.</p> <p>Scripting name: <code>StatisticsNoRecompute</code></p>
Drop if exist	<p>Specifies that the named, preexisting clustered, nonclustered, or XML index is dropped and rebuilt.</p> <p>Scripting name: <code>DropExisting</code></p>

2.8.6 XML Indexes (SQL Server)

SQL Server 2005 provides improvements in indexing XML data. PowerDesigner supports these new features through table indexes with the type set to XML.

Creating an XML Index

To create an XML index:

1. Create a standard index and, on the *General* tab, select **XML** in the *Type* field.
2. Click the *Microsoft* tab and specify any appropriate additional options.

XML Index Properties

You can modify an object's properties from its property sheet. To open an XML index property sheet, double-click its Browser entry.

The following extended attributes are available on the *Microsoft* tab:

Name	Description
Primary	Specifies that this is the primary XML index. Scripting name: <code>XMLPrimary</code>
Primary index	Specifies the primary XML index to use in creating a secondary XML index. Scripting name: <code>PrimaryXMLIndex</code>
Secondary XML index type	Specifies the type of the secondary XML index. Scripting name: <code>SecondaryXMLIndexType</code>
Fill factor	Specifies a percentage that indicates how full the database engine should make the leaf level of each index page during index creation or rebuild. Scripting name: <code>FillFactor</code>
Max degree of parallelism	Overrides the max degree of parallelism configuration option for the duration of the index operation. Use MAXDOP to limit the number of processors used in a parallel plan execution. The maximum is 64 processors. Scripting name: <code>MaxDop</code>
Index padding	Specifies index padding. Scripting name: <code>PadIndex</code>

Name	Description
Statistics no recompute	Specifies whether distribution statistics are recomputed. Scripting name: StatisticsNoRecompute
Drop existing	Specifies that the named, preexisting clustered, nonclustered, or XML index is dropped and rebuilt. Scripting name: DropExisting
Sort in temporary database	Specifies whether to store temporary sort results in tempdb. Scripting name: SortInTempDB
Allow row locks	Specifies whether row locks are allowed. Scripting name: AllowRowLocks
Allow page locks	Specifies whether page locks are allowed. Scripting name: AllowPageLocks

2.8.7 XML Data Types (SQL Server)

SQL Server allows you to store XML documents and fragments in a database.

Procedure

1. Create a standard column and, on the *General* tab, select **XML** in the *Data type* field.
2. Enter the following properties in the *Microsoft* tab:

Name	Description
XML schema collection	Specifies an XML schema collection for the type. Scripting name: XMLSchemaCollection
Content type	Specifies the nature of the content to be stored in the column. You can choose between: <ul style="list-style-type: none"> ◦ CONTENT – [default] the data can contain multiple top-level elements. ◦ DOCUMENT – the data can contain only one top-level element. Scripting name: ContentType

2.8.7.1 XML Schema Collections (SQL Server)

An XML schema collection provides validation of and data type information about the XML to be stored in columns with the XML data type. Schemas provide information about the types of attributes and elements in the XML data type instance to allow it to be stored significantly more compactly than untyped XML.

Context

PowerDesigner models XML schema collections as extended objects with a stereotype of <<XMLSchemaCollection>>, and lists them under the *Model* menu and in the *XML Schema Collections* folder under the model in the Browser.

Procedure

1. Select to access the *List of XML Schema Collections*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *Microsoft* tab:

Name	Description
Owner	Specifies the name of a user, role, or schema as the owner of the schema collection. Scripting name: Owner
XML model	Specifies an XML model to link to the schema. Scripting name: XMLModel
Content	Specifies the content of the xml schema. By default this field contains the %xmlModel-Content% template, which represents the content of the linked XML model. Scripting name: Content

2.8.8 Database Mirroring (SQL Server)

SQL Server supports database mirroring, in which the principal server sends, in real-time, blocks of its database log records to the mirror instance which, in the event of failover, can be made available within a few seconds.

Context

PowerDesigner supports database mirroring with endpoints and extensions on the database object.

Procedure

1. Right-click the model in the Browser, select *Properties* and, on the *General* tab, click the *Create* tool to the right of the *Database* field.
2. Click the Mirroring tab and specify any appropriate properties.

Name	Description
Enable mirroring	Enables mirroring for the database. Scripting name: <code>EnableMirroring</code>
Partner/ Witness	Specifies the role that the database will play in the mirroring relationship. You can choose between: <ul style="list-style-type: none">○ Partner – the database is either a principal or mirror database.○ Witness – the database acts as a witness to a mirroring relationship. A SET WITNESS clause affects both copies of the database, but can only be specified on the principal server. If a witness is set for a session, a quorum is required to serve the database, regardless of the SAFETY setting. Scripting names: <code>Partner</code> , <code>Witness</code>

Name	Description
Options	<p>Specifies mirroring options for the database. You can choose between:</p> <ul style="list-style-type: none"> ○ <None> ○ server ○ off ○ failover ○ force_service_allow_data_loss ○ resume ○ safety full ○ safety off ○ suspend ○ timeout <p>Scripting name: <code>MirrorOptions</code></p>
Server	<p>For partner mirroring, specifies the server network address of an instance of SQL Server to act as a failover partner in a new database mirroring session.</p> <p>For witness mirroring, specifies an instance of the Database Engine to act as the witness server for a database mirroring session.</p> <p>Scripting name: <code>MirrorServer</code></p>
Time-out	<p>[if partner is selected] Specifies the time-out period in seconds. The time-out period is the maximum time that a server instance waits to receive a PING message from another instance in the mirroring session before considering that other instance to be disconnected.</p> <p>Scripting name: <code>TimeOut</code></p>

2.8.8.1 End Points (SQL Server)

An end point encapsulates a transport protocol and a port number, and enables SQL Server to communicate over the network.

Context

PowerDesigner models end points as extended objects with a stereotype of `<>EndPoint`, and lists them under the *Model* menu and in the *End Points* folder under the model in the Browser.

Procedure

1. Select **Model > End Points** to access the *List of End Points*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select **New > End Point**).
2. Enter the following properties in the *Microsoft* tab:

Name	Description
Owner	Specifies the owner of the endpoint. Scripting name: Owner
State	Specifies the state of the endpoint at creation. You can choose between: <ul style="list-style-type: none">○ started○ stopped○ disabled Scripting name: State
Protocol: Name	Specifies the transport protocol to be used by the endpoint. You can choose between: <ul style="list-style-type: none">○ http○ tcp Scripting name: Protocol
Protocol: Argument	Allows you to enter arguments for the chosen protocol. Scripting name: ProtocolArgument
Language: Name	Specifies the type of content to be sent. You can choose between: <ul style="list-style-type: none">○ soap○ tsql○ service_broker○ database_mirroring Scripting name: Language
Language: Argument	Allows you to enter arguments for the chosen language. Scripting name: LanguageArgument

2.8.9 Service Broker (SQL Server)

SQL Server provides Service Broker, which manages a queue of services, and allows applications that use it to communicate by sending messages to one another as part of a conversation. The participants in a conversation must agree on the name and content of each message.

PowerDesigner supports service broker through the following objects:

- Message types - define the type of data that a message can contain.
- Contracts - define which message types an application uses to accomplish a particular task.
- Queues - store messages.
- Event notifications - execute in response to a DDL statements and SQL Trace events by sending information about these events to a Service Broker service.
- Services - are specific tasks or sets of tasks.

2.8.9.1 Message Types (SQL Server)

Message types define the type of data that a message can contain and specify the type of XML validation that SQL Server performs for messages of that type. For arbitrary or binary data, you can specify that SQL Server performs no validation.

Context

PowerDesigner models message types as extended objects with a stereotype of <<MessageType>>, and lists them under the [Model](#) menu and in the [Message Types](#) folder under the model in the Browser.

Procedure

1. Select [Model](#) [Message Types](#) to access the [List of Message Types](#), click the [Add a Row](#) tool, and then click the [Properties](#) tool (or right-click the model or a package in the Browser, and select [New](#) [Message Type](#)).
2. Enter the following properties in the [Microsoft](#) tab:

Name	Description
Owner	Specifies a database user or role as the owner of the message type. If the current user is dbo or sa, this may be the name of any valid user or role. Otherwise, it must be the name of the current user, a user that the current user has IMPERSONATE permission for, or a role to which the current user belongs. By default, the message type belongs to the current user. Scripting name: Owner

Name	Description
Validation	<p>Specifies how the Service Broker validates the message body for messages of this type. You can choose between:</p> <ul style="list-style-type: none"> ◦ none [default] – no validation performed ◦ empty – message must contain no data ◦ well_formed_xml – message must contain well-formed XML ◦ valid_xml with schema collection – message must conform to the specified XML schema <p>Scripting name: Validation</p>
Schema	<p>Specifies the name of the schema to be used for validating the message contents.</p> <p>Scripting name: SchemaCollectionName</p>

2.8.9.2 Contracts (SQL Server)

Contracts define the message types used in a conversation. The initiating service specifies the contract when the conversation begins and the target service specifies the contracts that the target service accepts conversations for.

Context

PowerDesigner models contracts as extended objects with a stereotype of <<Contract>>, and lists them under the *Model* menu and in the *Contracts* folder under the model in the Browser.

Procedure

1. Select to access the *List of Contracts*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *Microsoft* tab:

Name	Description
Owner	<p>Specifies a database user or role as the owner of the contract. If the current user is dbo or sa, this may be the name of any valid user or role. Otherwise, it must be the name of the current user, a user that the current user has IMPERSONATE permission for, or a role to which the current user belongs. By default, the contract belongs to the current user.</p> <p>Scripting name: Owner</p>

- Click the *Message Types* tab, and create or add message contracts as necessary to associate message types with the contract and specify by whom they may be sent.

2.8.9.3 Message Contracts (SQL Server)

Message contracts associate a message type with a contract, and specify which parties to the conversation can send that type of message.

Context

PowerDesigner models message contracts as extended objects with a stereotype of <<MessageContract>>, and lists them under the *Model* menu and in the *Message Contracts* folder under the model in the Browser.

Procedure

- Select to access the *List of Message Contracts*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select .

Alternatively, you can create or add message contracts using the tools on the *Message Types* tab of a contract.

- Enter the following properties in the *Microsoft* tab:

Name	Description
Sent by	<p>Specifies which endpoint can send a message of the indicated message type. Contracts document the messages that services can use to have specific conversations. Each conversation has two endpoints: the initiator endpoint, the service that started the conversation, and the target endpoint, the service that the initiator is contacting.</p> <p>Scripting name: Sender</p>

Name	Description
Message type	Specifies the message type of the contract. Scripting name: <code>MessageType</code>

2.8.9.4 Queues (SQL Server)

When a message arrives for a service, Service Broker places the message on the queue associated with the service.

Context

PowerDesigner models queues as extended objects with a stereotype of <<Queue>>, and lists them under the *Model* menu and in the *Queues* folder under the model in the Browser.

Procedure

1. Select to access the *List of Queues*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select .
2. Enter the following properties in the *Microsoft* tab:

Name	Description
Owner	Specifies the owner of the queue. Scripting name: <code>Owner</code>
Status	Specifies that the queue is available. This is the default. If a queue is unavailable, no messages can be added to or removed from it. If you create a queue as unavailable, then no messages can be added to it until it is made available with an ALTER QUEUE statement. Scripting name: <code>Status</code>

Name	Description
Retention	<p>Specifies that all messages sent or received on conversations using this queue are retained in the queue until the conversations have ended. This allows you to retain messages for auditing purposes, or to perform compensating transactions if an error occurs.</p> <p>The default is to not retain messages in the queue in this way.</p> <p>Scripting name: <code>Retention</code></p>
Activation	<p>Specifies that a stored procedure is required to activate message processing for the queue.</p> <p>Scripting name: <code>Activation</code></p>
Status (activation)	<p>Specifies that Service Broker activates the associated stored procedure when the number of procedures currently running is less than <code>MAX_QUEUE_READERS</code> and when messages arrive on the queue faster than the stored procedures receive messages.</p> <p>This is the default.</p> <p>Scripting name: <code>ActivationStatus</code></p>
Procedure	<p>Specifies the name of the stored procedure to activate to process messages in this queue.</p> <p>Scripting name: <code>ActivationProcedureName</code></p>
MaxQueueReaders	<p>Specifies the maximum number of instances of the activation stored procedure that the queue can start at the same time. Must be set to between 0 and 32767.</p> <p>Scripting name: <code>ActivationMaxQueueReaders</code></p>
Execute as	<p>Specifies the user under which the activation stored procedure runs. SQL Server must be able to check the permissions for this user at the time that the queue activates the stored procedure. You can choose between:</p> <ul style="list-style-type: none"> ○ SELF - the stored procedure executes as the current user. (The database principal executing this <code>CREATE QUEUE</code> statement.) ○ OWNER - the stored procedure executes as the owner of the queue. <p>Scripting name: <code>ActivationExecuteAs</code></p>
File group	<p>Specifies the SQL Server filegroup on which to create the queue.</p> <p>Scripting name: <code>FileGroup</code></p>

2.8.9.5 Event Notifications (SQL Server)

An event notification sends information about a database or server event to a service broker service.

Context

PowerDesigner models event notifications as extended objects with a stereotype of <<EventNotification>>, and lists them under the *Model* menu and in the *Event Notifications* folder under the model in the Browser.

Procedure

1. Select to access the *List of Event Notifications*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *Microsoft* tab:

Name	Description
Applies on	<p>Specifies the scope of the event notification. You can choose between:</p> <ul style="list-style-type: none">○ database – the notification fires whenever the specified event in the FOR clause occurs anywhere in the instance of SQL Server.○ server - the notification fires whenever the specified event in the FOR clause occurs in the current database.○ queue - the notification fires whenever the specified event in the FOR clause occurs in the current queue. Can be specified only if FOR QUEUE_ACTIVATION or FOR BROKER_QUEUE_DISABLED is also specified. <p>Scripting name: AppliesOn</p>
Queue	<p>Specifies the queue to which the event notification applies. Available only if Applies on is set to "queue".</p> <p>Scripting name: Queue</p>
With fan in	<p>Instructs SQL Server to send only one message per event to any specified service for all event notifications that:</p> <ul style="list-style-type: none">○ are created on the same event.○ are created by the same principal (as identified by SID).○ specify the same service and broker_instance_specifier.○ specify WITH FAN_IN. <p>Scripting name: WithFanIn</p>

Name	Description
Events	<p>Specifies the name of the event type that causes the event notification to execute. Can be a Transact-SQL DDL, SQL Trace, or Service Broker event type.</p> <p>Scripting name: <code>Events</code></p>
Service	<p>Specifies the target service that receives the event instance data. SQL Server opens one or more conversations to the target service for the event notification. This service must honor the same SQL Server Events message type and contract that is used to send the message. See Services (SQL Server) [page 458].</p> <p>Scripting name: <code>Service</code></p>
Instance	<p>Specifies a service broker instance against which <code>broker_service</code> is resolved. Use 'current database' to specify the service broker instance in the current database.</p> <p>Scripting name: <code>Instance</code></p>

2.8.9.6 Services (SQL Server)

Services are specific tasks or set of tasks. Service Broker uses the name of the service to route messages, deliver messages to the correct queue within a database, and enforce the contract for a conversation.

Context

PowerDesigner models services as extended objects with a stereotype of `<>Service`, and lists them under the [Model](#) menu and in the [Services](#) folder under the model in the Browser.

Procedure

1. Select to access the [List of Services](#), click the [Add a Row](#) tool, and then click the [Properties](#) tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the [Microsoft](#) tab:

Name	Description
Owner	<p>Specifies the owner of the service.</p> <p>Scripting name: <code>Owner</code></p>

Name	Description
Queue	Specifies the queue that receives messages for the service. The queue must exist in the same database as the service. Scripting name: Queue

3. Click the *Contracts* tab, and create or add contracts as necessary to associate them with the service.

2.8.9.7 Routes (SQL Server)

For outgoing messages, Service Broker determines routing by checking the routing table in the local database. For messages on conversations that originate in another instance, including messages to be forwarded, Service Broker checks the routes in msdb.

Context

PowerDesigner models routes as extended objects with a stereotype of <<Route>>, and lists them under the *Model* menu and in the *Routes* folder under the model in the Browser.

Procedure

1. Select to access the *List of Routes*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *Microsoft* tab:

Name	Description
Owner	Specifies the owner of the route. Scripting name: Owner
Remote service	[v2005] Specifies the name of the remote service to which the route points. Scripting name: Service
Broker instance	Specifies the database that hosts the target service. Scripting name: BrokerInstance

Name	Description
Lifetime	<p>Specifies the amount of time, in seconds, that SQL Server retains the route in the routing table.</p> <p>Scripting name: <code>Lifetime</code></p>
Address	<p>Specifies the network address for the route. The <code>next_hop_address</code> specifies a TCP/IP address in the following format:</p> <pre>TCP://{{ dns_name netbios_name ip_address }} : port_number</pre> <p>Scripting name: <code>Address</code></p>
Mirror address	<p>Specifies the network address for a mirrored database with one mirrored database hosted at the <code>next_hop_address</code>. The <code>next_hop_mirror_address</code> specifies a TCP/IP address in the following format:</p> <pre>TCP://{{ dns_name netbios_name ip_address }} : port_number</pre> <p>Scripting name: <code>MirrorAddress</code></p>

2.8.9.8 Remote Service Bindings (SQL Server)

Remote service bindings create a binding that defines the security credentials to use to initiate a conversation with a remote service.

Context

PowerDesigner models remote service bindings as extended objects with a stereotype of <<RemoteServiceBinding>>, and lists them under the *Model* menu and in the *Remote Service Bindings* folder under the model in the Browser.

Procedure

1. Select **► Model ► Remote Service Bindings** to access the *List of Remote Service Bindings*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select **► New ► Remote Service Binding**).
2. Enter the following properties in the *Microsoft* tab:

Name	Description
Owner	Specifies the owner of the binding. Scripting name: Owner
Remote service	Specifies the remote service to bind to the user identified in the WITH USER clause. Scripting name: RemoteService
User	Specifies the database principal that owns the certificate associated with the remote service identified by the TO SERVICE clause. Scripting name: User
Anonymous	Specifies that anonymous authentication is used when communicating with the remote service. Scripting name: Anonymous

2.8.10 Resource Governor (SQL Server)

Resource Governor lets you limit resource requests by workloads for CPU time and memory to optimize their allocation.

Resource Governor is available in SQL Server 2008 and higher. PowerDesigner supports Resource Governor through the following objects:

- Workload groups – are containers for sets of similar session requests.
- Resource pools – represent the physical resources of the server.

2.8.10.1 Workload Groups (SQL Server)

A workload group serves as a container for session requests that are similar, to allow the aggregate monitoring of resource consumption and the application of a uniform policy to all the requests in the group. A group defines the policies for its members.

Context

PowerDesigner models workload groups as extended objects with a stereotype of <<WorkloadGroup>>, and lists them under the *Model* menu and in the *Workload Groups* folder under the model in the Browser.

Procedure

1. Select to access the *List of Workload Groups*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *Microsoft* tab:

Name	Description
Importance	Specifies the relative importance of a request in the workload group. Scripting name: <code>Importance</code>
Request maximum memory	Specifies the maximum amount of memory that a single request can take from the pool. Scripting name: <code>RequestMaxMemoryGrantPercent</code>
Request maximum CPU	Specifies the maximum amount of CPU time, in seconds, that a request can use. Scripting name: <code>RequestMaxCpuTimeSec</code>
Memory grant request time-out	Specifies the maximum time, in seconds, that a query can wait for a memory grant (work buffer memory) to become available. Scripting name: <code>RequestMemoryGrantTimeoutSec</code>
Maximum degree of parallelism	Specifies the maximum degree of parallelism (DOP) for parallel requests. Scripting name: <code>MaxDop</code>
Maximum requests	Specifies the maximum number of simultaneous requests that are allowed to execute in the workload group. Scripting name: <code>GroupMaxRequests</code>
Resource pool	Associates the workload group with the specified resource pool. Scripting name: <code>ResourcePool</code>

2.8.10.2 Resource Pools (SQL Server)

A resource pool represents the physical resources of the server.

Context

PowerDesigner models resource pools as extended objects with a stereotype of <<ResourcePool>>, and lists them under the *Model* menu and in the *Resource Pools* folder under the model in the Browser.

Procedure

1. Select to access the *List of Resource Pools*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *Microsoft* tab:

Name	Description
CPU percent Min	Specifies the guaranteed average CPU bandwidth for all requests in the resource pool when there is CPU contention. The value is an integer, with a default setting of 0. Scripting name: <code>MinCpuPercent</code>
CPU percent Max	Specifies the maximum average CPU bandwidth that all requests in resource pool will receive when there is CPU contention. The value is an integer, with a default setting of 100. Scripting name: <code>MaxCpuPercent</code>
Memory percent Min	Specifies the minimum amount of memory reserved for this resource pool that can not be shared with other resource pools. The value is an integer, with a default setting of 0. Scripting name: <code>MinMemoryPercent</code>
Memory percent Max	Specifies the total server memory that can be used by requests in this resource pool. The value is an integer, with a default setting of 100. Scripting name: <code>MaxMemoryPercent</code>

2.8.11 Schemas (SQL Server)

In SQL Server, schemas are distinct namespaces, separate from the users who created them, and can be transferred between users.

Context

PowerDesigner models schemas as users with a stereotype of <<Schema>>, and lists them under the *Model* menu and in the *Schemas* folder under the model in the Browser.

Procedure

1. Select to access the *List of Schemas*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *General* tab:

Name	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Owner	Specifies the name of the database-level principal user that owns the schema. This user may own other schemas, any of which may be his default schema. Scripting name: SchemaOwner

2.8.12 Synonyms (SQL Server)

PowerDesigner supports synonyms for SQL Server 2005 and higher through the standard synonym object.

Synonyms can be created for the following types of objects:

- Assembly (CLR) Stored Procedure
- Assembly (CLR) Table-valued Function
- Assembly (CLR) Scalar Function
- Assembly Aggregate (CLR) Aggregate Functions
- Replication-filter-procedure
- Extended Stored Procedure
- SQL Scalar Function
- SQL Table-valued Function
- SQL Inline-table-valued Function
- SQL Stored Procedure
- View
- Table

For general information about synonyms, see [Synonyms \(PDM\) \[page 174\]](#).

2.8.13 Analysis Services (SQL Server)

PowerDesigner allows you to retrieve and generate Microsoft SQL Server 2005 Analysis Server (SSAS) cubes using the Microsoft SQL Server 2005 Analysis Services add-in. You must have installed the SQL Server 2005 Management Tools client component.


To enable analysis services in PowerDesigner, select **Tools** **> General Options**, click the Add-ins category, select the Microsoft SQL Server 2005 Analysis Services add-in (PowerDesigner.AddIn.Pdm.SQLServer.dll), and then click **OK** to install it and return to the model.

2.8.13.1 Specifying a Data Source for Cubes


Before generating cubes, you must define a data source with an OLE DB connection that will specify from where the cubes will be populated.

Procedure

1. Create a data source in your PDM from the List of data sources or by right-clicking the model in the browser and selecting **New** **> Data Source** from the contextual menu.
2. Select the **OLE DB** tab and specify the kind of data provider.



- Click the Ellipsis tool to the right of the connection string field to open the provider-specific configuration dialog.



- Complete the parameters appropriately, click *Apply to Connection String*, and then *Test Connection*. Then click *OK* to return to the data source property sheet.
- Click *OK* to return to your model.

Results


When you have created the appropriate data sources, you can proceed with generating your cubes.

2.8.13.2 Generating Cubes for Microsoft SQL Server 2005

The Microsoft SQL Server 2005 Analysis Services add-in enables the generation of cubes.


Procedure

1. Select **Tools > Microsoft SQL Server 2005 Analysis Services > Generate Cubes** to open the wizard.




Click Next to continue.

2. Enter a server name, and select the database you want to generate to:




Click Next to continue.

3. The Select Cubes page lists the cubes available in the model, along with whether they currently exist in the database. Select the cubes you want to generate:



Click Next to continue.

4. The Generate Cubes page lists the cubes to be generated:



Click Finish to begin generation. Progress is displayed in the wizard, which will close automatically after successful completion.

If a cube already exists in the database, it is dropped and recreated. If a related dimension already exists, it is reused. To fully generate a cube, your model must include a complete mapping to a table.

2.8.13.3 Reverse Engineering Microsoft SQL Server 2005 Cubes


The Microsoft SQL Server 2005 Analysis Services add-in enables the reverse engineering of cubes.

Context

Before reverse-engineering cubes, you should create one or more PDMs to model the tables which provide its data. As part of the reverse-engineering process, PowerDesigner will create links from the reversed cubes to these tables.


Procedure

1. Select **Tools > Microsoft SQL Server 2005 Analysis Services > Reverse Engineer Cubes** to open the wizard.




Click Next to continue.

2. Enter a server name, and select the database you want to reverse from:




Click Next to continue.


3. The Select Cubes page lists the available cubes. Select the cubes you want to reverse engineer and then click Next to continue:



4. The Configure Data Sources page lists the data sources that are required to populate the selected cubes. For each source, select the Physical Data Model in which the tables are modeled, and then click Next to continue:



5. The Reverse Engineer Cubes page lists the cubes to be reversed:



Click Finish to begin reverse-engineering. Progress is displayed in the wizard, which will close automatically after successful completion.

2.9 Netezza

To create a PDM with support for features specific to the Netezza DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select **Database > Edit Current DBMS** and expand the **Profile** node.

The following sections list the extensions provided for Netezza.

Columns (v5.0 and higher)

The following extensions are available on the *Standard Checks* tab:

Name	Description
Default constraint name	Specifies the constraint name for default constraint Scripting name: DefaultConstName
Not null constraint name	Specifies the constraint name for not null constraint. Scripting name: NotNullConstName

Tables

The following extensions are available on the *Options* tab:

Name	Description
Distribution type	Specifies the type of row distribution. You can choose between None, hash, and random (on <i>General</i> tab for v4.5). Scripting name: Distribution
Columns	[hash or random distribution] Specifies the hash distribution columns (on <i>General</i> tab for v4.5). Scripting name: DistributeOnExplicitColumnList
Organize on	Specifies whether or not the table is organized. Scripting name: Organized
Columns	[organized table] Specifies the list of columns. Scripting name: OrganizedColumnList
Options	Displays the options defined for the table. Scripting name: TableOption

Databases (v5.0 and higher)

The following extensions are available on the *General* tab:

Name	Description
Character set	Specifies the default character set and collation. The default and only supported value is Latin9. Scripting name: Charset
Collation	The collation is binary. You cannot specify other values. Scripting name: Collation

Users/Groups (v5.0 and higher)

The following extensions are available on the *Options* tab:

Name	Description
SysId	Specifies the SYSID clause to choose the group ID of the new user/group. Scripting name: SysId
Owner	The user that created this user/group. Scripting name: Owner
Rowset limit	Specifies the maximum number of rows any query run by this user (or group) can return. Scripting name: RowsetLimit
Query timeout	Specifies the amount of time a query can run before the system sends the administrator a message. Scripting name: QueryTimeout
Session idle timeout	Specifies the amount of time a session can be idle before the system terminates it. Scripting name: SessionTimeout
Session priority	[group only] Specifies the default priority for the group. Scripting name: DefPriority
Default priority	[user only] Specifies the default priority for the user. Scripting name: DefPriority

Name	Description
Maximum priority	Specifies the maximum priority for the user/group. Scripting name: MaxPriority
Minimum resource	[group only] Specifies the minimum percentage of the system that a resource group will use when it has jobs. Scripting name: ResourceMinimum
Maximum resource	[group only] Specifies the maximum percentage of the system that a resource group can use. Scripting name: ResourceMaximum
Job maximum	[group only] Specifies the maximum number of concurrent jobs that a single resource group can run. Scripting name: JobMaximum
Password	[user only] Specifies the password used for database connection. Scripting name: PasswordDisplay
Valid until	[user only] Specifies the password validity. Scripting name: ValidUntil
Expire	[user only] Specify is the password expires on next connection. Scripting name: ExpirePassword
Authentication	[user only] Overrides the authentication for the user to LOCAL if specified. DEFAULT is the connection setting or whatever authentication is set. Scripting name: Authentication

Sequences (v5.0 and higher)

The following extensions are available on the [Options](#) tab:

Name	Description
Datatype	Specifies the data type. The value can be any exact integer type such as byteint, smallint, integer, or bigint. Scripting name: As
Start with	Specifies the starting value. Scripting name: StartWith

Name	Description
Increment	Specifies the increment value. The integer value can be any positive or negative integer, but it cannot be zero. Scripting name: <code>IncrementBy</code>
Minimum	Specifies the minimum value of the sequence. Scripting name: <code>Minvalue</code>
No min value	Results in a value of 1. Scripting name: <code>NoMinvalue</code>
Maximum	Specifies the maximum value of the sequence. Scripting name: <code>Maxvalue</code>
No max value	Results in the largest value for the specified datatype. Scripting name: <code>NoMaxvalue</code>
Cycle	Specifies whether the sequence continues to generate values after reaching either its maximum value (in an ascending sequence) or its minimum value (in a descending sequence). Scripting name: <code>Cycle</code>

2.9.1 History Configurations (Netezza)

History configurations provide support for query history logging. PowerDesigner models history configurations as extended objects with a stereotype of <>HistoryConfiguration>>.

Creating an History Configuration

You can create an history configuration in any of the following ways:

- Select to access the List of history configurations, and click the *Add a Row* tool.
- Right-click the model or package in the Browser, and select .

History Configuration Properties

You can modify an object's properties from its property sheet. To open an history configuration property sheet, double-click its Browser entry in the History Configurations folder.

The following extended attributes are available on the *Options* tab:

Name	Description
History type	Specifies the type of the database to create, which can be QUERY or NONE. Specify NONE to disable history collection. This is a required option which does not have a default value. Scripting name: Histtype
Data to collect	Specifies the history data to collect. Specify multiple values using comma-separated values, or click the <i>Select</i> tool to the right of the field to select them. Scripting name: Collect
Database / User / Password	Specifies the history database to which the captured data will be written, along with the user and password to use for accessing and inserting data. Scripting name: Database, User, Password
Load interval	Specifies the number of minutes to wait before checking the staged area for history data to transfer to the loading area. Scripting name: Loadinterval
Load retry	Specifies the number of times that the load operation will be retried. The valid values are 0 (no retry), 1 or 2. Scripting name: Loadretry
Minimum / Maximum threshold	Specify the minimum and maximum amounts of history data in MB to collect before transferring the staged batch files to the loading area. Values of 0 disable these threshold checks. Scripting name: Loadminthreshold, Loadmaxthreshold
Disk full threshold	This option is reserved for future use. Any value you specify will be ignored. The default value is 0. Scripting name: Diskfullthreshold
Storage limit	Specifies the maximum size of the history data staging area in MB. Scripting name: Storage limit
Enable history	Specifies to log information about queries to the query history database. Scripting name: Enablehist
Enable system	Specifies to log information about system queries. A system queries accesses at least one system table but no user tables. Scripting name: Enablesystem
Version	Specifies the query history schema version of the configuration. The version must match the version number specified in the nzhistcreatedb command; otherwise, the loader process will fail. Scripting name: Version

Name	Description
Definition	Specifies the attribute that stores the object definition. Scripting name: ObjectDefn

2.10 Oracle

To create a PDM with support for features specific to the Oracle DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select  *Database*  *Edit Current DBMS*  and expand the *Profile* node.

Note

When working with Oracle v11gR2, use the Oracle v11g DBMS definition file. Support for Oracle v8-9 is deprecated.

When working with Oracle triggers, you can use the TRGBODY and TRGDESC variables. For information about working with variables, see *Customizing and Extending PowerDesigner > DBMS Definition Files > PDM Variables and Macros*.

The following table lists Oracle dimension objects and their equivalents in PowerDesigner:

Oracle object	PowerDesigner object
Dimension	Dimension (see Dimensions (PDM) [page 238])
Hierarchy	Dimension hierarchy (see Hierarchies (PDM) [page 241])
Level	Dimension attribute used in a hierarchy (see Fact and Dimension Attributes (PDM) [page 239])
Attribute	Dimension attribute used as detail attribute (see Fact and Dimension Attributes (PDM) [page 239])

The following sections list the extensions provided for Oracle.

Note

We do not provide documentation for the properties on the *Physical Options* and certain other tabs, though minimal information is available for them in the Resource Editor. For information about these properties, consult your DBMS reference documentation.

Note

In Oracle, the `storage` composite physical option is used as a template to define all the storage values in a storage entry to avoid having to set values independently each time you need to re-use them same values in a storage clause. For this reason, the Oracle physical option does not include the storage name (%s).

Abstract Data Types and Attributes

The following extensions are available on the *General* tab of abstract data types:

Name	Description
Editionable	[12c and higher] Specifies that the type is an editioned object (if editioning is enabled for the schema object type TYPE in schema). This applies to both type specification and body. Scripting name: Editionable

The following extensions are available on the *Oracle* tab for attributes of abstract data types of type OBJECT or SQLJ_OBJECT:

Name	Description
Declare REF	Generates a REF modifier on attribute to declare references, which hold pointers to objects. Scripting name: RefAttribute

Columns

The following extensions are available on the *Oracle* tab:

Name	Description
Check constraint	[v11g and higher] You can specify the following options: <ul style="list-style-type: none">Deferrable - Specifies that in subsequent transactions you can use the SET CONSTRAINT clause to defer checking of this constraint until after the transaction is committed.Initially deferred - Specifies that Oracle should check this constraint at the end of subsequent transactions. Scripting name: CheckDeferrable, NotNullDeferrable, CheckInitiallyDeferred, NotNullInitiallyDeferred
Deferred option of check constraint	[up to v10gR2] Defines the deferred option of a column constraint check. It is used in the definition or create and add items statements. Scripting name: ExtColumnDeferOption

Name	Description
Mandatory columns	<p>You can specify the following options:</p> <ul style="list-style-type: none"> Constraint name/Name of not null constraint - Defines the name of the not null constraint for a column. [v11g and higher] Deferrable - Specifies that in subsequent transactions you can use the SET CONSTRAINT clause to defer checking of this constraint until after the transaction is committed. [v11g and higher] Initially deferred - Specifies that Oracle should check this constraint at the end of subsequent transactions. [up to v10gR2] Deferred option of not null constraint - Defines the deferred option of a column not null constraint. An empty value means "Not deferrable". <p>Scripting name: <code>ExtNotNullConstraintName</code>, <code>ExtNotNullDeferOption</code></p>
Encrypted	<p>[v10gR2 and higher] Specifies that column is encrypted. You can specify the following options:</p> <ul style="list-style-type: none"> Algorithm - Specifies the algorithm used for encryption. With salt - Specifies that the encryption adds salt to encoded data. Identified by Password - Provides the password for encrypting the column <p>Scripting name: <code>Encrypted</code>, <code>Algorithm</code>, <code>EncryptionWithSalt</code>, <code>IdentifiedByPassword</code></p>
Identity	<p>[v12c and higher] Specifies that the column stores a number incrementing with each insertion. You can specify the following options:</p> <ul style="list-style-type: none"> Generated - Specifies when the identity clause applies to the column. Start - Specifies the value to begin the sequence with. Increment - Specifies the interval between the sequence numbers. Cycle - Specifies that the sequence continues to generate values after reaching either its maximum or minimum value. If this option is not selected the sequence cannot generate more values after reaching its maximum or minimum value. Order - Specifies that sequence numbers must be generated in order of request. Cache - Specifies that values of the sequence are preallocated. You can additionally specify how many values of the sequence the database preallocates and keeps in memory for faster access. Minvalue, Maxvalue - Specify that the sequence has a minimum and/or maximum value, which you specify in the fields to the right of the options. <p>Scripting name: <code>Identity</code>, <code>Generated</code>, <code>StartWith</code>, <code>IncrementBy</code>, <code>Cycle</code>, <code>Order</code>, <code>HasCache</code>, <code>CacheValue</code>, <code>HasMinvalue</code>, <code>Minvalue</code>, <code>HasMaxvalue</code>, <code>Maxvalue</code></p>
Options	<p>[v12c and higher] You can specify the following options:</p> <ul style="list-style-type: none"> Invisible - Specifies that the column is a hidden column. To display or assign a value to an INVISIBLE column, you must specify its name explicitly. Default on null - Specifies that Oracle assigns the DEFAULT column value when a subsequent INSERT statement attempts to assign a value that evaluates to NULL. <p>Scripting name: <code>Invisible</code>, <code>DefaultOnNull</code></p>

XML Virtual Columns

If the table type is set to XML, the *Columns* tab is replaced by the *XML Virtual Columns* tab. The following extensions are available on the *General* tab of XML virtual columns:

Name	Description
Expression	Specifies the SQL expression used to compute virtual column value. Scripting name: Expression

Database Packages

The following extensions are available on the *Oracle* tab:

Name	Description
Add serially_reusable pragma on package specification	Specifies that the pragma serially_reusable clause must be applied on the database package specification. Scripting name: IsSpecPragma
Add serially_reusable pragma on package body	Specifies that the pragma serially_reusable clause must be applied on the database package body declaration. Scripting name: IsPragma
Editionable	[12c and higher] Specifies that the package is an editioned object (if editioning is enabled for the schema object type PACKAGE in schema). This applies to both package specification and body. Scripting name: Editionable

Models

The following extensions are available on the *Oracle* tab:

Name	Description
Password Encryption	[v10gR2 and higher] Specifies the master key for encoding and decoding encrypted data. Scripting name: PasswordEncryption

References

The following extensions are available on the *Oracle* tab:

Name	Description
Deferred option	Defines the deferred option of a reference. It is used in the definition of create and add items statements. Scripting name: ExtReferenceDeferOption
Exceptions into	Specifies a table into which Oracle places the ROWIDs of all rows violating the constraint. Scripting name: ExceptionsInto
Rely	Specifies whether an enabled constraint is to be enforced. Specify RELY to enable an existing constraint without enforcement. Specify NORELY to enable and enforce an existing constraint. Scripting name: Rely
Disable	Disables the integrity constraint. Scripting name: Disable
Validate	Checks that all old data also obeys the constraint. Scripting name: Validate

Tables

The following extensions are available on the *Oracle* tab:

Name	Description
Materialized view log	Specifies the materialized view log associated with the table. Scripting name: MaterializedViewLog

The following extensions are available on the [XML Properties](#) tab (for v11g and higher) when the table type is set to XML:

Name	Description
Definition	<p>Specifies that the properties of object tables are essentially the same as those of relational tables.</p> <p>However, instead of specifying columns, you specify attributes of the object.</p> <p>Scripting name: <code>XmlTypeObjProperty</code></p>
Storage type	<p>Specifies that XMLType columns can be stored in LOB, object-relational, or binary XML columns.</p> <p>Scripting name: <code>XMLTypeStorage</code></p>
Basic file	<p>Use this clause to specify the traditional LOB storage.</p> <p>Scripting name: <code>BasicFile</code></p>
Secure file	<p>Use this clause to specify high-performance LOB.</p> <p>Scripting name: <code>SecureFile</code></p>
LOB segment name	<p>Specify the name of the LOB data segment. You cannot use <code>LOB_segname</code> if you specify more than one <code>LOB_item</code>.</p> <p>Scripting name: <code>LOBSegname</code></p>
LOB parameters	<p>Use this clause to specify various elements of LOB parameters.</p> <p>Scripting name: <code>LOBParameters</code></p>

Tablespaces

The following extensions are available on the [Oracle](#) tab:

Name	Description
Size specification	<p>[v10g and higher] Specifies whether the tablespace is a bigfile or smallfile tablespace. This clause overrides any default tablespace type setting for the database. You can choose from the following settings:</p> <ul style="list-style-type: none"> • bigfile - contains only one datafile or tempfile. The maximum size of the single datafile or tempfile is 128 terabytes (TB) for a tablespace with 32K blocks and 32TB for a tablespace with 8K blocks. • smallfile - a traditional Oracle tablespace. <p>Scripting name: <code>SizeSpecification</code></p>

Name	Description
Temporary tablespace	<p>Use this option to create a locally managed temporary tablespace, which is an allocation of space in the database that can contain transient data that persists only for the duration of a session. This transient data cannot be recovered after process or instance failure.</p> <p>Scripting name: <code>Temporary</code></p>
Undo tablespace	<p>Use this option to create an undo tablespace. When you run the database in automatic undo management mode, Oracle Database manages undo space using the undo tablespace instead of rollback segments. This clause is useful if you are now running in automatic undo management mode but your database was not created in automatic undo management mode.</p> <p>Scripting name: <code>Undo</code></p>

Note

If you do not have a login "System", when reversing tablespaces via a live database connection, physical options will not be reversed. If you want to cancel the reverse engineering of tablespace physical options, you should clear the `SqlAttrQuery` query in the Tablespace category in the Oracle DBMS.

Users

The following extensions are available on the *General* tab (for v9i and higher):

Name	Description
Identification type	<p>Specifies how the user will be identified. You can choose between:</p> <ul style="list-style-type: none"> • <code>by</code> - requires a password • <code>externally</code> - requires a distinguished name • <code>globally</code> - requires a distinguished name <p>Scripting name: <code>Identification</code></p>
Distinguished name	<p>[external or global identification types] Specifies the user's distinguished name (DN) in the directory or certificate.</p> <p>Scripting name: <code>DistinguishedName</code></p>
Password	<p>[by identification type] Specifies the user password.</p> <p>Scripting name: <code>ClearPassword</code></p>

The following extensions are available on the *Options* tab:

Name	Description
Default tablespace	Specifies the default tablespace for objects that the user creates. Scripting name: DefaultTablespace
Temporary tablespace	Specifies the tablespace or tablespace group for the user's temporary segments. Scripting name: TemporaryTablespace
Quota definition	Specifies the maximum amount of space the user can allocate in the tablespace. Scripting name: QuotaDefinition
Profile	Specifies the profile to assign to the user. Scripting name: Profile
Password expire	Specifies that the user's password will expire. Scripting name: PasswordExpire
Account lock	Select lock to lock the user's account and disable access or unlock to enable access to the account. Scripting name: AccountLock

Views

The following extensions are available on the *Oracle* tab:

Name	Description
Super view object	Used in the UNDER clause to specify the superview the current object view is based on. Scripting name: ExtObjSuperView
Object view key	Specifies the attributes of the object type that will be used as a key to identify each row in the object view. Scripting name: ExtObjOIDList
Object view type	Defines the type of the object view. Scripting name: ExtObjViewType
Force	When set to TRUE, allows you to create the view regardless of the existence of the base tables or the owner privileges on these tables. Scripting name: ExtViewForce

Name	Description
Editioning	[v12c and higher] Specifies that the view is an editioning view, a single-table view that selects all rows from the base table and displays a subset of the base table columns. You can specify that the view is: <ul style="list-style-type: none"> • editioning • editionable • editionable editioning • noneditionable Scripting name: Editioning
Bequeath	[v12c and higher] Specifies whether functions referenced in the view are executed using the view invoker's rights or the view definer's rights. Scripting name: Bequeath

Synonyms

The following extensions are available on the *General* tab:

Name	Description
Editionable	[v12c and higher] Specify whether the synonym is an editioned or noneditioned object if editioning is enabled for the schema object type SYNONYM in schema. Scripting name: Editionable

2.10.1 Object and SQLJ Object Data Types (Oracle)

Oracle v8 and higher allows you to specify a table type of "Object", and to base the table on an object or SQLJ object abstract data type, so that the table uses the properties of the ADT and the ADT attributes become table columns.

Procedure

1. Select to open the List of Abstract Data Types, and click the *Add a Row* tool. Enter a name for the new ADT, and click the *Properties* tool to open its property sheet.
2. Select OBJECT or SQLJ_OBJECT from the *Type* list to display additional *Attributes* and *Procedures* tabs.
3. Enter as many attributes and procedures as appropriate.
4. Click *OK* to close the property sheet and return to your model.

Once you have defined your data type, you can base a table on it by opening the table property sheet, selecting Object in the *Type* field, and then selecting your new data type in the *Based on* field.

2.10.2 Bitmap Join Indexes (Oracle)

A bitmap join index is a bitmap index described through a join query. It is defined on a base table, and stores the row ids from the base table along with the indexed columns from the joined tables. You can design a bitmap join index either automatically or manually. For detailed information about bitmap join indexes, see your Oracle documentation.

2.10.2.1 Automatically Creating Bitmap Join Indexes Through Rebuilding

You can automatically generate a bitmap join index for each fact table and the dimension tables that it references. Each generated bitmap join index consists of the references that link a fact table to all the dimension tables located on a single axis proceeding from the fact table.

Context

A reference between two fact tables does not generate any bitmap join index. A bitmap join index is constrained and can only be defined for tables that are organized in a connected tree.

Procedure

1. Select  [Tools](#)  [Rebuild Objects](#)  [Rebuild Join Indexes](#) to open the Rebuild Join Indexes dialog box, and select one of the following modes:
 - Delete and Rebuild - all existing indexes are deleted before join index rebuild.
 - Preserve - preserves all existing join indexes in the PDM.
 2. Click the [Selection](#) tab, select one or more fact tables in the list, and then click [OK](#).
- A confirmation box asks if you want to continue.
3. Click [Yes](#) to generate a bitmap join index for each fact table.

Note

Automatically generated bitmap join indexes appear in the list of join indexes. To display the list, select  [Model](#)  [Join Indexes](#).

2.10.2.2 Manually Creating Bitmap Join Indexes

You can manually create bitmap join indexes from the list of join indexes or via the base table property sheet.

Procedure

1. Select to open the List of Join Indexes, click the *Add a Row* tool, enter a bitmap join index name in the *Name* column, and then click the *Properties* tool to open the new bitmap join index property sheet.
2. Select a base table on the *General* tab.

Note

You can, alternately, create a bitmap join index from a table property sheet by clicking the *Add a Row* tool. In this case, the *Base table* field is set automatically.

3. Click the *References* tab, and then click the *Add References* tool to open a selection window, which lists the available references depending on the selected base table. Select one or more references in the list, and then click *OK*.
The selected reference is displayed in the References list.
4. Click the *Columns* tab, and then click the *Add Columns* tool to open a selection window, which lists the available columns depending on the selected references. Select one or more columns in the list, and then click *OK*.
The selected columns are displayed in the Columns list.
5. Click *OK* to complete the creation of the bitmap join index and return to the model.

2.10.2.3 Bitmap Join Index Properties

A bitmap join index has the following properties:

Property	Description
Name	The name of the item which should be clear and meaningful, and should convey the item's purpose to non-technical users.
Code	The technical name of the item used for generating code or scripts, which may be abbreviated, and should not generally include spaces.
Comment	Additional information about the bitmap join index.
Stereotype	Sub-classification among bitmap join indexes.

Property	Description
Owner	Name of the user who created the bitmap join index.
Base table	Name of the table that stores the bitmap join index.

The following tabs are also available:

- Columns - Lists the columns used for the index. These columns proceed from the different dimension tables linked to the base table. When you create a bitmap join index manually, you have to select the columns to use. When you create a bitmap join index by rebuilding, the list of columns is initialized with all columns of the tables involved in the join except foreign keys.
- References - Lists the references used for the index.
- Physical Options - You can define physical options for bitmap join indexes generation. These options override the default physical options defined in the model. You can choose to generate these options by selecting the Physical Options check box in the Join Index groupbox in the Keys and Indexes tab of the Generation dialog box.

2.10.3 Database Packages (Oracle)

In Oracle, packages encapsulate related procedures, functions, and associated cursors and variables together as a unit in the database. Packages usually have two parts, a specification and a body. The specification is the interface with your applications; it declares the types, variables, constants, exceptions, cursors, and subprograms available for use. The body fully defines cursors and subprograms, and so implements the specification.

Packages provide advantages in the following areas:

- Encapsulation of related procedures and variables in a single named, stored unit in the database. This provides for better organization during the development process and makes privilege management easier.
- Separation of public and private procedures, variables, constants, and cursors.
- Improved performance since the entire package is loaded into memory when an object from the package is called for the first time.

You can generate and reverse engineer database packages in the same way as other database objects (see [Generating and Reverse-Engineering Databases \[page 288\]](#)). When you reverse engineer a database package, the sub-objects (variable, procedure, cursor, exception, and type) are created from the specification and the body of the database package.

Creating a Database Package

You can create a database package in any of the following ways:

- Select to access the List of Database Packages, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select .

Database Package Properties

To view or edit a database package's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Owner	Specifies the name of the database package owner, which you choose from the list of users.
Privilege	Lets you specify whether the functions and procedures in the database package execute with the privileges and in the schema of the user who owns it (definer), or with the privileges and in the schema of CURRENT_USER (invoker).
Table	Specifies the table with which the database package is associated.
Template	Specifies the template on which the database package is based (see Database Package Templates [page 499]). If you use a template, then the remaining tabs of the property sheet will be completed by the template. If you make any modifications to the other tabs, then the <i>User-Defined</i> button to the right of the field is depressed and the package is detached from the template and will no longer be automatically updated when you modify the definition of the table with which it is associated.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- Procedures – Lists the procedures associated with the database package (see [Database Package Procedures \[page 494\]](#)).
- Variables - Lists the variables associated with the database package (see [Database Package Variables \[page 495\]](#)).
- Cursors - Lists the cursors associated with the database package (see [Database Package Cursors \[page 496\]](#)).
- Exceptions – Lists the exceptions associated with the database package (see [Database Package Exceptions \[page 497\]](#)).
- Types - Lists the types associated with the database package (see [Database Package Types \[page 497\]](#)).
- Initialization - Lets you define initialization code for the database package body. Typically initialization holds statements that initialize database package variables. Initialization takes place after database package creation and compilation in the server.

- Specification - [hidden by default] Contains the public specification of the database.
- Preview - Displays the SQL code that will be generated for the database package.

2.10.3.1 Database Package Procedures

You create database package procedures on the *Procedures* tab of a database package using the *Add a Row* tool. To copy a procedure from elsewhere in the model, use the *Create from Procedure* tool.

i Note

To rebuild database package procedure dependencies (along with other procedure dependencies), select *Tools* *Rebuild Objects* *Rebuild Procedures Dependencies* (see [Rebuilding Trigger and Procedure Dependencies \[page 155\]](#)).

To view or edit a database package procedure's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
DB Package	Name of the database package to which the procedure belongs.
Type	Allows you to choose between procedure and function.
Return data type	Allows you to define the return data type of a function.
Pragma	Allows you to type a compiler directive, that is, a string for specifying compilation parameters for the procedure.
Public	Allows you to declare the procedure in the package specification and to permit use from outside the database package. A private procedure (check box deselected) is only defined in the package body.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- **Parameters** – Lists the input and output parameters required by the procedure (see [Database Package Parameters \[page 498\]](#)).
- **Body** - Specifies the body of the package procedure. Package procedures are not built using the structure of templates defined in the DBMS. You have to type the entire package procedure definition. To do so, you can use operators and functions to insert script items into the cursor definition.

For example, the definition of the CREDIT package procedure is the following:

```
CREATE PROCEDURE credit (Account_number NUMBER, Amount IN NUMBER) AS
BEGIN
UPDATE accounts
SET balance = balance + amount
WHERE account_id = acc_no;
END;
```

2.10.3.2 Database Package Variables

Variables can be declared within a package, and can be used in a SQL or PL/SQL statement to capture or provide a value when one is needed. For example, you can define the variable `in_stock` with a boolean data type to verify if a product is available or not. You create database package variables on the [Variables](#) tab of a database package using the [Add a Row](#) tool.

To view or edit a database package variable's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The [General](#) tab contains the following properties:

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the Code field.
DB Package	Name of the database package to which the variable belongs.
Data Type	Data type of the variable. You can use the Question Mark button to display the list of Standard Data Types.
Mandatory	If selected, indicates that the not null clause is set on the variable, thus making it mandatory.
Length	Allows you to define the variable length.
Precision	Number of places after the decimal point, for data values that can take a decimal point.
Default value	Default value of the variable.

Property	Description
Constant	Indicates that the variable is a constant. A constant has a value assigned. For example: Credit_Limit constant REAL := 500 000;
Public	Allows you to declare the variable in the package specification and to permit use from outside the database package. A private variable (check box deselected) is only defined in the package body.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

2.10.3.3 Database Package Cursors

A cursor is a multi-row query, which lets you name a work area and access its stored information. You create database package cursors on the [Cursors](#) tab of a database package using the [Add a Row](#) tool.

To view or edit a database package cursor's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The [General](#) tab contains the following properties:

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the Code field.
DB Package	Name of the database package to which the cursor belongs.
Return Data Type	Allows you to define the data type of a cursor result value.
Public	Allows you to declare the cursor in the package specification and to permit use from outside the database package. A private cursor (check box deselected) is only defined in the package body.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- [Parameters](#) – Lists the input and output parameters required by the cursor (see [Database Package Parameters \[page 498\]](#)).
- [Body](#) - Specifies the query to define the cursor. You can use operators and functions to insert script items into the cursor definition.

For example, the following cursor allows locating in table emp, the employee number, name, and function in a given department and for a given employee number:

```
Select empno, empname, job FROM emp WHERE deptno=20 and empno = num ;
```

2.10.3.4 Database Package Exceptions

PL/SQL allows you to explicitly handle internal and user-defined error conditions, called exceptions, that arise during processing of PL/SQL code. You create database package exceptions on the *Exceptions* tab of a database package using the *Add a Row* tool.

To view or edit a database package exception's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Properties	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
DB Package	Name of the database package to which the exception belongs.
Pragma	Allows you to type a compiler directive, that is, a string for specifying compilation parameters for the exception.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

2.10.3.5 Database Package Types

A type is a user-defined composite datatype that encapsulates a data structure along with the functions and procedures needed to manipulate the data. You create database package types on the *Types* tab of a database package using the *Add a Row* tool.

To view or edit a database package type's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
DB Package	Name of the database package to which the type belongs.
Type	Allows you to declare the type as type or subtype. A subtype contains all the attributes and methods of the parent type, it can contain additional attributes and can override methods from the type.
Public	Allows you to declare the type in the package specification and to permit use from outside the database package. A private type (check box deselected) is only defined in the package body.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

The following tabs are also available:

- *Body* - Used to declare the type contents.

The following example defines the type bank_account:

```
CREATE TYPE Bank_Account AS OBJECT (
  acct_number INTEGER(5),
  balance REAL,
  status VARCHAR2(10),
);
```

2.10.3.6 Database Package Parameters

Database package procedures and cursors can use input and output parameters. For example, in a CREDIT procedure, you could define the parameters Account Number and Amount. You create database package parameters on the *Parameters* tab of a database package procedure or cursor using the *Add a Row* or *Insert a Row* tools.

To view or edit a database package parameter's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator.

The *General* tab contains the following properties:

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Parent	Specifies the database package parent of the parameter. You can see the database package property sheet by clicking the Properties tool at the right of the field.
Data type	Data type of the parameter. You can use the Question Mark button to display the list of Standard Data Types.
Default Value	Default value of the parameter.
Parameter type	Type of the parameter.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas.

2.10.3.7 Database Package Templates

Instead of modeling each individual database package by hand, you can use a template and have PowerDesigner generate packages specific to each table. Database packages defined through a template are updated automatically when you make changes to the table definition, and you can quickly create packages for multiple tables from the Rebuild Table Database Packages dialog.

Database package templates are written in the PowerDesigner Generation Template Language (GTL). PowerDesigner provides a template for generating CRUD procedures, and you can create your own templates as necessary.

To define a database package from a template, simply select the template on the *General* tab of the database package property sheet.

Creating a Database Package Template

The available database package templates are defined in the DBMS resource file. Select *Database* *Edit Current Database*, click the *Database Package Templates* tab. To create a database package template, click the *Add a Row* tool

Database Package Template Properties

To open a template property sheet, select it in the list and click the *Properties* tool.

The *General* tab contains the following properties:

Property	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
DBMS	Specifies the DBMS version.

The following tabs are also available:

- *Body* - Contains a GTL template, which will generate a database package creation script based on the properties of the associated table. For detailed information about working with GTL, see *Customizing and Extending PowerDesigner > Customizing Generation with GTL* .

2.10.3.7.1 Rebuilding Table Database Packages

Database packages defined through templates are automatically updated when you modify the definition of the table with which they are associated. You can use the Rebuild Table Database Packages dialog to add database packages to tables that lack them or to overwrite any modifications you have made to packages associated with a template.

Procedure

1. Select  *Tools*  *Rebuild Objects*  to open the Rebuild Table Database Packages dialog.
2. Select a rebuild mode:
 - *Delete and Rebuild* - deletes all table database packages associated with templates (including those which have been modified) and recreates them from the template
 - *Add Missing Database Packages* - preserves existing database packages and creates packages only for those tables that lack them
3. Select the templates to use in the rebuild. You can select as many templates as necessary and the rebuild will create a database package for each template for each table.
4. [optional] Click the *Selection* tab and select the tables for which you want to rebuild database packages. By default all the tables in the model are selected.

5. Click **OK** to begin the rebuild.

2.10.4 Transparent Data Encryption (Oracle)

Oracle 10gR2 provides Transparent Data Encryption (TDE), encryption that is transparent for the user.

Context

When encrypting a column, Oracle creates an encryption key for the parent table and encrypts text data in the column with a user-specified encryption algorithm. The table key is encrypted using a master key and placed in the data dictionary.

The master key is stored in a secure location called a wallet, which can be a file on the database server. When a user enters data into an encrypted column, Oracle retrieves the master key from the wallet, decrypts the table key from the data dictionary, and uses it to encrypt the new data.

i Note

In order to access the master key used to encrypt the table keys, you must create a master password to open the wallet. To do this, right-click the model in the Browser, and select *Properties*. Click the *Oracle* tab, and enter your wallet password in the *Password Encryption* field. Click **OK** to return to the model. The password will be used to create alter statements for opening and closing the wallet.

You can create one or more encrypted column in one or more tables. You can specify the encryption algorithm to be used, but all columns in a particular table must use the same algorithm. If you create a second encrypted column in a table, and specify a different algorithm, the last specified algorithm will be used for all columns in the table.

Procedure

1. Create a column and open its property sheet.
2. On the *General* tab, specify any of the following types, which support encryption:
 - CHAR, NCHAR, VARCHAR2, and NVARCHAR2
 - DATE and TIMESTAMP
 - INTERVAL DAY TO SECOND and YEAR TO MONTH
 - NUMBER
 - RAW
3. Click the *Oracle* tab and select the *Encryption* checkbox.
4. Select an encryption algorithm from the list.
5. [optional] Select the *With salt* checkbox in order to add some random bits to the encryption key.
6. Click **OK** to complete the column definition.

2.10.5 Clusters (Oracle)

A cluster is a schema object that contains data from one or more tables, which have one or more columns in common. Oracle stores all the rows from all the tables that share the same cluster key together.

Context

PowerDesigner models clusters as extended objects with a stereotype of <<Cluster>>, and lists them under the *Model* menu and in the *Clusters* folder under the model in the Browser.

i Note

Clusters in Oracle v10gR2 and earlier are modeled as indexes with the Cluster check box selected. To upgrade such clusters to v11 or higher, you must generate a new PDM with the appropriate DBMS target from your original model. Simply changing the target DBMS will result in the loss of any existing clusters.

Procedure

1. Select to access the *List of Clusters*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *General* tab:

Name	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Owner	Specifies the owner of the cluster.

3. Click the *Columns* tab, create cluster columns as necessary, and specify the following properties for them:

Name	Description
Data type	Specifies the data type for the cluster column. Scripting name: <i>Datatype</i>

Name	Description
Length	Specifies the length for the cluster column. Scripting name: DatatypeLength
Precision	Specifies the precision for the cluster column. Scripting name: DatatypePrec
Sort	This clause instructs Oracle Database to sort the rows of the cluster on this column before applying the hash function. Scripting name: RowSort

4. Click the *Indexes* tab, create cluster indexes as necessary, and specify the following properties for them:

Name	Description
Owner	Specifies the owner of the cluster index. Scripting name: Owner
Unique	Specifies whether the cluster index is unique. Scripting name: Unique
Bitmap	Specifies if the index is to be created with a bitmap for each distinct key, rather than indexing each row separately. Scripting name: Bitmap
Sort	By default, Oracle Database sorts indexes in ascending order when it creates the index. You can specify NOSORT to indicate to the database that the rows are already stored in the database in ascending order, so that Oracle Database does not have to sort the rows when creating the index. Scripting name: Sort

2.10.6 Database Links (Oracle)

A database link is a schema object in one database that enables you to access objects on another database.

Context

Database links are supported for Oracle 11g and higher. PowerDesigner models database links as extended objects with a stereotype of <<Database Link>>, and lists them under the *Model* menu and in the Browser.

Procedure

1. Select to access the *List of Database Links*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *General* tab:

Name	Description
Name/Code/Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Public	Specifies whether the database link is available to all users. If False, then the database link is private and is available only to you. Scripting name: <code>Public</code>
Owner	Specifies the owner of the database link.

3. Click the *Oracle* tab and specify the following properties:

Name	Description
Shared	Specifies the use of a single network connection to create a public database link that can be shared among multiple users. If selected, you must also specify a user name and password for the target instance on the remote server. Scripting name: <code>Shared, AuthenticatedBy, AuthenticationPassword</code>
Connect to	Specifies the credentials used to connect to the remote database using a fixed user database link. You need to specify CURRENT_USER to create a current user database link. The current user must be a global user with a valid account on the remote database. If you do not specify a value, then the database link uses the credentials of each user who is connected to the database. Scripting name: <code>Username, Password</code>
Service name	Specifies the service name of a remote database. If you specify only the database name, then Oracle Database implicitly appends the database domain to the connect string to create a complete service name. Scripting name: <code>ServiceName</code>
Physical data model	Specifies the model that contains the objects of the remote database. Scripting name: <code>LinkModel</code>

2.10.7 Materialized View Logs (Oracle)

When DML changes are made to master table data, Oracle stores rows describing those changes in the materialized view log and then uses the materialized view log to refresh materialized views based on the master table.

Context

Materialized view logs are supported for Oracle 11g and higher. PowerDesigner models materialized view logs as extended objects with a stereotype of <>Materialized view log>>.

Procedure

1. Open the property sheet of the table to which you want to attach the log, select the Oracle tab, and click the Create button in the Materialized view log groupbox.
2. You can modify an object's properties from its property sheet. To open a materialized view log property sheet, double-click its Browser entry or click the Properties button on its parent table Oracle tab.

The *General* tab displays the master table name and the comment. The following properties are available on the Partitions tab:

Name	Description
Type	<p>Specifies the method for partitioning the table. You can choose between:</p> <ul style="list-style-type: none">○ Range/Composite - Partitions the table on ranges of values from the column list.○ Hash - Partitions the table using the hash method.○ List - Partitions the table on lists of literal values from column.○ Reference - Equipartitions the table being created (the child table) by a referential constraint to an existing partitioned table (the parent table).○ System - Partitions the table by the partitions specified. <p>When you select a type, additional options are displayed, to allow you to specify the appropriate parameters.</p>

2.10.8 Editions (Oracle)

Edition-based redefinition can be used to upgrade database components while an application is in use.

Context

Editions are supported for Oracle 12c and higher. PowerDesigner models editions as extended objects with a stereotype of <>Edition>>.

Procedure

1. You can create an edition in any of the following ways:
 - Select **Model** **Editions** to access the List of Editions, and click the *Add a Row* tool.
 - Right-click the model (or a package) in the Browser, and select **New** **Edition**.
2. Editions are used primarily in conjunction with materialized views. Open the property sheet of a materialized view, select the *Physical Options* tab, and expand the tree to `query_rewrite_clause`/`unusable_editions_clause` to specify editions that the materialized view is unusable before or after.

You can modify an object's properties from its property sheet. To open an edition property sheet, double-click its Browser in the Editions folder.

The following extensions are available on the *General* tab:

Name	Description
Parent edition	Specifies that the edition is created as a child of this edition. If no parent is specified, the edition is created as a child of the leaf edition. At the time of its creation, the new edition inherits all editioned objects from its parent edition. Scripting name: ParentEdition

2.11 SAP Business Suite

To create a PDM with support for features specific to the SAP Business Suite, select the DBMS on which your installation is running in the DBMS field of the New Model dialog, click **OK** to create an empty PDM, and then select **Tools** **SAP Business Suite** **Import SAP Business Suite Data Dictionary**. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select **Model** **Extensions**, select the SAP Business Suite extension, click the *Properties* tool, and expand the *Profile* node.

PowerDesigner supports importing any recent version of SAP® Business Suite.

The following sections list the extensions provided for SAP Business Suite.

Model

The following extensions are available on the *Data Dictionary* tab:

Name	Description
Host name	Specifies the host name or IP address of the server on which the Business Suite installation is running. Scripting name: HostName
User name	Specifies the user who connects to the Business Suite server. Scripting name: UserName

ABAP Components

ABAP components are based on standard PowerDesigner packages with a **ABAP Component** stereotype. The following extensions are available on the *Data Dictionary* tab:

Name	Description
Created by	Specifies the user who created the object and when the change was made. Scripting name: CreatedBy, CreatedOnDate, CreatedOnTime
Changed by	Specifies the user who last changed the object and when the change was made. Scripting name: ChangedBy, ChangedOnDate, ChangedOnTime
Parent	Specifies the ABAP component that is the parent of the present component. Scripting name: Parent
Customized by / Release notes by	Specify the users who customized the component and wrote the release notes for the customization. Scripting name: CustomizingResponsible, ReleaseNoteResponsible
Released	Provides release information about the component. Scripting name: Released

Name	Description
Support web / desktop	Specify that the component can be displayed in the SAP NetWeaver Portal and in the desktop NetWeaver client. Scripting name: <code>SupportWeb</code> , <code>SupportDesktop</code>
Visible	Specifies that the component should be visible to users. Scripting name: <code>Visible</code>

ABAP Packages

ABAP packages are based on standard PowerDesigner packages with an **ABAP Package** stereotype. The following extensions are available on the *Data Dictionary* tab:

Name	Description
Created by	Specifies the user who created the object and when it was created. Scripting name: <code>CreatedBy</code> , <code>CreatedOnDate</code> , <code>CreatedOnTime</code>
Changed by	Specifies the user who last changed the object and when the change was made. Scripting name: <code>ChangedBy</code> , <code>ChangedOnDate</code>
Parent	Specifies the ABAP component or package that is the parent of the package. Scripting name: <code>ApplicationComponent</code>
Software component	Specifies the software component to which the package is a support package. Scripting name: <code>SoftwareComponent</code>
Main package	Specifies whether the package is a: <ul style="list-style-type: none">• <empty> - Development Package• X - Main Package, which does not contain any development elements itself; and provides a structure for its children• S - Structure Package Scripting name: <code>MainPackage</code>
Namespace	Specifies a deprecated method for organizing package structures. Scripting name: <code>Namespace</code>
Owner	Specifies the user currently responsible for the package. Scripting name: <code>Owner</code>

Tables/Structures

The following extensions are available on the *Data Dictionary* tab:

Name	Description
Changed by	Specifies the user who last changed the object and when the change was made. Scripting name: ChangedBy, ChangedOnDate, ChangedOnTime
Parent package	Specifies the ABAP package that is the parent of the table or structure. Scripting name: PackageCode
Physical table	Specifies the database table on which the table or structure is based. Scripting name: PhysicalTableCode
Is extended	Specifies that the table contains extensions. Scripting name: IsExtended

Columns (Fields)

Business Suite fields are represented as columns in PowerDesigner. The following extensions are available on the *Data Dictionary* tab:

Name	Description
Field type	Specifies whether the field is: <ul style="list-style-type: none">• <Empty> - Built-in type• E - Data element• S - Structure• L - Table type Scripting name: FieldType
Domain	Specifies the domain attached to the column. Scripting name: Domain
ABAP data type	Specifies the data type used by the runtime environment: <ul style="list-style-type: none">• B, S, I - 1-byte, 2-byte, or 4-byte integer• C, N, B, F, G - Character, numerical, binary, float, or string• D, T - Date, or time• X, Y - Fixed or variable length raw Scripting name: ABAPDataType

Name	Description
Data dictionary data type	Specifies the data type used in the Dictionary. Scripting name: DataDictionaryDataType
Data element	Specifies the data element attached to the field, if of type E. Scripting name: DataElement
Include structure	Specifies the included structure attached to the field, if of type S. Scripting name: IncludeStructure
Lookup table	Specifies that lookup table from which to draw key values, if of type T. Scripting name: LookupTable
Reference field / table	For numerical or currency columns, specify the reference field and table. Scripting name: ReferenceField, ReferenceTable
Input help	Specifies the origin of input help: <ul style="list-style-type: none"> • <empty> - No input help exists • X - Explicit search help attachment to field • P - Input help implemented with check table • D - Explicit search help attachment to data element • F - Input help with fixed values • T - Input help based on data type Scripting name: InputHelp

Indexes

The following extensions are available on the *Data Dictionary* tab:

Name	Description
Changed by	Specifies the user who last changed the object and when the change was made. Scripting name: ChangedBy, ChangedOnDate, ChangedOnTime
DB index name	Specifies the associated database index name. Scripting name: DBIndexName

Name	Description
DB include exclude	<p>Specifies that a list of database systems is used as:</p> <ul style="list-style-type: none"> I - List of inclusions: create index on these DB systems. E - List of exclusions: do not create index on these DB systems. <p>Scripting name: DBIncludeExclude</p>
List of database systems 1-4	<p>Specify lists of database systems for inclusion or exclusion by the index.</p> <p>Scripting name: DBSYSSEL1, DBSYSSEL2, DBSYSSEL3, DBSYSSEL4</p>
Extension index	<p>Specifies that the index is an extension index.</p> <p>Scripting name: IsExtensionIndex</p>
Status	<p>Specifies the status of the index in the database:</p> <ul style="list-style-type: none"> <empty> - Create on database. O - Do not create on database. D - Create on database depending on DB <p>Scripting name: Status</p>

Data Elements

Data elements are based on PowerDesigner extended objects with a **Data Element** stereotype. The following extensions are available on the *Data Dictionary* tab:

Name	Description
Changed by	<p>Specifies the user who last changed the object and when the change was made.</p> <p>Scripting name: ChangedBy, ChangedOnDate, ChangedOnTime</p>
Package code	<p>Specifies the package containing the data element.</p> <p>Scripting name: PackageCode</p>
Default name	<p>Specifies the default name for components using the data element.</p> <p>Scripting name: DefaultName</p>
Original language	<p>Specifies the language in which the data element was defined.</p> <p>Scripting name: OriginalLanguage</p>
Data dictionary data type	<p>Specifies the data type of the column in terms of the ABAP Dictionary.</p> <p>Scripting name: DataDictionaryDataType, DataType</p>

Name	Description
Length / Output length	<p>Specifies the supported number of characters and the number that can be displayed in ABAP forms.</p> <p>Scripting name: <code>OutputLength</code>, <code>Length</code></p>
Precision	<p>Specifies the supported number of decimal places.</p> <p>Scripting name: <code>Precision</code></p>
Reference kind	<p>Specifies the category of dictionary type:</p> <ul style="list-style-type: none"> • <empty> - Direct type • E - Elementary type • S - Structured type • L - Table type • R - Reference type • D - Domain <p>Scripting name: <code>ReferenceKind</code></p>
Conversion routine	<p>Specifies function modules that are executed when values are input to and displayed in the ABAP screen field.</p> <p>Scripting name: <code>ConversionRoutine</code></p>
Value table	<p>Specifies that the permitted values for the data element are PK values of the selected table.</p> <p>Scripting name: <code>ValueTable</code></p>
Signed	<p>Specifies that negative values are supported.</p> <p>Scripting name: <code>Signed</code></p>
Lowercase	<p>Specifies that lowercase letters are supported.</p> <p>Scripting name: <code>Lowercase</code></p>
Fixed values	<p>Specifies that permitted values are limited to those specified.</p> <p>Scripting name: <code>FixedValues</code></p>

Domains

The following extensions are available on the *Data Dictionary* tab:

Name	Description
Changed by	Specifies the user who last changed the object and when the change was made. Scripting name: <code>ChangedBy</code> , <code>ChangedOnDate</code> , <code>ChangedOnTime</code>
Package code	Specifies the package containing the domain. Scripting name: <code>PackageCode</code>
Data dictionary data type	Specifies the data type of the column in terms of the ABAP Dictionary. Scripting name: <code>DataDictionaryDataType</code>
Base domain	Specifies the domain that the present domain extends. Scripting name: <code>BaseDomain</code>
Value table	Specifies that the permitted values for the domain are PK values of the selected table. Scripting name: <code>ValueTable</code>
Conversion routine	Specifies function modules that are executed when values are input to and displayed in the ABAP screen field. Scripting name: <code>ConversionRoutine</code>
Fixed values	Specifies that permitted values are limited to those specified. Scripting name: <code>FixedValues</code>
Signed	Specifies that negative values are supported. Scripting name: <code>Signed</code>

Views

The following extensions are available on the *Data Dictionary* tab:

Name	Description
Changed by	Specifies the user who last changed the object and when the change was made. Scripting name: <code>ChangedBy</code> , <code>ChangedOnDate</code> , <code>ChangedOnTime</code>
Root table code	Specifies the primary table of an aggregate. Scripting name: <code>RootTableCode</code>

Name	Description
View type	<p>Specifies that the view is a:</p> <ul style="list-style-type: none"> • H - Help view • D - Database view • P - Projection view • S - Structure view, data selection not possible • C - Maintenance view • E - Entity view (no longer supported) • V - View variant • A - Append view <p>Scripting name: viewType</p>
Delivery class	<p>Specifies that the delivery class of the view is:</p> <ul style="list-style-type: none"> • A - Application table • C - Customer table, maintained by customer • L - Table for storing temporary data • G - Customer table, SAP can add rows • E - Control table • S - System table, maintained by SAP • W - System table <p>Scripting name: DeliveryClass</p>
Maintenance status	<p>Specifies the maintenance status of the view:</p> <ul style="list-style-type: none"> • <empty> - Modifiable • R - Read only • U - Read and change • M - Time dependent view <p>Scripting name: MaintenanceStatus</p>

View Columns (View Fields)

The following extensions are available on the [Data Dictionary](#) tab:

Name	Description
ABAP form name	<p>Specifies the field's name in ABAP forms.</p> <p>Scripting name: ABAPFormName</p>

Name	Description
Base table / field	<p>Specify the table and field from which the field are drawn.</p> <p>Scripting name: <code>BaseTable</code>, <code>BaseField</code></p>
Data element	<p>Specifies the data element attached to the field.</p> <p>Scripting name: <code>DataElement</code></p>
Is key	<p>Specifies that the field belongs to a key area.</p> <p>Scripting name: <code>IsKey</code></p>
Lock mode	<p>Specifies the lock mode for the field:</p> <ul style="list-style-type: none"> • E - Write lock • S - Read lock • X - Exclusive lock <p>Scripting name: <code>LockMode</code></p>
Maintenance status	<p>Specifies the maintenance status of the field:</p> <ul style="list-style-type: none"> • <empty> - View is available as normal • R - View field can only be read • S - View field is used to form subsets • H - View field is not transferred to the maintenance screens <p>Scripting name: <code>MaintenanceStatus</code></p>

2.11.1 Importing an SAP Business Suite Data Dictionary

An SAP Business Suite installation is built on a complex database structure, which comprises many thousand tables with often cryptic names, and may include large numbers of extensions. In certain environments, there may be multiple servers, each with different extensions. PowerDesigner allows you to browse the application component and packages in the hierarchy, and to import them and their supporting logical objects for analysis, comparison, and merging of data dictionaries.

Procedure

1. Create a new PDM targeting the DBMS hosting your Business Suite server. For a server running SAP MaxDB, use the SAP HANA DBMS.
2. Select  **SAP Business Suite**  to open the wizard, and click **Next** on the Welcome page.

3. Enter your Business Suite connection parameters and then click *Next* to connect.

Use the tools to the right of the *Connection name* field to create a new connection profile, review the properties of the existing profile, or delete it. Business Suite connection profiles are stored in the registry.

i Note


The user you specify must have read access to the following tables:

<input type="radio"/> DD01L	<input type="radio"/> DD03L	<input type="radio"/> DD07L	<input type="radio"/> DD12L	<input type="radio"/> DD25T	<input type="radio"/> DD29L	<input type="radio"/> TDEVC
<input type="radio"/> DD01T	<input type="radio"/> DD03T	<input type="radio"/> DD07T	<input type="radio"/> DD12T	<input type="radio"/> DD26S	<input type="radio"/> DF14L	<input type="radio"/> TDEVCT
<input type="radio"/> DD02L	<input type="radio"/> DD04L	<input type="radio"/> DD08L	<input type="radio"/> DD17S	<input type="radio"/> DD27S	<input type="radio"/> DF14T	
<input type="radio"/> DD02T	<input type="radio"/> DD04T	<input type="radio"/> DD08T	<input type="radio"/> DD25L	<input type="radio"/> DD28S	<input type="radio"/> TADIR	


The schema name is optional but may, in some environments, provide the necessary read permissions.

4. Use the *Browse* and *Search* tabs to navigate in the component and package hierarchy, select components, packages, tables, and views to import, and then click *Next*.

- *Browse* - Expand the component and package hierarchy, and select application components and packages in the left pane to add their tables and views to the import. When you select a component or package to import, its supporting tables and views are added to the subtabs in the right pane, and the total number of tables and views to be imported is updated. Tables are selected for import by default, but views are not. You can select or deselect tables and views for import as necessary:



- **Search** - Choose whether to search for tables and/or views and whether to match whole words only, enter one or more strings to search on (separated by commas or new lines), and click **Search**. You can filter on your result set dynamically by entering a string in the filter field. Select tables and views from your results to add them to the import:




i Note

Since an ERP system can contain many thousands of tables, we recommend that you import only a limited subset of components or packages at a time. You can relaunch the wizard and import additional components or packages as many times as necessary.


5. Review the objects that will be imported and then click *Finish*.

The component and package structure is imported, with tables located in their appropriate package, and global domains and data elements are listed at the root of the model.



PowerDesigner stores the technical name of each object in its *Code* field, and uses the more intuitive short description of the object as its name. Thus, for example, the table identified as SCMATTRANSACT in the data dictionary is displayed as Schedule Manager: Registered SAP Transactions in PowerDesigner.

Each component and package contains a diagram which shows the objects it contains:



i Note

Not all packages contain tables. To view the structure of only those components and packages with diagrams that do contain tables, right-click the model in the Browser or a diagram background and select *View ABAP Diagrams Containing Tables*. Select a diagram in the tree and click *OK* to open it.

6. Review the imported metadata as appropriate. Configurable and filterable lists of each type of object are available from the *Model* menu. For example, to display the List of Data Elements, select **Model > Data Elements**:

List of Data Elements

	Name	Code
→	+/- Sign for Ranges	TFC_SIGN
2	ABAP Program Name	TFC_PROGRAMM
3	ABAP Program Name2	SCMA_PROGRAM
4	ABAP Time Stamp	ABSTAMP
5	Authorization Group for Closing Cockpit	TFC_AUTHGRP
6	Background job name	BTCJOB
7	Bool Indicator	TFC_ACTIVE
8	Business Document Service: Document ID	BDS_DOCID
9	Calendar Type	TFC_CALENDAR_
10	Chart of Accounts	TFC_KTOPL
11	Client	MANDT
12	Comment	FAGL_CLOCO_NO

i Note


To view lists of global objects, such as domains and data elements, ensure that you are in the context of the model root (by double-clicking the *Top-Level Component Diagram*) before opening the list. To view all the components, packages, or tables in the model, ensure that you are at root, open the list, and click the *Include Sub-Packages* tool in the list toolbar. For detailed information about working with object lists, see *Core Features Guide > Modeling with PowerDesigner > Objects > Object Lists*

7. [optional] Perform a new import to enrich your model. You can perform as many imports as necessary, and delete components, packages, or other objects as appropriate, to simplify your model and focus on the areas that interest you.
8. [optional] To compare two or more Business Suite installations, import each one into its own PDM, and select **Tools > Compare Models**. For detailed information about working in this dialog, see *Core Features Guide > Modeling with PowerDesigner > Comparing and Merging Models*.
9. [optional] PowerDesigner supports the merging of Business Suite PDMS and their generation to HANA to provide the basis for establishing a business intelligence environment for reporting on your Business Suite transactional data (see [Generating an SAP Business Suite Data Dictionary to HANA \[page 521\]](#)).

2.11.2 Generating an SAP Business Suite Data Dictionary to HANA

PowerDesigner can help you prepare a HANA table structure to allow consolidated reporting on one or more SAP Business Suite installations.

Context



Procedure

1. Create a PDM for each SAP Business Suite installation, and import the logical tables that you want to define warehouse reporting on (see [Importing an SAP Business Suite Data Dictionary \[page 515\]](#)).
2. Analyze and purify your models, deleting components, packages, tables, and columns that are not of interest to your reporting project.

Note

You should not edit the properties of Business Suite objects (except for the *Comment* field or *Definition* tab) or create new objects, in order to ensure the integrity of the metadata that will be generated to the HANA schema.

3. Select a model to act as the core warehouse model, and then select **Tools** **Merge Models** and merge the other models into it one after the other to create a superset of all the components, packages, tables, and columns that you want to generate to HANA.

For detailed information about merging models, see *Core Features Guide > Modeling with PowerDesigner > Comparing and Merging Models*.

4. Select **Tools** **SAP Business Suite** **Generate HANA Physical Data Model**.
5. Select whether you want to *Preserve package hierarchy*, which is the default mode, and will recreate the Business Suite component and package structure to the HANA PDM. Note that this structure does not represent HANA packages. Deselecting this option will suppress the creation of these packages and will generate all your tables to the new PDM root. In both cases, your tables will all be exported to the HANA catalog.
6. Click **OK** to begin the generation.

PowerDesigner generates a new PDM targeting the HANA DBMS.

Note

PowerDesigner generates the Business Suite component and package structure to the HANA PDM.

7. Export your tables to your HANA server (see [Exporting Objects to the HANA Repository \[page 535\]](#)). Implement loading of your transactional data to your HANA warehouse using your standard ETL solution.

2.12 SAP HANA

SAP® PowerDesigner® provides a design-time environment for modeling tables and supporting objects for generation to SAP HANA®, and supports reverse-engineering your HANA environment for inclusion in impact analysis of your global data landscape and across other modeling domains. PowerDesigner supports round-trip reverse-engineering and generation of HANA tables and other catalog objects directly or via CDS entities for SAP HANA® 1.0 and 2.0 databases. In addition, for SAP HANA® 1.0 environments, PowerDesigner supports initializing and reverse-engineering graphical calculation views (including the XML definition and projection list) for inclusion in impact analysis.

PowerDesigner serves the following principal use cases in your HANA environment:

- [HANA 1.0 and 2.0] Modeling a HANA database, including migration from another DBMS (see [Modeling for HANA Database \[page 524\]](#)):

Tasks	HANA 1.0 Database	HANA 2.0 Database
Design	Generation of a CDM or LDM to an SAP HANA 1.0 Database PDM. Generation of any PDM to an SAP HANA 1.0 Database PDM for migration purposes. Modeling of the following catalog objects: <ul style="list-style-type: none"> ○ Tables ○ Virtual tables ○ SQL Views ○ Dynamic tiering 	Generation of a CDM or LDM to an SAP HANA 2.0 Database PDM. Generation of any PDM to an SAP HANA 2.0 Database PDM for migration purposes. Modeling of the following catalog objects: <ul style="list-style-type: none"> ○ Tables ○ Virtual tables ○ SQL Views ○ Dynamic tiering
Generation / Reverse	Supported, including round-trip.	Supported, including round-trip.

- [HANA 1.0 and 2.0] Modeling a HANA database as CDS artifacts, including migration from another DBMS (see [Modeling for Core Data Services \(CDS\) \[page 550\]](#)):

Tasks	HANA 1.0 Classic Repository	HANA 1.0 and 2.0 HDI
Design	<p>Generation of a CDM or LDM to an SAP HANA 1.0 CDS Repository PDM.</p> <p>Generation of any PDM to an SAP HANA 1.0 CDS Repository PDM for migration purposes.</p> <p>Modeling of the following CDS artifacts:</p> <ul style="list-style-type: none"> ○ Contexts ○ Entities ○ Associations ○ Views ○ Simple and structured types <p>Not supported: view joins, anonymous types, enumerations.</p>	<p>Generation of a CDM or LDM to an SAP HANA 1.0 CDS HDI or SAP HANA 2.0 CDS HDI PDM.</p> <p>Generation of any PDM to an SAP HANA 1.0 CDS HDI or SAP HANA 2.0 CDS HDI PDM for migration purposes.</p> <p>Modeling of all classic HANA Repository artifacts, and:</p> <ul style="list-style-type: none"> ○ Constants ○ Extensions (for entities) - SAP HANA 2.0 CDS HDI only
Generation	Generation and activation of CDS artifacts.	Generation of CDS files for activation.
Reverse	<p>Not supported.</p> <p>Catalog tables activated from your CDS entities can be reversed to an SAP HANA 1.0 Database PDM.</p>	As per classic HANA Repository.

- [HANA 1.0] Visualization and impact analysis for HANA graphical calculation views and their dependencies (see [Calculation Views \(HANA\) \[page 529\]](#)):

Tasks	HANA 1.0 Classic Repository	HANA 1.0 HDI
Design	<p>Modeling of graphical calculation views, their sources, and projection lists in an SAP HANA 1.0 Database PDM.</p> <p>PowerDesigner allows you to specify the business purpose of your calculation views and their points of contact with other artifacts, while their internal logic and technical details are completed in HANA Modeler or Web IDE.</p> <div style="background-color: #ffffcc; padding: 5px;"> <p>i Note</p> <p>To model calculation views based on CDS artifacts, you must first generate your entities to HANA, activate them as tables, and then reverse the tables to an SAP HANA 1.0 Database PDM.</p> </div>	As per classic HANA Repository.
Generation	Support for initialization only. No updating of calculation views present on the HANA server.	As per classic HANA Repository.
Reverse	Read-only objects (including the XML definition, data sources, and projection list) linked to their sources for inclusion in impact analysis. Other properties, such as variables, parameters, hierarchies, and internal nodes are not reversed.	Not supported.

2.12.1 Modeling for HANA Database

PowerDesigner supports round-trip reverse-engineering and generation of HANA tables and other catalog objects directly or via CDS entities for SAP HANA® 1.0 and 2.0 databases. In addition, for SAP HANA® 1.0 environments, PowerDesigner supports initializing and reverse-engineering graphical calculation views (including the XML definition and projection list) for inclusion in impact analysis.

Context

This procedure describes migrating a database to HANA. PowerDesigner also supports:

- Reverse-engineering catalog objects manually via .
- [HANA 1.0 Classic Repository only] Reverse-engineering calculation views and their associated catalog objects from HANA via (see [Importing Objects from the HANA Repository \[page 539\]](#)).

- [HANA 1.0 and 2.0] Migrating a database to HANA via CDS artifacts (see [Modeling for Core Data Services \(CDS\) \[page 550\]](#)).

Procedure

1. Open your source CDM, LDM, or PDM and select [Tools](#) [Generate Physical Data Model](#).
2. Select **SAP HANA 1.0 Database** or **SAP HANA 2.0 Database** in the **DBMS** field, modify as appropriate the other options on this and the other tabs, and click **OK** to generate your HANA PDM.
3. Review the generated model and perform any appropriate modeling tasks. The following HANA-specific tools are available in the [SAP HANA Database](#) toolbox:

Tool	Description	Can Create In
	[HANA 1.0] HANA Package - An organizing container for HANA artifacts. See HANA Packages (HANA) [page 526] .	Anywhere
	Virtual Table - A mapping to a table located in a remote data source. See Virtual Tables (HANA) [page 527] .	Model Root
	[HANA 1.0] Calculation View - A view that can consume tables, SQL views and other calculation views and perform complex calculations. See Calculation Views (HANA) [page 529] .	HANA Package

The following standard PDM tools are available in the [Physical Diagram](#) toolbox:

Tool	Description	Can Create In
	Table - A collection of rows (records) that have associated columns (fields)..	Model Root
	Reference - A link between a primary or an alternate key in a parent table, and a foreign key of a child table.	Model Root
	View - A data structure that results from a SQL query and that is built from data in one or more tables.	Model Root
	Procedure - A precompiled collection of SQL statements stored under a name in the database and processed as a unit.	Model Root

4. Generate your model to HANA:
 - HANA 1.0: [catalog and repository objects] Use the wizard (see [Exporting Objects to the HANA Repository \[page 535\]](#)).
 - HANA 2.0: [catalog objects only] Use the [Database](#) [Generate Database](#) command.
5. Review and complete the definition of your calculation views in HANA Modeler or Web IDE.

2.12.1.1 HANA Packages (HANA)

[HANA 1.0] HANA packages group together related information objects in a structured way. In an SAP HANA® 1.0 Database PDM, tables are stored in the catalog (represented by the model root), while calculation views must be created in a HANA package.

Context

i Note

PowerDesigner support for SAP HANA® 2.0 is restricted to catalog objects. HANA packages are not supported.

Procedure

1. Select the *HANA Package* tool and click in the diagram.
2. Open the property sheet tab, and complete properties as appropriate.

The following properties are available on the *General* tab:

Name	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field. Scripting name: Name, Code, Comment
Use parent name-space	Not for use with HANA packages.
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas. Scripting name: Keywords

The following read-only properties are provided for information on the *HANA* tab:

Name	Description
Structure package	[read-only] Specifies that the package is a structural package. Scripting name: Structural
Package	[read-only] Specifies the HANA object name. Scripting name: _ObjectName_

- Click **OK** to complete the creation of the HANA package.

2.12.1.2 Virtual Tables (HANA)

With SAP HANA Smart Data Access, data can be merged in heterogeneous EDW landscapes (data federation), making it possible to access data in remote sources without having to replicate it to the SAP HANA database beforehand. PowerDesigner models virtual tables as tables with a stereotype of `VirtualTable` and remote sources as extended objects with a stereotype of `RemoteSource`.

Procedure

- Prepare the source PDM containing the table you want to access and have it open in your workspace.
- In the HANA PDM, select the *Virtual Table* tool and click in the diagram at the model root.
- In the object picker, select the source table and click **OK**.
PowerDesigner creates the virtual table and links it to a remote source initialized to point to the source model.
- Open the virtual table property sheet tab, give it an appropriate **Name**, and set its **Owner**.
- Click the *Properties* tool to the right of the *Remote source* field to open the remote source property sheet, and complete the properties of the remote source:

Name	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field. Scripting name: Name, Code, Comment
Adapter	Specifies the adapter, and the type of access method to be used by the SAP HANA database to access the data. Scripting name: RSAdapter

Name	Description
Configuration	Specifies the connection parameters for the adapter. Scripting name: RSConfiguration
Credential type / Credentials	Specifies the type of credentials required (currently only password) and the credentials to use Scripting name: RSCredentialType, RSCredentials
Model	Specifies the PDM that contains the definition of the remote source. Scripting name: RSPDM
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas. Scripting name: Keywords

2.12.1.3 Dynamic Tiering / Extended Storage (HANA)

SAP HANA dynamic tiering is a native big data solution providing large volume, warm data management capability. Your highest value data remains in memory, and cooler less-valuable data is saved to the extended store.

Procedure

1. Open the model property sheet, and click the *Create Extended Storage* button to the right of the *Extended storage* field.
2. Click the *Properties* button to open the extended storage property sheet and enter the following properties:

Name	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field. Scripting name: Name, Code, Comment
Configuration	Specifies the connection parameters for the adapter. Scripting name: ESConfiguration

Name	Description
Credential type / Credentials	Specifies the type of credentials required (currently only password) and the credentials to use Scripting name: ESCredentialType, ESCredentials
Keywords	Provide a way of loosely grouping objects through tagging. To enter multiple keywords, separate them with commas. Scripting name: Keywords

3. To specify that a table should be located in the extended storage, select the [Using extended storage](#) option on the [HANA](#) tab of the table property sheet.

2.12.1.4 Calculation Views (HANA)

[HANA 1.0] A calculation view can perform complex calculations and can have tables, standard views, and other calculation views as sources.

i Note

Analytic and attribute views are deprecated in HANA and should be migrated to calculation views (see SAP Note [2325817](#)).

PowerDesigner provides the following support for HANA 1.0 calculation views:

Tasks	HANA 1.0 Classic Repository	HANA 1.0 HDI
Design	<p>Modeling of graphical calculation views, their sources, and projection lists in an SAP HANA 1.0 Database PDM.</p> <p>PowerDesigner allows you to specify the business purpose of your calculation views and their points of contact with other artifacts, while their internal logic and technical details are completed in HANA Modeler or Web IDE.</p> <div style="background-color: #ffffcc; padding: 5px;"> <p>i Note</p> <p>To model calculation views based on CDS artifacts, you must first generate your entities to HANA, activate them as tables, and then reverse the tables to an SAP HANA 1.0 Database PDM.</p> </div>	As per classic HANA Repository.
Generation	Support for initialization only. No updating of calculation views present on the HANA server.	As per classic HANA Repository.

Tasks	HANA 1.0 Classic Repository	HANA 1.0 HDI
Reverse	Read-only objects (including the XML definition, data sources, and projection list) linked to their sources for inclusion in impact analysis. Other properties, such as variables, parameters, hierarchies, and internal nodes are not reversed.	Not supported.

i Note

PowerDesigner support for SAP HANA® 2.0 is restricted to catalog objects. Calculation views are not supported.

2.12.1.4.1 Creating a Calculation View

PowerDesigner supports creation of calculation views for export to HANA. Simple calculation views with one or two data sources can be designed within PowerDesigner, while more complex calculation views with three or more data sources can be initialized for completion in your HANA development tool.


Procedure

1. Prepare the data sources for your calculation view in your HANA Database PDM by importing them from HANA, generating from a CDM or LDM, or creating them manually.

i Note

PowerDesigner supports specifying tables, virtual tables, SQL views, and calculation views as sources for a calculation view. Analytic and attribute views may not be selected as calculation view sources.

In this example, the tables **SALES**, **REGION**, and **PRODUCT**, and the virtual table **SUPPLIER** are available as sources:



i Note

Calculation views cannot be modeled in a CDS PDM (see [Modeling for Core Data Services \(CDS\) \[page 550\]](#)). To model calculation views based on CDS artifacts, you must first generate your entities to HANA, activate them as tables, and then reverse the tables to an [SAP HANA Database 1.0](#) PDM.

2. Open a HANA package diagram, select the *Calculation View* tool in the toolbox, and click in the diagram.

i Note

You can only create calculation views under a HANA package.

3. Open the property sheet of the calculation view, and specify the following properties as appropriate on the *General* tab:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Owner	Specifies the schema that owns the calculation view.

Property	Description
Dimensional type	Specifies the type of the calculation view: <ul style="list-style-type: none"> ○ Cube - [default] Used to perform a calculation using a measure. ○ Dimension - Define hierarchies of data to be consumed by a cube. HANA Modeler or Web IDE do not permit calculation views of type Dimension to contain measures.

4. Select the *Data Sources* tab, click the *Add Objects* tool to specify your sources, and click *OK*.

If you select:

- One or two data sources - You can design the calculation view in PowerDesigner and generate and activate it directly in HANA.
- Three or more data sources - You can initialize the definition of the calculation view in PowerDesigner, but you must complete its definition in HANA Modeler or Web IDE.


5. Select the *Columns* tab, and click the *Add Objects* tool. Select one or more columns from the data sources and click *OK*.

6. [Cube calculation views] Select a column as the measure, by selecting its checkbox in the *M[easure]* column.

i Note

If the *M[easure]* column is not visible, click the *Customize Columns and Filter* tool to add it.

7. [optional] Select the *Source Columns* tab and review the columns listed there. To specify any additional columns that are implicated in the definition of the calculation view, so that they are included in impact analyses, click the *Add Objects* tool, select one or more columns from the data sources for the view, and click *OK*.
8. Click *OK* to complete the creation of the calculation view.



9. Generate the calculation view to the HANA repository (see [Exporting Objects to the HANA Repository \[page 535\]](#)) where its definition can be completed in HANA Modeler or Web IDE.

2.12.1.4.2 Performing an Impact Analysis on a Calculation View

Impact analysis is a core PowerDesigner feature that allows you to trace dependencies between objects in and across models and to understand the impact of making a change on any of the objects in the chain. You can use impact analysis to understand the dependencies of your calculation views on the sources they consume and their connections to objects in other types of models, including business process steps, enterprise architecture artifacts, and data movement flows.

Procedure


1. Reverse your calculation views and supporting objects from your classic HANA Repository (see [Importing Objects from the HANA Repository \[page 539\]](#)).

 Note


Your catalog objects may have been activated from CDS artifacts modeled in PowerDesigner (see [Modeling for Core Data Services \(CDS\) \[page 550\]](#)). If this is the case, to ensure that your CDS artifacts participate in the impact analysis, open the CDS model, select ► *Tools* ► *Rebuild Objects* ► *Rebuild Links to Catalog Objects* ▾, select the **SAP HANA Database 1.0** PDM containing the catalog objects activated from them, and click **OK**.

2. To launch an impact analysis on a table, column, or calculation view, select it in the diagram or Browser and select ► *Tools* ► *Impact and Lineage Analysis* ▾ (or press **Ctrl+F11**).

The analysis generates a tree view of influencing (lineage) and dependent (impacted) objects, which appears instantly in the dialog. The following example shows an initial analysis for the **SALESREPORT** calculation view:



You can modify the types of objects and connections that are included in the analysis, and export the analysis as a list or generate it to an impact analysis model including a diagram to visualize the analysis:



For detailed information, see *Core Features Guide > Linking and Synchronizing Models > Impact and Lineage Analysis*

2.12.1.5 Exporting Objects to the HANA Repository

While HANA tables are generated directly to the catalog, calculation views are exported to the HANA repository, where they will be completed and activated. PowerDesigner provides a wizard to export your objects to a HANA 1.0 repository and catalog in a single action. Exporting calculation views to SAP HANA® 2.0 environments is not supported and no wizard is provided.

Context

In an SAP HANA® 1.0 Database PDM, the HANA catalog is represented by the root of the model, while the HANA repository is represented by a structure of HANA packages. In order to generate your objects correctly, you must place your tables at the root (or in standard PowerDesigner packages), and your calculation views in their appropriate HANA packages.

Note

You can generate tables and other catalog objects to SAP HANA® 1.0 and SAP HANA® 2.0 environments through the standard and commands.

For information about the JDBC connection parameters necessary for connecting to the HANA catalog via SSL, see *Core Features Guide > Modeling with PowerDesigner > Getting Started with PowerDesigner > Connecting to a Database > Configuring Connection Profiles*.

Procedure

1. Select to open the wizard, and specify your deployment model:
 - o Repository [default] - Generate directly to the classic HANA repository.
 - o HDI - Generate files for loading to HANA. Enter the following parameters:

Parameter	Description
Generation Path	[required] Specifies the path to generate files.
HDI Namespace	[required] Specifies the namespace for generated artifacts.
Generate .hdbsynonym and .hdbsynonymconfig files	Enables the generation of these two files for each table consumed by a calculation view.
Generate .hdbvirtualtable and .hdbvirtualtableconfig files	Enables the generation of these two files for each virtual table consumed by a calculation view.

2. Click [Next](#).


If you selected to check the model, the wizard reviews it for consistency and displays any errors which may compromise the generation.

3. [repository environments] Enter your HANA repository connection parameters and then click [Next](#) to connect:

Parameter	Description
Connection Name	Select an existing connection from the list or use the tools to the right of the Connection field to create a new connection profile, review the properties of the existing profile, or delete it. HANA connection profiles are stored in the registry. <div style="background-color: #ffffcc; padding: 10px; margin-top: 10px;"><p>i Note</p><p>To reverse-engineer from or generate to HANA databases running in the HANA Cloud Platform, you must install the SAP HANA Cloud Connector and configure an appropriate service channel. For detailed information, see SAP HANA Cloud Platform > Services > Connectivity Service > SAP HANA Cloud Connector.</p></div>
Host name	Specifies the network name of the HANA appliance.
Instance number	Specifies the HANA instance number.
Mode	If your HANA system is installed in multiple-container mode, you must specify the container to connect to: <ul style="list-style-type: none">o <i>Single container</i> - [default] Single tenancy HANA system. Sets the port number to 3<nn>15 (where <nn> equals the instance number).o <i>Multiple containers</i> - Multitenancy HANA system. You can connect to:<ul style="list-style-type: none">o <i>System database container</i> - sets the port number to 3<nn>13o <i>Tenant database container</i> - Enter the <i>Name</i> of your container. Sets the port number to 3<nn><xx>, where <xx> is a number greater than 40, allocated to your database by the system.

Parameter	Description
User name/ password	<p>Specifies the credentials to connect with.</p> <p>i Note</p> <p>The account with which you connect must have at least the CONTENT_ADMIN, MODELING, and PUBLIC roles.</p>

4. Select HANA packages in your model in the left pane to make their contents available to export. Select the calculation views to export in the right pane, and then click **Next**.



If you have previously imported objects from HANA, the archive model helps to determine model changes since that point.


i Note

If the calculation view is already present on the HANA server, PowerDesigner will not overwrite it, even if you select it here.

i Note

Tabs to select analytic and attribute views are also available. These objects are now deprecated in HANA.

5. On the *Catalog Objects* tab, PowerDesigner automatically selects any catalog tables and views required by the selected calculation views. Select additional objects to export from the lists, and then click *Next*.



i Note

You can select additional schemas from the list to make their objects available for selection.

6. Review the objects that will be exported and then click *Finish*:

- o Repository environments - PowerDesigner generates the objects to the HANA Repository and catalog as appropriate.

i Note

If PowerDesigner detects conflicts between changes made in the model and changes to the same objects on the server, then a merge dialog (see *Core Features Guide > Modeling with PowerDesigner > Comparing and Merging Models*) will open to allow you to select, for each conflict, which of the

conflicting changes will prevail. The resolutions that you select will first be applied to the model, and then your changes will be exported to the server.

- HDI environments - PowerDesigner generates the appropriate files for loading and activation to the specified path.

2.12.1.6 Importing Objects from the HANA Repository

PowerDesigner provides a wizard to import read-only graphical calculation views and their sources from an SAP HANA® 1.0 Classic Repository for use in impact analysis. Importing calculation views from SAP HANA® 1.0 HDI or SAP HANA® 2.0 environments is not supported and no wizard is provided.

Context

i Note

You can reverse-engineer tables and other catalog objects from SAP HANA® 1.0 and SAP HANA® 2.0 environments through the standard reverse-engineering commands:

- Create new model: .
 - Reverse to existing HANA PDM: .
- For information about the JDBC connection parameters necessary for connecting to the HANA catalog via SSL, see *Core Features Guide > Modeling with PowerDesigner > Getting Started with PowerDesigner > Connecting to a Database > Configuring Connection Profiles*.

Procedure

1. To import into an existing PDM, select .

or

To import and create a new PDM, select .

2. Click *Next* on the Welcome page.
3. Enter your HANA repository connection parameters and then click *Next* to connect:

Parameter	Description
Connection Name	Select an existing connection from the list or use the tools to the right of the <i>Connection</i> field to create a new connection profile, review the properties of the existing profile, or delete it. HANA connection profiles are stored in the registry.
	<p>i Note</p> <p>To reverse-engineer from or generate to HANA databases running in the HANA Cloud Platform, you must install the SAP HANA Cloud Connector and configure an appropriate service channel. For detailed information, see SAP HANA Cloud Platform > Services > Connectivity Service > SAP HANA Cloud Connector.</p>
Host name	Specifies the network name of the HANA appliance.
Instance number	Specifies the HANA instance number.
Mode	If your HANA system is installed in multiple-container mode, you must specify the container to connect to: <ul style="list-style-type: none"> ○ <i>Single container</i> - [default] Single tenancy HANA system. Sets the port number to 3<nn>15 (where <nn> equals the instance number). ○ <i>Multiple containers</i> - Multitenancy HANA system. You can connect to: <ul style="list-style-type: none"> ○ <i>System database container</i> - sets the port number to 3<nn>13 ○ <i>Tenant database container</i> - Enter the <i>Name</i> of your container. Sets the port number to 3<nn><xx>, where <xx> is a number greater than 40, allocated to your database by the system.
User name/ password	Specifies the credentials to connect with.
	<p>i Note</p> <p>The account with which you connect must have at least the CONTENT_ADMIN, MODELING, and PUBLIC roles.</p>

4. Select packages in the HANA Repository in the left pane to make their contents available to import. Select the calculation views to import in the right pane, and then click *Next*.

The archive model retains a snapshot of the structure of your objects at import time to help in determining model changes when re-exporting to HANA.

Caution

PowerDesigner will only look for data sources for the selected calculation views in the packages you select in the left pane. If your calculation views depends on calculation views in packages other than those you have selected then the import will fail or be incomplete.

i Note

Tabs to select analytic and attribute views are also available. These objects are deprecated in HANA and should be migrated to calculation views (see SAP Note [2325817](#)).

5. On the *Catalog Objects* tab, PowerDesigner automatically selects any catalog tables and views required by the selected analytic, attribute, and calculation views for import. Select additional objects to import from the lists, and then click *Next*.

Note

You can select additional schemas from the list to make their objects available for selection.

6. Review the objects that will be imported and then click *Finish*.
7. If objects are already present in the model, a merge dialog will open (see *Core Features Guide > Modeling with PowerDesigner > Comparing and Merging Models*) to allow you to review the specific changes that will be made. Approve or reject the proposed changes, and then click *OK* to perform the import.
PowerDesigner will import schemas, users, tables, and views to the root of the model and analytic, attribute, and calculation views to their appropriate HANA packages. When the import is complete, click *Close* to exit the wizard.

2.12.1.7 SAP HANA Database Extensions

To create a PDM with support for features specific to the SAP HANA® DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select  *Database*  *Edit Current DBMS* and expand the *Profile* node.

The following sections list the extensions provided for SAP HANA.

Model

The following extensions are available on the *General* tab:

Name	Description
HDI Namespace	Specifies the namespace for use when generating files for HDI (see Exporting Objects to the HANA Repository [page 535]). Scripting name: Namespace
Extended storage	Specifies the extended storage for the HANA database (see Dynamic Tiering / Extended Storage (HANA) [page 528]). Use the tools to the right of the field to create, delete, or open the property sheet of the external storage. Scripting name: ExtendedStorage

Tables

The following extensions are available on the *General* tab:

Name	Description
Type	<p>Specifies the table type. You can choose between:</p> <ul style="list-style-type: none">• Row - [default] If the majority of table access involves selecting a few records, with all attributes selected, ROW-based storage is preferable.• Column - If the majority of table access will be through a large number of tuples, with only a few selected attributes, COLUMN-based storage should be used.• History column - Creates a table with a session type HISTORY, to support time travel queries, which are queries against historical states of the database.• Global temporary - The table definition is globally available while data is visible only to the current session. The table is truncated at the end of the session.• Local temporary - The table definition and data is visible only to the current session. The table is truncated at the end of the session. <p>Scripting name: FullType</p>
Using extended storage	[HANA 2.0] Creates an extended table (see Dynamic Tiering / Extended Storage (HANA) [page 528]). Scripting name: UseExtendedStorage

The following extensions are available on the *HANA* tab (HANA 1.0) or the *Physical Options (Common)* tab (HANA 2.0):

Name	Description
Logging	<p>Specifies whether table logging is activated. You can choose between:</p> <ul style="list-style-type: none">• logging - [default]• nologging - specifies that logging is deactivated. As a result, the definition of the table is persistent and globally available and data is temporary and global. The resource manager should therefore explicitly drop a NOLOGGING table. <p>Scripting name: LoggingType</p>
Retention period	[if nologging] Specifies the retention time in seconds of the table created as nologging. Scripting name: Retention
Auto-Merge	Specifies that automatic delta merge is triggered. Scripting name: AutoMerge
Unload priority	Specifies the unload priority for the table from 0 to 9, where 0 means the table cannot be unloaded and 9 means earliest unload. Scripting name: UnloadPriority

Name	Description
Schema flexibility	Specifies that the table schema is flexible. Scripting name: WithSchemaFlexibility
Location	Specifies that partitions will be created on the listed instances using round robin scheme. Scripting name: PartitionLocation
Multiple	[HANA 1.0] Specifies that the location targets multiple HANA instances. [HANA 2.0] This option is implicitly enabled when you specify more than one instance in the <i>Location</i> field. Scripting name: HasMultipleLocations
Using extended storage	[HANA 1.0] Creates an extended table (see Dynamic Tiering / Extended Storage (HANA) [page 528]). When selected, you can additionally enable support for <i>Row-level versioning</i> . Scripting name: UseExtendedStorage, EnableDelta
Group options	Specifies the group options. Scripting name: GroupOptionClause
Options text	[HANA 1.0] Specifies the SQL text of the table options. Options entered here will be set in their relevant fields, and changes to the fields are reflected here. Scripting name: FullTableOptions

The following extensions are available on the *Partitions* tab:

Name	Description
Type	Specifies the partition scheme type: <ul style="list-style-type: none"> • Hash - Distributes rows to partitions equally for load balancing and to overcome the 2 billion row limitation. Specify an <i>Expression</i> listing the columns to partition on and the <i>Quantity</i> of partitions to create. You may specify a second scheme of type <i>Hash</i> or <i>Range</i>. • Range - Creates partitions for specific values or value ranges. Specify an <i>Expression</i> and <i>Range specifier</i>. • RoundRobin - Distributes rows to partitions equally without specifying partitioning columns. Specify the <i>Quantity</i> of partitions to create. You may specify a second scheme of type <i>Range</i>. Scripting name: FirstPartitionElement, Hash1Expression, Hash1Quantity, Range1Expression, Range1Spec, Round1Quantity, SecondPartitionElement, Hash2Expression, Hash2Quantity, Range2Expression, Range2Spec

Columns

The following extensions are available on the *Detail* tab:

Name	Description
Column stored data type	Specifies the stored data type. Scripting name: StoreDataType
DDIC data type	Specifies the application data type. Scripting name: DDICDataType

Indexes

The following extensions are available on the *General* tab:

Name	Description
Type	Specifies the type of the index, which can be: <ul style="list-style-type: none">• <none> - [default] The server will choose the appropriate index type.• Cpbtree - Compressed Prefix B+-Tree, which can show better performance for larger keys for character, string, binary string, or decimal column types, or when the constraint is a composite key, or a non-unique constraint.• Btree - Maintains sorted data that performs efficient insertion, deletion and search of records.• Fulltext - Creates an additional data structure to enable text search features on a specific column in a table. Enables the <i>Full-Text</i> tab (see below). Scripting name: DescIndex
Descending [HANA 1.0] / Index order [HANA 2.0]	[btree only] Specifies that the index should be created in descending order. Scripting name: DescIndex
Fillfactor	[HANA 2.0] Specifies how each node of a new index is filled as an integer percentage from 50 to 100. The default value is 90. Scripting name: Fillfactor
Nowait	[HANA 2.0] Specifies that the CREATE INDEX statement returns an error immediately in case a table lock cannot be acquired. Scripting name: Nowait

Name	Description
Online	[HANA 2.0] Specifies that an intentional exclusive lock is acquired on the table during the index creation to allow other DML statements. Without the ONLINE option, an exclusive lock is acquired. The ONLINE option is available for row store tables. Scripting name: Online

The *Full-Text* tab is displayed when you select **Fulltext** in the *Type* list on the *General* tab:

Name	Description
Phrase index ratio	Specifies the percentage of the phrase index between 0.0 and 1.0. Scripting name: FTPPhraseIndexRatio
Search only	Specifies whether the original document should be stored or only the search results. When selected, the original document content is not stored. Scripting name: FTSearchOnly
Text analysis	Enables text analysis capabilities on the indexed column. Text analysis can extract entities such as persons, products, or places from documents, which are stored in a new table. Scripting name: FTTextAnalysis
Configuration	Specifies the path to a custom configuration file for text analysis. Scripting name: FTConfiguration
Fast pre-process	Specifies that fast preprocessing is used, and that linguistic searches are not possible. Scripting name: FTFastPreprocess
Fuzzy search index	Specifies that a fuzzy search is performed with an additional index (faster search, but higher memory consumption). Scripting name: FTFuzzySearchIndex
Change tracking	Specifies whether the index should be built in an <i>asynchronous</i> or <i>synchronous</i> manner. Scripting name: FTChangeTrackingElement
Flush every (minutes) / Flush after (documents)	Specify how frequently an asynchronous index should be update. Scripting name: FTFlushEvery , FTFlushAfter
Language detection / Language column	Specify the set of languages to be considered during language detection and the column where the language of a document is specified. Scripting name: FTLanguageDetection , FTLanguageColumn

Name	Description
MIME type / Mime-type column	Specify the default MIME type used for preprocessing (for example cf_M_TEXT_ANALYSIS_MIME_TYPES and the column where the MIME type of a document is specified. Scripting name: FTMimeType , FTMimeTypeColumn
Token separators	Specifies the set of ASCII characters used for token separation. Scripting name: FTTokenSeparators

Keys

The following extensions are available on the *General* tab:

Name	Description
Key type	Specifies the key type. Scripting name: KeyType

Views

The following extensions are available on the *Cache Options* tab:

Name	Description
Retention (min)	Specifies the maximum staleness threshold that user can see in minutes. Scripting name: CacheRetention
Refresh on update	Specifies to refresh the cache when the related table is updated. Scripting name: CacheRefreshOnUpdate
Projection list	Specifies the list of columns that will be cached (vertical cropping). Scripting name: Projection
Filter	Specifies a filter condition to limit the cache to a subset of elements (horizontal cropping). Scripting name: CacheFilter

Roles

The following extensions are available on the *General* tab:

Name	Description
Global visibility	Specifies that the role is available globally. Scripting name: GlobalVisibility
Global ID	[if global visibility] Specifies the external role name for the global user. Scripting name: GlobalID

References

The following extensions are available on the *HANA* tab:

Name	Description
Cardinality	Specifies the type of cardinality. Scripting name: HANACardinality
Join type	Specifies the join type. Scripting name: HANAJoinType
Language Column	Specifies the language column. Scripting name: HANALanguageColumn

Users

The following extensions are available on the *General* tab:

Name	Description
Identification	Specifies the type of identification (global, local or external). Scripting name: Identification
Distinguished name	Specifies the user's distinguished name (DN) in the directory or certificate. Scripting name: DistinguishedName

Name	Description
Password	Specifies the clear copy of the password. Scripting name: CopyPassword
Implicit Schema	Specifies that the database generation will use the stored procedure sp_grantdbaccess instead of a create user statement. Scripting name: ImplicitSchema
Default Schema	Specifies the first schema searched to resolve the names of objects for this user. Scripting name: DefaultSchema

Packages (HANA 1.0)

The following extensions are available on the [HANA](#) tab of HANA packages:

Name	Description
Structure package	Specifies that the package is a structural package Scripting name: Structural
Package	Specifies the HANA object name. Scripting name: _ObjectName_

Facts (Analytic Views) and Dimensions (Attribute Views) (HANA 1.0)

The following extensions are available on the [HANA](#) tab:

Name	Description
Default Client / Member	Specify the HANA default client, and (dimension only) member. Scripting name: DefaultClient , DefaultMember
Multidimensional reporting	[facts] Specifies that multidimensional reporting is enabled. Scripting name: MultidimensionalReporting
Package / Name / Version	Specifies the HANA package, object name, and version. Scripting name: _ObjectPackage_ , _ObjectName_ , _ObjectVersion_

Name	Description
Last Updated Date / at	Specifies when the dimension or fact was last edited. Scripting name: <code>_LastUpdatedDate_, _LastUpdatedTime_</code>

Dimension Attributes and Fact Attributes (HANA 1.0)

The following extensions are available on the [HANA](#) tab:

Name	Description
Default Member / Info Object	Specify the HANA default member and info object. Scripting Name: <code>DefaultMember, InfoObject</code>
Drill Down Enabled	Specifies the drill down is enabled for the attribute. Scripting Name: <code>DrillDownEnabled</code>
Hidden	Specifies that the attribute is hidden. Scripting Name: <code>IsHidden</code>
Key Attribute / Attribute Hierarchy Active	[Dimension attribute only] Specify that the attribute is a key attribute and that the attribute hierarchy is active. Scripting Name: <code>KeyAttribute, AttributeHierarchyActive</code>
Data Type / Length / Scale	Specify the data type, length and scale of the attribute. Scripting Name: <code>AttributeDataType, Length, AttributeScale</code>

Fact Measures (HANA 1.0)

The following extensions are available on the [HANA](#) tab:

Name	Description
Measure type	Specifies the type of the measure: <ul style="list-style-type: none"> • simple - a measurable analytical element that is derived from the data foundation. • amount - based on a combination of data from OLAP cubes, arithmetic operators, constants, and functions. • quantity - count the recurrence of an attribute.

Name	Description
Calculated measure	<p>Specify the data type, length and scale of the measure.</p> <p>Scripting Name: MeasureDataType, MeasureLength, MeasureScale</p>

2.12.2 Modeling for Core Data Services (CDS)

PowerDesigner supports modeling and generation of CDS artifacts to SAP HANA® 1.0 Classic Repository and SAP HANA® 1.0 and 2.0 HDI environments.

Context

PowerDesigner provides the following support for migrating a database to HANA via CDS artifacts:

Tasks	HANA 1.0 Classic Repository	HANA 1.0 and 2.0 HDI
Design	<p>Generation of a CDM or LDM to an SAP HANA 1.0 CDS Repository PDM.</p> <p>Generation of any PDM to an SAP HANA 1.0 CDS Repository PDM for migration purposes.</p> <p>Modeling of the following CDS artifacts:</p> <ul style="list-style-type: none"> • Contexts • Entities • Associations • Views • Simple and structured types <p>Not supported: view joins, anonymous types, enumerations.</p>	<p>Generation of a CDM or LDM to an SAP HANA 1.0 CDS HDI or SAP HANA 2.0 CDS HDI PDM.</p> <p>Generation of any PDM to an SAP HANA 1.0 CDS HDI or SAP HANA 2.0 CDS HDI PDM for migration purposes.</p> <p>Modeling of all classic HANA Repository artifacts, and:</p> <ul style="list-style-type: none"> • Constants • Extensions (for entities) - SAP HANA 2.0 CDS HDI only
Generation	Generation and activation of CDS artifacts.	Generation of CDS files for activation.
Reverse	<p>Not supported.</p> <p>Catalog tables activated from your CDS entities can be reversed to an SAP HANA 1.0 Database PDM.</p>	As per classic HANA Repository.

For detailed information about working with CDS, see the *SAP HANA Core Data Services (CDS) Reference* at https://help.sap.com/viewer/p/SAP_HANA_PLATFORM.

Procedure

1. Open your source CDM, LDM, or PDM, and select Tools Generate Physical Data Model.

Note

You can generate from a PDM targeting any DBMS, including from **SAP HANA 1.0 Database** or **SAP HANA 1.0 CDS Repository**.

2. Select **SAP HANA 1.0 CDS Repository**, **SAP HANA 1.0 CDS HDI**, or **SAP HANA 2.0 CDS HDI** in the **DBMS** field, modify as appropriate the other options on this and the other tabs, and click **OK** to generate your HANA CDS PDM.
3. Review the generated model and perform any necessary modeling tasks. The following tools are available in the CDS toolbox:

Tool	Description	Can Create In
	HANA Package - An organizing container for HANA artifacts. See HANA Packages (HANA) [page 526] .	Model Root or HANA Package
	Context - An organizing container for CDS artifacts. See Contexts (CDS) [page 552] .	Anywhere
	Entity - A table with a set of data elements that are organized using columns and rows. See Entities (CDS) [page 553] .	Anywhere
	Association - A relationship between two entities. See Associations (CDS) [page 555] .	Anywhere
	[HANA 1.0] View - A query based on one or more entities. See Views (CDS) [page 559] .	Anywhere
[none]	Simple type - A user-defined type. See Simple Types (CDS) [page 560] .	Context
	Structured type - A user-defined type containing a list of attributes. See Structured Types (CDS) [page 560] .	Context
[none]	[HDI] Constant - A user-defined constant value. See Constants (CDS) [page 561] .	Context

4. Generate directly to your classic HANA Repository (**SAP HANA 1.0 CDS Repository**), see [Exporting CDS Objects to the HANA Repository \[page 563\]](#) or to files (**SAP HANA 1.0 CDS HDI** or **SAP HANA 2.0 CDS HDI**), see [Generating CDS Files for Repository or HDI Environments \[page 564\]](#)).
5. Review and complete files in HANA Modeler (**SAP HANA 1.0 CDS Repository**) or in Web IDE (**SAP HANA 1.0 CDS HDI** or **SAP HANA 2.0 CDS HDI**) and then activate them.
6. [optional] Reverse-engineer the resulting catalog tables and any calculation views consuming them to an **SAP HANA 1.0 Database** PDM.

i Note

To ensure that your CDS artifacts participate in any impact analysis launched from the catalog objects or calculation views, open the CDS model, select **Tools** **Rebuild Objects** **Rebuild Links to Catalog Objects**, select the **SAP HANA 1.0 Database** PDM containing the catalog objects, and click **OK**.

2.12.2.1 Contexts (CDS)

Contexts provide a way of structuring your CDS artifacts. You can create contexts at the model root, under a HANA package, or under another context. In HDI environments, one file is generated for each top-level context.

Procedure

1. Select the **Context** tool in the **CDS** toolbox and click in the diagram.
2. Open the property sheet, and complete properties as appropriate:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the Code field.
Schema	[top-level CDS Repository contexts] Specifies the schema to which the context belongs.
Use parent name-space	Not for use with CDS contexts

3. Click **OK** to complete the creation of the context.
4. Press **Ctrl** and double-click the context symbol to open its diagram.

You can create any object (except a HANA package) inside a context.

i Note

If you define an artifact in one CDS document (top-level context) by referring to an artifact that is defined in another CDS document, PowerDesigner will automatically insert the appropriate **using** statement.

2.12.2.2 Entities (CDS)

A CDS entity is a table with a set of data elements that are organized using columns and rows. You can create entities at the model root, under a HANA package, or under another context. One file is generated for each top-level entity not in a context.

Procedure

1. Select the *Entity* tool in the *CDS* toolbox and click in the diagram.
2. Open the property sheet, and complete properties as appropriate:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Schema	[CDS Repository: entities created at root or in a HANA package] Specifies the schema to which the entity belongs.
Type	Specifies the type of the activated table. You can choose between: <ul style="list-style-type: none">○ Row - [default] If the majority of table access involves selecting a few records, with all attributes selected, ROW-based storage is preferable.○ Column - If the majority of table access will be through a large number of tuples, with only a few selected attributes, COLUMN-based storage should be used.○ Global temporary - The table definition is globally available while data is visible only to the current session. The table is truncated at the end of the session.
Unload priority	[HDI] Specifies the unload priority for the activated table from 0 to 9, where 0 means the table cannot be unloaded and 9 means earliest unload. Scripting name: UnloadPriority
Group options	[HDI] Specifies the group options for the activated table. Scripting name: GroupOptionClause

3. Click the *Columns* tab to specify the entity elements.

For each element, enter an appropriate *Name* and then select a type from the *Data type* field list (or click the ... tool to the right of the list to select a simple or structured type).

Note

Anonymous types and enumerations are not supported.

To specify an element as a key, select the checkbox in its *P* column.

The following extensions are available on the *Detail* tab of column property sheets:

Name	Description
Column stored data type	Specifies the stored data type. Scripting name: StoreDataType
DDIC data type	Specifies the application data type. Scripting name: DDICDataType

4. Click the entity *Indexes* tab to specify any indexes.

The following extensions are available on the *General* tab of index property sheets:

Name	Description
Type	Specifies the type of the index, which can be: <ul style="list-style-type: none">○ <none> - [default] The server will choose the appropriate index type.○ Cpbtree - Compressed Prefix B+-Tree, which can show better performance for larger keys for character, string, binary string, or decimal column types, or when the constraint is a composite key, or a non-unique constraint.○ Btree - Maintains sorted data that performs efficient insertion, deletion and search of records.○ Fulltext - Creates an additional data structure to enable text search features on a specific column in a table. Enables the <i>Full-Text</i> tab (see below). Scripting name: DescIndex
Descending [HANA 1.0] / Index order [HANA 2.0]	[btree only] Specifies that the index should be created in descending order. Scripting name: DescIndex
Fillfactor	[HANA 2.0] Specifies how each node of a new index is filled as an integer percentage from 50 to 100. The default value is 90. Scripting name: Fillfactor
Nowait	[HANA 2.0] Specifies that the CREATE INDEX statement returns an error immediately in case a table lock cannot be acquired. Scripting name: Nowait

Name	Description
Online	[HANA 2.0] Specifies that an intentional exclusive lock is acquired on the table during the index creation to allow other DML statements. Without the ONLINE option, an exclusive lock is acquired. The ONLINE option is available for row store tables. Scripting name: Online

5. [HDI] Click the entity *Partitions* tab and specify the partition scheme:

Name	Description
Type	Specifies the partition scheme type: <ul style="list-style-type: none"> ○ Hash - Distributes rows to partitions equally for load balancing and to overcome the 2 billion row limitation. Specify an <i>Expression</i> listing the columns to partition on and the <i>Quantity</i> of partitions to create. You may specify a second scheme of type <i>Hash</i> or <i>Range</i>. ○ Range - Creates partitions for specific values or value ranges. Specify an <i>Expression</i> and <i>Range specifier</i>. ○ RoundRobin - Distributes rows to partitions equally without specifying partitioning columns. Specify the <i>Quantity</i> of partitions to create. You may specify a second scheme of type <i>Range</i>. Scripting name: FirstPartitionElement , Hash1Expression , Hash1Quantity , Range1Expression , Range1Spec , Round1Quantity , SecondPartitionElement , Hash2Expression , Hash2Quantity , Range2Expression , Range2Spec

6. Click *OK* to complete the creation of the entity.

To preview the code to be generated:

- For entities created at the model root, use the entity's *Preview* tab.
- For entities created in a context, use the context's *Preview* tab.

2.12.2.3 Associations (CDS)

Associations define relationships between entities.


Procedure

1. Select the *Association* tool in the *CDS* toolbox and draw a link from the source to the target entity. PowerDesigner adds a new attribute with the name of the target entity to the source entity and sets its data type to **<target entity>**.
2. Double-click the association link to open its property sheet and click the *Joins* tab to specify additional properties.
3. Review the following properties in the *Info* tab *General* section:




Property	Description
Name	Identifies the object.
Associated element / Source entity / Cardinality	Specifies the element containing the association, its parent entity, and the cardinality at the source end of the association.
Target entity / Cardinality	Specifies the entity to which the association points and the cardinality at the target end of the association.

4. You can specify either a managed or unmanaged association.

In this example, the six **Address** elements are created through managed associations drawn from the **Person** entity to the **Address** entity (which uses the **StreetAddress** and **CountryAddress** structured types):





Association Type/Steps	Join Properties/Generated Code																
[default] Implicitly use the target entity's primary key as foreign key.	<p>Join Properties/Generated Code:</p> <p>General Joins Definition Rules</p> <p>Associated attribute: Person.Address_1</p> <p>Unmanaged association CDS Cardinality:</p> <table border="1"> <tr> <th>Parent Table Column</th> <th>Child Table Column</th> <th>Alias</th> <th>Sub-Element</th> </tr> <tr> <td></td> <td></td> <td></td> <td></td> </tr> <tr> <td></td> <td></td> <td></td> <td></td> </tr> <tr> <td></td> <td></td> <td></td> <td></td> </tr> </table> <p>Code:</p> <pre>Address_1: Association to Address;</pre>	Parent Table Column	Child Table Column	Alias	Sub-Element												
Parent Table Column	Child Table Column	Alias	Sub-Element														

Association Type/Steps	Join Properties/Generated Code
<p>To explicitly specify the target entity's primary key (e.g. id), as the foreign key, select it in the <i>Parent Table Column</i> column.</p>	<p>Join Properties/Generated Code:</p>  <p>Code:</p> <pre>Address_2: Association to Address { id };</pre>
<p>To specify one or more other elements from the target entity as foreign key elements, select them (e.g. zipcode, street, and country) in the <i>Parent Table Column</i> column.</p>	<p>Join Properties/Generated Code:</p>  <p>Code:</p> <pre>Address_3: Association[1] to Address { zipCode, street, country };</pre>
<p>To specify a cardinality for the association (e.g. 0..*), select or enter it in the <i>CDS Cardinality</i> field.</p>	<p>Join Properties/Generated Code:</p>  <p>Code:</p> <pre>Address_4: Association[0..*] to Address { zipCode };</pre>

Association Type/Steps	Join Properties/Generated Code																				
To specify sub-elements from structured types as foreign key elements, enter them manually (e.g. street.name) in the <i>Sub-Element</i> column.	<p>General Joins Definition Rules</p> <p>Associated attribute: Person.Address_5</p> <p>Unmanaged association CDS Cardinality:</p> <table border="1"> <thead> <tr> <th>Parent Table Column</th> <th>Child Table Column</th> <th>Alias</th> <th>Sub-Element</th> </tr> </thead> <tbody> <tr> <td>→ <None></td> <td><None></td> <td></td> <td>street.name</td> </tr> <tr> <td></td> <td></td> <td></td> <td></td> </tr> <tr> <td></td> <td></td> <td></td> <td></td> </tr> </tbody> </table> <p>Code:</p> <pre>Address_5: Association[*] to Address { street.name };</pre>	Parent Table Column	Child Table Column	Alias	Sub-Element	→ <None>	<None>		street.name												
Parent Table Column	Child Table Column	Alias	Sub-Element																		
→ <None>	<None>		street.name																		
To specify an alias for any of the foreign key elements, enter it in the <i>Alias</i> column.	<p>General Joins Definition Rules</p> <p>Associated attribute: Person.Address_6</p> <p>Unmanaged association CDS Cardinality:</p> <table border="1"> <thead> <tr> <th>Parent Table Column</th> <th>Child Table Column</th> <th>Alias</th> <th>Sub-Element</th> </tr> </thead> <tbody> <tr> <td>→ <None></td> <td><None></td> <td>streetName</td> <td>street.name</td> </tr> <tr> <td>2</td> <td><None></td> <td>countryName</td> <td>country.name</td> </tr> <tr> <td></td> <td></td> <td></td> <td></td> </tr> <tr> <td></td> <td></td> <td></td> <td></td> </tr> </tbody> </table> <p>Code:</p> <pre>Address_6: Association[*] to Address { street.name as streetName, country.name as countryName };</pre>	Parent Table Column	Child Table Column	Alias	Sub-Element	→ <None>	<None>	streetName	street.name	2	<None>	countryName	country.name								
Parent Table Column	Child Table Column	Alias	Sub-Element																		
→ <None>	<None>	streetName	street.name																		
2	<None>	countryName	country.name																		

In this example, the **inhabitants** element is defined by an unmanaged association, drawn from the **Room** entity to the **Employee** entity:



Association Type/Steps	Join Properties/Generated Code
<ul style="list-style-type: none"> ○ Select the <i>Unmanaged association</i> checkbox. ○ Select an element from the target entity in the <i>Parent Table Column</i> column. ○ Select an element from the source entity in the <i>Child Table Column</i> column. ○ [optional] Specify a cardinality. 	 <p>Code:</p> <pre>inhabitants: Association[*] to Employee on id = inhabitants.officeId;</pre>

- Click **OK** to complete the creation of the association.

2.12.2.4 Views (CDS)

A view is a virtual table based on the dynamic results returned in response to an SQL statement.

Procedure

- Select the *CDS View* tool in the toolbox and click in the diagram.

You can create views at the model root, under a HANA package, or under a context.

- In the selection dialog, select one or more tables and views to use as sources for the view and click **OK**.

i Note

For views with multiple sources, only joins of type *Union* are supported.

- Double-click the view symbol to open its property sheet. To edit the underlying query, select the *Query* tab and click the Properties tool.
 - *Columns* tab - lists the columns in the `SELECT` clause. You can add or delete columns in the list, specify aliases for them, and reorder the list using the arrows at the bottom of the tab.
 - *Where* tab - lists the expressions in the `WHERE` clause. You can add or delete expressions in the list, and reorder the list using the arrows at the bottom of the tab. For each line, select a column in each of the two *Expression* columns (or click the ellipsis button to specify a more complex expression), and select the appropriate operator between them. You can optionally enter a prefix and suffix.
 - *Group By* tab - lists the columns in the `GROUP BY` clause. You can add or delete columns in the list, and reorder the list using the arrows at the bottom of the tab.
 - *Having* tab - lists the expressions in the `HAVING` clause. You can add or delete expressions in the list, and reorder the list using the arrows at the bottom of the tab. For each line, select a column in each of the two

- Expression* columns (or click the ellipsis button to specify a more complex expression), and select the appropriate operator between them. You can optionally enter a prefix and suffix.
- *Order By* tab - lists the columns in the ORDER BY clause. You can add or delete columns in the list, and reorder the list using the arrows at the bottom of the tab. For each line, select a column (or click the ellipsis button to specify a more complex expression), and select ASC or DESC for the sort direction.
4. Click *OK* to complete the creation of the view.

2.12.2.5 Simple Types (CDS)

A simple type is a user-defined data type for your entity elements. Simple types can be created inside a context.

Procedure

1. Open a context diagram, select *Model* *Simple Types*, click the *Add a Row* tool, and then click the *Properties* tool.

Note

You can only create simple types under a context.

2. Enter an appropriate *Name* for the type and then select a type from the *Data type* field list (or click the ... tool to the right of the list to select another simple or structured type or constant).
3. Click *OK* to complete the creation of the simple type, which is now available for selection as a data type for other objects.

2.12.2.6 Structured Types (CDS)

A structured type is a data type comprising a list of attributes, each of which has its own data type.

Procedure

1. Open a context diagram, select the *Structured Type* tool in the *CDS* toolbox and click in the diagram.

Note

You can only create structured types under a context.

2. Enter an appropriate *Name* for the type and then click the *Columns* tab to define its attributes.
3. For each attribute, click the *Add a Row* tool, enter an appropriate *Name* for the attribute, and then select a type from the *Data type* field list (or click the ... tool to the right of the list to select a simple or structured type or constant).

-
4. Click **OK** to complete the creation of the structured type, which is now available for selection as a data type for other objects.

2.12.2.7 Constants (CDS)

Constants are named values to assign to columns. You can define constant values when working with HANA CDS HDI. PowerDesigner models CDS constants as columns in a special **Constants** table. You can create constants under a context.

Procedure

1. Open a context diagram, select **Model > Constants** to open the *List of Constants*, click the **Add a Row** tool, and click **OK** to create the **Constants** table.
2. Double-click the **Constants** table to open its property sheet and click the **Columns** tab.
3. Click the **Add a Row** tool to create a constant and then click the **Properties** tool to open its property sheet.
4. Enter the following properties on the **General** tab:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the Code field.
Data type	Specifies the data type of the constant. Depending on the type, you may also need to enter a Length and Precision .

5. Click the **Standard Checks** tab and enter the value of the constant in the **Values** groupbox **Default** field.
6. Click **OK** to complete the creation of the constant, which is now available for selection as a data type for other objects.

2.12.2.8 Extensions (CDS)

CDS extensions support delivering updates to database artifacts without modifying the original artifacts. PowerDesigner supports extensions for CDS entities.

Context

For more information about CDS extensions, see [Create a CDS Extension](#) in the SAP HANA Core Data Services (CDS) Reference and the SAP HANA blog post [CDS extension feature in HANA](#).

i Note

PowerDesigner supports extensions for CDS entities only. Extensions cannot be created for other CDS artifacts.

Procedure

1. Prepare your environment. You will require:
 - A base entity.
 - An entity to extend the base entity - this must be in a different HANA package or a different model.
2. Open the diagram containing your extension entity and add your base entity to the diagram as a shortcut.

In this example, the **Banking Customer** entity in the **Banking** package will extend the **Customer** entity in the **CRM** package:



3. Use the *Extension* tool to draw a link from your extension entity to your base entity:



2.12.2.9 Exporting CDS Objects to the HANA Repository

In SAP HANA® 1.0 Classic Repository environments, PowerDesigner provides a wizard to allow you to export your CDS entities and other objects to the HANA Repository.

Context

i Note

In SAP HANA® 1.0 and 2.0 HDI environments, you must generate CDS files, see [Generating CDS Files for Repository or HDI Environments \[page 564\]](#).

Procedure

1. Select  [Database](#)  [Apply Model Changes to HANA Repository](#)  to open the wizard, and click [Next](#) on the Welcome page.
The wizard checks your model for consistency and displays any errors which may compromise the generation.
2. Enter your HANA Repository connection parameters (see [Exporting Objects to the HANA Repository \[page 535\]](#)) and then click [Next](#) to connect.
3. Select HANA packages in your model in the left pane to make their contents available to export. Select the contexts, entities, and views to export in the right pane, and then click [Next](#).
Any supporting objects, such as types and associations are exported as necessary.

i Note

If you have previously imported objects from HANA, the archive model helps to determine model changes since that point.

4. Review the objects that will be exported and then click [Finish](#) to generate them to the HANA Repository.

i Note

If PowerDesigner detects conflicts between changes made in the model and changes to the same objects on the server, then a merge dialog (see *Core Features Guide > Modeling with PowerDesigner > Comparing and Merging Models*) will open to allow you to select, for each conflict, which of the conflicting changes will prevail. The resolutions that you select will first be applied to the model, and then your changes will be exported to the server.

2.12.2.10 Generating CDS Files for Repository or HDI Environments

PowerDesigner supports generating CDS files for loading to HANA.

Procedure

1. Select to open the *Generation* dialog.
2. Enter a directory in which to generate the files, and specify whether you want to perform a model check.
3. On the *Selection* tab, select the objects to generate files for. The following sub-tabs may be available:
 - *HANA Packages* - Lists any top level HANA packages.
 - *Contexts* - Lists top-level contexts. One file is generated for each selected context.
 - *CDS Entities* - Lists entities defined at the model root. One file is generated for each selected entity.
 - *CDS Views* - [HANA 1.0] Lists views defined at the model root. One file is generated for each selected view.
 - *Physical Data Models* - Lists the model node. Select the model if you want to generate a namespace file.
4. [optional] Click the *Generated Files* tab to review the files to generate. By default, one file is generated for each object selected on the *Selection* tab.
5. Click *OK* to begin generation.

When generation is complete, the *Generated Files* dialog opens, listing the files that have been generated to the specified directory. Select a file in the list and click *Edit* to open it in your associated editor, or click *Close* to exit the dialog.

2.13 SAP Adaptive Server Enterprise

To create a PDM with support for features specific to the SAP® Adaptive Server® Enterprise DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select and expand the *Profile* node.

Note

The DBMS definition files for AS Enterprise v12.5.3 and v15.0 are deprecated.

The following sections list the extensions provided for ASE.

Note

We do not provide documentation for the properties on the *Physical Options* and certain other tabs, though minimal information is available for them in the Resource Editor. For information about these properties, consult your DBMS reference documentation.

Tables

The following extensions are available on the *Partitions* tab (v15.0 and higher):

Name	Description
Partition	<p>Indicates how records are distributed on table partitions. You must choose between:</p> <ul style="list-style-type: none">• Range - partitioned according to specified ranges of values in the partitioning column or columns (Scripting name: <code>PartitionByRange</code>).• Hash - partitioned by a system-supplied hash function (Scripting name: <code>PartitionByHash</code>).• List - partitioned according to literal values specified in the named column (Scripting name: <code>PartitionByList</code>).• Round robin - partitioned in a sequential manner (Scripting name: <code>PartitionByRoundrobin</code>). <p>Each of the partitioning methods enables a list of partitions for you to complete, except round robin by partition number, which requires only that you specify the number of available partitions on a particular storage.</p> <p>Scripting name: Partition</p>
Columns	<p>[Range and Hash] Specifies an ordered list of columns used to determine into which partition a row belongs.</p> <p>Scripting name: <code>PartitionByRangeColumnListColumn</code>, <code>PartitionByHashColumnListColumn</code></p>
Column	<p>[List] Specifies the column used to determine into which partition a row belongs.</p> <p>Scripting name: <code>PartitionByListColumnName</code></p>
List	<p>[Round robin] Specifies the table partitions</p> <p>Scripting name: <code>PartitionByRoundrobinSegmentEnumOnAbsence</code></p>
Partition number	<p>[Round robin] Specifies the number of partitions for the table.</p> <p>Scripting name: <code>PartitionByRoundrobinSegmentEnumOnPresence</code></p>
Quantity	<p>[Round robin by partition number] Number of partitions for the table</p> <p>Scripting name: <code>PartitionByRoundrobinSegmentEnumPartitionNum</code></p>
Storage (segment)	<p>[Round robin by partition number] Specifies the name of the segment on which to place the table partition.</p> <p>Scripting name: <code>PartitionByRoundrobinSegmentEnumSegmentName</code></p>

Name	Description
[list of partitions]	[all but Round robin by partition number] Specifies the list of partitions to be used Scripting name: PartitionByRangePartitionListPartitionDefinition , PartitionByHashPartitionListPartitionDefinition , PartitionByListPartitionListPartitionDefinition , PartitionByRoundRobinPartitionListPartitionDefinition

Columns

The following extensions are available on the *AS Enterprise/Sybase* tab:

Name	Description
Store Java-SQL column in row	[v12.0 and higher] Specifies whether a Java-SQL column is stored separate from the row (set to False) or in storage allocated directly in the row (set to True). Scripting name: InRow
Computed column is materialized	[v15.0 and higher] Specifies that the computed column is materialized. Scripting name: Materialized
Encrypted	[v12.5.3a and higher] Specifies that the column is encrypted. Enabled only for columns with a datatype that supports encryption. Scripting name: Encrypted
Encryption key	[v12.5.3a and higher] Specifies an encryption key. Use the tools to the create or select a key (see Encryption Keys (ASE) [page 569]). Scripting name: EncryptionKey
Default decrypt value	[v15.5.0 and higher] Specifies the default constant value that is returned to users who do not have decrypt permissions. Scripting name: DecryptDefault
Compressed	[v15.7 and higher] Specifies that the data in the column is compressed. Scripting name: Compressed
Compression Level	[v15.7 and higher] Specifies the level of column data compression. Scripting name: CompressionLevel

Databases

The following extensions are available on the *General* tab:

Name	Description
Encryption key	[v16 and higher] Specifies the key used to encrypt the whole database. Scripting name: EncryptionKey
For cluster	[v15.5.0 and higher] Specifies that the database will support clustering. Scripting name: ForCluster
Type	[v15.5.0 and higher] Specifies the whether the database is of type: <ul style="list-style-type: none">• [for standard databases] inmemory, temporary, or inmemory temporary• [for cluster databases] temporary, global temporary, or system temporary Scripting name: DatabaseType

Keys

The following extensions are available on the *AS Enterprise/Sybase* tab:

Name	Description
Key index is descending	[v12.0 and higher] Specifies if the index created for a constraint is to be created in descending order for each column. Scripting name: DescKey

Model

The following extensions are available on the *Encryption* tab (v12.5.3a and higher):

Name	Description
Encryption password	Global encryption password. Scripting name: EncryptionPassword

Web Services

The following extensions are available on the *AS Enterprise/Sybase* tab (v15.0 and higher):

Name	Description
Port number	Specifies the web service port number. Scripting name: PortNumber
Server name	Specifies the web service server name. Scripting name: ServerName
Database name	Specifies the database name used in the URL to access the web service. Scripting name: DatabaseName

Web Operations

The following extensions are available on the *AS Enterprise/Sybase* tab (v15.0 and higher):

Name	Description
Alias	Specifies the name of the user-defined database alias. Scripting name: Alias
Secure	Security option. clear indicates that HTTP is used to access this Web service. ssl indicates HTTPS is used to access this Web service Scripting name: Secure

2.13.1 Proxy Tables (ASE)

SAP supports modeling for ASE proxy tables.

For more information, see [Proxy Tables \(ASE/SQL Anywhere\) \[page 610\]](#).

2.13.2 Encryption Keys (ASE)

Encryption keys are supported for ASE v12.5.3a and higher. PowerDesigner models encryption keys as extended objects with a stereotype of <<EncryptionKey>>.

Adaptive Server authentication and access control mechanisms ensure that only properly identified and authorized users can access data. You can encrypt data at the system, database level or at the column level, to restrict your security measures to only sensitive data, and minimize processing overhead.

Encrypting columns in Adaptive Server is more straightforward than using encryption in the middle tier, or in the client application. You use SQL statements to create the encryption keys and specify columns for encryption. Adaptive Server handles key generation and storage. Encryption and decryption of data occurs automatically and transparently as you write and read the data in encrypted columns. No application changes are required, and there is no need to purchase third-party software.

Creating an Encryption Key

You can create an encryption key in any of the following ways:

- Select  [Model](#)  to access the List of Encryption Keys, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select  [New](#) .

Encryption Key Properties

You can modify an object's properties from its property sheet. To open an encryption key property sheet, double-click its Browser entry in the Encryption Keys folder.

The following extended attributes are available on the [AS Enterprise/Sybase](#) tab:

Name	Description
Owner	Specifies the owner of the encryption key. Scripting name: Owner
For database encryption	Specifies that the encryption key will encrypt the entire database, rather than individual columns. Selecting this option sets the Key to master key with a length of 256, enables the Initialization vector option and disables the Padding of datatypes option. Scripting name: ForDatabaseEncryption

Name	Description
Key	<p>Specifies the kind of key. You can choose between:</p> <ul style="list-style-type: none"> • <code>user password</code> - Enables the <i>Password</i> field, in which you must enter an alphanumeric string of up to 255 bytes in length that Adaptive Server uses to generate the KEK. • <code>master key</code> - To use the master key (defined on the database). • <code>system key</code> - To use the <code>system_encr_passwd</code> database key (defined on the model). <p>Scripting name: <code>Passwd, PasswordPhrase</code></p>
Algorithm	<p>Specifies the algorithm used to generate the encryption key. Currently, Advanced Encryption Standard (AES) is the only algorithm supported.</p> <p>Scripting name: <code>Algorithm</code></p>
Key length	<p>Specifies the size in bits of the key to be created. Valid key lengths for AES are 128, 192 and 256 bits.</p> <p>Scripting name: <code>KeyLength</code></p>
Initialization vector	<p>Controls the use of an initialization vector when encrypting. When an initialization vector is used by the encryption algorithm, the ciphertext of two identical pieces of plaintext will be different, which would prevent the cryptanalyst from detecting patterns of data but would render the data on disk useless for indexing or matching without decryption.</p> <p>This option is enforced when the <i>For database encryption</i> option is selected.</p> <p>Scripting name: <code>InitVector</code></p>
Padding of datatypes	<p>Specifies the use of padding for datatypes whose length is less than one block. Padding can be used instead of an initialization vector to randomize the ciphertext. It is only suitable for columns whose plaintext length is less than half the block length. For the default AES algorithm the block length is 16 bytes.</p> <p>This option is disabled when the <i>For database encryption</i> option is selected.</p> <p>Scripting name: <code>Pad</code></p>
Default encryption key	<p>Allows the System Security Officer to create a default key for use on all encrypted columns which do not have a keyname specified in create table or alter table. This is a database specific default key for use with tables in the same database. The default key is stored in the database sysencryptkeys table, the same as non-default keys.</p> <p>Scripting name: <code>Default</code></p>
Dual control	<p>[v16.0 and higher] Specifies that the key must be encrypted using dual controls.</p> <p>Scripting name: <code>DualControls</code></p>
Password phrase	<p>[v15.0.2 to 15.7] Specifies a default key for use on all encrypted columns which do not have a keyname specified in create table or alter table. This is a database specific default key for use with tables in the same database. The default key is stored in the database sysencryptkeys table, the same as non-default keys.</p> <p>Scripting name: <code>PasswordPhrase</code></p>

The following tabs are also available:

- **Key Copies** - [v15.0.2 and higher] ASE allows users to access encrypted columns using their copy of a single key. A key copy is designated for an individual user with a private password known only to the user, ASE does not save the passwords on disk, so that even the SA cannot access the protected data. PowerDesigner models key copies as extended sub-objects with a <<KeyCopy>> stereotype, and the following extensions are available on the *AS Enterprise/Sybase* tab of its property sheet:
 - *User* - identifies the user for whom the key copy is made.
 - *Password* - specifies the password used to encrypt the key copy.

2.14 SAP IQ

To create a PDM with support for features specific to the SAP® IQ DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select ► *Database* ▶ *Edit Current DBMS* ▶ and expand the *Profile* node.

i Note

The DBMS definition files for IQ v12.x, v15.0, and v15.1 are deprecated.

The following sections list the extensions provided for IQ.

i Note

We do not provide documentation for the properties on the *Physical Options* and certain other tabs, though minimal information is available for them in the Resource Editor. For information about these properties, consult your DBMS reference documentation.

Tables

The following extensions are available on the *SAP IQ/Sybase* tab (v12.4.3 and higher):

Name	Description
DBSpace	[v15.0 and higher] Specifies the dbspace in which to create the table (see Dbspaces (IQ) [page 579]). Scripting name: DBSpace
Global temporary table	[v12.4.3 to 15.2] Specifies that the table is a global temporary table. Scripting name: ExtGlobalTemporaryTable

Name	Description
Scope	[v15.3 and higher] Specifies that the table is either a global or local temporary table. Scripting name: <code>TemporaryTableScope</code>
On commit	[v15.0 and higher] Action on commit. Scripting name: <code>OnCommit</code>
Not transactional	[v15.0 and higher] A table created using NOT TRANSACTIONAL is not affected by either COMMIT or ROLLBACK. Scripting name: <code>NotTransactional</code>
Remote location	[v15.0 and higher] Used to create a table at the remote location. Scripting name: <code>At</code>
Partition key	[v15.0 and higher] Specifies the partition key column. Scripting name: <code>PartitionKey</code>

Columns

The following extensions are available on the [SAP IQ/Sybase](#) tab (v12.4.3 and higher):

Name	Description
DBSpace	[v15.4 and higher] Specifies the database file (dbspace) in which to create the column (see Dbspaces (IQ) [page 579]). Scripting name: <code>DBSpace</code>
Number of distinct value (Iq unique)	Defines the cardinality of the column (to optimize the indexes internally). Scripting name: <code>ExtIqUnicity</code>

In addition, from v15.0 and higher, the [Partitions](#) tab allows you to override the allocations of partitioned column values to different dbspaces (see [Table and Column Partitions \(IQ\) \[page 580\]](#)).

Indexes

The following extensions are available on the [SAP IQ/Sybase](#) tab (v15.0 and higher):

Name	Description
With nulls not distinct	[v15.4 and higher, when Unique] Specifies that more than one null value is permitted despite the index requiring unique values. Scripting name: WithNullsNotDistinct
Tablespace	[Non-text indexes] Specifies the index dbspace (see Dbspaces (IQ) [page 579]). Scripting name: In
Notify	[Non-text indexes] Gives notification messages after n records are successfully added for the index. Scripting name: Notify
Word length	[WD indexes] Specifies the maximum word length that is permitted in the WD index. Scripting name: Limit
Delimited by	[WD indexes] Specifies separators to use in parsing a column string into the words to be stored in that column's WD index. Scripting name: DelimitedBy
Configuration	[Text indexes] Specifies the text configuration (see Text Configurations (IQ/SQL Anywhere) [page 593]) to be used to control the building of the text index. Scripting name: Configuration
Immediate refresh	[Text indexes v15.2 and higher] Specifies that the index is refreshed immediately each time data is written to the table. Scripting name: Refresh

Keys and References

The following extensions are available on the [General](#) tab (v15.0 and higher):

Name	Description
DBSpace	Specifies the DBSpace where the object is stored (see Dbspaces (IQ) [page 579]). Scripting name: DBSpace

Data Sources

The following extensions are available on the *Data Movement (Lifecycle)* tab (v15.0 and higher), and are required when the first phase of a lifecycle policy must manage data in an external database:

Name	Description
Remote server name	Specifies the name of the server where the remote database is located. Scripting name: Server
Remote database name	Specifies the name of the remote database from which data must be loaded. Scripting name: DatabaseName
Server class	Specifies the type of connection that must be made to the external database. Select the appropriate value from the list. Scripting name: ServerClass
Connection string	Specifies the connection string used to connect to the external database in the format: <ul style="list-style-type: none">• JDBC - <host>:<port>[/database name]• ODBC - <odbc name> Scripting name: JDBCConnectionString/ODBCConnectionString
User/group	Specifies the user or group name with which to log into the external database. Scripting name: ExternalLogin

Procedures

The following extensions are available on the *SAP IQ/Sybase* tab (v15.0 and higher):

Name	Description
Temporary	[standard functions] Specifies that the function is visible only by the connection that created it, and that it is automatically dropped when the connection is dropped. Scripting name: TempFunction
Return data type	Specifies the procedure return data type. Scripting name: ReturnDtpp
Routine characteristics	[standard functions] Transact-SQL-like error handling and deterministic options. Scripting name: RoutineCharacteristics

Name	Description
Sql security	[standard functions] Defines whether the function is executed as the INVOKER, the user who is calling the function, or as the DEFINER, the user who owns the function. Scripting name: SqlSecurity
URL	[web functions] Specifies the URL of the web service. Scripting name: URL
Type	[web functions] Specifies the format used when making the web service request. Scripting name: URLType
Header	[HTTP web functions] When creating HTTP web service client functions, use this clause to add or modify HTTP request header entries. Scripting name: Header
Soap header	[SOAP web functions] When declaring a SOAP web service as a function, use this clause to specify one or more SOAP request header entries. Scripting name: SoapHeader
Certificate	[web functions] To make a secure (HTTPS) request, a client must have access to the certificate used by the HTTPS server. The necessary information is specified in a string of semicolon-separated key/value pairs. Scripting name: Certificate
Client port	[HTTP web functions] Identifies the port number on which the HTTP client procedure communicates using TCP/IP. Scripting name: ClientPort
Namespace	[SOAP web functions] Identifies the method namespace usually required for both SOAP:RPC and SOAP:DOC requests. Scripting name: Namespace
Proxy	[web functions] Specifies the URI of a proxy server. Scripting name: Proxy

Users

The following extensions are available on the [General](#) tab (v15.0 and higher):

Name	Description
Force change	Controls whether the user must specify a new password when they log in. This setting overrides the password_expiry_on_next_login option setting in the login policy. Scripting name: ForcePasswordChange
Login policy	Specifies the login policy to assign to the user (see Login Policies (IQ/SQL Anywhere) [page 585]). Scripting name: LoginPolicy

Web Services

The following extensions are available on the [SAP IQ/Sybase](#) tab (v12.6 and higher):

Name	Description
Port number	Specifies the web service port number. Scripting name: PortNumber
Server name	Specifies the web service server name. Scripting name: ServerName
Name prefix	[DISH service type] Specifies a name prefix. Only SOAP services whose names begin with this prefix are handled. Scripting name: Prefix

Web Operations

The following extensions are available on the [SAP IQ/Sybase](#) tab (v12.6 and higher) when the service type is not dish:

Name	Description
URL	Determines whether URI paths are accepted and, if so, how they are processed. Scripting name: Url

2.14.1 Reference Architecture Modeling (IQ)

PowerDesigner provides a special EAM model to help you determine the architecture required to deploy an SAP IQ data warehouse solution to meet your anticipated workload. An advisor wizard generates architectures based on one or more hardware servers, and comparison tools help you choose the best architecture based on your requirements for cost and speed.

For detailed information, see *Enterprise Architecture > SAP IQ Reference Architecture Model*.

2.14.2 Information Lifecycle Management (IQ)

SAP IQ v15.0 and higher provides data placement capabilities and supports hierarchical storage management with relocation of less critical data to cheaper storage. PowerDesigner offers a simple modeling structure to cost effectively manage "aging" of data inside the data center from 1st tier high performance storage for frequently accessed data through 2nd tier near-line storage for data that is infrequently accessed to 3rd tier archive storage for data that must remain available for regulatory audits.

For detailed information about using PowerDesigner to model your IQ information lifecycle management, see [Lifecycles \(PDM\) \[page 206\]](#).

2.14.3 Events (IQ/SQL Anywhere)

Events allow you to automate and schedule actions.

Context

PowerDesigner models events as extended objects with a stereotype of <<Event>>, and lists them under the *Model* menu and in the Browser.

Procedure

1. Select to access the *List of Events*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *SAP IQ/SQL Anywhere* tab:

Name	Description
Event is scheduled	<p>Specifies that the server carries out a set of actions according to a schedule of times.</p> <p>If selected, this option disables the "Event is triggered" option.</p> <p>Scripting name: ScheduledEvent</p>
Schedule definition	<p>Enter the schedule of event trigger times here. Click the New button to launch a dedicated editor window.</p> <p>Scripting name: SchedulesText</p>
Event is triggered	<p>Specifies that the server carries out a set of actions when a predefined type of system event occurs.</p> <p>This option is the default and, if selected, disables the "Event is scheduled" option.</p> <p>Scripting name: TypedEvent</p>
Event type	<p>The event-type is one of the listed set of system-defined event types. The event types are case insensitive. To specify the conditions under which this event-type triggers the event, use the WHERE clause.</p> <p>Scripting name: EventType</p>
Trigger condition	<p>Determines the condition under which an event is fired. For example, to take an action when the disk containing the transaction log becomes more than 80% full, use the following triggering condition:</p> <pre>WHERE event_condition('LogDiskSpacePercentFree') < 20</pre> <p>The argument to the event_condition function must be valid for the event type.</p> <p>You can use multiple AND conditions to make up the WHERE clause, but you cannot use OR conditions or other conditions.</p> <p>Scripting name: TriggerCondition</p>
Handler	<p>Each event has one handler.</p> <p>The actions of an event handler are committed if no error is detected during execution, and rolled back if errors are detected.</p> <p>Scripting name: Handler</p>
Enable	<p>By default, event handlers are enabled. When DISABLE is specified, the event handler does not execute even when the scheduled time or triggering condition occurs. A TRIGGER EVENT statement does not cause a disabled event handler to be executed.</p> <p>Scripting name: Enable</p>
At (databases)	<p>If you want to execute events at remote or consolidated databases in a SQL Remote setup, you can use this clause to restrict the databases at which the event is handled. By default, all databases execute the event.</p> <p>Scripting name: Database</p>

2.14.4 Dbspaces (IQ)

IQ distributes user data across multiple disks at the application level by representing each device as a dbspace. A dbspace can be an operating system file or a raw disk partition. Dbspaces can contain both user data and internal database structures used for startup, recovery, backup, and transaction management.

PowerDesigner allows you to allocate tables and tables partitions, columns and column partitions, indexes, join indexes, keys, and references to specific dbspaces from each object's property sheet.

Creating a Dbspace

PowerDesigner models dbspaces as tablespaces with additional properties. You can create a dbspace in any of the following ways:

- Select **Model** **Tablespaces** to access the List of Tablespaces, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select **New** **Tablespace**.

Dbspace Properties

PowerDesigner models dbspaces as tablespaces (see [Tablespaces and Storages \(PDM\) \[page 216\]](#)) with the following additional properties on the **General** tab (v15.0 and higher):

Property	Description
Catalog store	Specifies that the dbspace is created for the catalog store and will contain a single dbfile. If you select this option, you must specify a path to the file. Scripting name: CatalogStoreDisplay
File path	Specifies a physical file path for the dbspace. Scripting name: As
Online	Specifies that the dbspace is online. Scripting name: Online
Read-only	Specifies that the online dbspace is read-only. Scripting name: ReadOnly
Striping	Specifies that the dbspace is available for striping. Scripting name: Striping
Stripe size (in kb)	Specifies the size of the stripes. Scripting name: Stripesizekb

In addition, the following tabs are available:

- Cost - allows you to specify the cost per GB of storage for the dbspace (see [Tablespace and Storage Properties \[page 217\]](#)).
- DBFiles - lists the dbfiles associated with the dbspace.

DBSpace Files

PowerDesigner models dbspace files as extended objects with a stereotype of <<DBSpaceFile>> with the following additional properties on the *General* tab (V15.0 and higher):

Property	Description
Path	Specifies the file path to the dbspace file. Scripting name: <code>FilePath</code>
Read-only	Specifies that the resource is read-only. Scripting name: <code>ReadOnly</code>
Size	Specifies that the size of the dbspace file. Scripting name: <code>Size</code> , <code>SizeUnit</code>
Reserve	Specifies the size of space to reserve, so that the dbspace can be increased in size in the future. Scripting name: <code>Reserve</code> , <code>ReserveUnit</code>

2.14.5 Table and Column Partitions (IQ)

A partition is a physical division of the contents of a database table, based on values in the column designated as the partition key, and allocated to a particular dbspace. You can override the allocation of values in certain columns by specifying column partitions.

Creating a Table Partition

In order to create table partitions, you must first select a column as the *Partition key* on the *SAP IQ/Sybase* tab of the table property sheet (see [SAP IQ \[page 571\]](#)), in order to display the *Partitions* tab.

You can create as many partitions as necessary for the table on this tab using the *Insert Row* and *Add a Row* tools.

i Note

Some PowerDesigner features automate the creation of partitions (see [Denormalizing Tables and Columns \[page 87\]](#) and [Modeling a Lifecycle \[page 207\]](#)). If you associate a table with a lifecycle (see [Lifecycles \(PDM\)](#)

[page 206]), PowerDesigner will delete all existing table partitions in order to create the necessary partitions to move data between lifecycle phases.

Table Partition Properties

To view or edit a partition's properties, double-click its Browser or list entry. The property sheet tabs and fields listed here are those available by default, before any customization of the interface by you or an administrator. The following properties are available on the *General* tab:

Property	Description
Parent object	[read only] Specifies the table of which the partition forms a part.
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Values	Specifies the upper bound of the partition, based on the value of the column specified as the partition key. The <code>max</code> keyword can only be set on the last partition.
DBSpace	Specifies the dbspace with which the partition is associated (see Dbspaces (IQ) [page 579]). Select a dbspace from the list or click the tools to the right of this field to create, delete, or search for a dbspace, or to open the property sheet of the selected dbspace.

Overriding Partition DBspaces for a Particular Column

You can override the allocation of values in a particular column from the table partition dbspace to an alternate dbspace. The column will continue to be partitioned based on the same partition key ranges, but the column values for each range will be allocated to the alternate dbspaces.

You create column partitions on the *Partitions* tab of the column property sheet. Click the *Properties* tool to specify the following properties:

Property	Description
Parent object	[read only] Specifies the column to which the partition belongs.
Comment	Provides more detailed information about the object.
Partition	Specifies the table partition for which this partition will redirect column values to an alternate dbspace.
Dbspace	Specifies the dbspace (see Dbspaces (IQ) [page 579]) to which column values contained within this table partition should be allocated.

2.14.6 Logical Servers and Policies (IQ)

SAP IQ v16 and higher supports logical servers, which provide the only means to access the multiplex server nodes. PowerDesigner models logical servers and logical server policies as extended objects with a stereotype of <<LogicalServer>> and <<LogicalServerPolicy>> respectively.

Creating a Logical Server

You can create a logical server in any of the following ways:

- Select to access the List of Logical Servers, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select .

Creating a Logical Server Policy

You can create a logical server policy in any of the following ways:

- Select to access the List of Logical Policies, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select .

Logical Server and Logical Server Policy Properties

You can modify an object's properties from its property sheet. To open a logical server or logical server policy property sheet, double-click its Browser entry in the Logical Servers or Logical Server Policies folder.

The following extended attributes are available on the *General* tab:

Name	Description
With stop server	Automatically shuts down all servers in the logical server when the TEMP_DATA_IN_SHARED_TEMP option is changed directly or indirectly. Scripting name: WithStopServer

The following extended attributes are available on the *SAP IQ* tab of logical servers:

Name	Description
Membership	<p>Lists the multiplex nodes (see Multiplex Servers (IQ) [page 584]) of the logical server.</p> <p>Select the <i>Add for logical coordinator membership</i> option to specifies a logical server membership to the current coordinator.</p> <p>Scripting name: <code>Membership</code>, <code>MembershipForLogicalCoordinator</code></p>
Policy	<p>Specifies the logical server policy applied to the server.</p> <p>Scripting name: <code>Policy</code></p>

The following extended attributes are available on the [SAP IQ](#) tab of logical server policies:

Name	Description
DQP enabled	<p>Specifies how query processing is distributed:</p> <ul style="list-style-type: none"> • 0 - Not distributed • 1 - [default] Distributed as long as a writable shared temporary file exists. • 2 - Distributed over the network, and the shared temporary store is not used <p>Scripting name: <code>DqpEnabled-disp</code></p>
Allow coordinator as member	<p>[ROOT policy only] Specifies that the coordinator can be a member of any user-defined logical server. Enabled by default.</p> <p>Scripting name: <code>AllowCoordinatorAsMember-disp</code></p>
Login redirection	<p>Enables login redirection for logical servers governed by specified login policy. By default, login redirection is disabled at the logical server level, allowing external connection management.</p> <p>Scripting name: <code>LoginRedirection-disp</code></p>
Redirection waiters threshold	<p>Specifies how many connections can queue before IQ redirects a connection to this logical server to another server.</p> <p>Scripting name: <code>RedirectionWaitersThreshold-disp</code></p>
Temp data in shared temp	<p>Enables temporary table data and eligible scratch data writes to the shared temporary store, provided that the shared temporary store has at least one read-write file added.</p> <p>Scripting name: <code>TempDataInSharedTemp-disp</code></p>

2.14.7 Multiplex Servers (IQ)

IQ v15.0 and higher supports multiplex, a highly scalable shared disk grid technology that allows concurrent data loads and queries via independent data processing nodes connected to a shared data source. PowerDesigner models multiplex servers as extended objects with a stereotype of <>MultiplexServer>>.

Creating a Multiplex Server

You can create a multiplex server in any of the following ways:

- Select **Model** **Multiplex Servers** to access the List of Multiplex Servers, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select **New** .

Multiplex Server Properties

You can modify an object's properties from its property sheet. To open a multiplex server property sheet, double-click its Browser entry in the Multiplex Servers folder.

The following extended attributes are available on the **SAP IQ/Sybase** tab:

Name	Description
Database	Specifies the database file with which the server is associated. Scripting name: Database
Host port list	Specifies the machine where the database engine will run. Scripting name: HostPortList
Role	Specifies the server's role in the multiplex environment. Scripting name: Role
Status	Specifies whether the server is included or excluded. If a multiplex secondary server will be shut down for an extended period of time, that server should be excluded. Excluding the server allows the coordinator to ignore this server when performing version cleanup. Scripting name: Status
Failover	Specifies that the server is a failover server. Scripting name: Failover

2.14.8 Login Policies (IQ/SQL Anywhere)

A login policy defines the rules to be followed when establishing a user's database connection.

Context

PowerDesigner models login policies as extended objects with a stereotype of <<LoginPolicy>>, and lists them under the *Model* menu and in the *Login Policies* folder under the model in the Browser.

Procedure

1. Select to access the *List of Login Policies*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *SAP IQ/SQL Anywhere* tab:

Name	Description
Password life time	Specifies the maximum number of days before a password must be changed. Scripting name: PasswordLifeTime
Password grace time	Specifies the number of days before password expiration during which login is allowed but the default post_login procedure issues warnings. Scripting name: PasswordGraceTime
Password expires	Specifies that the user's password will expire in the next login. Scripting name: PasswordExpiryOnNextLogin
Locked	Specifies that users are prohibited from establishing new connections. Scripting name: Locked
Maximum connections	Specifies the maximum number of concurrent connections allowed for a user. Scripting name: MaxConnections
Maximum failed log-ins	Specifies the maximum number of failed attempts, since the last successful attempt, to login to the user account before the account is locked. Scripting name: MaxFailedLoginAttempts

Name	Description
Auto unlock time	[v16 and higher] Specifies the time period after which locked accounts not granted the MANAGE ANY USER system privilege are automatically unlocked. Scripting name: AutoUnlockTime
Maximum days since login	Specifies the maximum number of days that can elapse between two successive logins by the same user. Scripting name: MaxDaysSinceLogin
Maximum non-dba connections	Specifies the maximum number of concurrent connections that a user without DBA authority can make. This option is only supported in the root login policy. Scripting name: MaxNonDBAConnections
Change password dual control	[v16 and higher] Specifies that two users, each granted the CHANGE PASSWORD system privilege, are required to change the password of another user. Scripting name: ChangePasswordDualControl
Default logical server	[v16 and higher] Specifies the server to which the user using this login policy connects when the connection string specifies no logical server. Scripting name: DefaultLogicalServer_disp
Root auto unlock time	[v16 and higher] Specifies the time period after which locked accounts granted the MANAGE ANY USER system privilege are automatically unlocked. Scripting name: RootAutoUnlockTime

[IQ v16 and higher] The following extended attributes are available on the [LDAP](#) tab:

Name	Description
Primary / Secondary server	Specify the names of the primary and secondary LDAP servers (see LDAP Servers (IQ) [page 587]). Scripting name: LDAPPrimaryServer, LDAPSecondaryServer
Auto fallback period	Specifies the time period, in minutes, after which automatic fallback to the primary server is attempted. Scripting name: LDAPAutoFallbackPeriod
Failover to standard authentication	Permits standard authentication when authentication via the LDAP server fails due to system resources, network outage, connection timeouts, or similar system failures. Scripting name: LDAPFailoverToStd

Name	Description
Record LDAP DN refresh time	Updates the <code>ldap_refresh_dn</code> value in the system table with the current time, stored in Coordinated Universal Time (UTC) Scripting name: <code>LDAPRefreshDN</code>

2.14.9 LDAP Servers (IQ)

IQ v16 and higher supports delegating the authentication of users to LDAP servers. PowerDesigner models LDAP servers as extended objects with a stereotype of <<LDAPServer>>.

Creating an LDAP Server

You can create an LDAP server in any of the following ways:

- Select **Model** **LDAP Servers** to access the List of LDAP Servers, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select **New** **LDAP Server** .

LDAP Server Properties

You can modify an object's properties from its property sheet. To open an LDAP server property sheet, double-click its Browser entry in the LDAP Servers folder.

The following extended attributes are available on the *General* tab:

Name	Description
Activate LDAP server after creation	Activates the LDAP server configuration object for immediate use upon creation. Scripting name: <code>WithActivate</code>

The following extended attributes are available on the *SAP IQ* tab:

Name	Description
Search DN	Specifies the host (by name or by IP address), port number, and the search to be performed for the DN lookup for a given user ID, along with the user created in the LDAP server for use by IQ, the password to use, and whether it is encrypted. Scripting name: <code>URL, AccessAccount, Password, Encrypted</code>

Name	Description
Attributes	<p>Specifies the host (by name or IP address) and the port number of the LDAP server to use for authentication of the user, the connection timeout and number of retries, and whether TLS or Secure LDAP protocol is used for connections for both DN searches and authentication.</p> <p>Scripting name: <code>AuthenticationURL</code>, <code>ConnectionTimeout</code>, <code>ConnectionRetries</code>, <code>TLS</code></p>

2.14.10 Remote Servers (IQ)

IQ v15.0 and higher supports remote servers, which define where remote objects mapped to a local proxy table are located. PowerDesigner models remote servers as extended objects with a stereotype of <<RemoteServer>>.

Creating a Remote Server

You can create a remote server in any of the following ways:

- Select to access the List of Remote Servers, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select .

Remote Server Properties

You can modify an object's properties from its property sheet. To open a remote server property sheet, double-click its Browser entry in the Multiplex Servers folder.

The following extended attributes are available on the *General* tab:

Name	Description
Class	<p>Specifies the remote server class.</p> <p>Scripting name: <code>Class</code></p>
Read-only	<p>Specifies that the remote server is a read-only data source. Any update request is rejected by IQ.</p> <p>Scripting name: <code>ReadOnly</code></p>
Connection	<p>Specifies the connection string in the format <code><machine-name>:<port-number> [/ <dbname>]</code> or as a data source name</p> <p>Scripting name: <code>ConnectionInfo</code></p>

2.14.11 External Logins (IQ)

IQ v15.3 and higher supports external logins, which are alternate login names and passwords that are used when communicating with a remote server. PowerDesigner models external logins as extended objects with a stereotype of <>ExternLogin>>.

Creating an External Login

You can create an external login in any of the following ways:

- Select **Model** **Extern Logins** to access the List of External Logins, and click the **Add a Row** tool.
- Right-click the model (or a package) in the Browser, and select **New** **External Login**.

External Login Properties

You can modify an object's properties from its property sheet. To open an external login property sheet, double-click its Browser entry in the External Logins folder.

The following extended attributes are available on the *General* tab:

Name	Description
Local login	Specifies the local login name to which the remote login is assigned. Scripting name: LocalLogin
Remote server	Specifies the name of the remote server. Scripting name: RemoteServer
Remote login	Specifies the user account on the remote server, which is associated with the local user login. Scripting name: RemoteLogin
Remote password	Specifies the password for the remote login Scripting name: RemotePassword

2.14.12 Spatial Data (IQ/SQL Anywhere)

Spatial data, which describes the position, shape, and orientation of objects in a defined space, can be stored using spatial reference systems.

Spatial data are supported for IQ v15.4 and higher and SQL Anywhere v12 and higher.

2.14.12.1 Spatial Reference Systems (IQ/SQL Anywhere)

Spatial data can be stored using spatial reference systems.

Context

Spatial data are supported for IQ v15.4 and higher and SQL Anywhere v12 and higher. PowerDesigner models spatial reference systems as extended objects with a stereotype of <<SpatialReferenceSystem>>, and lists them under the *Model* menu and in the *Spatial Reference Systems* folder under the model in the Browser.

Procedure

1. Select to access the *List of Spatial Reference Systems*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *General* tab:

Name	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Spatial reference system identifier	Specifies the SRID (srs-id) for the spatial reference system. Scripting name: SRS_Id
Organization	Specifies the organization that created the spatial reference system that the new spatial reference system is based on. Scripting name: Organization
Organization coor- dinate reference system ID	Specifies the numeric identifier the organization uses to identify the spatial reference system. Scripting name: OrganizationSRSId

3. Click the *Settings* tab and enter the following properties:

Name	Description
Line interpretation	Specifies how the SRS interprets lines between points. Scripting name: LineInterpretation
Axis order	Specifies the order in which values are given for each axis. Scripting name: AxisOrder
Polygon format	Specifies how polygons are interpreted. Scripting name: PolygonFormat
Storage format	Specifies how data is stored. Scripting name: StorageFormat
Definition	Specifies default coordinate system settings. If any attribute is set in a clause other than the DEFINITION clause, the value specified in the other clause is used regardless of what is specified in the DEFINITION clause. Scripting name: Definition
Type	Specifies whether the system is Projected, Geographic, or Engineering. If a definition is given, this attribute is computed from the definition text. Scripting name: SRSType
Transform definition	Specify a description of the transform to use for the spatial reference system. Scripting name: TransformDefinition

4. Click the *Coordinate* tab and enter the following properties:

Name	Description
<Axis>/ Bounded/ Unbounded	Specifies whether the axis is bounded or unbounded and, if it is bounded, the minimum and maximum values. Scripting name: BoundedCoordinate<Axis>, MinCoordinate<Axis>, MaxCoordinate<Axis>
Ellipsoid axis length	[round earth systems] Specifies the values to use for representing the Earth as an ellipsoid. Scripting name: SemiMajorAxisLength, SemiMinorAxisLength, InverseFlattening
Grid Size	[planar systems] Specifies the size of the grid to use when performing calculations. Scripting name: GridSize
Tolerance	[planar systems] Specifies the precision to use when comparing points. Scripting name: Tolerance

Name	Description
Linear/Angular unit of measure	Specify the linear and angular units of measure for the spatial reference system. Scripting name: <code>LinearUnitOfMeasure</code> , <code>AngularUnitOfMeasure</code>

2.14.12.2 Spatial Units of Measure (IQ/SQL Anywhere)

Spatial units of measure define the units in which geographic coordinates are measured and how these units are converted to radians or meters.

Context

Spatial data are supported for IQ v15.4 and higher and SQL Anywhere v12 and higher. PowerDesigner models spatial units of measure as extended objects with a stereotype of `<<SpatialUnitOf Measure>>`, and lists them under the [Model](#) menu and in the [Spatial Units of Measure](#) folder under the model in the Browser.

Procedure

1. Select to access the [List of Spatial Units of Measure](#), click the [Add a Row](#) tool, and then click the [Properties](#) tool (or right-click the model or a package in the Browser, and select .
2. Enter the following properties in the [General](#) tab:

Name	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the Code field.
Type	Specifies the kind of unit. Linear units are used for distances and angular units are used for angles. Scripting name: <code>Type</code>
Conversion factor	Specifies how to convert the defined units to the base unit of measure (radians or meters). Scripting name: <code>ConversionFactor</code>

2.14.13 Full Text Searches (IQ/SQL Anywhere)

Full text search can quickly find all instances of a term (word) in a database without having to scan table rows and without having to know which column a term is stored in. IQ (v15.2 and higher) and SQL Anywhere support full text searches through text configurations and text indexes, which store complete positional information for every instance of every term in every indexed column.

2.14.13.1 Text Configurations (IQ/SQL Anywhere)

Text configuration objects are supported for IQ (v15.2 and higher) and SQL Anywhere (v12 and higher) to control the creation of text indexes. PowerDesigner models text configurations as extended objects with a stereotype of <<TextConfiguration>>.

Text configurations contain a set of configuration settings that control the characteristics of text index data such as what terms to ignore, and the minimum and maximum length of terms to include in the index. Once you have created a text configuration, you can select it to control a text index on the [SAP IQ/SQL Anywhere/Sybase](#) tab of your text index property sheet (see [Text Indexes \(IQ/SQL Anywhere\) \[page 594\]](#)).

Creating a Text Configuration

You can create a text configuration in any of the following ways:

- Select to access the List of Text Configurations, and click the *Add a Row* tool.
- Right-click the model (or a package) in the Browser, and select .

Text Configuration Properties

You can modify an object's properties from its property sheet. To open a text configuration property sheet, double-click its Browser entry in the Text Configurations folder.

The following extended attributes are available on the *General* tab:

Name	Description
Owner	Specifies the owner of the text configuration. Use the tools to the right of the field to create or choose an owner or to delete or inspect the properties of the current owner. Scripting name: Owner
Template	Specifies a text configuration to use as the template for creating this one. Scripting name: ParentConfiguration

The following extended attributes are available on the *SAP IQ/SQL Anywhere/Sybase* tab:

Name	Description
Minimum/Maximum Term Length	Specify the minimum and maximum length in characters of terms that will be included in the index. Scripting name: <code>MinTermLength</code> , <code>MaxTermLength</code>
Term breaker	Specifies the name of the algorithm to use for separating column values into terms. Scripting name: <code>TermBreaker</code>
Stoplist	Specifies terms to ignore when building a text index. Scripting name: <code>StopList</code>

2.14.13.2 Text Indexes (IQ/SQL Anywhere)

Text indexes are supported for IQ (v15.2 and higher) and SQL Anywhere (v12 and higher) to enable fast full text searching.

You create a text index by creating a standard index (see [Creating Standard, Key, or Function-Based Indexes \[page 120\]](#)), and selecting the type `TEXT`. For information about the properties specific to text indexes, see [SAP IQ \[page 571\]](#).

2.14.14 Indexes (IQ)

Before creating IQ indexes, you should consider the implications of various types of indexes on the database server memory and disk space. The set of indexes you define for any given column can have dramatic impact on the speed of query processing.

There are four main criteria for choosing indexes:

- Number of unique values
- Types of queries
- Disk space usage
- Data types

You should consider all criteria in combination, rather than individually. Try to anticipate for the data in each column, the number of unique and total values, the query results users will want, and whether the data will be used in ad hoc joins or join indexes.

The following types of index are available:

- HG – HighGroup indexes are used for `GROUP BY`, `COUNT (DISTINCT)` and `SELECT DISTINCT` statements when data has more than 1000 unique values
- HNG – HighNonGroup indexes make equality comparisons, `SUM` and `AVG` calculations very fast when data has more than 1000 unique values. Nonequality comparisons can also be done

- **LF** – LowFast indexes are used for columns that have a very low number of unique values. This index also facilitates join index processing ([Join Indexes \(IQ/Oracle\) \[page 597\]](#)). It is one of the two indexes allowed for columns used in join relationships.
- **CMP** – Compare indexes are used for columns that store the binary comparison (<, >, or =) of any two distinct columns with identical data types, precision, and scale.
- **TEXT** – Full text indexes (see [Full Text Searches \(IQ/SQL Anywhere\) \[page 593\]](#)).
- **WD** – Used to index keywords by treating the contents of a CHAR or VARCHAR column as a delimited list.
- **DATE, TIME, and DTTM** – For date and timestamp columns.

For detailed information about choosing index types, see your IQ documentation.

2.14.14.1 Rebuilding IQ Indexes

As you develop a PDM or modify an existing one, you may change data types, alter the percentage of distinct values or change the number of values in tables. You must then rebuild the IQ indexes to reflect these changes.

Context

When you rebuild indexes, PowerDesigner determines the index type based on information contained from the table statistics, using the number field, which indicates the estimated number of records per table, and the percentage of distinct values to compute the number of unique values. If you have not specified a number of rows for the table, PD assumes that the table will include at least 1 row of data.

The rebuild process creates a FASTPROJECTION index for all columns, unless any of the following criteria apply:

Criteria	Index type
If no statistics are provided and the column has an undefined data type	No index is created
Low number of unique values in a column	LOWFAST
Column used in join predicate	
High number of unique values in a column	HIGHNONGROUP
No COUNT DISTINCT, SELECT DISTINCT, or GROUP BY queries required	
Column used in join predicate	HIGHGROUP
High number of unique values in a column (more than 1000)	
Anticipate COUNT DISTINCT, SELECT DISTINCT, or GROUP BY queries	
Column must enforce uniqueness	
Column without numeric datatype	No index is created
Column with date type	DATE


Criteria	Index type
Column with time type	TIME
Column with datetime or smalldatetime type	DTTM

For example (IQ v12.5, Table A contains 1500 rows)

Column	% Distinct values	Unique values	Rebuild indexes generates
Col_1 integer	100	1500	HG index
Col_2 integer	50	750	LF index
Col_3 integer	0	0	no index
Col_4 char (10)	100	1500	no index
Col_5 char (10)	50	750	LF index

Procedure

1. Select **Tools > Rebuild Objects > Rebuild Indexes** to open the *Rebuild Indexes* dialog box:



2. Select a default name to generates IQ indexes. You can use the following variables:

- %COLUMN% - Column name
 - %INDEXTYPE% - Type of index to be rebuilt
 - %TABLE% - Name or code of table (based on display preferences)
3. Specify a mode to use. You can choose between:
 - *Delete and Rebuild* - All existing indexes are deleted before index rebuild
 - *Preserve Indexes* - Preserves all existing indexes
 4. [optional] Select the *Include HNG and DATE/TIME indexes* option to permit the creation of these specialized indexes for appropriate columns. If you do not select this option then only HG and LF indexes will be created.
 5. [optional] Select the *Update statistics before rebuild* option to update such statistics as the number of records in a table and the number of distinct values in a column before performing the rebuild. Selecting this option can help with optimizing the rebuild.
 6. [optional] Click the *Selection* tab and select or clear checkboxes to specify for which tables you want to rebuild indexes.
 7. Click *OK*, and then *Yes* to confirm the rebuilding of your indexes.

2.14.15 Join Indexes (IQ/Oracle)

A join index is a special type of index, which represents a full outer join of two or more tables, where all rows from both tables are included in the result (with NULL returned for any column with no matching value). The query engine may use this full outer join as a starting point for queries that include left outer, right outer, and inner joins.

Join indexes are defined from references. You can create a join index for any set of columns that your users commonly join to resolve queries.

While some references are based on keys, IQ allows you to create user-defined references to include the exact join required by your foreseen queries.

Creating a Join Index

You can create a join index in any of the following ways:

- Open the property sheet of a table, click the *Join Index* tab, and click the *Add a Row* tool. The join index is created with the selected table specified as the base table.
- Select and click the *Add a Row* tool.
- Right-click the model or package in the Browser, and select
- Automatically, for each fact table and the dimension table it references by selecting (see [Automatically Creating Join Indexes Through Rebuilding \[page 598\]](#)).

Join Index Properties

You can modify an object's properties from its property sheet. To open a join index property sheet, double-click its Browser entry in the Join Indexes folder.

The *General* tab contains the following properties:

Property	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Stereotype	Extends the semantics of the object. You can enter a stereotype directly in this field, or add stereotypes to the list by specifying them in an extension file.
Owner	Specifies the user who is the owner of the join index (usually its creator). Use the tools to the right of the list to create, browse for, or view the properties of the currently selected object.
Comment	Descriptive label for the join index.
Base table	Specifies the name of the table or materialized view that stores the join index.
DBSpace	[IQ only] Specifies the DBSpace that will contain the join index.


The following tabs are also available:

- Columns - Lists the columns used for the join index.
- References - Lists the references used for the join index.

2.14.15.1 Automatically Creating Join Indexes Through Rebuilding

You can automatically generate a join index for each selected fact table and the dimension tables that it references. Each rebuilt join index contains the references that link the fact table to all the dimension tables located on a single axis proceeding from the fact table.


Context



A join index is constrained and can only be defined for tables that are organized in a connected tree. A reference between two fact tables does not generate any join index.

Procedure

1. Select **Tools > Rebuild Objects > Rebuild Join Indexes** to open the Rebuild Join Indexes dialog.
2. On the *General* tab, select the appropriate mode to use:
 - *Delete and Rebuild* - all existing indexes are deleted before join index rebuild.
 - *Preserve* - preserves all existing join indexes
3. Click the *Selection* tab, and select one or more fact tables from the list:



4. Click **OK**, and then **Yes** to confirm the rebuild.

A join index is generated for each fact table. The generated join indexes are available in the list of join indexes (select **Model > Join Indexes**).

2.14.15.2 Adding References to a Join Index

You can add a reference to any join index. You do this, for example, when you create a new reference that you want to include in an existing join index.

Procedure

1. Open the property sheet of the join index and, if necessary, specify the appropriate base table and DBSpace on the **General** tab.
2. Click the **References** tab, and click the **Add References** tool to open a selection box listing all the available references in the PDM. Select the appropriate references in the list and click **OK** to add them to the join index.
3. Click **OK** to save your changes and return to the model.

2.14.16 IQ Data Movement Scripts

PowerDesigner can generate data movement scripts to populate your AS IQ data warehouse from other databases. The script can generate a flat file for loading to the IQ data warehouse and create Insert Location statements for use with a proxy database (for ASE and ASA only).

Context

To create a data movement script, you must:

- [optional] Specify mappings between the tables in your data source and your AS IQ database
- Generate the data movement script

Procedure

1. To enable the Data Movement extensions in your model, select ► *Model* ► *Extensions*, click the *Attach an Extension* tool, select the *Data Movement IQ* (on the *General Purpose* tab), and click *OK* to attach it.
2. Right-click the model in the Browser and select *Properties* to open its property sheet, then click the *Data Movement* tab and set the following properties as appropriate to control the files used during data movement:

Property	Description
Field / Row delimiter	Specify the delimiters to be used between fields and between rows in the dump file.
Fully delimited file	Specifies that each row ends with a field delimiter before the row delimiter.
Maximum image or text size	Specifies the maximum length of an image (or text) record, to which it will be truncated if necessary.
Load file directory	Specifies the directory where the load file is located.

i Note

You can override these global data movement options for a specific table (and specify a table-specific dump file for importing) by opening its property sheet and enter table-specific values on the *Data Movement* tab.

3. In your IQ warehouse PDM, right-click the model in the Browser and select ► *New* ► *Data Source* to create a data source to populate your IQ Data Warehouse. Enter a name for the source and then click the *Models* tab, click the *Add Models* tool, and select your source model.
4. Click the data source *Database Connection* tab, and select a data source, login, and password to connect to your source database.
5. Click the data source *Data Movement* tab, and enter the following properties as appropriate to access the remote server:

Property	Description
Remote server name	Specifies the name of the remote server used in the interface file for IQ server.
Remote database name	Specifies the name of the remote database.
Data source name	Specifies the label given to the data source in the sql.ini file.
Dump file directory	Specifies the directory where the 'dump' file (external flat file), that contains the data to be imported, will be created.
Local user name	Specifies the database user name.

6. [optional] Select  *Tools*  and create mappings between your source and warehouse tables.

For detailed information about using the Mapping Editor, see *Core Features Guide > Linking and Synchronizing Models > Object Mappings*.

2.14.16.1 Generating the Data Movement Script

You can generate the data movement script from the *Tools* menu.

Procedure

1. Select  *Tools* , and specify a directory in which to generate your data movement files.
2. [optional] Click the *Selection* tab and specify for which tables and/or data sources you want to generate a data movement script.
3. [optional] Click the *Options* tab and specify the following generation options as appropriate:
 - *Use Mappings* – Specifies to use mappings to control the data movement.
 - *Data Movement Method* – Specifies the type of script to generate:
 - *Insert Location* – [IQ or ASE only] Create a loadscript for connecting the source database to the IQ server. If the data source is not an IQ or ASE database, then no loadscript will be generated.
 - *External File* – Create a dump file from the source database together with a loadscript to upload it to the IQ server.
4. [optional] Click the *Generated Files* tab to review the names and locations of the files to be generated.
5. Click *OK* to begin the generation of the data movement script.

2.15 SAP SQL Anywhere

To create a PDM with support for features specific to the SAP® SQL Anywhere® (formerly AS Anywhere) DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select and expand the *Profile* node.

Note

The DBMS definition files for AS Anywhere/ SQL Anywhere v9 and v10 are deprecated.

The following sections list the extensions provided for SQL Anywhere.

Note

We do not provide documentation for the properties on the *Physical Options* and certain other tabs, though minimal information is available for them in the Resource Editor. For information about these properties, consult your DBMS reference documentation.

Columns

The following extensions are available on the *SQL Anywhere/Sybase* tab (v10 and higher):

Name	Description
Column is compressed	Specifies whether this column is stored in a compressed format. Scripting name: Compressed

Tables

The following extensions are available on the *SQL Anywhere/Sybase* tab:

Name	Description
PCTFREE	<p>Specifies the percentage of free space to reserve for each table page. If there is no free space in a table page, every increase in the size of a row on that page requires the row to be split across multiple table pages, causing row fragmentation and possible performance degradation.</p> <p>Enter an integer between 0 (no free space is to be left on each page) and 100 (high values cause each row to be inserted into a page by itself. If PCTFREE is not set, 200 bytes are reserved in each page).</p> <p>Scripting name: <code>PctFree</code></p>
Dbspace (tablespace)	<p>Specifies the dbspace in which the table is to be created</p> <p>Scripting name: <code>DbspaceIn</code></p>
Remote location	<p>Creates a table at the specified remote location in addition to a proxy table on the current database that maps to the remote table. Supports the semicolon (:) as a field delimiter in the location-string. If no semicolon is present, a period is the field delimiter.</p> <p>Scripting name: <code>At</code></p>
Encrypted	<p>Encrypts the table using the encryption key and algorithm specified at database creation time. Encrypting a table may take time, depending on the size of the table.</p> <p>Scripting name: <code>Encrypted</code></p>
Temporary table/Global temporary table	<p>Specifies either temporary table is a global or a local temporary table.</p> <p>Scripting name: [v10 and higher] <code>TemporaryTable</code>, [up to v9] <code>ExtGlobalTemporaryTable</code></p>
Not transactional	<p>[temporary tables] Specifies that the temporary table is not affected by either COMMIT or ROLLBACK. This can provide performance improvements because operations on non-transactional temporary tables do not require entries in the rollback log. For example, NOT TRANSACTIONAL may be useful if procedures that use the temporary table are called repeatedly with no intervening COMMITS or ROLLBACKS.</p> <p>Scripting name: <code>TemporaryTableOptionsNotTransactional</code></p>
On commit	<p>[temporary tables] Specifies that the rows of a temporary table are deleted on COMMIT.</p> <p>Scripting name: <code>TemporaryTableOptionsOnCommit</code></p>

Indexes

The following extensions are available on the *SQL Anywhere/Sybase* tab:

Name	Description
Tablespace	[Non-text indexes] Specifies the index dbspace. Scripting name: <code>In</code>
Virtual index	[v10 and higher] The VIRTUAL keyword is primarily for use by the Index Consultant. A virtual index mimics the properties of a real physical index during the evaluation of query plans by the Index Consultant and when the PLAN function is used. You can use virtual indexes together with the PLAN function to explore the performance impact of an index, without the often time consuming and resource consuming effects of creating a real index. Scripting name: <code>Virtual</code>
Notify	[Non-text indexes v12 and higher] Gives notification messages after n records are successfully added for the index. Scripting name: <code>Notify</code>
Word length	[Non-text indexes v12 and higher] Specifies the maximum word length that is permitted. Scripting name: <code>Limit</code>
Delimited by	[Non-text indexes v12 and higher] Specifies separators to use in parsing a column string into the words to be stored in the index. Scripting name: <code>DelimitedBy</code>
Text index	[v12 and higher] Specifies whether the index is a text index or not. Scripting name: <code>TextIndex</code>
Configuration	[Text indexes v12 and higher] Specifies the text configuration (see Text Configurations (IQ/SQL Anywhere) [page 593]) to be used to control the building of the text index. Scripting name: <code>Configuration</code>
Immediate refresh	[Text indexes v12 and higher] Specifies that the index is refreshed immediately each time data is written to the table. Scripting name: <code>Refresh</code>

Users

The following extensions are available on the [General](#) tab (v12 and higher):

Name	Description
Force change	Controls whether the user must specify a new password when they log in. This setting overrides the password_expiry_on_next_login option setting in the login policy. Scripting name: ForcePasswordChange
Login policy	Specifies the login policy to assign to the user (see Login Policies (IQ/SQL Anywhere) [page 585]). Scripting name: LoginPolicy

Web Services

The following extensions are available on the [SQL Anywhere/Sybase](#) tab (v9 and higher):

Name	Description
Port number	Specifies the web service port number. Scripting name: PortNumber
Server name	Specifies the web service server name. Scripting name: ServerName
Name prefix	[DISH service type] Specifies a name prefix. Only SOAP services whose names begin with this prefix are handled. Scripting name: Prefix

Web Operations

The following extensions are available on the [SQL Anywhere/Sybase](#) tab (v9 and higher) when the service type is not dish:

Name	Description
URL	Determines whether URI paths are accepted and, if so, how they are processed. Scripting name: Url

2.15.1 Auto-Increment Columns

Auto-increment columns are equivalent to identity columns in those DBMS that support identity columns.

If you switch from SQL Anywhere to a DBMS that supports identity columns, the Identity checkbox will be selected for each auto-increment column. On the other hand, if you switch to SQL Anywhere, identity columns will be assigned the autoincrement default value.

When you reverse engineer a script containing identity columns (using ASE-compatible syntax), these are automatically converted into auto-increment columns in SQL Anywhere.

2.15.2 Mirror Servers (SQL Anywhere)

SQL Anywhere supports database mirroring through the use of mirror servers.

Context

Mirror servers are supported from v12 and higher. PowerDesigner models mirror servers as extended objects with a stereotype of <>MirrorServer<>, and lists them under the *Model* menu and in the *Mirror Servers* folder under the model in the Browser.

Procedure

1. Select to access the *List of Mirror Servers*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *Options* tab:

Name	Description
Type	<p>Specifies the type of mirror server to create. You can choose between:</p> <ul style="list-style-type: none"> ○ Primary - defines a virtual or logical server, whose name is the alternate server name for the database, which can be used by applications to connect to the server currently acting as the primary server. There can be only one PRIMARY server for a database. ○ Mirror - defines a virtual or logical server, whose name is the alternate server name for the database, which can be used by applications to connect to the server currently acting as the read-only mirror. There can be only one MIRROR server for a database. ○ Arbiter - assists in determining which of the PARTNER servers takes ownership of the database. The arbiter server must be defined with a connection string that can be used by the partner servers to connect to the arbiter. There can be only one ARBITER server for a database. ○ Partner - is eligible to become the primary server and take ownership of the database. You must define two PARTNER servers for database mirroring, and both must have a connection string and a state file. In a read-only scale-out system, you must define one PARTNER server. This server is the root server, and runs the only copy of the database that allows both read and write operations. ○ Copy - In a read-only scale-out system, this value specifies that the database server is a copy node. All connections to the database on this server are read-only. You do not have to explicitly define copy nodes for the scale-out system; you can choose to have the root node define the copy nodes when they connect. <p>Scripting name: Type</p>
Using auto parent	<p>[Copy only] Specifies that the primary server will assign a parent for this server.</p> <p>Scripting name: UsingAutoParent</p>
Parent	<p>[Copy only] Specifies a tree of servers for a mirroring or scale-out system and indicates the servers from which the non-participating nodes obtain transaction log pages.</p> <p>Scripting name: ParentServer</p>
Alternate parent	<p>[Copy only] Specifies an alternate parent for the copy node.</p> <p>Scripting name: AlternateParentServer</p>
Primary	<p>[Copy only] Specifies that the parent server is the primary server.</p> <p>Scripting name: PrimaryParentServer</p>
Connection string	<p>Specifies the connection string to be used to connect to the server.</p> <p>Scripting name: ConnectionString</p>
Log file	<p>Specifies the location of the log file that is sent between mirror servers.</p> <p>Scripting name:LogFile</p>

Name	Description
Preferred	[Partner only] Specifies whether the server is the preferred server in the mirroring system, which assumes the role of primary server whenever possible. Scripting name: Preferred
State file	[Arbiter, Partner] Specifies the location of the file used for maintaining state information about the mirroring system. Scripting name: StateFile

2.15.3 Spatial Data (SQL Anywhere)

SQL Anywhere (v12 and higher) can store spatial data (data that describes the position, shape, and orientation of objects in a defined space) using spatial reference systems.

For more information, see [Spatial Data \(IQ/SQL Anywhere\) \[page 589\]](#).

2.15.4 Events, Login Policies, and Full Text Searches (SQL Anywhere)

PowerDesigner supports modeling for SQL Anywhere events (v10 and higher), login policies (v12 and higher), and full text searches (v12 and higher).

For detailed information, see [Events \(IQ/SQL Anywhere\) \[page 577\]](#), [Login Policies \(IQ/SQL Anywhere\) \[page 585\]](#), and [Full Text Searches \(IQ/SQL Anywhere\) \[page 593\]](#).

2.15.5 Certificates (SQL Anywhere)

SQL Anywhere supports X.509 certificates for transport-layer security.

Context

Certificates are supported from v16.0 and higher. PowerDesigner models certificates as extended objects with a stereotype of <<Certificate>>, and lists them under the [Model](#) menu and in the [Certificates](#) folder under the model in the Browser.

Procedure

1. Select to access the *List of Certificates*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *General* tab:

Name	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Type	Specifies the type of the certificate, which can be a string, variable, or file. Scripting name: <code>CertificateSourceType</code>
Certificate	Specifies the source of the certificate. Scripting name: <code>CertificateSource</code>

2.15.6 Proxy Tables (ASE/SQL Anywhere)

A proxy table is used to access data in a remote table; it has all the attributes of the remote table, but does not contain any data locally. PowerDesigner uses an extension file to provide support for generating the script for a proxy table in order to run it in an ASE or SQL Anywhere database.

Procedure

1. To enable the proxy table extensions in your model, select , click the *Attach an Extension* tool, select the Proxy Tables file (on the *General Purpose* tab), and click *OK* to attach it.
2. For each proxy table, right-click a table in another PDM target model, drag it to the model where you want to create a proxy table, release the right mouse button and select one of the following:
 - o *Create Shortcut Here* - Creates a non-modifiable reference to the original table.
 - o *Replicate Here* - Creates a modifiable reference to the original table. You can desynchronize the *Code* property of the replica to give the proxy table a different name in the local model.

For more information about shortcuts and replicas, see *Core Features Guide > Linking and Synchronizing Models > Shortcuts and Replicas*.

Note

A custom check verifies that the proxy table is not the child table of a reference.

3. Right-click the model in the browser and select ► *New* ► *Data Source* to create a new data source to provide access to the remote tables on the server, and ensure that the *GenerateAsProxyServer* property on the *Extended Attributes* tab is set to *True*.

i Note

A single data source can contain information for several models if they represent a single remote server.

4. Add the models from which you have drawn your proxy tables in the *Models* tab.
5. Click the *Database Connection* tab, and define the data source name, login and password and click *OK* to return to your model.

2.15.6.1 Generating the Remote Server and Proxy Tables Creation Scripts

You can generate the remote server and proxy tables creation scripts from the model containing proxy tables in order to run them in the database.

Procedure

1. Select ► *Tools* ► *Proxy Tables* ► *Generate Proxy Tables* to open the Generation dialog, and click the *Options* tab.
2. Set an appropriate value for the *UserReplica* and *UserShortcut* options to allow you to generate the proxy tables corresponding to replica and/or external shortcuts.
3. Set the *Generate proxy servers* option to *True* to generate proxy servers. You can deselect any proxy servers you do not want to generate.
4. Click *OK* to begin generation.

The generated script is displayed in the Result dialog.

5. [optional] Double-click the generated SQL file or click the *Edit* button to open the script in a text editor.
6. Run the script on your database in order to create the proxy tables.

2.16 Teradata

To create a PDM with support for features specific to the Teradata DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select ► *Database* ► *Edit Current DBMS* and expand the *Profile* node.

i Note

The DBMS definition files for Teradata V2R5 and V2R6 are deprecated.

The following sections list the extensions provided for Teradata.

Abstract Data Types

The following extensions are available on the [Teradata](#) tab (V2R6 and higher):

Name	Description
Predefined data type	[type:distinct] Indicates that character column comparison uses character case (upper and lower) to raise differences. Scripting name: PredefinedDataType
Dimension	[v14 and higher, type:array] Specifies the dimension(s) of the array as [n1] [n2] Scripting name: Dimension
Nullify	[v14 and higher, type:array] Initializes all of the elements of array_type_name to null when the type is constructed. Scripting name: DefaultNull

Abstract Data Type Procedures

The following extensions are available on the [Teradata](#) tab if the type is distinct (V2R6 and higher):

Name	Description
Return data type	Specifies the name of the data type returned by the method, which can be either a predefined data type or a UDT. Scripting name: ReturnDataType
Self as result	Specifies that the method is type-preserving. If so, then the data type specified in the RETURNS clause for the method must have the same name as UDT_name. Scripting name: SelfAsResult
As locator	Specifies that BLOB and CLOB types must be represented by a locator. The Teradata Database does not support in-memory LOB parameters: an AS LOCATOR phrase must be specified for each LOB parameter and return value. Scripting name: ReturnAsLocator
Character set	Specifies the CHARACTER SET clause for character data type. Scripting name: ReturnCharSet

Name	Description
Cast data type	Specifies a computed attribute that show the datatype and its length and precision. Scripting name: CastDataTypeDisplay
As locator	Specifies that BLOB and CLOB types must be represented by a locator. Scripting name: CastAsLocator
Specific method name	Specifies the specific name of the method whose signature is being added to the type definition for UDT_name. Scripting name: SpecificMethodName
Parameter style	Specifies the parameter style for the method defined by this signature. Scripting name: ParameterStyle
Returns null on null input	Specifies that the method defined by this signature is not called if any of the arguments passed to it is null. Instead, it returns a null. Scripting name: ReturnsNullOnNullInput
Deterministic	Specifies that the result of invoking the method defined by this signature is deterministic. Scripting name: Deterministic
Glop set	[v13 and higher]Specifies the glop set with which the method is associated. Scripting name: GlopSet
Language	Specifies the language (either C or C++) used to write the source code for the method defined by this signature. Scripting name: Language

Columns

The following extensions are available on the *Teradata* tab:

Name	Description
Character set	Specifies the character set to be used. Scripting name: CharacterSet
Case specific	Specifies that character column comparison is case-sensitive. Scripting name: CaseSpecific

Name	Description
Compress	<p>[v15 and higher] Compresses specified values and nulls in one or more columns of a table to zero space. When the data in a column matches a value specified in the COMPRESS phrase, then that value is stored only once in the table header regardless of how many times it occurs as a field value for the column, thus saving disk storage space.</p> <p>Attribute must be enclosed in parenthesis when it is composed of multiple values.</p> <p>Scripting name: Compress</p>
Multi-value compression	<p>[v15 and higher] Specifies if the compression is multi-valued.</p> <p>Scripting name: Compress</p>
Compress using	<p>[v15 and higher] Specifies that compress_udf_name is the name of the UDF to be used to compress CHARACTER, GRAPHIC, or BYTE data in this column algorithmically.</p> <p>Scripting name: CompressUsing</p>
Decompress using	<p>[v15 and higher] Specifies that decompress_udf_name is the name of the UDF to be used to decompress character, graphic, or byte data in this column algorithmically.</p> <p>Scripting name: DecompressUsing</p>
Always generate value	<p>Specifies that identity column values are always system-generated. You cannot insert values into, nor update, an identity column defined as <code>GENERATED ALWAYS</code>.</p> <p>If not selected, identity column values are system-generated unless the user does not enter a non-null value.</p> <p>Scripting name: ExtGenAlways</p>
Partition	<p>[v15 and higher] Specifies the partition to which the column is assigned.</p> <p>Scripting name: ExtGenAlways</p>

Databases

The following extensions are available on the *Teradata* tab:

Name	Description
Owning database	<p>Specifies the name of the immediate owning user or database. The default is the user name associated with the current session.</p> <p>Scripting name: FromDatabaseName</p>
Account	<p>Specifies the account ID identifiers.</p> <p>Scripting name: Account</p>

Name	Description
Fallback	Specifies whether to create and store a duplicate copy of each table created in the new database. Scripting name: <code>Fallback</code>
Journal	Specifies the number of before change images to be maintained by default for each data table created in the new database. Scripting name: <code>Journal</code>
After journal	Specifies the type of image to be maintained by default for data tables created in the new database. Scripting name: <code>AfterJournal</code>
Default journal table	Specifies the default table that is to receive the journal images of data tables created in the new database. Scripting name: <code>DefaultJournalTable</code>
Permanent	Specifies the number of bytes to be reserved for permanent storage of the new user database. The space is taken from unallocated space in the database of the immediate owner. Scripting name: <code>PermanentSpace</code>
Spool	Specifies the number of bytes (n) to be allocated for spool files. The default is the largest value that is not greater than the owner spool space, and that is a multiple of the number of AMPs on the system. Scripting name: <code>SpoolSpace</code>
Temporary	Specifies how much space (in bytes) is to be allocated for creating temporary tables by this user. Note that temporary space is reserved prior to spool space for any user defined with this characteristic. Scripting name: <code>TemporarySpace</code>

Indexes

The following extensions are available on the *Teradata* tab:

Name	Description
Primary Index	Specifies that the index is the primary index. Scripting name: <code>PrimaryIndex</code>

Name	Description
Partition by	[primary key] Lets you select the used function to evaluate partition condition. <ul style="list-style-type: none"> case_n: Evaluates a list of conditions and returns the position of the first condition that evaluates to TRUE, provided that no prior condition in the list evaluates to UNKNOWN. range_n: Evaluates an expression and maps the result into one of a list of specified ranges and returns the position of the range in the list. Scripting name: PartitionBy
Partition expression	[primary key] Specifies an SQL expression used to define the partition to which a partitioned primary index row is assigned when it is hashed to its AMP. Scripting name: PartitionExpression
Ordering type	[not primary key] Select VALUES to optimize queries that return a contiguous range of values, especially for a covering index or a nested join. Select HASH to limit hash-ordering to one column, rather than all columns (the default) Scripting name: OrderingType
Column	[not primary key] Row ordering on each AMP by a single NUSI column: either value-ordered or hash-ordered. Scripting name: OrderByColumnList
All	Specifies that a NUSI should retain row ID pointers for each logical row of a join index (as opposed to only the compressed physical rows). Scripting name: AllIndex
Index has name	Specifies that the index will be generated with its name (as Teradata allows index with no name). Scripting name: NamedIndex

References

The following extensions are available on the *General* tab:

Name	Description
Check option	Specifies if the constraint is to be validated or not. Scripting name: CheckOption

Tables

The following extensions are available on the [Teradata](#) tab:

Name	Description
Type	<p>Specifies whether the table to be created is a global temporary table or a volatile table:</p> <ul style="list-style-type: none">• GLOBAL TEMPORARY - a temporary table definition is created and stored in the data dictionary for future materialization. You can create global temporary tables by copying a table WITH NO DATA, but not by copying a table WITH DATA.• VOLATILE - specifies that a volatile table be created, with its definition retained in memory only for the course of the session in which it is defined. <p>Scripting name: <code>GlobalTemporary</code></p>
Commit row action	<p>Specifies the action to take with the contents of a global temporary table when a transaction ends:</p> <ul style="list-style-type: none">• DELETE - clears the temporary table of all rows.• PRESERVE - retains the rows in the table after the transaction is committed. <p>Scripting name: <code>CommitRowAction</code></p>
Duplicate row control	<p>Controls the treatment of duplicate rows. If there are uniqueness constraints on any column or set of columns in the table definition, then the table cannot have duplicate rows even if it is declared as MULTISET. Some client utilities have restrictions with respect to MULTISET tables.</p> <p>Scripting name: <code>SetOrMultiset</code></p>
Primary index	<p>Specifies the primary index of the table (see Primary Indexes (Teradata) [page 622]).</p> <p>Scripting name: <code>PrimaryIndex</code></p>
Partition	<p>Specifies the partition SQL for the table.</p>

Users

The following extensions are available on the [Teradata](#) tab :

Name	Description
Owner	<p>Specifies the database (or user) that owns the current user.</p> <p>Scripting name: <code>DBOwner</code></p>
Permanent	<p>Specifies the number of bytes to be reserved for permanent storage of the new user database. The space is taken from unallocated space in the database of the immediate owner.</p> <p>Scripting name: <code>PermanentSpace</code></p>

Name	Description
Spool	<p>Specifies the number of bytes (n) to be allocated for spool files. The default is the largest value that is not greater than the owner spool space, and that is a multiple of the number of AMPs on the system.</p> <p>Scripting name: SpoolSpace</p>
Temporary	<p>Specifies how much space (in bytes) is to be allocated for creating temporary tables by this user. Note that temporary space is reserved prior to spool space for any user defined with this characteristic.</p> <p>Scripting name: TemporarySpace</p>
Account	<p>Specifies the account ID identifiers.</p> <p>Scripting name: Account</p>
Fallback	<p>Specifies whether to create and store a duplicate copy of each table created in the new database.</p> <p>Scripting name: Fallback</p>
Journal	<p>Specifies the number of before change images to be maintained by default for each data table created in the new database.</p> <p>Scripting name: Journal</p>
After journal	<p>Specifies the type of image to be maintained by default for data tables created in the new database.</p> <p>Scripting name: AfterJournal</p>
Default table	<p>Specifies the default table that is to receive the journal images of data tables created in the new database.</p> <p>Scripting name: DefaultJournalTable</p>
Database	<p>Specifies the default database name.</p> <p>Scripting name: DefaultDatabase</p>
Role	<p>Specifies the default role for the user.</p> <p>Scripting name: DefaultRole</p>
Character set	<p>Specifies the default character data type.</p> <p>Scripting name: DefaultCharacterSet</p>
Collation	<p>Specifies the default collation for this user.</p> <p>Scripting name: Collation</p>
Time zone	<p>Specifies the default time zone displacement for the user.</p> <p>Scripting name: TimeZone</p>

Name	Description
Date format	Specifies the default format for importing and exporting DATE values for the user. Scripting name: DateForm
Profile name	Specifies a profile to the user. Scripting name: Profile
Startup string	Specifies a startup string. Scripting name: Startup

Views

The following extensions are available on the *Teradata* tab:

Name	Description
Lock type	Specifies the type of lock to be placed. Scripting name: LockType
Locked object class	Specifies the type (class) of the object to be locked. Scripting name: LockedClass
Locked object	Specifies the name of the object to be locked. Scripting name: LockedObjt
No wait	Specifies that if the indicated lock cannot be obtained, the statement should be aborted. Scripting name: NoWait

2.16.1 Partitions (Teradata)

Teradata partitions allow you partition table data by range, case, or column.

Context

PowerDesigner models partitions as extended sub-objects with a stereotype of **Partition**.

Procedure

1. Open the property sheet of a table, select the *Partitions* tab and click the *Add a Row* tool. The *Partition* field on the *Teradata* tab is updated to reflect the partitions that you create.
2. Click the *Properties* tool to open the partition property sheet and enter the following properties in the *General* tab:

Name	Description
Table	<p>Specifies the parent table of the partition. Scripting name: ParentObject</p>
Type	<p>Specifies the type of the partition:</p> <ul style="list-style-type: none">○ Range n - Specify a range and interval in the <i>Expression</i> field.○ Case n - Specify criteria for the partition in the <i>Expression</i> field.○ Column - [if no primary index is defined on the table] Create objects in the <i>Column Groups</i> list, open their property sheets and associate columns with them. Select the <i>All but</i> option to create a single-column partition with autocompression and a system-determined COLUMN or ROW format for each column, if any, that is not specified in the column group list. Scripting name: PartitionType, AllBut
Expression	<p>Specifies the partitioning expression for partitions of type Range n or Case n. Scripting name: Expression</p>
Column Groups	<p>Lists the groups of columns that will be partitioned for partitions of type Column. Select an item in the list and click the <i>Properties</i> tool to define its type, and the columns of the parent table to which it applies. You can specify partitioning by:</p> <ul style="list-style-type: none">○ Row○ Column○ Auto - Teradata determines the optimum partitioning format. Select the <i>All but</i> option to compress data as physical rows that are inserted into that column partition of a column-partitioned table if an appropriate method can be calculated. Scripting name: PartitionColumns
Add	<p>Specifies that the maximum number of partitions for a partitioning level is the number of partitions it defines plus the value of the BIGINT constant value specified in this field. Scripting name: AddConstant</p>
Partition sql	<p>Specifies the SQL statement that defines the partition. You can enter SQL in this field to generate appropriate PowerDesigner objects or create the objects and have them generate the SQL in this field. Changes to objects or the SQL are synchronized with the other. Scripting name: Gen</p>

2.16.2 Transform Groups (Teradata)

A transform is a mechanism for creating an external representation of the UDT that is used when exporting and importing data between the client and the Teradata server. This mechanism allows most Teradata client utilities and open APIs to transparently move data to and from a UDT without the need for special logic or metadata.

Context

PowerDesigner supports replication groups for Teradata v13 and higher as extended objects with a stereotype of <<TransformGroup>>.

Procedure

1. Select **Model > Transform Groups** to access the *List of Transform Groups*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select **New > Transform Group**).
2. Enter the following properties in the *General* tab:

Name	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.

3. Enter the following properties in the *Teradata* tab:

Name	Description
UDT	Specifies the name of the user-defined type associated with the transform group. Scripting name: UDT
To sql with	Specifies the function name and parameters to be used as the tosql routine for this transform group, and whether or not it is specific. Scripting name: ToName, ToParms, ToSpecific

Name	Description
From sql with	<p>Specifies the method or function name and parameters to be used as the fromsql routine for this transform group, and whether or not it is specific and/or instantiable.</p> <p>Scripting name: <code>FromType</code>, <code>FromName</code>, <code>FromParms</code>, <code>FromSpecific</code>, <code>FromInstance</code>, <code>FromUDT</code></p>

2.16.3 Database Permissions (Teradata)

You can define multiple databases in a PDM for Teradata, and also define permissions on the database object.

For more information on permissions, see [Granting Object Permissions \[page 169\]](#).

2.16.4 Primary Indexes (Teradata)

In Teradata, users tend to use indexes rather than key constraints.

Procedure

1. Open the property sheet of an index from the Indexes tab of a table, or from the List of Indexes available by selecting .
2. Click the *Teradata* tab and select the *Primary Index* checkbox.
3. Click *OK* to close the index property sheet.

When a primary index is based on a key, it is automatically unique. You can make this primary index non-unique by detaching the index from the key. To do so, select <None> in the *Columns Definition* list in the *Columns* tab of the index property sheet, and set the *PrimaryIndex* extended attribute of the index to True.

Once defined, you can decide to generate indexes or keys in the SQL script, and you can also decide to generate them inside or outside the table creation script.

2.16.5 Error Tables (Teradata)

Teradata can record errors encountered when writing to a data table in an error table associated with the data table.

Context

Error tables are supported for Teradata v12 and higher. PowerDesigner models error tables as extended objects with a stereotype of <>ErrorTable<>.

Procedure

1. Select to access the *List of Error Tables*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *General* tab:

Name	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Owner	Specifies the name of the database containing the error table. Scripting name: Owner
Data table	Specifies the data table for which the error table is being created. Scripting name: DataTable
Use name at genera- tion	Specifies that the error table will be generated with its name. Scripting name: HasName

2.16.6 Join Indexes (Teradata)

Join indexes are materialized views that improve access times for cross-table queries, and which are automatically updated when changes are made to the underlying tables.

Context

Join indexes are supported for Teradata v12 and higher. PowerDesigner models join indexes as views with a stereotype of <>JoinIndex<>.

Procedure

1. Select **Model > Join Indexes** to access the *List of Join Indexes*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select **New > Join Index**).
2. Enter the following properties in the *General* tab:

Name	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Fallback	Specifies that the join index uses fallback protection. Scripting name: Fallback
Checksum	Enables a table-specific disk I/O integrity checksum level. The checksum setting applies to primary data rows, fallback data rows, and all secondary index rows for the index. Scripting name: Checksum

3. To complete the view, specify a view query (see [View Queries \[page 125\]](#)).

2.16.7 Hash Indexes (Teradata)

Hash indexes are designed to improve query performance like join indexes, but may in addition enable you to avoid accessing the base table.

Context

PowerDesigner supports replication groups for Teradata v12 and higher as extended objects with a stereotype of <>HashIndex<>.

Procedure

1. Select to access the *List of Hash Indexes*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *General* tab:

Name	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Table	Specifies the base table on which the hash index is defined. Scripting name: Table
Database	Specifies the name of the database containing the base table. By default the same as the database in which the hash index is created. Scripting name: Owner
Fallback	Specifies that the hash index uses fallback protection. Scripting name: Fallback
Checksum	Enables a table-specific disk I/O integrity checksum level. The checksum setting applies to primary data rows, fallback data rows, and all secondary index rows for the index. Scripting name: Checksum

3. Enter the following properties in the *Teradata* tab:

Name	Description
Columns	Specifies the base table columns on which the hash index is defined Scripting name: <code>Columns</code>
Distributed columns	Specifies an optional, explicitly specified column set on which the hash index rows are distributed across the AMPs. This is a subset of index column list. Scripting name: <code>ByColumns</code>
Order by columns	Specifies the row ordering on each AMP, which must be either value-ordered or hash-ordered. Scripting name: <code>OrderByColumns</code>
Ordering type	[if Order by columns are specified] Specifies the ordering type of the ORDER BY column. Scripting name: <code>OrderByType</code>

2.16.8 Glop Sets (Teradata)

Glop sets are sets of persistent data used in external procedures and functions.

Context

PowerDesigner supports glop sets for Teradata v13 and higher as extended objects with a stereotype of `<<GlopSet>>`.

Procedure

1. Select to access the *List of Glop Sets*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *General* tab:

Name	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.
Owner	Specifies the owner of the glop set. Scripting name: Owner

2.16.9 Replication Groups (Teradata)

Replication groups contain tables to be replicated.

Context

PowerDesigner supports replication groups for Teradata v13 and higher as extended objects with a stereotype of <>ReplicationGroup>>.

Procedure

1. Select to access the *List of Replication Groups*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select).
2. Enter the following properties in the *General* tab:

Name	Description
Name/Code/ Comment	Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.

Name	Description
List of tables	<p>Specifies the tables to be included in the replication group. You can enter table names here as a comma-separated list and on the <i>Tables</i> tab. Both lists are synchronized and if any table name does not currently exist in the model, then it will be created.</p> <p>Scripting name: TableList</p>

- Click the *Tables* tab and add or create tables to be included in the replication group.

2.16.10 Replication Rules and Rule Sets (Teradata)

Replication rules are patterns for matching table names to include in replication groups. Rules are collected into sets, which are in turn associated with replication groups.

Context

PowerDesigner supports replication rule sets and rules for Teradata v13 and higher as extended objects with a stereotype of <<ReplicationRuleSet>> and extended sub-objects with a stereotype of <<ReplicationRule>>.

Procedure

- Select to access the *List of Replication Rule Sets*, click the *Add a Row* tool, and then click the *Properties* tool (or right-click the model or a package in the Browser, and select *Replication Rule Set*).
- Enter the following properties in the *General* tab:

Name	Description
Name/Code/ Comment	<p>Identify the object. The name should clearly convey the object's purpose to non-technical users, while the code, which is used for generating code or scripts, may be abbreviated, and should not normally include spaces. You can optionally add a comment to provide more detailed information about the object. By default the code is generated from the name by applying the naming conventions specified in the model options. To decouple name-code synchronization, click to release the = button to the right of the <i>Code</i> field.</p>
Default	<p>Specifies that all the rules in the rule set are default rules.</p> <p>Scripting name: DefaultRules</p>

Name	Description
Replication group	Specifies the name of the replication group to which the rule set is assigned. Scripting name: ReplicationGroup

3. Click the *Patterns* tab and add patterns to the rule set with the following properties.

Name	Description
Object kind	Specifies the type of database object to be added to the replication rule set. Scripting name: ObjectKind
Like/And not like	Specifies pattern strings to match or exclude against the fully qualified names of the objects of certain SQL statements. The specified string literals can contain wildcard characters. Scripting name: LikeClause, NotLikeClause
Escape character	Specifies an escape character for the like and not like patterns. Scripting name: EscapeLike, EscapeNotLike
Sql	[property sheet only] Displays the SQL expression corresponding to the values entered in the other fields. Scripting name: Definition

2.17 Other Databases

The following sections list extensions to other DBMS families supported by PowerDesigner.

2.17.1 Informix SQL

To create a PDM with support for features specific to the Informix SQL DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select and expand the *Profile* node.

Note

The DBMSs for Informix v8-9 are deprecated.

The following sections list the extensions provided for Informix SQL.

Columns

The following extensions are available on the *Informix* tab:

Name	Description
Serial Start	Specifies the initial value of the column with a SERIAL datatype. Scripting name: ExtSerialStart

Indexes

The following extensions are available on the *Extended Attributes* tab:

Name	Description
IndexSpec	Specifies an internal index definition (indexkeys column). Scripting name: IndexSpec

Procedures

The following extensions are available on the *Extended Attributes* tab:

Name	Description
InternalID	Specifies an internal identifier in the server, which is used to retrieve the function of an index expression. Scripting name: InternalID

2.17.2 Ingres

To create a PDM with support for features specific to the Ingres DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select  *Database*  *Edit Current DBMS* and expand the *Profile* node.

The following sections list the extensions provided for Ingres.

Columns

The following extensions are available on the *Extended Attributes* tab:

Name	Description
NotDefault	Specifies that the column needs a value. This generates the "not default" clause in the sql statement. Scripting name: NotDefault

Users

The following extensions are available on the *Ingres* tab:

Name	Description
Default group	Specifies the default group the user belongs to. Scripting name: DefaultGroup
Expiration date	Specifies an optional expiration date associated with each user. Any valid date can be used. Once the expiration date is reached, the user is no longer able to log on. If the expire_date clause is omitted, the default is noexpire_date. Scripting name: ExpireDate
Limiting security label	Allows a security administrator to restrict the highest security label with which users can connect to Ingres when enforcing mandatory access control (MAC). Scripting name: LimitingSecurityLabel
Profile	Allows a profile to be specified for a particular user. If the profile clause is omitted, the default is noprofile. Scripting name: Profile
External password	Allows a user's password to be authenticated externally to Ingres. The password is passed to an external authentication server for authentication. Scripting name: ExternalPassword

2.17.3 Interbase

To create a PDM with support for features specific to the Interbase DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select  *Database*  *Edit Current DBMS*  and expand the *Profile* node.

The following sections list the extensions provided for Interbase.

Indexes

The following extensions are available on the *Interbase* tab:

Name	Description
Row sort	Defines that the default value of the index (ascending or descending) is defined on the index and not on the column. Scripting name: ExtAscDesc

Sequences

The following extensions are available on the *Interbase* tab:

Name	Description
First value	Specifies the sequence first value for Interbase generator. Scripting name: ExtStartWith
Increment value	Specifies the sequence increment value for Interbase generator. Scripting name: ExtIncrement

2.17.4 Microsoft Access

To create a PDM with support for features specific to the MS Access DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select   and expand the *Profile* node.

Note

The DBMS definition file for Microsoft Access 2000 is deprecated.

The following sections list the extensions provided for MS Access.

Columns

The following extended attributes are available on the *Access* tab:

Name	Description
Allow Zero Length	Specifies whether a zero-length string ("") is a valid entry in a table column. Applies only to Text, Memo, and Hyperlink table fields. Scripting name: ExtAllowZeroLength

2.17.4.1 Generating a Microsoft Access Database

PowerDesigner and MS Access use .dat files to exchange information. You must pass via the appropriate access<version> database delivered with PowerDesigner in order to convert the .dat files generated into Access database files.

Procedure

1. Select  *Database* > *Generate Database* to launch the standard Database Generation dialog (see [Generating a Database from a PDM \[page 298\]](#)), set any appropriate options, and click *OK*.
2. Open the appropriate access<version> database in the PowerDesigner \tools directory.
3. Select the *Generate Access database from script file* radio button and enter or select a destination database file in the *Select database* field.
4. Select the .dat file generated by PowerDesigner in the *Script file* field.
5. Click the *Create* button to create the database file, and then click the *Open MDB* button to open the generated database.

2.17.4.2 Reverse Engineering a Microsoft Access Database

PowerDesigner and MS Access use .dat files to exchange information. You must pass via the appropriate access<version> database delivered with PowerDesigner in order to convert an Access database file into the .dat file required by PowerDesigner.

Procedure

1. Open the appropriate access<version> database in the PowerDesigner \tools directory.

2. Select the *Reverse engineer Access database to script* radio button and select the database file to reverse in the *Select database* field.
3. Enter the .dat file to be generated in the *Script file* field.
4. Click the *Create* button to generate the .dat file and then reverse engineer this script in PowerDesigner (see [Reverse Engineering from Scripts \[page 323\]](#)).

2.17.5 MySQL

To create a PDM with support for features specific to the MySQL DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select *Database* *Edit Current DBMS* and expand the *Profile* node.

Note

The DBMSs for MySQL v3.22 and 3.23 are deprecated. In v4.0 the attributes listed below are available on the *Extended Attributes* tab.

Note that when developing for MySQL and using double quotes as a delimiter, it is necessary to set the sql_mode to ANSI_QUOTES:

```
SET sql_mode='ANSI_QUOTES'
```

The following sections list the extensions provided for MySQL.

Columns

The following extended attributes are available on the *MySQL* tab:

Name	Description
Retrieve with leading zeros	When displayed, the default padding of spaces is replaced with zeros. For example, for a column declared as INT(5) ZEROFILL, a value of 4 is retrieved as 00004. If you specify ZEROFILL for a numeric column, MySQL automatically adds the UNSIGNED attribute to the column. Scripting name: <code>ZeroFill</code>
Unsigned	Indicates negative values are not allowed for the column. Scripting name: <code>Unsigned</code>
National	A way to indicate that a CHAR column should use UTF8 character set. Scripting name: <code>National</code>

Name	Description
Character set	Set of symbols and encodings. Scripting name: CharSet
Collation	Set of rules for comparing characters in a character set. Scripting name: Collate

Indexes

The following extended attributes are available on the *MySQL* tab:

Name	Description
Full text index	Indicates that the index is a full text index. Scripting name: FullText

Keys

The following extended attributes are available on the *MySQL* tab:

Name	Description
Unique key	When set to True, indicates that the key is unique. False implies that the key allows duplicate values. Scripting name: ExtUnique

Models

The following extended attributes are available on the *MySQL* tab:

Name	Description
Database type	Indicates the type of the database, as specified in the extended attribute type DatabaseType. Scripting name: DatabaseType

References

The following extended attributes are available on the *MySQL* tab:

Name	Description
Reference match type	Indicates the reference match type, as specified in the extended attribute type ReferenceMatchType. Scripting name: ReferenceMatch

Tables

The following extended attributes are available on the *MySQL* tab:

Name	Description
Temporary table	[v5.0 and higher] Used to create a temporary table. A temporary table is visible only to the current connection, and is dropped automatically when the connection is closed. Scripting name: Temporary

2.17.6 NonStop SQL

To create a PDM with support for features specific to the NonStop SQL DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select  *Database*  *Edit Current DBMS*  and expand the *Profile* node.

The following sections list the extensions provided for NonStop SQL.

Columns

The following extensions are available on the *Extended Attributes* tab:

Name	Description
ExtType	Specifies an extended type for columns. Select either signed or unsigned in the Value column. Scripting name: ExtType

2.17.7 PostgreSQL

To create a PDM with support for features specific to the PostgreSQL DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select [Database](#) [Edit Current DBMS](#) and expand the [Profile](#) node.

Note

The DBMS definition file for PostgreSQL v7.3 is deprecated.

The following sections list the extensions provided for PostgreSQL.

Databases

The following extensions are available on the [PostgreSQL](#) tab:

Name	Description
Template	The name of the template from which to create the new database, or DEFAULT to use the default template. Scripting name: Template
Encoding	Character set encoding to use in the new database. Specify a string constant (e.g., 'SQL_ASCII'), or an integer encoding number, or DEFAULT to use the default encoding. Scripting name: Encoding

Domains

The following extensions are available on the [PostgreSQL](#) tab. To display this tab, select [BaseType](#) or [CompositeType](#) in the [Stereotype](#) field on the [General](#) tab and click [Apply](#):

Name	Description
Definition	[Composite Type] The composite type is specified by a list of attribute names and data types. This is essentially the same as the row type of a table, but using CREATE TYPE avoids the need to create an actual table when all that is wanted is to define a type. A stand-alone composite type is useful as the argument or return type of a function. Scripting name: CompositeDefinition
Length	[Base Type] Specifies the internal length of the new type. Scripting name: ExtTypeLength

Name	Description
Array Element type	[Base Type] Specifies the type of the array elements. Scripting name: ExtTypeElement
Array delimiter	[Base Type] Specifies the delimiter character for the array. Scripting name: ExtTypeDelimiter
By Value	[Base Type] Specifies that operators and functions which use this data type should be passed an argument by value rather than by reference. Scripting name: ExtTypePassedByValue
Input function	[Base Type] Specifies the name of a function, created by CREATE FUNCTION, which converts data from its external form to the internal form of the type. Scripting name: ExtTypeInput
Output function	[Base Type] Specifies the name of a function, created by CREATE FUNCTION, which converts data from its internal form to a form suitable for display. Scripting name: ExtTypeOutput
Send function	[Base Type] Specifies the name of a function, created by CREATE FUNCTION, which converts data of this type into a form suitable for transmission to another machine. Scripting name: ExtTypeSend
Receive function	[Base Type] Specifies the name of a function, created by CREATE FUNCTION, which converts data of this type from a form suitable for transmission from another machine to internal form. Scripting name: ExtTypeReceive

Groups

The following extensions are available on the [PostgreSQL](#) tab (v8 and higher):

Name	Description
Group identifier (id)	The SYSID clause can be used to choose the PostgreSQL group ID of the new group. This is normally not necessary, but may be useful if you need to recreate a group referenced in the permissions of some object. Scripting name: SysId

Procedures

The following extensions are available on the *PostgreSQL* tab:

Name	Description
Language	<p>The name of the language that the function is implemented in. May be SQL, C, internal, or the name of a user-defined procedural language. (See also extended attribute type <code>ProcLanguageList</code>.)</p> <p>Scripting name: <code>ProcLanguage</code></p>

References

The following extensions are available on the *PostgreSQL* tab (v8 and higher):

Name	Description
Deferrable	<p>Controls whether the constraint can be deferred. A constraint that is not deferrable will be checked immediately after every command. Checking of constraints that are deferrable may be postponed until the end of the transaction.</p> <p>Only foreign key constraints currently accept this clause. All other constraint types are not deferrable.</p> <p>Scripting name: <code>Deferrable</code></p>
Foreign key constraint deferred	<p>If a constraint is deferrable, this clause specifies the default time to check the constraint.</p> <p>False means the constraint is INITIALLY IMMEDIATE, it is checked after each statement. This is the default.</p> <p>True means the constraint is INITIALLY DEFERRED, it is checked only at the end of the transaction.</p> <p>Scripting name: <code>ForeignKeyConstraintDeferred</code></p>

Tables

The following extensions are available on the *PostgreSQL* tab (v8 and higher):

Name	Description
Temporary state	<p>If specified, the table is created as a temporary table. Temporary tables are automatically dropped at the end of a session, or optionally at the end of the current transaction.</p> <p>Scripting name: <code>Temporary</code></p>

Tablespaces

The following extensions are available on the *PostgreSQL* tab (v8 and higher):

Name	Description
Location	Specifies the directory that will be used for the tablespace. The directory must be specified by an absolute path name. Scripting name: TbspLocation
Owner	Specifies the name of the user who will own the tablespace. If omitted, defaults to the user executing the command. Only superusers may create tablespaces, but they can assign ownership of tablespaces to non-superusers. Scripting name: TbspOwner

Users

The following extensions are available on the *General* tab (v8 and higher):

Name	Description
Is schema	Specifies that the user is a schema. If TRUE, the user is allowed to create databases. Scripting name: Schema
Owner	[schemas] Specifies the owner of the schema. Scripting name: Owner

The following extensions are available on the *PostgreSQL* tab (v8 and higher):

Name	Description
User identifier (id)	Specifies the PostgreSQL user ID of the new user. This is normally not necessary, but may be useful if you need to recreate the owner of an orphaned object. Scripting name: SysId
Create database	Specifies that the user can create databases. Scripting name: CreateDB

Name	Description
Create user	Specifies that the user can create users and turns the user into a superuser who can override all access restrictions. Scripting name: <code>CreateUser</code>
Validity	Specifies an absolute time after which the user's password is no longer valid. By default, the password will be valid forever. Scripting name: <code>Validity</code>
Encrypted password	Specifies that the password is stored encrypted in the system catalogs. Scripting name: <code>EncryptedPassword</code>

2.17.8 Red Brick Warehouse

To create a PDM with support for features specific to the Red Brick Warehouse DBMS family, select the appropriate version in the DBMS field of the New Model dialog. To view these extensions to the PowerDesigner metamodel in the Resource Editor, select  [Database](#)  [Edit Current DBMS](#) and expand the [Profile](#) node.

The following sections list the extensions provided for Red Brick Warehouse.

Columns

The following extensions are available on the [Red Brick](#) tab:

Name	Description
Unique	Specifies that duplicate values are not allowed in the column. Declaring a column UNIQUE does not enforce uniqueness on the column; to enforce uniqueness, you must also build a BTREE index on the column. Scripting name: <code>IsUnique</code>

Procedures

The following extensions are available on the *Red Brick* tab:

Name	Description
Macro Type	Specifies the type of macro. You can choose either Public or Temporary. If you do not select a type, a private macro is created by default. Scripting name: MacroType

Important Disclaimers and Legal Information

Coding Samples

Any software coding and/or code lines / strings ("Code") included in this documentation are only examples and are not intended to be used in a productive system environment. The Code is only intended to better explain and visualize the syntax and phrasing rules of certain coding. SAP does not warrant the correctness and completeness of the Code given herein, and SAP shall not be liable for errors or damages caused by the usage of the Code, unless damages were caused by SAP intentionally or by SAP's gross negligence.

Gender-Neutral Language

As far as possible, SAP documentation is gender neutral. Depending on the context, the reader is addressed directly with "you", or a gender-neutral noun (such as "sales person" or "working days") is used. If when referring to members of both sexes, however, the third-person singular cannot be avoided or a gender-neutral noun does not exist, SAP reserves the right to use the masculine form of the noun and pronoun. This is to ensure that the documentation remains comprehensible.

Internet Hyperlinks

The SAP documentation may contain hyperlinks to the Internet. These hyperlinks are intended to serve as a hint about where to find related information. SAP does not warrant the availability and correctness of this related information or the ability of this information to serve a particular purpose. SAP shall not be liable for any damages caused by the use of related information unless damages have been caused by SAP's gross negligence or willful misconduct. All links are categorized for transparency (see: <https://help.sap.com/viewer/disclaimer>).



**go.sap.com/registration/
contact.html**

© 2018 SAP SE or an SAP affiliate company. All rights reserved.
No part of this publication may be reproduced or transmitted in any form or for any purpose without the express permission of SAP SE or an SAP affiliate company. The information contained herein may be changed without prior notice.
Some software products marketed by SAP SE and its distributors contain proprietary software components of other software vendors. National product specifications may vary.
These materials are provided by SAP SE or an SAP affiliate company for informational purposes only, without representation or warranty of any kind, and SAP or its affiliated companies shall not be liable for errors or omissions with respect to the materials. The only warranties for SAP or SAP affiliate company products and services are those that are set forth in the express warranty statements accompanying such products and services, if any. Nothing herein should be construed as constituting an additional warranty.
SAP and other SAP products and services mentioned herein as well as their respective logos are trademarks or registered trademarks of SAP SE (or an SAP affiliate company) in Germany and other countries. All other product and service names mentioned are the trademarks of their respective companies.
Please see <https://www.sap.com/corporate/en/legal/copyright.html> for additional trademark information and notices.