



A+ LAB SERIES V5

Lab 6: Windows Network Settings

Document Version: **2026-01-02**

Material in this Lab Aligns to the Following	
CompTIA A+ (220-1201) Exam Objectives	2.3: Summarize services provided by networked hosts. 2.4: Explain common network configuration concepts. 2.6: Given a scenario, configure basic wired/wireless small office/home office (SOHO) networks. 5.5: Given a scenario, troubleshoot network issues.
CompTIA A+ (220-1202) Exam Objectives	1.3: Compare and contrast basic features of Microsoft Windows editions. 1.6: Given a scenario, configure Microsoft Windows settings. 1.7: Given a scenario, configure Microsoft Windows networking features on a client/desktop. 2.2: Given a scenario, configure and apply basic Microsoft Windows OS security settings.

Contents

Introduction	3
Objective	3
Lab Topology	4
Lab Settings	5
1 Windows Network Tools	6
1.1 Accessing Network and Sharing Center	6
1.2 Change Adapter Settings	9
2 Advanced Sharing Settings	14
2.1 Configure Network Sharing Settings	14
3 Utilize and Examine Network Troubleshooting Problems	16
3.1 Network Troubleshooting Steps in Windows 11	16
3.2 Network Troubleshooting Steps in Windows 10	17
4 Using Network Command-Line Utilities	19
4.1 Interacting with the Win10-OS CLI	19

Introduction

The Network and Sharing Center, accessible via the Control Panel in Windows 10 and 11, is a key applet for configuring and managing a range of networking features. This utility provides an integrated overview of network configurations, facilitating a range of essential network management tasks. Enhancements in Windows 10 aimed at simplifying the user interface have led to a more streamlined experience, minimizing overlapping features. Moreover, with an increased emphasis on mobility, both Windows 10 and 11 have moved wireless network management to more prominent locations within the operating system. However, the Network and Sharing Center remains the core repository for detailed network settings, ensuring it remains a critical component for users and administrators managing network configurations.


Objective

In this lab, you will explore the Network and Sharing Center, a pivotal Control Panel applet in Windows 10 and 11 that serves as the central hub for configuring network settings and performing various networking tasks. It provides a comprehensive view of network configurations, making it easy to interact with network-related features. Enhancements in both Windows 10 and 11 have streamlined the interface to minimize redundancy, improving usability. Reflecting Microsoft's increased focus on mobility, wireless network management in these versions has been strategically relocated to enhance accessibility. Despite these updates, the core functionality and layout of the Network and Sharing Center have been preserved, maintaining a consistent user experience across Windows 10 and 11. This applet remains accessible through the Control Panel and serves as a critical tool for network management in both operating systems.

In this lab, we will be performing the following tasks:

- Access the Network and Sharing Center using the Control Panel.
- Review the ability to change the adapter settings by examining the adapter properties.
- Change the Static IP Address for the machine and review the configuration using the Command Prompt.
- Review and change the Advanced Sharing Settings.
- Utilize and examine the Network Troubleshooting utility on both Windows 10 and Windows 11.
- Use Network Command-Line Utilities to review the following commands: ipconfig, ping, tracert, netstat, net, net accounts, net use, and nslookup.

Lab Topology



Lab Settings

The information in the table below will be needed in order to complete the lab. The task sections below provide details on the use of this information.

Virtual Machine	IP Address	Account (if needed)	Password (if needed)
Win10-OS	192.168.1.10 / 24	sysadmin	NDGLabpass123!
Win11-OS	192.168.1.11 / 24	sysadmin	NDGLabpass123!

1 Windows Network Tools

In Windows 10 and 11, a workgroup remains a peer-to-peer network configuration in which computers on the same local network share resources without centralized administration. Typically used in small offices or home networks (SOHO), workgroups facilitate resource sharing among a limited number of devices. By default, Windows computers are set to the "WORKGROUP", ensuring seamless integration for basic networking needs. However, with advancements in Windows 10 and 11, workgroup management has seen slight enhancements to improve the user experience, particularly in how devices discover and join workgroups. These updates maintain the simplicity of workgroup configurations while improving security and ease of access, reflecting Microsoft's ongoing commitment to refining networking features for smaller, decentralized networks.

1.1 Accessing Network and Sharing Center


In all versions of *Windows*, the *Network and Sharing Center* can be accessed in multiple ways. Two common ways are to use Search and to use the *Control Panel*. The lab will be run on Windows 11, but the exercises will work the same way on other versions.

1. Open a console connection to the **Win11-OS** system.




To launch the console for a lab device, you can click on the respective tab in the navigation bar at the top or navigate to the *Topology* section and click the lab device's corresponding image.

2. Select the **Windows Start button**. When searching for apps, settings, or documents, type **Control Panel**. Click **Open** to start the Control Panel Applet.




3. Select the drop-down **arrow**, change the *View by* to **Small icons**, and click **Network and Sharing Center** in the list. A window opens, showing basic network information and active networks.



4. From this page, you have options to change the network settings:

- View Network Status: Check your network's status, including whether you're connected, the network type (public or private), and the active network name.
- Change Adapter Settings: Access network connections to configure, enable, or disable network adapters.
- Set Up a New Connection or Network: Create new connections, such as VPN, dial-up, or wireless networks.
- Manage Wireless Networks: Although Windows 11 has moved some of these functions to the "Settings" app, you can still manage wireless profiles here.
- Change Sharing Options: Control how your computer shares files and printers with other network users.


5. The available networks are shown, with only the *Unidentified network* being available in this lab environment.




6. Leave the *Win11-OS* system with the *Network and Sharing Center* open to continue with the next task.

1.2 Change Adapter Settings


1. While viewing the *Network and Sharing Center*, click on **Change Adapter Settings** in the left pane.




2. Explore the availability of network adapters on the machine. If you have an Ethernet, Wi-Fi, or any other type of network adapter, it will be listed here. Right-click on **Ethernet0** and choose **Properties**.




3. In the *Ethernet0 Properties* window, place a check mark next to **Internet Protocol Version 4 (TCP/IPv4)**, and double-click **Internet Protocol Version 4 (TCP/IPv4)**.



4. Here, you can configure the computer to use a static IP address or obtain one from a *DHCP* server. Change the machine's static IP address to 192.168.1.77, the static Subnet mask to 255.255.255.0, and the static Default gateway to **192.168.1.1**. Click **OK**.



- Click **OK** on the *Ethernet0 Properties* window.
- Select the **Start** button, in the search box, type **cmd**, select **Open** to open the command prompt interface.



- Select to place your cursor in the command prompt window, type the command below, followed by pressing the **Enter** key to verify that the newly assigned static IP address is configured correctly.

```
ipconfig /all
```

```
C:\Users\sysadmin>ipconfig /all


Windows IP Configuration

Host Name . . . . . : Win11-OS
Primary Dns Suffix . . . . . :
Node Type . . . . . : Hybrid
IP Routing Enabled. . . . . : Yes
WINS Proxy Enabled. . . . . : No


Ethernet adapter Ethernet0:

Connection-specific DNS Suffix . :
Description . . . . . : vmxnet3 Ethernet Adapter
Physical Address. . . . . : 00-50-56-B3-C7-08
DHCP Enabled. . . . . : No
Autoconfiguration Enabled . . . . : Yes
IPv4 Address. . . . . : 192.168.1.77(Preferred)
Subnet Mask . . . . . : 255.255.255.0
Default Gateway . . . . . : 192.168.1.1
DNS Servers . . . . . : 8.8.8.8
NetBIOS over Tcpip. . . . . : Enabled
```


8. Verify the IPv4 address configurations. Once confirmed, type **exit** followed by pressing the **Enter** key to close the command prompt window.
9. To allow other computers on the private network to reach the Win11-OS System, the firewall will need to be disabled for the private network.
10. On the taskbar, select the *search box*, type **firewall** in the search box. Select **Open** to open the Firewall and network protection system settings.



11. Select **Public Network**.



12. Under *Microsoft Defender Firewall*, select the **toggle button** to turn the firewall off.



13. Select **Yes** to allow changes to the User Account Control.



14. Close all open Firewall & network protection windows.

15. Close the **Network Connections** window.

16. Leave the *Win11-OS* system with the *Network and Sharing Center* window open to continue with the next task.

2 Advanced Sharing Settings


In *Windows 11*, you have two network profiles: *Private* and *Public*, which you can view on the *Advanced Sharing Settings* page. *Windows 11* has two profiles: *Private* or *Public*. These profiles are used to manage how the computer communicates with the network. Only one profile can be active at a time.

2.1 Configure Network Sharing Settings


1. In the *Network and Sharing Center* window, on the left pane, click on **Change advanced sharing settings**.




2. Select the drop-down arrow for Private networks. Notice the configuration options available for the current profile, Private networks. The File and printer sharing radio button is set to Off. This configuration will prevent anyone on the network with permission from accessing the files in this folder.



3. Select the drop-down arrow for All networks. Select the Public folder sharing toggle button and turn it **On**. Scroll to locate **File Sharing Connections** and make sure it's set to **use 128-bit encryption**. Ensure that the radio button for **Password protected sharing** is set to **On**. This will help secure access to shared files by requiring username and passwords.



4. Close the window for Advanced sharing settings by selecting the **X** in the top right of the open window.




5. Leave the Network and Sharing Center window open. Leave the *Win11-OS* system open to continue with the next task.


3 Utilize and Examine Network Troubleshooting Problems

3.1 Network Troubleshooting Steps in Windows 11


1. While in the *Network and Sharing Center* window, in the main pane, click on **Troubleshoot problems**.



2. Select the drop-down **arrow** for Other troubleshooters. This will open *Other troubleshooters* in a new window.



3. You will see a list of troubleshooting links. Review the variety of troubleshooting options. **Close** the Other troubleshooters window.




4. Close the **Control Panel** window.

3.2 Network Troubleshooting Steps in Windows 10


1. Open a console connection to the **Win10-OS** system.




2. Using the Network troubleshooter can help diagnose and fix common connection problems. Click the Start button, then click the **Settings** icon.



3. In the *Windows Settings*, click on **Network & Internet**.




- Underneath the *Status* header, click on **Troubleshoot**.



The network troubleshooter will run and attempt to discover and, if possible, resolve the issues with the network connection or configuration. The error displayed may be different than the error shown in the documentation.

- Read the results and click **Close**.



- Close the Settings Window.
- Leave the *Win10-OS* machine open to continue with the next task.


4 Using Network Command-Line Utilities

All the computers you are working with in the lab topology are on the same subnet and connected to the network. Hardware issues, firewall settings, incorrect IP addressing, and errors in network configuration can all cause problems with network connectivity. In this task, you will use command-line tools to view useful information to help you discover network configurations and troubleshoot.

To execute specific commands, open the command prompt using an administrator token to grant the cmd.exe process the highest level of privilege.

4.1 Interacting with the Win10-OS CLI

1. Click the **Start** button, type **cmd**. Select **Run as administrator** for the Command Prompt.




- Click **Yes** to allow the UAC to make changes.




- In the command prompt window, type the `ipconfig /?` command and press **Enter** to view help for the command. Ipconfig's primary use is to find TCP/IP configuration information, but it also has many useful switches that can be used with the help switch.

```
ipconfig /?
```

A screenshot of a Windows command prompt window. The command prompt shows the path `C:\WINDOWS\system32` and the command `ipconfig /?` has been entered and executed. The output displays the "USAGE:" section of the command's help, listing various switches like `/allcompartments`, `/renew`, `/release`, `/flushdns`, etc. The command `ipconfig /?` is highlighted with a red rectangular box.

- Type `ipconfig` to view the *TCP/IP* configuration information. This command will show the current *Windows* IP configuration.

```
ipconfig
```

A screenshot of a Windows command prompt window. The command prompt shows the path `C:\WINDOWS\system32` and the command `ipconfig` has been entered and executed. The output displays the "Windows IP Configuration" section, showing details for the "Ethernet adapter Ethernet0:", including the "Connection-specific DNS Suffix", "Link-local IPv6 Address", "IPv4 Address" (192.168.1.10), "Subnet Mask" (255.255.255.0), and "Default Gateway". The command `ipconfig` is highlighted with a red rectangular box.

5. To view more detailed information about the machine's TCP/IP configuration, enter `ipconfig /all`. What is the *MAC* address of the local network adapter? Is *DHCP* being used on this system? What is the *DNS* server? All these questions and more can be answered with this command.

```
ipconfig /all
```

```
C:\WINDOWS\system32>ipconfig /all

Windows IP Configuration

Host Name . . . . . : Win10-OS
Primary Dns Suffix . . . . . :
Node Type . . . . . : Hybrid
IP Routing Enabled. . . . . : No
WINS Proxy Enabled. . . . . : No

Ethernet adapter Ethernet0:

Connection-specific DNS Suffix . :
Description . . . . . : vmxnet3 Ethernet Adapter
Physical Address. . . . . : 00-50-56-B3-1B-22
DHCP Enabled. . . . . : No
Autoconfiguration Enabled . . . . : Yes
Link-local IPv6 Address . . . . . : fe80::6171:6c43:91c7:fe0f%3(Preferred)
IPv4 Address. . . . . : 192.168.1.10(Preferred)
Subnet Mask . . . . . : 255.255.255.0
Default Gateway . . . . . :
DHCPv6 IAID . . . . . : 100683862
DHCPv6 Client DUID. . . . . : 00-01-00-01-2C-63-15-FF-00-50-56-B3-1B-22
DNS Servers . . . . . : 8.8.8.8
NetBIOS over Tcpip. . . . . : Enabled

C:\WINDOWS\system32>
```




Other `ipconfig` switches that are useful to use at the CLI when troubleshooting network issues are:

- `ipconfig /release` - sends a message to the server that forces the client to give up its leased DHCP address.
- `ipconfig /renew` – executed to request a new IP address
- `ipconfig /flushdns` – flushes and resets the DNS client resolver cache helpful if you change DNS servers or an IP address assigned to a domain name changes

6. In the command prompt interface, enter the `ping 192.168.1.77` command. Is it successful? When referring to the topology, this is the *IP* address of the *Win11-OS* host. Using the *ping* command verifies connectivity to it.

```
ping 192.168.1.77
```




```
C:\WINDOWS\system32>ping 192.168.1.77

Pinging 192.168.1.77 with 32 bytes of data:
Reply from 192.168.1.77: bytes=32 time<1ms TTL=127
Reply from 192.168.1.77: bytes=32 time<1ms TTL=127
Reply from 192.168.1.77: bytes=32 time<1ms TTL=127
Reply from 192.168.1.77: bytes=32 time<1ms TTL=127

Ping statistics for 192.168.1.77:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms
```

7. At the command prompt, enter the `tracert 192.168.1.77` command. *Tracert* traces the route a packet takes to reach a destination and shows information about each hop along that route. Based on the command output, this device is on the same local subnet as *Win11-OS*.

```
tracert 192.168.1.77
```



```
C:\WINDOWS\system32>tracert 192.168.1.77

Tracing route to WIN11-OS [192.168.1.77]
over a maximum of 30 hops:

  1    <1 ms    <1 ms    <1 ms  WIN11-OS [192.168.1.77]

Trace complete.

C:\WINDOWS\system32>_
```



Because this lab environment is a flat network (a single subnet), only one hop is shown.

8. Enter the `netstat -help` command and review the available options. This network utility displays network connections from the host machine.

`netstat -help`

```
C:\WINDOWS\system32>netstat -help
Displays protocol statistics and current TCP/IP network connections.

NETSTAT [-a] [-b] [-e] [-f] [-n] [-o] [-p proto] [-r] [-s] [-t] [-x] [-y] [interval]

-a          Displays all connections and listening ports.
-b          Displays the executable involved in creating each connection or
           listening port. In some cases well-known executables host
           multiple independent components, and in these cases the
           sequence of components involved in creating the connection
           or listening port is displayed. In this case the executable
           name is in [] at the bottom, on top is the component it called,
           and so forth until TCP/IP was reached. Note that this option
           can be time-consuming and will fail unless you have sufficient
           permissions.
-e          Displays Ethernet statistics. This may be combined with the -s
           option.
-f          Displays Fully Qualified Domain Names (FQDN) for foreign
           addresses.
-n          Displays addresses and port numbers in numerical form.
-o          Displays the owning process ID associated with each connection.
-p proto    Shows connections for the protocol specified by proto; proto
           may be any of: TCP, UDP, TCPv6, or UDPv6. If used with the -s
           option to display per-protocol statistics, proto may be any of:
           IP, IPv6, ICMP, ICMPv6, TCP, TCPv6, UDP, or UDPv6.
-q          Displays all connections, listening ports, and bound
           nonlistening TCP ports. Bound nonlistening ports may or may not
           be associated with an active connection.
-r          Displays the routing table.
```


9. Enter the `netstat -an | more` command. This network utility displays a list of all open network connections on the computer, the ports they use, and the foreign IP address they are connected to, which is useful for tracking unexpected connections. Use the output of the `netstat -help` command to learn what the `a` and `-n` switches display. Use the spacebar to continue viewing the output until the prompt returns.

```
netstat -an | more
```

```
C:\WINDOWS\system32>netstat -an |more
Active Connections

 Proto Local Address           Foreign Address         State
 TCP    0.0.0.0:135             0.0.0.0:0               LISTENING
 TCP    0.0.0.0:445             0.0.0.0:0               LISTENING
 TCP    0.0.0.0:5040            0.0.0.0:0               LISTENING
 TCP    0.0.0.0:49664           0.0.0.0:0               LISTENING
 TCP    0.0.0.0:49665           0.0.0.0:0               LISTENING
 TCP    0.0.0.0:49666           0.0.0.0:0               LISTENING
 TCP    0.0.0.0:49667           0.0.0.0:0               LISTENING
 TCP    0.0.0.0:49668           0.0.0.0:0               LISTENING
 TCP    0.0.0.0:49669           0.0.0.0:0               LISTENING
 TCP    192.168.1.10:139        0.0.0.0:0               LISTENING
 TCP    [::]:135                [::]:0                  LISTENING
 TCP    [::]:445                [::]:0                  LISTENING
 TCP    [::]:49664              [::]:0                  LISTENING
 TCP    [::]:49665              [::]:0                  LISTENING
 TCP    [::]:49666              [::]:0                  LISTENING
 TCP    [::]:49667              [::]:0                  LISTENING
 TCP    [::]:49668              [::]:0                  LISTENING
 TCP    [::]:49669              [::]:0                  LISTENING
 UDP    0.0.0.0:123             *:.*                    *.*
 UDP    0.0.0.0:500             *:.*                    *.*
 UDP    0.0.0.0:4500            *:.*                    *.*
 UDP    0.0.0.0:5050            *:.*                    *.*
 UDP    0.0.0.0:5353            *:.*                    *.*
 UDP    0.0.0.0:5355            *:.*                    *.*
 UDP    127.0.0.1:1900          *:.*                    *.*
 UDP    127.0.0.1:59309         *:.*                    *.*
 UDP    127.0.0.1:59313         *:.*                    *.*
 UDP    192.168.1.10:137        *:.*                    *.*
 UDP    192.168.1.10:138        *:.*                    *.*
 UDP    192.168.1.10:1900       *:.*                    *.*
 UDP    192.168.1.10:59312     *:.*                    *.*
 UDP    [::]:123                *:.*                    *.*
 UDP    [::]:500                *:.*                    *.*
 UDP    [::]:4500              *:.*                    *.*
 UDP    [::]:5353              *:.*                    *.*
 UDP    [::]:5355              *:.*                    *.*
 UDP    [::1]:1900              *:.*                    *.*
 UDP    [::1]:59311            *:.*                    *.*
 UDP    [fe80::6171:6c43:91c7:fe0f%3]:1900 *:.*
 UDP    [fe80::6171:6c43:91c7:fe0f%3]:59310 *:.*

C:\WINDOWS\system32>
```


10. Enter the `net` command to review the syntax of the command and to list the subset of commands for the `net` command. This network utility is used to manage the network and view its settings.

`net`

```
C:\WINDOWS\system32>net
The syntax of this command is:

NET
[ ACCOUNTS | COMPUTER | CONFIG | CONTINUE | FILE | GROUP | HELP |
  HELPMMSG | LOCALGROUP | PAUSE | SESSION | SHARE | START |
  STATISTICS | STOP | TIME | USE | USER | VIEW ]

C:\WINDOWS\system32>
```

11. Enter the `net accounts` command. This command lets you view account settings and modify various account options from the command line. If you are unable to access the *GUI* and need to change user account login settings from the command line, this command is invaluable. Use `net accounts /?` for the full syntax.

`net accounts`

```
C:\WINDOWS\system32>net accounts
Force user logoff how long after time expires?:      Never
Minimum password age (days):                        0
Maximum password age (days):                        42
Minimum password length:                             0
Length of password history maintained:               None
Lockout threshold:                                   Never
Lockout duration (minutes):                          30
Lockout observation window (minutes):                 30
Computer role:                                       WORKSTATION
The command completed successfully.

C:\WINDOWS\system32>
```

12. You can type `net use /?` to display help for the `net use` command. The `net use` command lists the resources you are currently connected to. By using one or more available switches, you can connect to new resources and disconnect from existing ones.
13. Enter the `net use` command with no switches. This allows you to view current network connections. You will see by the output that you are not connected to any network resources.


```
C:\WINDOWS\system32>net use
New connections will be remembered.

There are no entries in the list.

C:\WINDOWS\system32>
```

14. Now you will use the *net* command to connect to a network resource. Enter
`net use * "\\Win11-OS\Users\sysadmin\Downloads" /user:sysadmin Training$`.
Select **Enter**.

```
net use * "\\Win11-OS\Users\sysadmin\Downloads" /user:sysadmin NDGLabpass123!
```



```
C:\WINDOWS\system32>net use * "\\Win11-OS\Users\sysadmin\Downloads" /user:sysadmin NDGLabpass123!  
Drive Z: is now connected to \\Win11-OS\Users\sysadmin\Downloads.  
The command completed successfully.  
C:\WINDOWS\system32>
```




The * allows the system to select the drive letter assigned to the resource
\\Win11-OS\Users\sysadmin\Downloads is the network resource being mapped

sysadmin – username
NDGLabpass123! - password

15. Enter the `net use` command. This allows you to view current network connections. You will see any network resources you are currently connected to. The mapped network drive is Z.


```
net use
```



```
C:\WINDOWS\system32>net use  
New connections will be remembered.  
  
Status      Local      Remote  
-----  
OK          Z:         \\Win11-OS\Users\sysadmin\Downloads  
                                     Microsoft Windows Network  
The command completed successfully.  
C:\WINDOWS\system32>
```

16. Enter the `net use Z: /delete` command. This allows you to remove the network connection to Drive Z. If you type `net use`, you will see any network resources you are currently connected to. The mapped network, drive Z:, should be removed.

```
net use Z: /delete
```



```
C:\WINDOWS\system32>net use Z: /delete
Z: was deleted successfully.


C:\WINDOWS\system32>net use
New connections will be remembered.

There are no entries in the list.

C:\WINDOWS\system32>
```

17. *Nslookup* is a command-line utility that queries the DNS to obtain a domain name, IP address mapping, or other types of DNS records. Enter the `nslookup` command.


```
nslookup
```



```
C:\WINDOWS\system32>nslookup
Default Server: Unknown
Address: 8.8.8.8
```



Example output of a Windows system using DNS server.



```
> nslookup netdevgroup.com
Server: netdevgroup.com
Address: 34.214.209.23
```

Because this lab environment is not connected to the internet and uses no DNS server while running Windows it is not resolving the names. In Windows operating systems an `nslookup` will by default check the specified DNS server for the record and will not look at the hosts file.

18. The lab is now complete; you may end the reservation.