

CONTENTS

Introduction

How To Use This Guide

Verify UFW Status

Enable UFW

Disable UFW

Block an IP Address

Block a Subnet

Block Incoming Connections to a Network Interface

Allow an IP Address

Allow Incoming Connections to a Network Interface

Delete UFW Rule

List Available Application Profiles

Enable Application Profile

Disable Application Profile

Allow SSH

Allow Incoming SSH from Specific IP Address or Subnet

Allow Incoming Rsync from Specific IP Address or Subnet

Allow Nginx HTTP / HTTPS

Allow Apache HTTP / HTTPS

Allow All Incoming HTTP (port 80)

Allow All Incoming HTTPS (port 443)

Allow All Incoming HTTP and HTTPS

Allow MySQL Connection from Specific IP Address or Subnet

Allow PostgreSQL Connection from Specific IP Address or Subnet

Block Outgoing SMTP Mail

Conclusion

RELATED

Initial Server Setup with Ubuntu 12.04

<u>View</u> ♂

How To Install Ruby on Rails on Ubuntu 12.04 LTS (Precise Pangolin) with RVM

View 🗹




UFW Essentials: Common Firewall Rules and Commands

Published on August 20, 2015 · Updated on December 15, 2021

Security Ubuntu Firewall Networking



By Mitchell Anicas and Erika Heidi





Introduction

UFW (uncomplicated firewall) is a firewall configuration tool that runs on top of <code>iptables</code>, included by default within Ubuntu distributions. It provides a streamlined interface for configuring common firewall use cases via the command line.

This cheat sheet-style guide provides a quick reference to common UFW use cases and commands, including examples of how to allow and block services by port, network interface, and source IP address.

How To Use This Guide

- This guide is in cheat sheet format with self-contained command-line snippets.
- Jump to any section that is relevant to the task you are trying to complete.
- When you see highlighted text in this guide's commands, keep in mind that this text should refer to IP addresses from your own network.

Remember that you can check your current UFW ruleset with sudo ufw status or sudo ufw status verbose.

Verify UFW Status

To check if ufw is enabled, run:



The output will indicate if your firewall is active or not.

Enable UFW



If you got a Status: inactive message when running ufw status, it means the firewall is not yet enabled on the system. You'll need to run a command to enable it.

By default, when enabled UFW will block external access to all ports on a server. In practice, that means if you are connected to a server via SSH and enable ufw before allowing access via the SSH port, you'll be disconnected. Make sure you follow the section on how to enable SSH access of this guide before enabling the firewall if that's your case.

To enable UFW on your system, run:

```
$ sudo ufw enable Copy
```

You'll see output like this:

```
Output
Firewall is active and enabled on system startup
```

To see what is currently blocked or allowed, you may use the verbose parameter when running ufw status, as follows:

```
Status: active
Logging: on (low)
Default: deny (incoming), allow (outgoing), deny (routed)
New profiles: skip
```

Disable UFW

If for some reason you need to disable UFW, you can do so with the following command:

```
$ sudo ufw disable Copy
```

Be aware that this command will fully disable the firewall service on your system.

Block an IP Address

To block all network connections that originate from a specific IP address, run the following command, replacing the highlighted IP address with the IP address that you want to block:

```
$ sudo ufw deny from 203.0.113.100

Output
Rule added
```

In this example, from 203.0.113.100 specifies a source IP address of "203.0.113.100".

If you run sudo ufw status now, you'll see the specified IP address listed as denied:

All connections, coming in or going out, are blocked for the specified IP address.



Block a Subnet

If you need to block a full subnet, you may use the subnet address as from parameter on the ufw deny command. This would block all IP addresses in the example subnet 203.0.113.0/24:

```
$ sudo ufw deny from 203.0.113.0/24

Output
Rule added
```

Block Incoming Connections to a Network Interface

To block incoming connections from a specific IP address to a specific network interface, run the following command, replacing the highlighted IP address with the IP address you want to block:

```
$ sudo ufw deny in on eth0 from 203.0.113.100

Output
Rule added
```

The in parameter tells ufw to apply the rule only for incoming connections, and the on etho parameter specifies that the rule applies only for the etho interface. This might be useful if you have a system with several network interfaces (including virtual ones) and you need to block external access to some of these interfaces, but not all.

Allow an IP Address

To allow all network connections that originate from a specific IP address, run the following command, replacing the highlighted IP address with the IP address that you want to allow access:

```
$ sudo ufw allow from 203.0.113.101

Output
Rule added
```

If you run sudo ufw status now, you'll see output similar to this, showing the word ALLOW next to the IP address you just added.


```
Output
Status: active

To Action From
-- -----
...
Anywhere ALLOW 203.0.113.101
```

You can also allow connections from a whole subnet by providing the corresponding subnet mask for a host, such as 203.0.113.0/24.

Allow Incoming Connections to a Network Interface

To allow incoming connections from a specific IP address to a specific network interface, run the following command, replacing the highlighted IP address with the IP address you want to allow:





The in parameter tells ufw to apply the rule only for incoming connections, and the on etho parameter specifies that the rule applies only for the etho interface.

If you run sudo ufw status now, you'll see output similar to this:

```
Output
Status: active

To Action From
-- -----
Anywhere on eth0 ALLOW 203.0.113.102
```

Delete UFW Rule

To delete a rule that you previously set up within UFW, use ufw delete followed by the rule (allow or deny) and the target specification. The following example would delete a rule previously set to allow all connections from an IP address of 203.0.113.101:

```
$ sudo ufw delete allow from 203.0.113.101

Output
Rule deleted
```

Another way to specify which rule you want to delete is by providing the rule ID. This information can be obtained with the following command:

```
Status: active

To Action From
---

[1] Anywhere DENY IN 203.0.113.100

[2] Anywhere on eth0 ALLOW IN 203.0.113.102
```

From the output, you can see that there are two active rules. The first rule, with highlighted values, denies all connections coming from the IP address 203.0.113.100. The second rule allows connections on the etho interface coming in from the IP address 203.0.113.102.

Because by default UFW already blocks all external access unless explicitly allowed, the first rule is redundant, so you can remove it. To delete a rule by its ID, run:

```
$ sudo ufw delete 1 Copy
```

You will be prompted to confirm the operation and to make sure the ID you're providing refers to the correct rule you want to delete.

```
Output

Deleting:
deny from 203.0.113.100

Proceed with operation (y|n)? y

Rule deleted
```

If you list your rules again with sudo ufw status, you'll see that the rule was removed.

List Available Application Profiles

Upon installation, applications that rely on network communications will typically set up a UFW profile that you can use to allow connection from external addresses. This is often the same as running ufw allow from, with the advantage of providing a shortcut that abstracts the specific port numbers a service uses and provides a user-friendly nomenclature to referenced services.



To list which profiles are currently available, run the following:

```
$ sudo ufw app list
```

If you installed a service such as a web server or other network-dependent software and a profile was not made available within UFW, first make sure the service is enabled. For remote servers, you'll typically have OpenSSH readily available:

```
Output
Available applications:
OpenSSH
```

Enable Application Profile

To enable a UFW application profile, run ufw allow followed by the name of the application profile you want to enable, which you can obtain with a sudo ufw app list command. In the following example, we're enabling the OpenSSH profile, which will allow all incoming SSH connections on the default SSH port.

```
$ sudo ufw allow "OpenSSH"

Output
Rule added
Rule added (v6)
```

Remember to quote profile names that consist of multiple words, such as Nginx HTTPS.

Disable Application Profile

To disable an application profile that you had previously set up within UFW, you'll need to remove its corresponding rule. For example, consider the following output from sudo ufw status:

```
$ sudo ufw status
                                                                                            Сору
Status: active
То
                            Action
                                         From
OpenSSH
                            ALLOW
                                         Anywhere
Nginx Full
                            ALLOW
                                         Anvwhere
OpenSSH (v6)
                            ALLOW
                                         Anywhere (v6)
                            ALLOW
                                         Anywhere (v6)
Nginx Full (v6)
```

This output indicates that the Nginx Full application profile is currently enabled, allowing any and all connections to the web server both via HTTP as well as via HTTPS. If you'd want to only allow HTTPS requests from and to your web server, you'd have to first enable the most restrictive rule, which in this case would be Nginx HTTPS, and then disable the currently active Nginx Full rule:


```
$ sudo ufw allow "Nginx HTTPS"
$ sudo ufw delete allow "Nginx Full"
```

Remember you can list all available application profiles with sudo ufw app list.

Allow SSH

When working with remote servers, you'll want to make sure that the SSH port is open to connections so that you are able to log in to your server remotely.

The following command will enable the OpenSSH UFW application profile and allow all connections to the default SSH port on the server:



Сору

```
Rule added
Rule added (v6)
```

Although less user-friendly, an alternative syntax is to specify the exact port number of the SSH service, which is typically set to 22 by default:

```
$ sudo ufw allow 22

Output
Rule added
Rule added (v6)
```

Allow Incoming SSH from Specific IP Address or Subnet

To allow incoming connections from a specific IP address or subnet, you'll include a from directive to define the source of the connection. This will require that you also specify the destination address with a to parameter. To lock this rule to SSH only, you'll limit the proto (protocol) to tcp and then use the port parameter and set it to 22, SSH's default port.

The following command will allow only SSH connections coming from the IP address 203.0.113.103:

```
$ sudo ufw allow from 203.0.113.103 proto tcp to any port 22

Output
Rule added
```

You can also use a subnet address as from parameter to allow incoming SSH connections from an entire network:

```
$ sudo ufw allow from 203.0.113.0/24 proto tcp to any port 22

Output
Rule added
```

Allow Incoming Rsync from Specific IP Address or Subnet

The Rsync program, which runs on port 873, can be used to transfer files from one computer to another.

To allow incoming rsync connections from a specific IP address or subnet, use the from parameter to specify the source IP address and the port parameter to set the destination port 873. The following command will allow only Rsync connections coming from the IP address 203.0.113.103:

```
$ sudo ufw allow from 203.0.113.103 to any port 873

Output
Rule added

To allow the entire 203.0.113.0/24 subnet to be able to rsync to your server, run:

$ sudo ufw allow from 203.0.113.0/24 to any port 873

Copy

Output
Rule added
```



Allow Nginx HTTP / HTTPS

have Nginx installed and enabled as a service, run the following command to identify which profiles are available:

```
$ sudo ufw app list | grep Nginx

Output
Nginx Full
Nginx HTTP
Nginx HTTPS
```

To enable both HTTP and HTTPS traffic, choose Nginx Full. Otherwise, choose either Nginx HTTP to allow only HTTPs to allow only HTTPS.

The following command will allow both HTTP and HTTPS traffic on the server (ports 80 and 443):

```
$ sudo ufw allow "Nginx Full"

Output
Rule added
Rule added (v6)
```

Allow Apache HTTP / HTTPS

Upon installation, the Apache web server sets up a few different UFW profiles within the server. Once you have Apache installed and enabled as a service, run the following command to identify which profiles are available:

```
$ sudo ufw app list | grep Apache

Output
Apache
Apache Full
Apache Secure
```

To enable both HTTP and HTTPS traffic, choose Apache Full. Otherwise, choose either Apache for HTTP or Apache Secure for HTTPS.

The following command will allow both HTTP and HTTPS traffic on the server (ports 80 and 443):

```
$ sudo ufw allow "Nginx Full"

Output
Rule added
Rule added (v6)
```

Allow All Incoming HTTP (port so)

Web servers, such as Apache and Nginx, typically listen for HTTP requests on port 80. If your default policy for incoming traffic is set to drop or deny, you'll need to create a UFW rule to allow external access on port 80. You can use either the port number or the service name (http) as a parameter to this command.

To allow all incoming HTTP (port 80) connections, run:



An alternative syntax is to specify the port number of the HTTP service:

```
$ sudo ufw allow 80

Copy

Output
Rule added
Rule added (v6)
```

Allow All Incoming HTTPS (port 443)

HTTPS typically runs on port 443. If your default policy for incoming traffic is set to drop or deny, you'll need to create a UFW rule to allow external access on port 443. You can use either the port number or the service name (https) as a parameter to this command.

To allow all incoming HTTPS (port 443) connections, run:

```
$ sudo ufw allow https

Output
Rule added
Rule added (v6)
```

An alternative syntax is to specify the port number of the HTTPS service:

```
$ sudo ufw allow 443

Output
Rule added
Rule added (v6)
```

Allow All Incoming HTTP and HTTPS

If you want to allow both HTTP and HTTPS traffic, you can create a single rule that allows both ports. This usage requires that you also define the protocol with the proto parameter, which in this case should be set to tcp.

To allow all incoming HTTP and HTTPS (ports 80 and 443) connections, run:

```
$ sudo ufw allow proto tcp from any to any port 80,443


Output
Rule added
Rule added (v6)
```

Allow MySQL Connection from Specific IP Address or Subnet

MySQL listens for client connections on port 3306. If your MySQL database server is being used by a client on a remote server, you'll need to create a UFW rule to allow that access.

To allow incoming MySQL connections from a specific IP address or subnet, use the from parameter to specify the source IP address and the port parameter to set the destination port 3306.

The following command will allow the IP address 203.0.113.103 to connect to the server's MySQL port:



To allow the entire 203.0.113.0/24 subnet to be able to connect to your MySQL server, run:

```
$ sudo ufw allow from 203.0.113.0/24 to any port 3306

Copy

Output
Rule added
```

Allow PostgreSQL Connection from Specific IP Address or Subnet

PostgreSQL listens for client connections on port 5432. If your PostgreSQL database server is being used by a client on a remote server, you need to be sure to allow that traffic.

To allow incoming PostgreSQL connections from a specific IP address or subnet, specify the source with the from parameter, and set the port to 5432:

```
$ sudo ufw allow from 203.0.113.103 to any port 5432

Output
Rule added

To allow the entire 203.0.113.0/24 subnet to be able to connect to your PostgreSQL server, run:

$ sudo ufw allow from 203.0.113.0/24 to any port 5432

Output
```

Block Outgoing SMTP Mail

Mail servers, such as Sendmail and Postfix, typically use port 25 for SMTP traffic. If your server shouldn't be sending outgoing mail, you may want to block that kind of traffic. To block outgoing SMTP connections, run:

```
$ sudo ufw deny out 25

Output
Rule added
Rule added (v6)
```

This configures your firewall to drop all outgoing traffic on port 25. If you need to reject outgoing connections on a different port number, you can repeat this command and replace 25 with the port number you want to block.

Conclusion

Rule added

UFW is a powerful tool that can greatly improve the security of your servers when properly configured. This reference guide covers some common UFW rules that are often used to configure a firewall on Ubuntu.

Most of the commands in this guide can be adapted to fit different use cases and scenarios, by changing parameters such as the source IP address and/or destination port. For more detailed information about each command parameter and available modifiers, you can use the man utility to check UFW's manual:






The <u>official UFW page on Ubuntu's documentation</u> is another resource you can use as reference for more advanced use cases and examples.

Want to learn more? Join the DigitalOcean Community!

Join our DigitalOcean community of over a million developers for free! Get help and share knowledge in our Questions & Answers section, find tutorials and tools that will help you grow as a developer and scale your project or business, and subscribe to topics of interest.

Sign up \rightarrow




Still looking for an answer?

Ask a question Search for more help

Was this helpful? Yes No

Comments

10 Comments



This textbox defaults to using Markdown to format your answer.

You can type **!ref** in this text area to quickly search our full set of tutorials, documentation & marketplace offerings and insert the link!

Sign In or Sign Up to Comment

Synchro • July 15, 2021

Great article, but I have a few suggestions to make it a bit safer. I'd recommend preferring the app definitions over port numbers. Most of the time services are just single ports on single...

David Hile • January 3, 2018

A useful tip:

Usually a UFW profile such as OpenSSH is created when you install the openssh-server

olivebay84 • August 9, 2017

can you also add on how to save those rules , that is to make them persistent because I cant find it nowhere.

rejkpp • November 21, 2016

What do I need to configure with wordpress installed?

I have followed the initial server setup for ubuntu 16.04, installed LEMP, set-up virtual hosts and

<u>Joswellve11a9f3</u> • April 28, 2016

I have installed wowza in my server and in step I was demanding to open the port 1935, i execute the commande "sudo ufw enable" and as a result I had no access to my ssh! How can I get ba...

plsharevme • April 16, 2016

after i enable ufw , i cannot get sudo apt-get update to work ,it keep say could not resolve mirror digitalocean

douzr12 • February 28, 2016

Thanks Mitchell Anicas for the article. It's helpful very much; I have a question, Can I make rules to deny or allow MAC addresses?

craiganderson • February 3, 2016

I'm wondering if you can tell me what the following UFW log entries mean? (I replaced my server IP with xxx.xxx.xxx.xxx):



okneloper • January 31, 2016

"If your server shouldn't be sending outgoing mail, you may want to block that kind of traffic. To block outgoing SMTP mail, which uses port 25, run this command:"

craiganderson • January 29, 2016

Should the following command block web traffic as well? Meaning, prevent anyone accessing from this IP address from accessing any websites on the server?

Load More Comments



This work is licensed under a Creative Commons Attribution-NonCommercial- ShareAlike 4.0 International License.

Try DigitalOcean for free

Click below to sign up and get \$100 of credit to try our products over 60 days!

Sign up \rightarrow

Popular Topics

Ubuntu

Linux Basics

JavaScript

React

Python

Security

Apache

MySQL

Databases

Docker

Kubernetes

Ebooks

Browse all topic tags

All tutorials →

Questions

Q&A



Events

Tech Talks

Hacktoberfest

Deploy

Get involved

Community Newsletter


Hollie's Hub for Good

Write for DOnations

Community tools and integrations

Hatch Startup program





Interested in whales, protecting them, and their connection to helping prevent climate change? We recommend checking out the Whale and Dolphin Conservation.

Reset easter egg to be discovered again / Permanently dismiss and hide easter egg







You get paid; we donate to tech nonprofits.

Featured on Community Kubernetes Course Learn Python 3 Machine Learning in Python Getting started with Go Intro to Kubernetes

DigitalOcean Products Virtual Machines Managed Databases Managed Kubernetes Block Storage Object Storage Marketplace VPC Load Balancers



UFW Essentials: Common Firewall Rules and Commands | DigitalOcean 8/31/2022 Welcome to the developer cloud DigitalOcean makes it simple to launch in the cloud and scale up as you grow - whether you're running one virtual machine or ten thousand. Learn More ၁ jonsmith oww. Community Solutions Contact Company **Products** Web & Mobile Apps **Products Overview** Website Hosting Kubernetes Game Development Report Abuse App Platform **CSS-Tricks** Streaming Write for DOnations Share your ideas **Partners** Managed Databases **Droplets for Demos** Startups Referral Program Hatch Startup Program SaaS Solutions **Press** deploy by DigitalOcean Agency & Web Dev Shops **Load Balancers Shop Swag** Managed Cloud Hosting Research Program **Big Data Investor Relations Tools & Integrations Business Solutions API Open Source Cloud Hosting for** Pricing Newsletter Signup Release Notes © 2022 DigitalOcean, LLC. All rights reserved.





