

D365 F&O warehouse Management Systems (Advance Warehousing)-1

This document is the continuation of the previous document shared by me on same topic mentioned at Header.

Unit Sequence group

The unit sequence group defines the sequence of units that can be used in warehouse operations. The sequence determines the order of units in which warehouse work is generated and it is applied when work is created for quantities on a purchase order line or transfer order line. The unit sequence group should include units of measure that range from the smallest to the largest unit and can be used for the product in warehouse operations.

Note- The smallest unit in a sequence group that you associate with an item must match the inventory unit that is defined for the corresponding product.

Navigation - Warehouse management > Setup > Warehouse setup > Unit sequence groups

Finance and Operations | Warehouse management > Setup > Warehouse > Unit sequence groups

Standard view

Unit sequence groups

Unit sequence group ID: PC | Name: PC

Line details

Line number	Unit	License pla...	License pla...	Use unit fo...	Default uni...	Default uni...	Default container t...	Default uni...	Wave label type
1.0000000000	PC	0							

License plate - A unique number that is assigned to a warehouse entity such as a pallet, bin, cart, or individual item for tracking inventory. You can use this number to ascertain the item location, item quantity, product dimension, and tracking dimension of the entity.

Benefits of Using License Plates

Efficiency: Handling items as a grouped unit speeds up processes such as receiving, picking, and shipping. It reduces the time spent on scanning individual items by allowing a single scan of the license plate.

Accuracy: By managing items at the license plate level, the likelihood of errors decreases. It ensures that the items grouped under a license plate move together, minimizing misplacements and inaccuracies in order fulfillment.

Tracking and Visibility: License plates enhance the traceability of items within the warehouse. At any point, you can know exactly where items are, how they're grouped, and their movement history, thereby improving inventory control.

D365 F&O warehouse Management Systems (Advance Warehousing)-1

License plate packing type

Enter an ID for a license plate packing type that is added to the license plate number.

License plate grouping

Select this option if you want quantities of items that are larger than a pallet to be grouped into a single license plate for the receipt. If you do not select this option, a separate license plate will be requested for each quantity of the unit that you receive. If you want to use license plate grouping when work is processed a mobile device, you need to select the License plate grouping option on the mobile device menu item for receipt.

Use unit for cycle counting

Select this option to use the unit for cycle counting. The selected units will be available for a warehouse worker using a mobile device to count available inventory. You can select a maximum of four units in the sequence group. If you select more than four units, they will not be shown on the mobile device.

Default unit for purchase and transfer

Select the default unit for purchase and transfer orders. Only one unit can be selected.

Default unit for production

Select the default unit for production. Only one unit can be selected.

Default container type

Select the default container type to be used on license plates. Container types are used to define the physical characteristics of a tangible carrying unit, such as cage, box, pallet, or a shipping container.

Default unit for material consumption

Select the default unit for material consumption. Only one unit can be selected.

Wave label type

Label type is used for each wave label build. Note: the value is required if several wave labels have to be generated for a work line.

Note – output of all these parameters will be described when we reach other setups (mobile device)


D365 F&O warehouse Management Systems (Advance Warehousing)-1

Location Format

Location formats are a naming system used to create unique and consistent names for the different location bin positions used within a warehouse. It can be useful to use separators as part of the location format to make it easier to identify components of the location such as the aisle number. For example, these components could be aisle, rack, shelf, and bin

At least one should be created so I created a default the length should be limited to 20

Navigation - Warehouse management > Setup > Warehouse > Location formats




Location types

Navigation - Warehouse management > Setup > Warehouse > Location types

Location types can be used as filtering options to control the different warehouse management processes. As a minimum, you must create staging and final shipping location types in order to define the outbound warehouse management process.

D365 F&O warehouse Management Systems (Advance Warehousing)-1



Finance and Operations

Warehouse management > Setup > Warehouse > Location types

← Edit + New Delete Options

Location types

Standard view * ∨


Filter

Location type	Description
PACK	Packing station
PICK	Picking/ Issue location
QC	QC
RECV	Receiving Baydoor
RETURN	Return location
SHIP	Shipping Baydoor
TEMP	Temporary
USER	USER

Location Profiles

The definition of location profiles is very important. Grouped locations capacity can be controlled here, as can the policies related to what inventory gets stored and how it's stored. Location profiles can be used as filtering options to control the different warehouse management processes. As a minimum, you must create a user location profile in order to enable WMS.

Navigation - Warehouse management > Setup > Warehouse > Location Profiles



Finance and Operations

Warehouse management > Setup > Warehouse > Location profiles

← Edit + New Delete Options

Filter

Standard view ∨

Location profiles

Location profile ID	Name
ALL_BIN	Any category_bin

General

Location format	DEF	Allow mixed items	☒ Yes	Generate check digit	☒ No	Enable location status	☒ No
Location type	PICK	Enable location product dimensi...	☒ No	Override rules for batch days	☒ No	Enable license plate positioning	☒ No
Dock management profile ID		Allow mixed inventory statuses	☒ Yes	Allowed container type group		Display mobile device LP position	☒ No
Use license plate tracking	☒ No	Allow mixed inventory batches	☒ Yes	Enable item in location	☒ No		
Allow negative inventory	☒ No	Allow cycle counting	☒ Yes	Enable location activity date and ...	☒ No		

D365 F&O warehouse Management Systems (Advance Warehousing)-1

Dock management profile ID

Select a dock management profile. The dock management profile contains information about the inventory types that cannot be mixed at a particular warehouse location.

Use license plate tracking

This option enables license plate tracking at a location. If this is turned on, all inventory at the location will need to have a license plate assigned and the license plate will always need to be specified during inventory movements.

Allow negative inventory

Select this option to allow negative inventory of items at a specified location. Locations that use license plate tracking cannot have negative inventory for items.

Allow mixed items

Select this option to allow the storage of mixed items at the specified location. If you select this option, you must select the Allow mixed inventory batches option.

Enable location product dimension specific mixing

When enabled, you can specify which product dimensions that can be mixed on the location. This is only supported when "Allow mixed items" is set to No

Allow mixed inventory statuses

Set this option to Yes if you want to allow items with different inventory statuses to be stored at the location that is specified in this profile. If this option is turned off, all inventory in the location will need to have the same inventory status. Consider the impact that will have on a situation where you need to change inventory status for some of the stored goods in a location. If mixed inventory statuses is not allowed, you would need to move the goods to another empty location before you can change the status.

Allow mixed inventory batches

This option allows you to store batches of mixed inventory items at the location that is specified in this profile. If this option is set to No, all inventory in the profile location must belong to the same batch. This is useful if you want to keep different batches in the same location.

Allow cycle counting

This option allows cycle counting to be processed for locations with this location profile. It can be useful to be able to control whether cycle counting should be allowed in certain areas of the

D365 F&O warehouse Management Systems (Advance Warehousing)-1

warehouse. For example, you might want to disallow cycle counting in areas such as receiving or staging areas where inventory is only stored on a temporary basis while it waits to be picked up.

Generate check digit

Select this option to generate a check digit for the specified location. You can use a check digit to authenticate a location for warehouse mobile device transactions.

Override rules for batch days

Enable this option to override the rule for how many days the inventory batch expiration dates can differ. This option allows mixing of inventory batches that don't obey this rule.

Allowed container type group

This option prevents a location with this profile from holding different kinds of container types. To limit locations to specific container types, the records that are defined on the Allowed container types page must be associated with the location profile. When you assign an allowed container type group to a location profile, license plates can be stored only if the allowed container types are associated with them. You can enable this functionality only when the Use license plate tracking option is set to Yes.

Enable item in location

When enabled, the item field on the location will be updated for any locations using this location profile.

Enable location activity date and time

When enabled, the location activity date and time field on the location will be updated for any location using this location profile.

Enable location activity date and time

When enabled, the location activity date and time field on the location will be updated for any location using this location profile.

Enable location status

When enabled, the Aging date and Location status fields on the location will be updated for any locations using this location profile.

Enable license plate positioning

When enabled, the license plate position will be maintained for license plates in the location.

Display mobile device LP position

D365 F&O warehouse Management Systems (Advance Warehousing)-1

When enabled, the license plate position value will be shown to the user on the mobile device during adjustment in and during counting.

Allowed product dimension mixing		
PRODUCT DIMENSIONS	Size	Color
Configuration	☒ No	☒ No
☒ No		Style
		☒ No

Configuration

When enabled, items with different configurations can be stored on the location.

Size

When enabled, items with different sizes can be stored on the location.

Color

When enabled, items with different colors can be stored on the location.

Style

When enabled, items with different styles can be stored on the location.

Dimensions		
Storage unit	Actual location height	Usable location height
	230.00	0.00
Volume utilization percentage	Actual location width	Usable location width
100.00	100.00	0.00
Volumetric method used for inventory location	Actual location depth	Usable location depth
☐ Usable dimensions	45.00	0.00
☒ Use location volume	Actual location volume	Usable location volume
	1,035,000.00	0.00
	Maximum weight	
	0.00	

We can choose the dimension of the location and mention what will be the utilized/Actual volume

D365 F&O warehouse Management Systems (Advance Warehousing)-1

Replenishment			
Exceed location capacity	Work availability threshold type	Overflow quantity	Overflow unit
☒ No	☒ Quantity	0.00000	
	☐ Percent		Overflow percentage
			0.00

Exceed location capacity

When enabled, the maximum capacity of the location will be allowed to be exceeded by replenishment work.

Work availability threshold type

What method is used for determining when to release more work. Capacity uses a percentage based on stocking limits or volumetrics. Quantity uses a specific quantity value.

Overflow quantity

Quantity at which the location overflows. Work will be available whenever the location on hand + work quantity is below this value. Any replenishment work above this value will be blocked, and will have to be unblocked manually. Any location stocking limits will not be will be taken into consideration when calculating the work quantity.

Overflow unit

Unit associated with the overflow quantity.

Overflow percentage

Percentage at which the location overflows. Work will be available whenever the location on hand percentage + work quantity percentage is below this percentage. Any replenishment work quantity percentage above this value will be blocked and will have to be unblocked manually. Any location stocking limits will be taken into consideration when calculating the work quantity percentage. If no location stocking limits are defined, work quantity percentage will be calculated by volume if volume constraints are defined on location profile.

Location Stocking Limits

You can use the **Location stocking limits** page) to control the load capacity at warehouse locations without having to use the more advanced processes for volumetric calculations of physical products.


The purpose of location stocking limits is to evaluate the maximum quantity that a location can contain. You can set up the feature on any of three levels, each of which has its own tab on the **Location stocking limits** page

D365 F&O warehouse Management Systems (Advance Warehousing)-1

- Products
- Product variants
- Container types

For each level, you can define different field values. The system will then evaluate the capacity of a specific location, based on the **Quantity** and **Unit** values for each row. It will select the most detailed matching record first. For example, a row that has a value in the **Location profile ID** field will be evaluated before a row that has a value only in the **Warehouse** field. The remaining capacity will also be evaluated, based on the **Quantity** value for the location stocking limit record that is used.

Navigation - Warehouse management > Setup > Warehouse > Location stocking limits



Warehouse selection

Use this option to specify for which warehouses will the stocking limit be valid for. If Warehouse is selected, the the warehouse and location can be specified and will be used to define the stocking limit. There won't be any fallback for the locations. If Warehouse group is selected, then it will be possible to specify a warehouse group and location profile, and the stocking limit will be valid for all the locations under this location profile, in all the warehouses that are part of the specified warehouse group. If All is selected, the behavior is similar to Warehouse group, just that the stocking limit will be valid for all warehouses.

Allow unlimited quantity

When enabled, the location quantity is unlimited. If this check box is cleared, you need to specify the unit and quantity of the item to be stocked in the location.

Stocking limit at location

Warehouse	Location	Location profile ID	Item Number	Unit	Qty
WMS-001	Recv001	Recv	Item A001	Kg	2.5

Purchase order receiving

PO number	Item Number	Unit	Qty	On hand	Allowed Qty
-----------	-------------	------	-----	---------	-------------

D365 F&O warehouse Management Systems (Advance Warehousing)-1

PO00001	Item A001	Kg	4	1	1.5
---------	-----------	----	---	---	-----

In above mentioned example we can receive only 1.5 Kg at Recv001 remaining have to received at other location having empty space.

Warehouse Zone groups

They are nothing but the floors/areas in the warehouse (To identify location accurately)

Eg- Different Floor numbers having same bin location

1F – having Bin Rack 01 in row A0

2F - having Bin Rack 01 in row A0

Warehouse zones can be used as filters for options to control the different warehouse management processes. You need to create a zone group before you can define a zone.

Navigation - Warehouse management > Setup > Warehouse > Warehouse zone groups

Finance and Operations Warehouse management > Setup > Warehouse > Warehouse zone groups

Warehouse zone groups

Standard view

Filter

Zone group ID	Zone group name
1F	1F
2F	2F
GF	GF
MF	MF

Zones

This basically helps to identify and locate items on the basis of their types

Eg- Packing material

Semi finished goods

Finished goods

Incoming material

Quarantine material

If you have a rather large warehouse, the point of using zones in the warehouse would be that it's possible to distinguish between where you want to pick your items or store your pick items,

D365 F&O warehouse Management Systems (Advance Warehousing)-1

your bulk items, frozen items, etc. So, using zones make it easier to have one item placed in many bins and to have default places where to pick and put away and to refill the pick bins.

So, if you have a large and complex warehouse, the zone functionality might come in handy.

It's set up on the location card in the field directed put away and pick.

So this is the location I'm working at.

It's my production plant in this example, and I have defined different zones in my location in this plant.

So first of all, I have a receipt zone meaning when I post a purchase receipt, it goes into my receipt zone so I can have one or several bins defined in receipt zone and I know all the items in there are still awaiting a put away.

Likewise, on the outbound side, I could have a shipping zone that contains all my bins that are marked as shipping bins or set up as shipping bins.

I would have a picking zone and I can refill my picking zone with algorithms in [Business Central](#).

So it's easy for me to have all my high running items in the picking zone available.

Then I could create a bulk zone for items that I want to store away and to fulfill from the bulk zone into the picking zone or the next one, which I have called my warehouse zone so this is my high running zone for picking into my production area containing my raw materials and semi-finished products.

So from the bulk zone, I will refill my warehouse zone to be able to pick faster.

Then I have a production zone.

It could have been just one bin, but I could also if I have a complex production, I could add many bins in consumption and output bins in my production zone so I could pick into that zone.

Likewise, I could have a cross docking zone in the lower-left corner and the cross docking zone is meant for items that I receive and I want to transfer it directly to the shipping zone so I don't want to make put aways and picks.

I just want to add it directly to purchase orders.

A frozen zone or other kinds of special zone could be dedicated zones for items that need to be treated specially.

So I could add functionality on the item and on the bins on the zone that makes the item being fixed to that zone with those bins.

On my zone, I could add bins, of course, all kinds of bins and the bins will be part of the setup coming from the zone so it's easier to control my complete inventory.

D365 F&O warehouse Management Systems (Advance Warehousing)-1

Finance and Operations Warehouse management > Setup > Warehouse > Zones

← Save + New Delete Options

Zones

Standard view * ▾

Filter

Zone ID	Zone name	Zone group ID
C01-01	ANY CATEGORY	1F ▾

Additional location zones

Three new zone fields are available in Microsoft Dynamics 365 Supply Chain Management. Warehouse managers can use them to define additional warehouse organizations or layouts. The new zone fields can be set either manually or by using the Location setup wizard. They can be used in any query or filtering that uses the Locations table.

No additional setup is required to use the zone fields.

Locations

Create locations using the Location setup wizard

Navigation - Warehouse management > Setup > Warehouse > Location setup wizard

Standard view ▾

Location setup wizard

Warehouse Location profile ID Additional Zone 2

Zone ID Additional Zone 1 Additional Zone 3

Line number	Segment description	From num...	To number	Static text	Length
-------------	---------------------	-------------	-----------	-------------	--------

Icon: Folder with numbers 01, 02, 03, 04, 05

1. Go to **Warehouse management > Setup > Warehouse > Location setup wizard**.


D365 F&O warehouse Management Systems (Advance Warehousing)-1

2. In the **Warehouse** field, select the drop-down button to open the lookup.
3. In the list, find and select the desired record.
4. In the list, select the link in the selected row.
5. In the **Zone ID** field, select the drop-down button to open the lookup.
6. In the list, find and select the desired record.
7. In the list, select the link in the selected row.
8. In the **Location profile ID** field, select the drop-down button to open the lookup.
9. In the list, find and select the desired record.
10. In the list, select the link in the selected row.
11. In the list, mark the selected row.
12. In the **From number** field, enter a number. The From number and To number fields define how many locations will be created. For example, if you set From number to 1 and To number to 3 for all four lines in the location format, 81 locations will be created (3x3x3x3).
13. In the **To number** field, enter a number.
14. In the list, find and select the desired record.
15. In the **From number** field, enter a number.
16. In the **To number** field, enter a number.
17. In the list, find and select the desired record.
18. In the **From number** field, enter a number.
19. In the **To number** field, enter a number.
20. In the list, find and select the desired record.
21. In the **From number** field, enter a number.
22. In the **To number** field, enter a number.
23. Select Create.

D365 F&O warehouse Management Systems (Advance Warehousing)-1

Create locations manually

Navigation - Warehouse management > Setup > Warehouse > Locations



Fixed Locations

A permanent location that is assigned to an item in a warehouse. Multiple items can have the same fixed location, and a single item can have multiple fixed locations.

You can define the locations to be used per product or per product variant. It's possible to create multiple fixed locations for the same product within the same warehouse.

Navigation - Warehouse management > Setup > Warehouse >Fixed Locations

