

AutoPatch – Configuration Guide

Basic information:

AutoPatch offers Windows Update Rings where configuration should consist of a minimum of 2 rings. Essentially a Ring1 for Test and a Ring2 for Production.

- Ring1 – Should have user devices that represent different workflows from within the company, so different workflows get the Ring1 Windows Updates first. These users have a Role of informing if the Updates ‘break’ functionality in anyway, and report it to the one responsible for their IT.
- Ring2 – This ring is basically just everyone else that is not in Ring1

AutoPatch Windows Updates includes Updates for:

- Quality
- Feature
- Driver
- Applications (Microsoft)

Pre-Configuration:

To get started you simply need to make a Azure Security Group for each Ring in your configuration. Example Setup (Start the Groups with customer syntax, in this example ill just use netIP):

Azure Pre-Configuration:

- netIP-AutoPatch-Ring1
 - Group Type: Assigned Group
 - This is an assigned group for user devices that will be part of the Test Ring
 - netIP-AutoPatch-Ring2
 - Group Type: Dynamic Device Group
 - This is a Dynamic Group to contain all devices NOT in Ring1.
 - Example Dynamic Group Syntax
- ```
(device.managementType -eq "MDM") and (device.deviceOSType -eq "Windows")
and (device.displayName -notEndsWith "DeviceNameInRing1Group")
```
- For each device in Ring1 you can repeat the syntax:
    - and (device.displayName -notEndsWith "DeviceNameInRing1Group")
    - Where you replace “DeviceNameInRing1Group” with the actual device name

### *Intune Pre-Configuration:*

- Ensure that “Manage Client Broker” has been enabled in the Tenant at the following location:
  - Tenant Administration | Tenant management | Manage client broker
  - Click Manage client broker

- Add the Ring Azure Security Groups under the Windows Autopatch Client Broker
- Ensure “Windows Data” connector is enabled in the following location:
  - Tenant Administration | Connectors and tokens | Windows Data | Windows Data

## AutoPatch Configuration:

### *Intune Configuration:*

If there are existing Update Rings, they should be disabled and deleted, AutoPatch is superior, and we don't want existing Update Rings to conflict with AutoPatch configuration. After cleanup do the following configuration:

- Tenant administration | Autopatch groups | Create Autopatch Group
  1. Basics
    - a. Give the configuration set a name like: netip-AutoPatch-Rings
  2. Deployment Rings
    - a. It will already have 2 rings available, a Test and a Last
      - i. If you need to add another ring, here is where you do it, otherwise..
    - b. Add your Azure Security Group for Ring1 to 'Test'
    - c. Add your Azure Security Group for Ring2 to 'Last'
  3. Update types
    - a. Default is to select all
      - i. Edit as needed
  4. Deployment Settings
    - a. Feature Updates
      - i. Consider carefully what version you want regarding stability for devices
    - b. Driver Updates
      - i. \*Use the same approval method for all deployment rings
        1. This is best option for solid Ring1 tests
    - c. Microsoft Edge Updates
      - i. Put all types as: Stable
      - ii. This is so everyone is on the same Channel for updates.
  5. Release Schedules
    - a. Review settings, and adjust Ring Deployments for anything that is not 'Test'
    - b. Discuss with customer how long the Deadline should be for Updates to roll out to everyone else, after Test has received the,. Default is 2 days.
  6. Scope Tags
    - a. Skip this
  7. Review + create
    - a. Finalize and Create the Configuration-Set

## Post-Configuration:

AutoPatch is now setup, but it creates certain groups that it wants to manage. We chose to make our own Azure Groups, so that, incase AutoPatch is deleted, we are able to retain our groups to use in future configurations. As such our Azure Groups need to be added to the additional Azure Groups that AutoPatch Created.

### *Azure Post-Configuration:*

AutoPatch will have made groups based on the Configuration-Set Name, in our example we used: netip-AutoPatch-Rings

- Autopatch then creates groups like:
  - netip-AutoPatch-Rings – Test
  - netip-AutoPatch-Rings – Last
- Add our Azure Security Groups to the additional AutoPatch Groups:
  - netIP-AutoPatch-Ring1 gets added to netip-AutoPatch-Rings – Test
  - netIP-AutoPatch-Ring2 gets added to netip-AutoPatch-Rings – Last

## Final thoughts and considerations:

1. Make sure your Azure groups are setup with User-Devices in the Ring1 Test Group
2. Ensure that the Ring2 Dynamic Group's Syntax excludes the Ring1 devices.
3. Ensure the customer understands the Role of Ring1 users.
4. That's it, you have successfully deployed Autopatch configuration.