



Prometheus AI Crypto Bot

Quick Start Guide for Customers

Auto-trade crypto from TradingView signals - secure, simple, yours.

The Prometheus AI Crypto Bot runs on your Windows PC and places crypto trades automatically from your indicator's signals (or manually), with automatic take-profits, risk guardrails, live analytics, and bank-grade encrypted storage for your API keys. Works with **Binance, Binance.US, Bybit, OKX, KuCoin and Bitget**.

Get started in 5 steps

1. Open the app and create a **PIN** (it encrypts your saved keys).
2. Create an exchange **API key** with trading enabled (see page 2).
3. Paste your **API Key + Secret**, pick your exchange and **Spot**, then click **Connect** - keep **Safe Mode** on for your first run.
4. (Selling model) paste your **Licence token** under **Webhook -> Cloud signals** to receive signals automatically - no setup, no ngrok.
5. Watch it work in Safe Mode, then turn Safe Mode off and trade a **small size**.

What the screen shows

- **Top bar:** connection status, exchange, balance and live P&L.
- **Left:** API Settings, your public IP (for whitelisting), Open Positions, and BUY / SELL.
- **Right:** Trade Settings (4 tabs) and the live Trade Log.

1. Create your exchange API key

On your exchange go to **API Management -> Create API**, then set the permissions below. This is the most important step - most connection problems come from a missing permission or IP whitelist.

Enable Reading	Yes	Yes	Balance & positions
Spot & Margin Trading	Yes	-	Place spot orders
Futures / Derivatives	-	Yes	Place futures orders
Withdrawals	OFF	OFF	Never needed - keep it disabled
IP whitelist	Yes	Yes	Required once trading is on

- **Disable Withdrawals - always.** The bot never withdraws; a leaked key with withdrawals could drain funds.
- **IP whitelist:** in the app click **Show my IP -> Copy**, paste it into your exchange's "trusted IPs" box. (Tip: if your home IP changes, the app warns you to update it.)
- **Passphrase:** OKX, KuCoin and Bitget give you a third secret - paste it into the app's Passphrase field. Binance and Bybit do not use one.
- **United States:** binance.com is blocked - choose **Binance.US** in the exchange list (or Bybit / OKX / KuCoin / Bitget).

2. Connect (start in Safe Mode)

1. Select your **Exchange** and **Market** (Spot is the safer default).
2. Paste **API Key**, **Secret** (and **Passphrase** if shown).

3. Leave **Safe Mode** ON for the first run - real prices & balance, but fills are simulated, so you can verify everything risk-free.
4. Click **Connect**. The status light turns green and your balance appears.
5. Happy? Turn Safe Mode off (you'll confirm once) and trade small.

3. The settings tabs

- **Execution:** Trade Size - now in coin or **USDT (\$)** - Sizing mode (Fixed lot / Fixed \$ / Risk %), Auto-place SL/TP with TP1/TP2 scale-out, order type, a **Slippage guard**, a **round-up-to-minimum** toggle, and (futures) leverage & margin with a high-leverage warning.
- **Modes & Risk:** Manual trading, **Safe Mode**, Read-only, the full **Guardrails** set (daily loss/profit halt, max positions, cooldown, dedupe, **loss-streak pause**, **max-drawdown halt**, **trading-hours** window), trailing stop, move-to-breakeven, plus **Run on Windows startup** and **Minimize to tray** for 24/7 running (see page 5).
- **Webhook:** the TradingView webhook + **Strategy filter** (acts only on your indicator), a **Test Signal** button, and **Cloud signals** - paste your Relay URL + Licence token.
- **Alerts:** Sound, Desktop and **Telegram** notifications (with Test buttons), an "important events only" filter, and an end-of-day **P&L summary**.

4. Trading & analytics

- **Manual:** pick a Symbol, set the size, press **BUY** or **SELL**.
- **Automatic:** signals arrive by webhook or cloud and the bot opens the trade plus its TP1/TP2 brackets for you.
- **Open Positions:** Close Selected, **Close %** (bank part of a winner - 25/33/50/75%), Set SL/TP, or **PANIC: Close All** to flatten everything instantly.
- **Analytics:** win rate, realized P&L and an equity curve, with a date-range filter, Clear, and Export CSV for your records.

Fees & sizing - read this

- Spot fees are about **0.1% per fill (~0.2% per round trip)**. Keep your take-profit above ~0.25% so wins clear the fee.
- **More trades is not more profit** - frequent trading bleeds capital in fees. Quality over quantity.
- On a \$500 balance, a 0.006 BTC lot (~\$420) uses most of your funds, so you hold one position at a time. Lower the size to run more, or add capital.
- On Binance, holding **BNB** lowers fees by ~25%.

Troubleshooting

Insufficient balance	Your lot costs more than your balance (size is in coins, not \$). Lower the Trade Size.
Invalid API-key / -2015	Trading not enabled or IP not whitelisted. Enable Spot/Futures and add your IP (Show my IP).
Restricted location / 451	Exchange blocked in your region. US: use Binance.US. Else: another exchange or turn off VPN.
Balance shows \$0	Funds are in the other wallet. Move USDT to Spot (Market=Spot) or Futures (Market=Futures).
does not have market symbol	Pair mismatch - use the exchange's pair (e.g. BTCUSDT, not BTCUSD).

5. Power tools & running 24/7

These newer controls let you test safely, take profit smarter, cap your risk and keep the bot trading around the clock. All are optional - defaults are off.

Test & take profit

- **Test Signal** (Webhook tab): fires a fake BUY through the *real* pipeline - sizing, order and SL/TP bracket - on your selected symbol. In **Safe Mode** it is simulated (no real order); with Safe Mode off it asks before placing a real test trade. Use it to prove your size and brackets are correct before going live.
- **Close %** (Open Positions): select a position, pick **25/33/50/75%** and click **Close %** to bank part of a winner (a reduce-only market order) while letting the rest run. Click again to scale out further; **Close Selected** exits the remainder.

Smarter execution (Execution tab)

- **Slippage guard (%)**: skip a signal if price has already moved more than this from the indicator's entry - stops you chasing a candle that ran. e.g. **0.5** = skip if >0.5% away. **0** = off.
- **Round small orders up to the minimum**: if your lot is below the exchange's ~\$5 minimum, tick this to bump it up to the minimum instead of blocking the trade.
- **Leverage warning**: choosing more than **10x** on Futures pops a reminder that liquidation sits near -100/leverage % from entry. Lower leverage = more breathing room.

Extra guardrails (Modes & Risk tab)

- **Loss-streak limit + pause**: after N losing trades in a row, pause new entries for the set number of seconds - a circuit-breaker for a bad run.
- **Max drawdown halt (%)**: if account equity falls this far from its high-water mark, stop opening trades until you reset.
- **Trading-hours window**: only trade between a start and end hour (your PC's local time); set both to 0 to trade all day. Supports overnight windows (e.g. 22 -> 6).

Run 24/7 (Modes & Risk tab)

- **Run automatically when Windows starts**: launches the bot at login. Combine with Safe Mode off + a saved Licence/Webhook so it trades unattended after a reboot.
- **Minimize to system tray on close**: the window's X hides the app to the tray (near the clock) instead of quitting - it keeps trading in the background. Click the tray icon to **Show**, or right-click -> **Quit** to fully exit.
- For true 24/7, leave the PC on (or use a small always-on PC/VPS) and keep your exchange IP whitelist updated.

Security checklist

- Withdrawals **disabled** on the API key.
- Your IP added to the key's whitelist.
- Tested in **Safe Mode** before going live.
- Trading a **small size** until you trust it.
- Keys live only in the app - encrypted behind your PIN.

Need help? Email support@prometheusai.tech or visit prometheusai.tech. Trading places real orders with real money when Safe Mode is off - start small, keep withdrawals off, and never risk funds you can't afford to lose.