

Procédure GRBL + Clonezilla :

Si les commandes ne fonctionnent pas, mettre les bonnes variables d'environnement :

```
nano /root/.bashrc
```

```
export PATH=$PATH:/sbin:/usr/sbin
```

```
source /root/.bashrc
```

Mettre les bonnes adresses IP :

1 ere carte réseau en dhcp :

```
allow-hotplug ens33
```

```
iface ens33 inet dhcp
```

2eme en static (réseau privé)

Secondary interface - réseau Privé

```
allow-hotplug ens34
```

```
iface ens34 inet static
```

```
address 192.168.50.10
```

```
netmask 255.255.255.0
```

Puis Reboot

ensuite apt upgrade + update

install des paquets dependants :

```
apt-get install rsync gawk gnupg curl
```

Install des depots :

```
curl -s https://drbl.org/GPG-KEY-DRBL | gpg --no-default-keyring --keyring gnupg-ring:/etc/apt/trusted.gpg.d/GPG-KEY-DRBL.gpg --import
```

```
chmod 644 /etc/apt/trusted.gpg.d/GPG-KEY-DRBL.gpg
```

```
echo "deb http://free.nchc.org.tw/drbl-core drbl stable" >> /etc/apt/sources.list
```

```
apt update
```

Install drbl

```
apt-get install drbl
```

Vérifié sur les postes si SecureBoot activé.

Éditer le fichier **/etc/drbl/drbl.conf** pour activer la compatibilité **secure boot** :

```
uefi network secure boot for clients. This is still in testing.
```

```
secure_boot_client="yes"
```

ensuite : `drblsrv -i`

puis : `drblpush -i`

Editer le fichier /tftpboot/nbi_img/grub/grub.cfg :

Faire .save du fichier grub.cfg en grub.cfg.save

```
# Created by gen-grub-efi-nb-menu! Do NOT edit unless you know what you are doing!
```

```
set default=clonezilla-se-client
```

```
set timeout_style=menu
```

```
set timeout=10
```

```
set hidden_timeout_quiet=false
```

```
set graphic_bg=yes
```

```
# tftpd_opt can be tftpd_opt=tftp or tftpd_opt="tftp,$tftp_server_ip", e.g., tftpd_opt=tftp,192.168.66.254
```

```
set tftpd_opt=tftp
```

```
# "run_load_netboot" is the flag to avoid load_netboot to be run more than once.
```

```
#
```

```
function load_netboot {
```

```
    set prefix=($tftpd_opt)/grub
```

```
    echo "Grub CPU and platform: $grub_cpu, $grub_platform"
```

```
    echo 'Network status: '
```

```
    net_ls_cards
```

```
    net_ls_addr
```

```
    net_ls_routes
```

```
    # sleep 5
```

```
}
```

```
#
```

```
function load_gfxterm {
```

```
    set gfxmode=auto
```

```
    insmod efi_gop
```

```
    insmod efi_uga
```

```
    insmod gfxterm
```

```
    terminal_output gfxterm
```

```
}
```

```
load_netboot
```

```
# Somehow the grub2 from CentOS 7 will look for unicode.pf2.pf2 if using "loadfont unicode.pf2". While in Debian/Ubuntu it's OK to use "loadfont unicode.pf2".
```

```
if [ x"${graphic_bg}" = xyes ]; then
```

```

if loadfont unicode; then
    load_gfxterm
elif loadfont unicode.pf2; then
    load_gfxterm
fi
fi

if background_image drblwp.png; then
    set color_normal=black/black
    set color_highlight=magenta/black
else
    set color_normal=cyan/blue
    set color_highlight=white/blue
fi

# Decide if the commands: linux/initrd (default) or linuxefi/initrdefi
set linux_cmd=linux
set initrd_cmd=initrd
export linux_cmd initrd_cmd

if [ "${grub_cpu}" = "x86_64" -o "${grub_cpu}" = "i386" ];then
    set linux_cmd=linuxefi
    set initrd_cmd=initrdefi
fi

menuentry "Clonezilla-live" --id clonezilla-se-client {
    echo "Enter Clonezilla..."

    echo 'Loading Linux kernel vmlinuz-pxe...'

    #Add live-netdev="eth0" to force eth0 as primary interface and avoid WWAN0 boot priority see :
https://sourceforge.net/p/clonezilla/discussion/Help/thread/1f90134ddd/

    $linux_cmd Clonezilla-live-vmlinuz initrd=Clonezilla-live-initrd.img boot=live union=overlay username=user
    hostname=hirsute config components noswap edd=on nomodeset enforcing=0 locales=fr_FR.UTF-8 keyboard-layouts=fr
    ocs_live_extra_param= ocs_live_batch=no net.ifnames=0 noeject netboot=nfs
    nfsroot=192.168.10.1:/tftpboot/node_root/clonezilla-live/ ocs_server="192.168.10.1" ocs_daemonon="\ssh\"
    ocs_prerun="\mount -t nfs 192.168.10.1:/home/partimag /home/partimag/\ " ocs_live_run="\clonezilla -l en_US.UTF-8 -p
    choose -k --skip-lite-menu \"

    echo 'Loading initial ramdisk initrd-pxe.img...'

    $initrd_cmd Clonezilla-live-initrd.img
}

menuentry "Local operating system (if available)" --id local-disk {

```

```
echo "Booting first local disk..."

# Generate boot menu automatically

configfile grub/boot-local-efi.cfg

# If not chainloaded, definitely no uEFI boot loader was found.

echo "No uEFI boot loader was found!"

sleep 15

}
```

```
menuentry "Reboot" --id reboot {

    echo "System rebooting..."

    reboot

}
```

```
menuentry "Shutdown" --id shutdown {

    echo "System shutting down..."

    halt

}
```

```
menuentry 'uEFI firmware setup' 'uefi-firmware' {

    echo "Entering uEFI firmware setup..."

    insmod efifwsetup

    fwsetup

}
```

Preparation Master :

Installé toutes les Maj Windows Update

Installé tous les logiciels que l'on souhaite

Généré le fichier depuis ce site : [Generate autounattend.xml files for Windows 10/11](#)

Intégré le fichier dans C:

Ensuite faire un sysprep : `sysprep /generalize /oobe /shutdown /unattend:C:\unattend.xml`

Sauvegarde du Master :

Boot PXE sur le master et lancement de la sauvegarde.

Choisir **device-image**

Choisir **Beginner**

Choisir **savedisk**

Choisir le **disque** à sauvegarder

Choisir l'option de **compression** : z9p

Skip check

Skip

Pas de chiffage

Entrée puis Yes

Restauration d'une image sur les postes :

Choisir **device-image**

Choisir le mode **Beginner**

Choisir **restoredisk**

Choisir l'**image** à restaurer depuis la liste proposée

Choisir le **disque de destination**

Skip check

Entrée puis Yes

Reboot.