Introduction to the Solana CLI

Before running any Solana CLI commands, let's go over some conventions that you will see across all commands. First, the Solana CLI is actually a collection of different commands for each action you might want to take. You can view the list of all possible commands by running:

solana --help To zoom in on how to use a particular command, run:

solana < COMMAND

--help where you replace the text with the name of the command you want to learn more about.

The command's usage message will typically contain words such as, or. Each word is a placeholder for thetype of text you can execute the command with. For example, you can replace with a number such as42 or100.42. You can replace with the base58 encoding of your public key, such as9grmKMwTiZwUHSExjtbFzHLPTdWoXgcg1bZkhvwTrTww.

Keypair conventions

Many commands using the CLI tools require a value for a. The value you should use for the keypair depends on what type of command line wallet you created.

For example, the CLI help shows that the way to display any wallet's address (also known as the keypair's pubkey), is:

solana-keygen pubkey < KEYPAIR

Below, we show how to resolve what you should put independing on your wallet type.

Paper Wallet

In a paper wallet, the keypair is securely derived from the seed words and optional passphrase you entered when the wallet was created. To use a paper wallet keypair anywhere the text is shown in examples or help documents, enter the uri schemeprompt:// and the program will prompt you to enter your seed words when you run the command.

To display the wallet address of a Paper Wallet:

solana-keygen pubkey prompt://

File System Wallet

With a file system wallet, the keypair is stored in a file on your computer. Replacewith the complete file path to the keypair file.

For example, if the file system keypair file location is/home/solana/my_wallet.json , to display the address, do:

solana-keygen pubkey /home/solana/my_wallet.json

Hardware Wallet

If you chose a hardware wallet, use yourkeypair URL, such asusb://ledger?key=0.

solana-keygen pubkey usb://ledger?key

0 Previous Install the Solana CLI Next Solana CLI Reference and Usage