Use metrics to monitor performance

Use the-metrics-enabled option to enable the Prometheus monitoring and alerting service to access Eth Signer.

Install Prometheus

To use Prometheus with EthSigner, install the Prometheus main component. On MacOS, install with Homebrew:

brew install prometheus

Setting up and running Prometheus with EthSigner

To configure Prometheus to run with EthSigner:

```
1. Configure Prometheus to poll EthSigner. For example, add the following YAML fragment to the theprometheus.yml
 2. file:
 3. Example configuration
 4. global
 5. :
 6. scrape interval
 7. :
 8. 15s
 9. scrape_configs
10. :
11. -
12. job_name
13. :
14. "prometheus"
15. static_configs
16. :
17. -
18. targets
19. :
20. [
21. "localhost:9090"
22. ]
23. -
24. job_name
25. :
26. "ethsigner-prod"
27. scrape timeout
28. :
29. 10s
30. metrics path
31. :
32. /metrics
33. scheme
34. :
35. http
36. static_configs
37. :
38. -
39. targets
40. :
41. [
42. "localhost:9546"
43. ]
44. note
45. Alternatively create your own YAML file and add the above example configuration.
46. Start EthSigner with the-metrics-enabled
47. option.
48. ethsigner --chain-id
49. =
50. 2018
51. \
52. --downstream-http-port
53. =
```

54. 8590 55. --metrics-enabled 56. = 57. true 58. \ 59. file-based-signer --key-file 60. = 61. /Users/me/signer/keyFile --password-file 62. = 63. /Users/me/signer/passwordFile 64. TheJVM 65., and PROCESS 66. metrics categories are enabled by default. Use the -metrics-category 67. command line option to update the available categories. 69. To view the full list of available EthSigner metrics viewhttp:///metrics 70. By default this ishttp://localhost:9546/metrics 72. In another terminal, run Prometheus specifying theprometheus.yml 73. file: 74. prometheus --config.file 75. =

View Prometheus graphical interface

- 1. Open a web browser tohttp://localhost:9090
- 2. to view the Prometheus graphical interface.
- 3. ChooseGraph

76. prometheus.yml

78. .

4. from the menu bar and click the Console

77. View the Prometheus graphical interface

- 5. tab below.
- 6. From theInsert metric at cursor
- 7. drop-down, select a metric and clickExecute
- 8. . The values display. Edit this page Last updatedonMar 30, 2023 byEric LinPrevious Configure TLS Next Create external signers