



Helm Customization Guide for UnityCloud

Release UC-5.2.0

Updated: May 2025

Affirmed Networks Inc.

A Microsoft Company

Copyright© 2025 Affirmed Networks, Inc. All Rights Reserved.

AFFIRMED & DESIGN®, ACUITAS SERVICE MANAGEMENT SYSTEM®, AFFIRMED NETWORKS MOBILE CONTENT CLOUD™, AFFIRMED OPEN WORKFLOW™, AFFIRMED MOBILE CONTENT CLOUD™, UnityCloud™, UnityCloud PaaS™, UnityCloud Platform™, UnityCloud Operations™, UnityCloud Ops™, Operations and Policy Manager (OPM)™ and other trademarks and designs are the registered or unregistered trademarks of Affirmed Networks, Inc. and its subsidiaries in the United States and in foreign countries. All other trademarks are the property of their respective owners. The Affirmed Networks, Inc. trademarks may not be used in connection with any product or service that is not Affirmed Networks' in any manner that is likely to cause confusion among customers or in any manner that disparages or discredits Affirmed Networks, Inc.

This document contains information that is the property of Affirmed Networks, Inc. This document may not be copied, reproduced, reduced to any electronic medium or machine readable form, or otherwise duplicated, and the information herein may not be used, disseminated or otherwise disclosed, except with the prior written consent of Affirmed Networks, Inc.

AMF-MME Helm Documentation

fed-amf-mme values

Contents

- [Global Parameters](#)
- [File Server Parameters](#)
- [Configuration Manager Parameters](#)
- [Istio Gateway Parameters](#)
- [DNS Agent Parameters](#)
- [GTP-C Agent Parameters](#)
- [NRF Agent Parameters](#)
- [Timer Parameters](#)
- [Subscriber Analyzer Parameters](#)
- [AMF Call Control Parameters](#)
- [AMF Tracking Area Manager Parameters](#)
- [AMF Monitor Parameters](#)
- [AMF N2 Parameters](#)
- [LI X1 Parameters](#)
- [LI X2 Parameters](#)
- [Istio LI Gateway Parameters](#)
- [MME Call Control Parameters](#)
- [MME Tracking Area Manager Parameters](#)
- [MME S1 Parameters](#)
- [Diameter Base Parameters](#)
- [Routing Parameters](#)
- [Interface Manager Parameters](#)
- [Unified Load Balancer Parameters](#)
- [Common dataplane Parameters](#)
- [LB PPE Parameters](#)

global

Description

Global parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
vault	Vault Related attributes			No	object
secretNames	Name of secrets to be pulled from AKV or Hashicorp Vault			No	object
defaultRbacEnabled	Configuring defaultRbacEnabled to true will create clusterrolebinding. Configuring defaultRbacEnabled to false, clusterrolebinding will not be created. Examples: - false	true		No	boolean
enableNfEgressCommunication	Configuration to enable NF external communication through Istio Egress Gateway for use cases like mTLS communication Examples: - true	false		No	boolean
enableStaticNfEgressCommunication	Configuration to enable statically configured NF external communication through Istio Egress Gateway for use cases like mTLS communication Examples: - true	false		No	boolean
nodeDataplaneAffinity	If some worker nodes have been assigned a nodetype of "dataplane", and this variable is "true", pod-lb_ppe pods will be exclusively assigned to those dataplane nodes.	false		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
defaultClusterRole	clusterrole and PSP for is created as a part of fed-rbac. defaultClusterRole options are restricted-cr, permissive-network-cr, permissive-full-cr Examples: - permissive-network-cr	permissive-network-cr		No	string
defaultServiceAccountName	serviceaccount will be created by default. defaultServiceAccountName configuration is used to create default serviceaccount per namespace Examples: - fed-amf-mme-serviceaccount	fed-amf-mme-serviceaccount		No	string
enableLivenessProbe	Support Liveness Probe in this federation; must be true in this federation Examples: - true - false	true		No	boolean
podPriorityEnabled	Support enabling pod priority in this federation; must be true in this federation Examples: - true - false	true		No	boolean
destinationSubsetsEnabled	Controls whether subsets and weights in Destination rule and Virtual services are enabled or not. Examples: - true - false	false		No	boolean
kargoProfileTag	This enables creation of specific kargo-default-profile for fed-amf-mme			No	string
ingressNetworkPolicy	network policies configuration			No	object
tabdb	PaaS Tabular database associations			No	object
filesserver	PaaS filesserver associations			No	object
istio	Istio related configurations			No	object
mesh	PaaS service mesh associations			No	object
monitoring	PaaS Monitoring associations			No	object
registry	PaaS container registry associations			No	object
envVars	Environment variables			No	object
encryptDecryptKey	Secret pass phrase used for Encryption/Decryption of LI Data only. This is a private key needed in case AKV is not enabled and encryptPaasDataForLI is enabled.			No	object
grafana	PaaS Grafana association			No	object
logging	PaaS logging association			No	object
fileCheckPath	Need to set only while using Mellanox NIC. Directory where multus config file is present on local node Examples: - /etc/cni/net.d	/etc/cni/net.d		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
fileCheckFile	Need to set only while using Mellanox NIC. Name of the multus config file on local node Examples: - 00-multus.conf			No	string
license	PaaS License Server Selector			No	object
enableGtpcAgent	Use this variable to enable/disable gtpcagent Examples: - true - false	true		No	boolean
enableLIX1	Use this variable to enable/disable the li-x1 microservice. Examples: - true	true		No	boolean
enableLIX2	Use this variable to enable/disable the li-x2 microservice. Examples: - true	true		No	boolean
enableAmfFunction	Support AMF function in this federation. Examples: - true - false	true		No	boolean
enableMmeFunction	Support MME function in this federation. Examples: - true - false	false		No	boolean
onPrem	Enable On-premises deployment. Examples: - true - false	false		No	boolean
useSas	Controls whether SAS logging is enabled or not Examples: - true - false	false		No	boolean
sasAddress	SAS Server address Examples: - 1.1.1.101			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
sasTracingNonUEAssociatedEnabled	Controls whether SAS tracing for non UE associated procedure is enabled or not	false		No	boolean
	Examples:				
	- true - false				
customCoreDumpPath	Core dump files generated inside a container are written to this location and then left there, rather than relocating cores using the paas pod-cores_mgr. This path should be mounted to a valid storage device.			No	string
	Examples:				
	- /mnt/coreDumps				
opentelemetry				No	object
diameterGroups	This deployment variable ensures diameter service names are known to application monitors. The diameter group names given here are referenced in pod-diameter_base scope. If a group name is added to/removed from the below list, user must make sure to add/remove the corresponding entry in diameterGroups of pod-diameter_base scope as well. This is because the group name in below list is referenced by the pod-diameter_base scope.			No	array
metricsScrapeInterval	Prometheus metrics scrape interval. Default value set to 1m,promethues will scrape the metrics for every 1 minute.	1m		No	string
	Examples:				
	- 1m				
topologySpreadConstraints	Pod topology spread constraints control how pods of given microservice type are spread across the cluster among failure-domains such as regions, zones, nodes, and other user-defined topology domains. This can help to achieve high availability as well as efficient resource utilization.			No	object
externalGtpcSvc	External GTPC service parameters			No	array
fqdnIpList	FQDN to LB service IP mapping used by applications.			No	array
issu	ISSU parameters			No	object

global vault

Description

Vault Related attributes

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Vault feature	false		No	boolean
	Examples:				
	- false				
	- true				
azureKeyVault	AzureKeyVault related configurations			No	object

global vault azureKeyVault

Description

AzureKeyVault related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	AzureKeyVault Enable/Disable flag	false		No	boolean
	Examples:				
	- false				
tenantID	Tenant ID of Customer where AzureKeyVault is deployed			No	string
keyVaultName	KeyVault of Customer where secrets are stored			No	string
aksCluster	Azure Kuberetes Cluster	true		No	boolean
	Examples:				
	- false				
userManagedId	ClientID of User managed ID			No	string
workloadIdentity	workload Identity	true		No	boolean
	Examples:				
	- false				

global secretNames

Description

Name of secrets to be pulled from AKV or Hashicorp Vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cfgmgr	Name of secrets used by configuration manager			No	object
likey	Name of the secrets used by LI when AKV Vault is enabled			No	object
ingressgwl	Name of the secrets used by Ingress LI Gateway when AKV vault is enabled			No	object
egressgwl	Name of the secrets used by Egress LI Gateway when AKV vault is enabled			No	object

global secretNames cfgmgr

Description

Name of secrets used by configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
confdKey	Vault Secret Name for confd AES key			No	string
encryptConfigKeySecretName	Vault Secret Name for Encyrpt Config key			No	string
adminDomainCAkeySecretName	Vault Secret Name for Admin Domain CA key			No	string
liadminDomainCAkeySecretName	Vault Secret Name for LI Admin Domain CA key			No	string
maintDomainCAkeySecretName	Vault Secret Name for Maint domain CA key			No	string
limaintDomainCAkeySecretName	Vault Secret Name for LI Maint domain CA key			No	string
rootDomainCAkeySecretName	Vault Secret Name for root domain CA key			No	string
rootPasswdSecretName	Vault Secret Name for root password			No	string
rootPubkeySecretName	Vault Secret Name for root public key			No	string
m2mPubkeySecretName	Vault Secret Name for m2m public key			No	string
adminUsers	List of Admin users for configuration manager			No	array

Parameter	Description	Default	Value/Range	Mandatory	Type
liadminUsers	List of LI Admin users for configuration manager			No	array
operUsers	List of Oper users for configuration manager			No	array
lioperUsers	List of LI Oper users for configuration manager			No	array
readonlyUsers	List of read-only users for configuration manager			No	array
userProvided	Secret Name of certificates used by RESTCONF			No	object

[global secretNames cfgmgr](#) adminUsers

Description

List of Admin users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

[global secretNames cfgmgr](#) liadminUsers

Description

List of LI Admin users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

[global secretNames cfgmgr](#) operUsers

Description

List of Oper users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

[global secretNames cfgmgr](#) lioperUsers

Description

List of LI Oper users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

[global secretNames cfgmgr](#) readonlyUsers

Description

List of read-only users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

[global secretNames](#) [cfgmgr](#) [userProvided](#)

Description

Secret Name of certificates used by RESTCONF

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
tls crtSecretName	Secret Name of server TLS certificate			No	string
tls keySecretName	Secret Name of server TLS key			No	string
ca certSecretName	Secret Name of CA certificate			No	string

[global secretNames](#) [likey](#)

Description

Name of the secrets used by LI when AKV Vault is enabled

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
secretName	vault secret name for li-key			No	string
versionsToSync	Number of versions to sync			No	integer

[global secretNames](#) [ingressgwli](#)

Description

Name of the secrets used by Ingress LI Gateway when AKV vault is enabled

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
userProvided	AKV provided certificates			No	object

[global secretNames](#) [ingressgwli](#)/[userProvided](#)

Description

AKV provided certificates

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ca certSecretName	cacertSecretName Configuration				
	Examples:			No	string
tls crtSecretName	tls crtSecretName configuration				
	Examples:			No	string
tls keySecretName	tls keySecretName configuration				
	Examples:			No	string

[global secretNames](#) [egressgwli](#)

Description

Name of the secrets used by Egress LI Gateway when AKV vault is enabled

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
userProvided	AKV provided certificates			No	object

[global secretNames](#) egressgwli/userProvided

Description

AKV provided certificates

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cacertSecretName	cacert Configuration				
	Examples:			No	string
tls crtSecretName	tls crtSecretName configuration				
	Examples:			No	string
tlskeySecretName	tlskeySecretName configuration				
	Examples:			No	string

[global ingressNetworkPolicy](#)

Description

network policies configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabled network policy	true		No	boolean
ingressTrafficNamespaces	Namespaces which are required to be allowed for ingress traffic			No	array

[global tabdb](#)

Description

PaaS Tabular database associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
etcd	Etcd database association			No	object

[global tabdb](#) etcd

Description

Etcd database association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Etcd db instance name				
	Examples:	etcd-server		No	string
	- etcd-server				
svc	Tab-DB service path				
	Examples:	etcd-cluster-client.fed-db-etcd.svc.cluster.local		No	string
	- etcd-cluster-client.fed-db-etcd.svc.cluster.local				

Parameter	Description	Default	Value/Range	Mandatory	Type
port	Tab-DB service port	2379		No	string
targetPort	Tab-DB service target port	31869		No	string

global fileserver

Description

PaaS fileserver associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ui	Fileserver UI association			No	object
nfs	NFS fileserver association			No	object

global fileserver ui

Description

Fileserver UI association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
loadBalancerPort	Fileserver UI load balancer port	85		No	string
serviceAnnotations	Service annotations			No	object

global fileserver ui serviceAnnotations

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

global fileserver nfs

Description

NFS fileserver association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Fileserver remote host address				
remoteHost	Examples: - 1.1.1.100			No	string
	Fileserver remote file path				
remotePath	Examples: - /filestore	/filestore		No	string
remotePort	Fileserver remote host port	85		No	string

global istio

Description

Istio related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtls	Istio mutual TLS related configuration			No	object

[global istio](#) mtls

Description

Istio mutual TLS related configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable istio mutual TLS	false		No	boolean

[global](#) mesh

Description

PaaS service mesh associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio service mesh association			No	object

[global mesh](#) istio

Description

Istio service mesh association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGwLi	Istio service mesh LI ingress GW			No	object
	Service mesh ingress gateway				
ingressGw	Examples: - ingress-gateway	ingress-gateway		No	string
	Specific IP requested for Ingress Gateway LoadBalancer service				
ingressGwIP	Examples: -			No	string
	FQDN to be added as annotation to the Ingress Gateway LoadBalancer service				
ingressGwFQDN	Examples: -	amf.com		No	string
mtlsEnabled	Enable/disable istio mutual TLS	false		No	boolean
egressGwTLSLi	Istio egress gateway TLS for LI			No	object
ingressGwTLSLi	Istio ingress gateway TLS for LI			No	object
serviceAnnotations	Service annotations			No	object

[global mesh istio](#) ingressGwLi

Description

Istio service mesh LI ingress GW

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGwIP	Specific IP requested for LI Ingress Gateway LoadBalancer service				
	Examples:			No	string
	-				
ingressInitialProtocol	protocol for ingressGwLi port				
	Examples:	https		No	string
	-				
serviceAnnotations	Service annotations			No	object

[global mesh istio](#) [ingressGwLi/serviceAnnotations](#)

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

[global mesh istio](#) [egressGwTLSLi](#)

Description

Istio egress gateway TLS for LI

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio egress gateway TLS for LI				
	Examples:	false		No	boolean
	- true				
mode	Istio egress gateway TLS mode for LI.				
	Examples:	MUTUAL		No	string
	- MUTUAL				
userProvided	userProvided CERTIFICATES			No	object
userProvidedVault	Helm configuration to use user provided certificates configured in vault			No	object

[global mesh istio](#) [egressGwTLSLi](#) [userProvided](#)

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvided Certificates				
	Examples:	false	No	boolean	
	- false				
	- true				

Parameter	Description	Default	Value/Range	Mandatory	Type
cacert	cacert Configuration				
	Examples:			No	string
	- Copy and Paste End User generated Certificate				
tls crt	tls crt configuration				
	Examples:			No	string
	- Copy and Paste End User generated Certificate				
tls key	tls key configuration				
	Examples:			No	string
	- Copy and Paste End User generated Certificate				

global mesh istio egressGwTLSLi userProvidedVault

Description

Helm configuration to use user provided certificates configured in vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvidedVault Certificates				
	Examples:				
	- false	false		No	boolean
	- true				

global mesh istio ingressGwTLSLi

Description

Istio ingress gateway TLS for LI

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio ingress gateway TLS for LI				
	Examples:				
	- true	false		No	boolean
	- false				
mode	Istio ingress gateway TLS mode for LI.				
	Examples:		MUTUAL	No	string
	- MUTUAL				
userProvided	userProvided CERTIFICATES			No	object
userProvidedVault	Helm configuration to use user provided certificates configured in vault			No	object

global mesh istio ingressGwTLSLi userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvided Certificates	false		No	boolean
	Examples:				
	- false				
cacert	- true				
	cacert Configuration			No	string
	Examples:				
tlskey	- Copy and Paste End User generated Certificate				
	tlskey configuration			No	string
	Examples:				
tlskey	- Copy and Paste End User generated Certificate				
	Examples:			No	string
	- Copy and Paste End User generated Certificate				

[global mesh istio ingressGwTLS](#)[Li userProvidedVault](#)

Description

Helm configuration to use user provided certificates configured in vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvidedVault Certificates	false		No	boolean
	Examples:				
	- false				
	- true				

[global service](#) [serviceAnnotations](#)

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

[global monitoring](#)

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association		No		object

[global monitoring](#) [prometheus](#)

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
namespace	Monitoring namespace	fed-prometheus		No	string
	Examples:				
	- fed-prometheus				
enabled	Enable/disable prometheus monitoring	true		No	boolean

global registry

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

global registry docker

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string
imagePullSecret	Pull an image from a private registry			No	string

global envVars

Description

Environment variables

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
fedType	Federation type	amf-mme	Enumerations: - amf-mme	No	string
	Examples:				
	- amf-mme				
fedUniqueName	Federation unique name	default		No	string
	Examples:				
	- smf				
encryptPaasDataForLI	Enable / Disable LI paas content encryption/decryption. When encryption is enabled, and AKV vault is in use the encryption/decryption key value(Secret pass phrase) will be retrieved from the vault. If AKV vault is not in use it is mandatory to provide a secret pass phrase in the encryptDecryptKey field as a input	true		No	boolean
configDataEncryptionEnable	Enable config JSON file encryption. When true, also requires injection of encryption key as kubernetes secret or it won't encrypt.	false		No	boolean
	Examples:				
	- true - false				

Parameter	Description	Default	Value/Range	Mandatory	Type
enableRoaming	Enable / Disable roaming feature.	false		No	boolean
	Examples:				
	- true				
	- false				
enableAmfSet	Enable / Disable amfSet feature.	false		No	boolean
	Examples:				
	- true				
	- false				

global encryptDecryptKey

Description

Secret pass phrase used for Encryption/Decryption of LI Data only. This is a private key needed in case AKV is not enabled and encryptPaasDataForLI is enabled.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable creation of Kubernetes secret for encryptDecryptKey.key	true		No	boolean
key	Encryption Key value (secret pass phrase). It can be alphanumeric and case sensitive.			No	string
	Examples:				
	- abcd1234PQRS				

global grafana

Description

PaaS Grafana association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association	true		No	boolean
url	Exposed grafana URL			No	string
	Examples:				
	- http: //1.1.1.1:3000				
prometheusinfo	Prometheus server association			No	object

global grafana prometheusinfo

Description

Prometheus server association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
url	Prometheus server URL	http: //prometheus.fed-prometheus:9090		No	string
	Examples:				
	- https: //prometheus.fed-prometheus:9090				

global logging

Description

PaaS logging association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable logging association	false		No	boolean
	Examples:				
	- true				
	- false				
fluentd	fluentd configurations			No	object
elastic	Elasticsearch association			No	object
enableAddITargets	Enable/disable additional destinations	false		No	boolean
	Examples:				
	- true				
	- false				
addITargets	Additional logging output destination configuration			No	array
alerts	Elastalert association			No	object

global logging fluentd

Description

fluentd configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	fluentd buffer configurations			No	object

global logging fluentd buffer

Description

fluentd buffer configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Total buffer size. Maximum amount of buffer space each fluentd thread would use to keep logs. After this space is exhausted, fluentd would start deleting oldest logs to make room for new logs.	512m		No	string
retryWait	Interval(seconds) at which the buffer flush is retried in case of failure.	180s		No	string
maxRetries	Max number of retries to flush a buffer chunk. After this is exhausted, fluentd would delete the chunk.	10		No	integer

global logging elastic

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ip	Elasticsearch IP address			No	string
	Examples:				
	- 10.15.10.161				
Port	Elasticsearch port	9200		No	integer

global logging addITargets

Description

Additional logging output destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			Yes	object

[global logging addlTargets](#) [forward](#)

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
Hostname or IP Address of the forward server					
Examples:					
host	- 192.168.1.1			No	string
	- forward-server.com				
Port of the forward server					
port	Examples:	24224		No	integer
	- 24224				

[global logging alerts](#)

Description

Elastalert association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Enable/disable event based alerts					
Examples:					
enabled	- false	false		No	boolean
	- true				
Elastalert IP address					
host	Examples:			No	string
	- 10.15.16.64				
port	Elastalert port number	3030		No	integer
realert	Alerts will be repeated after the realert duration			No	object
receivers	The platform on which alerts can be sent			No	array

[global logging alerts](#) [realert](#)

Description

Alerts will be repeated after the realert duration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minutes	An explanation about the purpose of this instance.	1		No	integer

global logging alerts receivers

Description

The platform on which alerts can be sent

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
slack	Slack channel			No	object
post	Configuration for HTTP post			No	object
email	Configuration for email receiver			No	object

global logging alerts receivers slack

Description

Slack channel

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
webhookurl	Webhook url of the receiver slack channel			No	string

global logging alerts receivers post

Description

Configuration for HTTP post

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
http_post_url	HTTP post URL			No	string

global logging alerts receivers email

Description

Configuration for email receiver

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
to_address	Receiver email address			No	string
smtp_host	The smtp host ip			No	string
smtp_port	The smtp port number			No	string
smtp_ssl	This should be disabled	false		No	boolean
from_addr	Sender address			No	string

global license

Description

PaaS License Server Selector

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
flexera	Flexera license server information			No	object

global license flexera

Description

Flexera license server information

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
remoteHost	Flexera license server host				
	Examples:			No	string
	- 10.163.67.251				
remotePort	Flexera license server port				
	Examples:			No	string
	- 7070				

global opentelemetry

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable opentelemetry	true		No	boolean
tlsEnabled	Enable mTLS on opentelemetry	false		No	boolean
tracing	Configuration options for opentelemetry traces			No	object

global opentelemetry tracing

Description

Configuration options for opentelemetry traces

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable opentelemetry tracing	true		No	boolean
host	opentelemetry fqdn			No	string
port	opentelemetry port	80		No	integer

global diameterGroups

Description

This deployment variable ensures diameter service names are known to application monitors. The diameter group names given here are referenced in pod-diameter_base scope. If a group name is added to/removed from the below list, user must make sure to add/remove the corresponding entry in diameterGroups of pod-diameter_base scope as well. This is because the group name in below list is referenced by the pod-diameter_base scope.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
groupName	Name of diameter-base group				
	Examples:				
	- group1			Yes	string
	- group2				
enabled	Enable/disable diameter-base group				
	Examples:				
	- true			Yes	boolean
	- false				

global topologySpreadConstraints

Description

Pod topology spread constraints control how pods of given microservice type are spread across the cluster among failure-domains such as regions, zones, nodes, and other user-defined topology domains. This can help to achieve high availability as well as efficient resource utilization.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable pod topology spread constraints	true		No	boolean
	Examples:				
	- false				
constraints	- true			No	array
	List of pod topology spread constraints to be applied.				

global topologySpreadConstraints constraints

Description

List of pod topology spread constraints to be applied.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Definition of pod topology spread constraint to be applied to the pod specification.			No	object

global topologySpreadConstraints constraints 0

Description

Definition of pod topology spread constraint to be applied to the pod specification.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxSkew	Describes the degree to which pods may be unevenly distributed. It's the maximum permitted difference between the number of matching pods in any two topology domains of a given topology type. It must be greater than zero.	1		No	integer
	Examples: - 1				
topologyKey	Its the key of node labels. If two nodes are labelled with this key and have identical values for that label, the Kubernetes scheduler treats both nodes as being in the same topology. The scheduler tries to place a balanced number of Pods into each topology domain.	kubernetes.io/hostname		No	string
	Examples: - kubernetes.io/hostname				
whenUnsatisfiable	Indicates how to deal with a pod if it doesn't satisfy the defined pod topology spread constraint.	ScheduleAnyway		No	string
	Examples:				
	- ScheduleAnyway - DoNotSchedule				

global externalGtpcSvc

Description

External GTPC service parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable external service	true		Yes	boolean
	Examples: - false				
name	Name of external gtpc agent service	n26-amf	Enumerations: - n26-amf - s11-mme - s10 - n26-mme	Yes	string
	Examples: - s10				
loadBalancerIP	IP assigned to the load balancer for this service. Examples: - 1.1.1.1			Yes	string
secondaryIP	Secondary IP assigned to the load balancer for this service. Examples: - 2.2.2.2			No	string
loadBalancerFQDN	If specified, this is added as an annotation to the gtpc_agent service. Other applications can then query to find the FQDN through which external peers can reach this application Examples: - pgw.affirmed.com			No	string
type	Interface type for gtpc_agent microservice			Yes	array

global fqdnIpList

Description

FQDN to LB service IP mapping used by applications.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
fqdn	FQDN. Examples: - n2-primary-fqdn			Yes	string
	- n2-secondary-fqdn - s6-fqdn - s1-fqdn - sgs-fqdn				
ipAddresses	External IP address of the NF interface.			Yes	array

global issu

Description

ISSU parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable ISSU	true		No	boolean
	Examples:				
	- true				
	- false				
preUpgrade	Pre-upgrade parameters			No	object
postUpgrade	Post-upgrade parameters			No	object
preRollback	Pre-rollback parameters			No	object
postRollback	Post-rollback parameters			No	object
test	helm test parameters			No	object
mmeKpis	KPIs to be validated for MME			No	array
amfKpis	KPIs to be validated for AMF			No	array

global issu preUpgrade

Description

Pre-upgrade parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
validatePods	Validate pods status			No	boolean
validateKpis	Validate KPIs			No	boolean
validateNfState	Validate NF state			No	boolean

global issu postUpgrade

Description

Post-upgrade parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
validatePods	Validate pods status			No	boolean
validateKpis	Validate KPIs			No	boolean
validateNfState	Validate NF state			No	boolean

global issu preRollback

Description

Pre-rollback parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
validatePods	Validate pods status			No	boolean
validateKpis	Validate KPIs			No	boolean
validateNfState	Validate NF state			No	boolean

global issu postRollback

Description

Post-rollback parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
validatePods	Validate pods status			No	boolean
validateKpis	Validate KPIs			No	boolean
validateNfState	Validate NF state			No	boolean

global issu test

Description

helm test parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
validatePods	Validate pods status			No	boolean
validateKpis	Validate KPIs			No	boolean
validateNfState	Validate NF state			No	boolean

global issu mmeKpis

Description

KPIs to be validated for MME

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the KPI			Yes	string
threshold	Threshold value for the KPI			Yes	number

global issu amfKpis

Description

KPIs to be validated for AMF

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the KPI			Yes	string
threshold	Threshold value for the KPI			Yes	number

pod-fileserver

Description

PaaS Fileserver Microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable fileserver				
enabled	Examples: - true - false	true		No	boolean
deployment	Deployment parameters			No	object
pvc	Persistent Volume Claim (PVC) configuration			No	object

pod-fileserver deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer

pod-fileserver pvc

Description

Persistent Volume Claim (PVC) configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
web	PVC web configuration			No	object
cfg	PVC cfg configuration			No	object

pod-fileserver pvc web

Description

PVC web configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Requests storage for pvc				
requestsStorage	Examples: - 25Gi	5Gi		No	string
	Storage class name for pvc				
storageClassName	Examples: - rook-cephfs	web		No	string

pod-fileserver pvc cfg

Description

PVC cfg configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Requests storage for pvc				
requestsStorage	Examples: - 25Gi	5Gi		No	string
	Storage class name for pvc				
storageClassName	Examples: - rook-cephfs	cfg		No	string

pod-cfgmgr

Description

Config Manager Microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable cfgmgr	true		No	boolean
	Examples:				
	- true - false				
confd	Conf parameters			No	object
rbacEnabled	Configuring rbacEnabled to true will create clusterrolebinding. Configuring rbacEnabled to false, clusterrolebinding will not be created.	true		No	boolean
	Examples:				
	- false				
clusterRole	clusterrole and PSP for is created as a part of fed-rbac. clusterrole options are restricted-cr, permissive-network-cr, permissive-full-cr	permissive-full-cr		No	string
	Examples:				
	- permissive-full-cr				
serviceAccountName	serviceAccountName configuration is used to create serviceaccount per pod	cfgmgr-serviceaccount		No	string
	Examples:				
	- cfgmgr-serviceaccount				
deployment	Deployment parameters			No	object
service	Service parameters			No	object

pod-cfgmgr confd

Description

Conf parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
aes256cfb128Key	encoded confd aes256cfb128Key, echo f9c4065f6592b38cc3dbaf2033f73b6c54751c4425faf688857704004306d65a	base64		No	

pod-cfgmgr deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer

pod-cfgmgr service

Description

Service parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
portPrefix	Service port prefix	301	min: 301 max: 309	No	number

Parameter	Description	Default	Value/Range	Mandatory	Type
loadBalancerIP	Load Balancer IP address				
	Examples:			No	string
	- 10.1.1.101				
loadBalancerFQDN	If specified, this is added as an annotation to the cfgmgr service. Other applications can then query to find the FQDN through which external peers can reach this application				
	Examples:			No	string
	- cfgmgr.amf.affirmed.com				
serviceAnnotations	Service annotations			No	object

pod-cfgmgr service/propoerties/serviceAnnotations

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

pod-istio_gw

Description

Istio Gw Microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable istio-gw				
	Examples:			No	boolean
	- true	true			
istioNspace	Istio namespace				
	Examples:			No	string
	- fed-istio	fed-istio			
egressGateway	Egress gateway parameters			No	object
ingressGateway	Ingress gateway parameters			No	object

pod-istio_gw egressGateway

Description

Egress gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable egress gateway				
	Examples:			No	boolean
	- true	true			
deployment					
	Deployment parameters			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

pod-kafka_rplay_agt deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
strategy	Deployment Update strategy			No	object

pod-kafka_rplay_agent deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-kafka_rplay_agent deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	25%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	25%		No	string

pod-istio_gw egressGateway hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable egress gateway HPA				
	Examples:	true		No	boolean
	- false				
workerCpuRequests	CPU request egress application				
	Examples:	800m		No	string
	- 800m				
minReplicas	Specify the minimum replica count for egress gateway				
	Examples:	1		No	integer
	- 3				

Parameter	Description	Default	Value/Range	Mandatory	Type
maxReplicas	Specify the maximum replica count for egress gateway	5		No	integer
	Examples:				
	- 5				
averageUtilization	Specify the target CPU utilization level when hpa would trigger	80		No	integer
	Examples:				
	- 80				

pod-istio_gw ingressGateway

Description

Ingress gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable ingress gateway	true		No	boolean
	Examples:				
	- true - false				
deployment	Deployment parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

pod-kafka_rplay_agt deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
strategy	Deployment Update strategy			No	object

pod-kafka_rplay_agent deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-kafka_rplay_agent deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	25%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	25%		No	string

pod-istio_gw ingressGateway hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable ingress gateway HPA				
	Examples:	true		No	boolean
	- false				
workerCpuRequests	CPU request ingress application				
	Examples:	800m		No	string
	- 800m				
minReplicas	Specify the minimum replica count for ingress gateway				
	Examples:	1		No	integer
	- 3				
maxReplicas	Specify the maximum replica count for ingress gateway				
	Examples:	5		No	integer
	- 5				
averageUtilization	Specify the target CPU utilization level when hpa would trigger				
	Examples:	80		No	integer
	- 80				

pod-dns_agent

Description

DNS Agent Microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable DNS agent				
	Examples:				
	- true	true		No	boolean
	- false				
deployment	Deployment parameters			No	object
upgrade	Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

pod-dns_agent deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count				
	Examples:	1	min: 0	No	integer
	- 1				
strategy	Deployment Update strategy			No	object
injectIstioProxy	Enable/Disable istio-proxy				
	Examples:				
	- true	false		No	boolean
	- false				

pod-dns_agent deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-dns_agent deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

pod-dns_agent upgrade

Description

Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable canary sequence				
	Examples:				
	- true	false		No	boolean
	- false				
canaryVersWeight	Canary pod weight percentage				
	Examples:	0	min: 0	No	integer
	- 0		max: 100		

Parameter	Description	Default	Value/Range	Mandatory	Type
stableVersWeight	Stable pod weight percentage	100	min: 0 max: 100	No	integer
	Examples:				
	- 0				
stableVersion	Stable pod image version			No	string
	Examples:				
	- 0.0.0				
stableInfraImage	Infra container stable image			No	string
	Examples:				
	-				
stableWorkerImage	Worker container stable image			No	string
	Examples:				
	-				

pod-dns_agent hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA	true		No	boolean
	Examples:				
	- true				
	- false				
infraCpuRequests	Infra container HPA CPU requests	10m		No	string
	Examples:				
	- 10m				
workerCpuRequests	Worker container HPA CPU requests	980m		No	string
	Examples:				
	- 980m				
workerCpuLimits	Worker container HPA CPU limits	1000m		No	string
	Examples:				
	- 1000m				
maxReplicas	Pod maximum replicas	5	min: 0	No	integer
	Examples:				
	- 5				
minReplicas	Pod mininum replicas	2	min: 0	No	integer
	Examples:				
	- 2				

Parameter	Description	Default	Value/Range	Mandatory	Type
averageUtilization	Pod average utilization	75	min: 0 max: 100	No	integer
	Examples:				
	- 75				

pod-gtpc_agent

Description

GTP-C Agent Microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
PMNDeployment	Enable/disable PMNDeployment	false		No	boolean
	Examples:				
	- true - false				
deployment	Deployment parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
tracing	Tracing parameters			No	object

pod-gtpc_agent deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1	min: 0	No	integer
	Examples:				
	- 1				
strategy	Deployment Update strategy			No	object
injectIstioProxy	Enable/Disable istio-proxy	false		No	boolean
	Examples:				
	- true - false				

pod-gtpc_agent deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-gtpc_agent deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

pod-gtpc_agent hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA				
	Examples:				
	- true	true		No	boolean
	- false				
infraCpuRequests	Infra container HPA CPU requests				
	Examples: - 10m	10m		No	string
workerCpuRequests	Worker container HPA CPU requests				
	Examples: - 980m	980m		No	string
workerCpuLimits	Worker container HPA CPU limits				
	Examples: - 1000m	1000m		No	string
maxReplicas	Pod maximum replicas				
	Examples: - 3	3	min: 0	No	integer
minReplicas	Pod minimum replicas				
	Examples: - 1	1	min: 0	No	integer
averageUtilization	Pod average utilization				
	Examples: - 75	75	min: 0 max: 100	No	integer

pod-gtpc_agent tracing

Description

Tracing parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable tracing	false		No	boolean
	Examples: - false				
samplerType	Sampler type. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration	probabilistic	Enumerations: - const - probabilistic - ratelimiting - remote	No	string
	Examples: - probabilistic				
samplerParam	Sampler parameter. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration	1.0		No	string
agentPort	UDP port exposed by jaeger-agent	6831		No	string
	Examples: - 6831				
logEnabled	Enable/disable jaeger logging	false	Enumerations: - true - false	No	string

pod-nrf_agent

Description

NRF Agent Microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable NRF agent	true		No	boolean
	Examples: - true - false				
deployment	Deployment parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

pod-nrf_agent deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer
	Examples:				
	- 1				
strategy	Deployment Update strategy			No	object
injectIstioProxy	Enable/Disable istio-proxy	false		No	boolean
	Examples:				
	- true				
	- false				

pod-nrf_agent deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-nrf_agent deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

pod-nrf_agent hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA	true		No	boolean
	Examples:				
	- true				
	- false				
infraCpuRequests	Infra container HPA CPU requests	10m		No	string
	Examples:				
	- 10m				
workerCpuRequests	Worker container HPA CPU requests	980m		No	string
	Examples:				
	- 980m				

Parameter	Description	Default	Value/Range	Mandatory	Type
workerCpuLimits	Worker container HPA CPU limits				
	Examples: - 1000m	1000m		No	string
maxReplicas	Pod maximum replicas				
	Examples: - 3	3		No	integer
minReplicas	Pod mininum replicas				
	Examples: - 1	1		No	integer
averageUtilization	Pod average utilization				
	Examples: - 75	75		No	integer

pod-timer

Description

Timer Microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable timer microservice				
	Examples: - true	true		No	boolean
	- false				
strategy	Deployment Update strategy			No	object
deployment	Deployment parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
rbacEnabled	Configuring rbacEnabled to true will create clusterrolebinding. If set to false, clusterrolebinding will not be created.				
	Examples: - false	true		No	boolean
role	clusterrole is created as a part of fed-rbac.				
	Examples: - chronos-operator-role	chronos-operator-role		No	string
serviceAccountName	serviceAccountName configuration is used to create serviceaccount per pod				
	Examples: - chronos-operator-serviceaccount	chronos-operator-serviceaccount		No	string

[pod-timer deployment strategy](#)

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-timer deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	25%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	25%		No	string

pod-timer deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 3	3		No	integer

pod-timer hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable HPA				
enabled	Examples: - true - false	true		No	boolean
	Infra container HPA CPU requests				
infraCpuRequests	Examples: - 70m	70m		No	string
	Worker container HPA CPU requests				
workerCpuRequests	Examples: - 900m	900m		No	string
	Worker container HPA CPU limits				
workerCpuLimits	Examples: - 4000m	4000m		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
workerMemoryRequests	Worker container HPA memory requests				
	Examples:	1Gi		No	string
	- 1Gi				
workerMemoryLimits	Worker container HPA memory limits				
	Examples:	4Gi		No	string
	- 4Gi				
maxReplicas	Pod maximum replicas				
	Examples:	5		No	integer
	- 5				
minReplicas	Pod mininum replicas				
	Examples:	1		No	integer
	- 1				
averageUtilization	Pod average utilization				
	Examples:	50		No	integer
	- 50				

pod-sub_analyzer

Description

Sub Analyzer Microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable sub-analyzer				
	Examples:				
	- true	true		No	boolean
	- false				
deployment	Deployment parameters			No	object
upgrade	Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicatory are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

pod-sub_analyzer deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer
	Examples:				
	- 1				
strategy	Deployment Update strategy			No	object
injectIstioProxy	Enable/Disable istio-proxy	false		No	boolean
	Examples:				
	- true				
	- false				

pod-sub_analyzer deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-sub_analyzer deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

pod-sub_analyzer upgrade

Description

Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable canary sequence	false		No	boolean
	Examples:				
	- true				
	- false				
canaryVersWeight	Canary pod weight percentage	0	min: 0 max: 100	No	number
stableVersWeight	Stable pod weight percentage	0	min: 0 max: 100	No	number

Parameter	Description	Default	Value/Range	Mandatory	Type
stableVersion	Stable pod image version			No	string
	Examples:				
	- 0.0.0				

pod-sub_analyzer hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA	true		No	boolean
	Examples:				
	- true - false				
infraCpuRequests	Infra container HPA CPU requests	10m		No	string
	Examples:				
	- 10m				
workerCpuRequests	Worker container HPA CPU requests	980m		No	string
	Examples:				
	- 980m				
workerCpuLimits	Worker container HPA CPU limits	1000m		No	string
	Examples:				
	- 1000m				
maxReplicas	Pod maximum replicas	5		No	integer
	Examples:				
	- 5				
minReplicas	Pod mininum replicas	1		No	integer
	Examples:				
	- 1				
averageUtilization	Pod average utilization	75		No	integer
	Examples:				
	- 75				

pod-amf_cc

Description

AMF Call Control Microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable AMF Call Control	true		No	boolean
	Examples:				
	- true - false				
upgrade	Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.			No	object
deployment	Deployment parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
tracing	Tracing parameters			No	object
cnaInfraThreadPoolSizeDbClient	DB client thread pool size	40		No	integer
	Examples:				
	- 40				

pod-amf_cc upgrade

Description

Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable canary sequence	false		No	boolean
	Examples:				
	- true - false				
canaryVersWeight	Canary pod weight percentage	0	min: 0 max: 100	No	integer
	Examples:				
	- 0				
stableVersWeight	Stable pod weight percentage	0	min: 0 max: 100	No	integer
	Examples:				
	- 0				

Parameter	Description	Default	Value/Range	Mandatory	Type
stableVersion	Stable pod image version				
	Examples:			No	string
	- 0.0.0				

pod-amf_cc deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count				
	Examples:	1		No	integer
	- 1				
strategy	Deployment Update strategy			No	object
traceLogEnabled	Enable/disable tracelog				
	Examples:				
	- true	false		No	string
	- false				
injectIstioProxy	Enable/Disable istio-proxy				
	Examples:				
	- true	false		No	boolean
	- false				

pod-amf_cc deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-amf_cc deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

pod-amf_cc hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA	true		No	boolean
	Examples:				
	- true - false				
infraCpuRequests	Infra container HPA CPU requests	100m		No	string
	Examples: - 100m				
workerCpuRequests	Worker container HPA CPU requests	1000m		No	string
	Examples: - 1000m				
kafkaCpuRequests	kafka client container HPA CPU requests	50m		No	string
	Examples: - 50m				
workerCpuLimits	Worker container HPA CPU limits	1100m		No	string
	Examples: - 1100m				
workerMemoryRequests	Worker container HPA Memory requests	500Mi		No	string
	Examples: - 500Mi				
maxReplicas	Pod maximum replicas	5		No	integer
	Examples: - 5				
minReplicas	Pod mininum replicas	1		No	integer
	Examples: - 1				
averageUtilization	Pod average utilization	75		No	integer
	Examples: - 75				

pod-amf_cc tracing

Description

Tracing parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable tracing	false		No	boolean
	Examples:				
	- true - false				

Parameter	Description	Default	Value/Range	Mandatory	Type
samplerType	Sampler type. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration				
	Examples: - probabilistic			No	string
samplerParam	Sampler parameter. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration				
	Examples: - 1.0			No	string
agentPort	UDP port exposed by jaeger-agent				
	Examples: - 6831	6831		No	string
logEnabled	Enable/disable jaeger logging				
	Examples: - true - false	false		No	string

pod-amf_ta

Description

AMF Tracking Area Manager Microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable AMF Tracking Area Manager				
	Examples: - true - false	true		No	boolean
upgrade	Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.			No	object
deployment	Deployment parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

pod-amf_ta upgrade

Description

Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable canary sequence	false		No	boolean
	Examples:				
	- true				
canaryVersWeight	Canary pod weight percentage	0	min: 0 max: 100	No	integer
	Examples:				
	- 0				
stableVersWeight	Stable pod weight percentage	0	min: 0 max: 100	No	integer
	Examples:				
	- 0				
stableVersion	Stable pod image version			No	string
	Examples:				
	- 0.0.0				

pod-amf_ta deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer
	Examples:				
	- 1				
strategy	Deployment Update strategy			No	object
injectIstioProxy	Enable/Disable istio-proxy	false		No	boolean
	Examples:				
	- true				
tnlaSeparation	Enable/Disable TNLA Separation	true		No	boolean
	Examples:				
	- true				
readOnEtcdWatchFail	Enable/Disable Read from etcd upon etcd watch failure	true		No	boolean
	Examples:				
	- true				
	- false				

pod-amf_ta deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

[pod-amf_ta deployment strategy](#) [rollingUpdate](#)

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

[pod-amf_ta](#) [hpa](#)

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA				
	Examples:				
	- true	true		No	boolean
	- false				
infraCpuRequests	Infra container HPA CPU requests				
	Examples:	10m		No	string
	- 10m				
workerCpuRequests	Worker container HPA CPU requests				
	Examples:	980m		No	string
	- 980m				
workerCpuLimits	Worker container HPA CPU limits				
	Examples:	1000m		No	string
	- 1000m				
maxReplicas	Pod maximum replicas				
	Examples:	2		No	integer
	- 2				
minReplicas	Pod mininum replicas				
	Examples:	1		No	integer
	- 1				
averageUtilization	Pod average utilization				
	Examples:	75		No	integer
	- 75				

[pod-amf_monitor](#)

Description

AMF Monitor Microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable AMF Monitor	true		No	boolean
	Examples:				
	- true				
	- false				
deployment	Deployment parameters			No	object

[pod-amf_monitor](#) deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer
	Examples:				
	- 1				
apiServiceHost	Virtual service host (IP or FQDN)			No	string
	Examples:				
	- amf.com				
apiServicePort	Ingress GW node port			No	string
	Examples:				
	- 80				
injectIstioProxy	Enable/Disable istio-proxy	false		No	boolean
	Examples:				
	- true				
	- false				

pod-amf_n2

Description

AMF N2 Microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable AMF N2	true		No	boolean
	Examples:				
	- true				
	- false				
deployment	Deployment parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

[pod-amf_n2](#) deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count				
	Examples:	1		No	integer
	- 1				
strategy	Deployment Update strategy			No	object
version	Deployment version, if upgrading from 2.1.1 to later this variable must be set, otherwise the defaulted to empty				
	Examples:			No	string
	- 2.1.1				
traceLogEnabled	Enable/disable tracelog				
	Examples:				
	- true	false		No	string
lbTunnelIpFamily	LB tunnel ip family				
	Examples:	ipv4		No	string
	- ipv4				
injectIstioProxy	Enable/Disable istio-proxy				
	Examples:				
	- true	false		No	boolean
	- false				

pod-amf_n2 deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-amf_n2 deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

pod-amf_n2 hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA	true		No	boolean
	Examples:				
	- true				
	- false				
infraCpuRequests	Infra container HPA CPU requests	20m		No	string
	Examples:				
	- 20m				
workerCpuRequests	Worker container HPA CPU requests	1000m		No	string
	Examples:				
	- 1000m				
workerCpuLimits	Worker container HPA CPU limits	1100m		No	string
	Examples:				
	- 1100m				
workerMemoryRequests	Worker container HPA Memory requests	600Mi		No	string
	Examples:				
	- 600Mi				
maxReplicas	Pod maximum replicas	3		No	integer
	Examples:				
	- 3				
minReplicas	Pod minimum replicas	1		No	integer
	Examples:				
	- 1				
averageUtilization	Pod average utilization	75		No	integer
	Examples:				
	- 75				

pod-li_x1

Description

LI X1 microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rbacEnabled	Configuring rbacEnabled to true will create clusterrolebinding. Configuring rbacEnabled to false, clusterrolebinding will not be created.	true		No	boolean
	Examples:				
	- false				

Parameter	Description	Default	Value/Range	Mandatory	Type
clusterRole	clusterrole and PSP for is created as a part of fed-rbac. clusterrole options are restricted-cr, permissive-network-cr, permissive-full-cr Examples: - permissive-network-cr	permissive-network-cr		No	string
serviceAccountName	serviceAccountName configuration is used to create serviceaccount per pod Examples: - li-x1-serviceaccount	li-x1-serviceaccount		No	string
cnalnfraThreadPoolSizeDbClient	Infra thread pool size count Examples: - 1000	1000		No	string
deployment	Deployment parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
upgrade	Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicatory are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.			No	object

pod-li_x1 deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer
strategy	Deployment Update strategy			No	object

pod-li_x1 deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-li_x1 deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

pod-li_x1 hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA				
	Examples:	false		No	boolean
	- false				
infraCpuRequests	Infra container HPA CPU requests				
	Examples:	10m		No	string
	- 10m				
workerCpuRequests	Worker container HPA CPU requests				
	Examples:	390m		No	string
	- 390m				
workerCpuLimits	Worker container HPA CPU limits				
	Examples:	1000m		No	string
	- 1000m				
maxReplicas	The maximum number of simultaneous instances of this pod allowed				
	Examples:	1		No	integer
	- 3				
minReplicas	The minimum number of simultaneous instances of this pod allowed				
	Examples:	1		No	integer
	- 1				
averageUtilization	Pod average utilization				
	Examples:	75		No	integer
	- 75				

pod-li_x1 upgrade

Description

Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable canary sequence	false		No	boolean
	Examples: - false				
canaryVersWeight	Canary pod weight percentage	0	min: 0 max: 100	No	integer
stableVersWeight	Stable pod weight percentage	0	min: 0 max: 100	No	integer
stableVersion	Stable pod image version			No	string
	Examples: - 0.0.0				
stableInfralImage	Infra container stable image			No	string
	Examples: -				
stableWorkerImage	Worker container stable image			No	string
	Examples: -				

pod-li_x2

Description

LI X2 microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rbacEnabled	Configuring rbacEnabled to true will create clusterrolebinding. Configuring rbacEnabled to false, clusterrolebinding will not be created.	true		No	boolean
	Examples: - false				
clusterRole	clusterrole and PSP for is created as a part of fed-rbac. clusterrole options are restricted-cr, permissive-network-cr, permissive-full-cr	permissive-network-cr		No	string
	Examples: - permissive-network-cr				
serviceAccountName	serviceAccountName configuration is used to create serviceaccount per pod	li-x2-serviceaccount		No	string
	Examples: - li-x2-serviceaccount				
cnaInfraThreadPoolSizeDbClient	Infra thread pool size count	1000		No	string
	Examples: - 1000				
deployment	Deployment parameters			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
upgrade	Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicator are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.			No	object

[pod-li_x2 deployment](#)

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer
strategy	Deployment Update strategy			No	object

[pod-li_x2 deployment strategy](#)

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

[pod-li_x2 deployment strategy rollingUpdate](#)

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

[pod-li_x2 hpa](#)

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA				
	Examples:	false		No	boolean
	- false				
infraCpuRequests	Infra container HPA CPU requests				
	Examples:	10m		No	string
	- 10m				
workerCpuRequests	Worker container HPA CPU requests				
	Examples:	390m		No	string
	- 390m				
workerCpuLimits	Worker container HPA CPU limits				
	Examples:	1000m		No	string
	- 1000m				
maxReplicas	The maximum number of simultaneous instances of this pod allowed				
	Examples:	1		No	integer
	- 3				
minReplicas	The mininum number of simultaneous instances of this pod allowed				
	Examples:	1		No	integer
	- 1				
averageUtilization	Pod average utilization				
	Examples:	75		No	integer
	- 75				

pod-li_x2 upgrade

Description

Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicatory are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable canary sequence				
	Examples:	false		No	boolean
	- false				
canaryVersWeight	Canary pod weight percentage	0	min: 0 max: 100	No	number
stableVersWeight	Stable pod weight percentage	0	min: 0 max: 100	No	number

Parameter	Description	Default	Value/Range	Mandatory	Type
stableVersion	Stable pod image version				
	Examples:			No	string
	- 0.0.0				
stableInfraImage	Infra container stable image				
	Examples:			No	string
	-				
stableWorkerImage	Worker container stable image				
	Examples:			No	string
	-				

pod-istio_gw_li

Description

Istio LI Gateway microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable istio-gw-li				
	Examples:	true		No	boolean
	- false				
mesh	PaaS service mesh associations			No	object
istioNspace	Istio namespace				
	Examples:	fed-istio		No	string
	- fed-istio				
ingressGateway	Ingress LI gateway parameters			No	object
egressGateway	Egress LI gateway parameters			No	object
paasSelector	PAAS parameters			No	object

pod-istio_gw_li mesh

Description

PaaS service mesh associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio service mesh association			No	object

pod-istio_gw_li mesh istio

Description

Istio service mesh association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGw	Service mesh ingress gateway LI				
	Examples:			No	string
	- ingress-gateway				
ingressGwIP	Specific IP requested for Ingress Gateway LI LoadBalancer service				
	Examples:			No	string
	-				
ingressGwFQDN	FQDN to be added as annotation to the Ingress Gateway LI LoadBalancer service				
	Examples:	amfli.com		No	string
	-				
mtlsEnabled	Enable/disable istio mutual TLS	false		No	boolean

pod-istio_gw_li ingressGateway

Description

Ingress LI gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable LI ingress gateway				
	Examples:	true		No	boolean
	- false				

pod-istio_gw_li egressGateway

Description

Egress LI gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable egress LI gateway				
	Examples:	true		No	boolean
	- false				
deployment	Deployment parameters			No	object
hpa	Egress LI gateway hpa parameters			No	object

pod-kafka_rplay_agt deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
strategy	Deployment Update strategy			No	object

pod-kafka_rplay_agent deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

[pod-kafka_rplay_agent deployment strategy](#) [rollingUpdate](#)

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	25%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	25%		No	string

[pod-istio_gw_li egressGateway](#) [hpa](#)

Description

Egress LI gateway hpa parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable egress LI gateway HPA				
	Examples:	true		No	boolean
	- false				
workerCpuRequests	CPU request egress application				
	Examples:	200m		No	string
	- 200m				
minReplicas	Specify the mininum replica count for egress LI gateway				
	Examples:	1		No	integer
	- 3				
maxReplicas	Specify the maximum replica count for egress LI gateway				
	Examples:	5		No	integer
	- 5				
averageUtilization	Specify the target CPU utilization level when hpa would trigger				
	Examples:	80		No	integer
	- 80				

[pod-istio_gw](#) [paasSelector](#)

Description

PAAS parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
jaegerHostName	Jaeger host (IP or FQDN)				
	Examples:				
	- 10.10.10.10	fqdn.com		No	string
	- fqdn.com				

[pod-mme_cc](#)

Description

MME Call Control Microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable MME Call Control	true		No	boolean
	Examples:				
	- true				
externalHost	External host (IP or FQDN)			No	string
	Examples:				
	- 0.0.0.0				
upgrade	Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicator are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.			No	object
deployment	Deployment parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
destinationRule	Istio destination rule			No	object
tracing	Tracing parameters			No	object

pod-mme_cc upgrade

Description

Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicator are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable canary sequence	false		No	boolean
	Examples:				
	- true				
canaryVersWeight	Canary pod weight percentage	0	min: 0 max: 100	No	integer
	Examples:				
	- 0				
stableVersWeight	Stable pod weight percentage	100	min: 0 max: 100	No	integer
	Examples:				
	- 0				

Parameter	Description	Default	Value/Range	Mandatory	Type
	Stable pod image version				
stableVersion	Examples: - 0.0.0			No	string
	Infra container stable image				
stableInfraImage	Examples: -			No	string
	Worker container stable image				
stableWorkerImage	Examples: -			No	string

pod-mme_cc deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 2	2	min: 0	No	integer
strategy	Deployment Update strategy			No	object
	Virtual service host (IP or FQDN)				
apiServiceHost	Examples: - mme.com			No	string
	Enable/disable tracelog				
traceLogEnabled	Examples: - true - false			No	string
	Enable/Disable istio-proxy				
injectIstioProxy	Examples: - true - false	false		No	boolean

pod-mme_cc deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-mme_cc deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

pod-mme_cc hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA				
	Examples:				
	- true	true		No	boolean
	- false				
infraCpuRequests	Infra container HPA CPU requests				
	Examples:	25m		No	string
	- 25m				
workerCpuRequests	Worker container HPA CPU requests				
	Examples:	1000m		No	string
	- 1000m				
workerCpuLimits	Worker container HPA CPU limits				
	Examples:	1100m		No	string
	- 1100m				
maxReplicas	Pod maximum replicas				
	Examples:	5	min: 0	No	integer
	- 5				
minReplicas	Pod minimum replicas				
	Examples:	2	min: 0	No	integer
	- 2				
averageUtilization	Pod average utilization				
	Examples:	75	min: 0 max: 100	No	integer
	- 75				

pod-mme_cc destinationRule

Description

Istio destination rule

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable TLS				
	Examples:				
tlsEnabled	- true	false		No	boolean
	- false				

pod-mme_cc tracing

Description

Tracing parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable tracing				
	Examples:				
enabled	- true	false		No	boolean
	- false				
	Sampler type. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration				
samplerType	Examples:			No	string
	- probabilistic				
	Sampler parameter. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration				
samplerParam	Examples:			No	string
	- 1.0				
	UDP port exposed by jaeger-agent				
agentPort	Examples:	6831		No	string
	- 6831				
	Enable/disable jaeger logging				
	Examples:				
logEnabled	- true	false		No	string
	- false				

pod-mme_ta

Description

MME Tracking Area Manager Microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable MME Tracking Area Manager				
	Examples:				
enabled	- true	true		No	boolean
	- false				
deployment	Deployment parameters			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

pod-mme_ta deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 2	1	min: 0	No	integer
strategy	Deployment Update strategy			No	object
	Enable/Disable istio-proxy				
injectIstioProxy	Examples: - true - false	false		No	boolean

pod-mme_ta deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-mme_ta deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

pod-mme_ta hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable HPA				
enabled	Examples: - true - false	true		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
infraCpuRequests	Infra container HPA CPU requests				
	Examples:	10m		No	string
	- 10m				
workerCpuRequests	Worker container HPA CPU requests				
	Examples:	980m		No	string
	- 980m				
workerCpuLimits	Worker container HPA CPU limits				
	Examples:	1000m		No	string
	- 1000m				
maxReplicas	Pod maximum replicas				
	Examples:	2	min: 0	No	integer
	- 2				
minReplicas	Pod mininum replicas				
	Examples:	2	min: 0	No	integer
	- 2				
averageUtilization	Pod average utilization				
	Examples:	75	min: 0 max: 100	No	integer
	- 75				

pod-mme_s1

Description

MME S1 Microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable MME S1				
	Examples:				
	- true	true		No	boolean
deployment	Deployment parameters				
				No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

pod-mme_s1 deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	2	min: 0	No	integer
	Examples:				
	- 2				
strategy	Deployment Update strategy			No	object
traceLogEnabled	Enable/disable tracelog	false		No	string
	Examples:				
	- true				
	- false				
lbTunnelIpFamily	LB tunnel ip family	ipv4		No	string
	Examples:				
	- ipv4				
injectIstioProxy	Enable/Disable istio-proxy	false		No	boolean
	Examples:				
	- true				
	- false				

pod-mme_s1 deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-mme_s1 deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

pod-mme_s1 hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA	true		No	boolean
	Examples:				
	- true				
	- false				

Parameter	Description	Default	Value/Range	Mandatory	Type
infraCpuRequests	Infra container HPA CPU requests				
	Examples:	20m		No	string
	- 20m				
workerCpuRequests	Worker container HPA CPU requests				
	Examples:	1000m		No	string
	- 1000m				
workerCpuLimits	Worker container HPA CPU limits				
	Examples:	1100m		No	string
	- 1100m				
maxReplicas	Pod maximum replicas				
	Examples:	2	min: 0	No	integer
	- 2				
minReplicas	Pod minimum replicas				
	Examples:	2	min: 0	No	integer
	- 2				
averageUtilization	Pod average utilization				
	Examples:	75	min: 0 max: 100	No	integer
	- 75				

pod-diameter_base

Description

Diameter Base Microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
diameterGroups	Diameter Groups parameters			No	array

[pod-diameter_base](#) [diameterGroups](#)

Description

Diameter Groups parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
groupName	Name of diameter-base group				
	Examples:			Yes	string
	- group1				
enabled	Enable/disable diameter-base group				
	Examples:			Yes	boolean
	- true - false				
ratelimit	Rate limiting related variables. quota determines the number of incoming requests for this microservice that will be allowed per configured interval from the microservice configured as the sourceApp.			Yes	object

Parameter	Description	Default	Value/Range	Mandatory	Type
transport	diameter-base transport protocol				
	Examples:				
	- sctp	sctp		Yes	string
sctpEncapType	- tcp				
	SCTP enapsulation type				
	Examples:				
role	- sctp_lb	sctp_lb		Yes	string
	- rfc6951				
	Role of diameter-base group1				
reserveStreamId0	Examples:				
	- client	client		Yes	string
	- server				
externallpServiceId	Reserve stream ID				
	Examples:				
	- true	true		No	string
deployment	- false				
	Service ID				
	Examples:				
hpa	- s6-fqdn	s6-fqdn		Yes	string
	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all				
	Tracing parameters			No	object
tracing					

pod-diameter_base diameterGroups ratelimit

Description

Rate limiting related variables. quota determines the number of incoming requests for this microservice that will be allowed per configured interval from the microservice configured as the sourceApp.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable ratelimiting				
	Examples:				
	- true	true		No	boolean
quota	- false				
	Number of incoming requests allowed				
	Examples:				
tracing	- 100	100		No	integer
	- 200				

Parameter	Description	Default	Value/Range	Mandatory	Type
interval	Configured time interval	10s		No	string
	Examples:				
	- 10s				
sourceApp	Source app	istio-ingressgateway		No	string
	Examples:				
	- istio-ingressgateway				

pod-diameter_base diameterGroups deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1	min: 0	No	integer
	Examples:				
	- 1				
	- 2				
strategy	Deployment Update strategy			No	object

pod-diameter_base deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-diameter_base deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

pod-diameter_base diameterGroups hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA	true		No	boolean
	Examples:				
	- true				
	- false				
infraCpuRequests	Infra container HPA CPU requests	10m		No	string
	Examples:				
	- 10m				
workerCpuRequests	Worker container HPA CPU requests	980m		No	string
	Examples:				
	- 980m				
workerCpuLimits	Worker container HPA CPU limits	1000m		No	string
	Examples:				
	- 1000m				
minReplicas	Pod minimum replicas	1	min: 0	No	integer
	Examples:				
	- 1				
	- 2				
maxReplicas	Pod maximum replicas	1	min: 0	No	integer
	Examples:				
	- 1				
	- 2				
averageUtilization	Pod average utilization	75	min: 0 max: 100	No	integer
	Examples:				
	- 50				
	- 75				

pod-diameter_base diameterGroups tracing

Description

Tracing parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable tracing	true		No	boolean
	Examples:				
	- true				
	- false				

Parameter	Description	Default	Value/Range	Mandatory	Type
samplerType	Sampler type. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration	probabilistic	Enumerations: - const	No	string
	Examples: - probabilistic		- probabilistic - ratelimiting - remote		
samplerParam	Sampler parameter. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration Examples: - 1.0	1.0		No	string
agentPort	UDP port exposed by jaeger-agent Examples: - 6831	6831		No	string
logEnabled	Enable/disable jaeger logging Examples: - true - false	false		No	string

pod-routing

Description

Routing microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable Routing microservice	false		No	boolean
	Examples: - true				
deployment	Deployment parameters			No	object

[pod-routing](#) deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer
	Examples: - 1				

pod-interface_mgr

Description

Interface Manager microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable Interface Manager microservice				
enabled	Examples: - true	false		No	boolean
deployment	Deployment parameters			No	object

pod-interface_mgr deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer

pod-ulb

Description

Unified Load Balancer Microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable Unified Load Balancer microservice				
enabled	Examples: - false	true		No	boolean
	Configuring rbacEnabled to true will create clusterrolebinding. Configuring rbacEnabled to false, clusterrolebinding will not be created.				
rbacEnabled	Examples: - false	true		No	boolean
	clusterrole and PSP for is created as a part of fed-rbac. clusterrole options are restricted-cr, permissive-network-cr, permissive-full-cr				
clusterRole	Examples: - permissive-network-cr - permissive-full-cr	permissive-network-cr		No	string
	serviceAccountName configuration is used to create serviceaccount per service type				
serviceAccountName	Examples: - ulb-serviceaccount	ulb-serviceaccount		No	string
deployment	Deployment parameters			No	object

pod-ulb deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
strategy	Deployment Update strategy			No	object
config	List configs related to deployments of ULB			No	object

pod-ulb deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-ulb deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of pods that can be unavailable during the update process.	1		No	string
maxSurge	Specifies the maximum number of pods that can be created over the desired number of pods.	0		No	string

pod-ulb deployment config

Description

List configs related to deployments of ULB

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
additionalNetworks	Networks defined over Multus managed interfaces.			No	array
deploymentGroups	List of deployment groups			No	array

pod-ulb deployment config additionalNetworks

Description

Networks defined over Multus managed interfaces.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the network.				
	Examples:			Yes	string
	- corenet				
netAttachDefName	Network attachment definition name to identify the interface pool from which interfaces are assigned by Multus.				
	Examples:			No	string
	- net-sr1				
netAttachDefNamespace	Network attachment definition namespace to identify the interface pool from which interfaces are assigned by Multus.				
	Examples:			No	string
	- {{- .Release.Namespace }}				

Parameter	Description	Default	Value/Range	Mandatory	Type
resourceName	Resource name to identify the network-attachment-definition.				
	Examples: - sr1			No	string
resourcePrefix	Prefix used to address SR-IOV network resources.				
	Examples: - dataplane.io			No	string
vlanId	VLAN identifier to be used on the secondary interface.				
	Examples: - 1480	0		No	integer
sriovEnabled	Flag to specify if SR-IOV mode is enabled.				
	Examples: - true	false		No	boolean
createSriovNetAttachDefs	Flag to specify if network attach definition needs to be created.				
	Examples: - true	false		No	boolean

pod-ulb deployment config deploymentGroups

Description

List of deployment groups

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the deployment group				
	Examples: - access			Yes	string
scalingPolicy	Scaling policy of the deployment group			No	object
schedulingPolicy	Scheduling policy of the deployment group			No	object
endpoints	Endpoints info				
	Examples: - [OrderedDict({'ips': ['10.163.68.34'], 'defaultGw': '10.163.68.1', 'prefixLength': 24, 'sctp': OrderedDict({'enabled': True, 'ports': [36412, 38412]}), 'udp': OrderedDict({'enabled': True, 'ports': [8000, 8010]}), 'frontEnd': OrderedDict({'multus': OrderedDict({'networkName': 'accessnet1', 'lbExtDevice': 'net2'})})})]			Yes	array
frontEnd	Type of frontEnd to use for the deployment group			No	object

pod-ulb deployment config deploymentGroups scalingPolicy

Description

Scaling policy of the deployment group

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Number of replicas for a deploement group				
	Examples: - 1			No	integer
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

pod-ulb deployment config deploymentGroups scalingPolicy hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA				
	Examples:				
	- true - false	true		No	boolean
infraCpuRequests	Infra container HPA CPU requests				
	Examples: - 10m	10m		No	string
workerCpuRequests	Worker container HPA CPU requests				
	Examples: - 980m	980m		No	string
workerCpuLimits	Worker container HPA CPU limits				
	Examples: - 1000m	1000m		No	string
maxReplicas	Pod maximum replicas				
	Examples: - 5	1	min: 0	No	integer
minReplicas	Pod mininum replicas				
	Examples: - 2	1	min: 0	No	integer
averageUtilization	Pod average utilization				
	Examples: - 75	75	min: 0 max: 100	No	integer

pod-ulb deployment config deploymentGroups schedulingPolicy

Description

Scheduling policy of the deployment group

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
nodeSelector	Node selector to schedule the pod on a specific node.			No	array

[pod-ulb deployment config deploymentGroups schedulingPolicy nodeSelector](#)

Description

Node selector to schedule the pod on a specific node.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Label name to select the node				
label	Examples: - kubernetes.io/hostname			No	string
	Value of the label to select the node				
value	Examples: - aks-worker-33339762-vmss000000			No	string

[pod-ulb deployment config deploymentGroups endpoints](#)

Description

Endpoints info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	List of Endpoint IP addresses (IPv4/IPv6)				
ips	Examples: - ['10.163.68.34', '2275:0:ca:12b:3e94:d505:14e2:8ff0']			Yes	array
	Default Gateway IP				
defaultGw	Examples: - 10.163.68.1 - 2275:0:ca:12b::1			No	string
	Prefix Length				
prefixLength	Examples: - 24 - 64			No	integer
sctp	SCTP protocol			No	object
udp	UDP protocol			No	object
	Type of frontEnd to use for the endpoint				
frontEnd	Examples: - OrderedDict({'multus': OrderedDict({'networkName': 'accessnet1', 'lbExtDevice': 'net2'})})			No	object

[pod-ulb deployment config deploymentGroups endpoints sctp](#)

Description

SCTP protocol

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable SCTP protocol for the endpoint				
enabled	Examples: - true	false		No	boolean
ports	List of open ports for peer initiated associations.			No	array

pod-ulb deployment config deploymentGroups endpoints udp

Description

UDP protocol

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable UDP protocol for the endpoint				
enabled	Examples: - true	false		No	boolean
ports	List of udp ports			No	array

pod-ulb deployment config deploymentGroups endpoints frontEnd

Description

Type of frontEnd to use for the endpoint

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Multus frontEnd.				
multus	Examples: - OrderedDict({'networkName': 'accessnet', 'lbExtDevice': 'net2'})			No	object

pod-ulb deployment config deploymentGroups endpoints frontEnd multus

Description

Multus frontEnd.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	AdditionalNetwork name which is already defined.				
networkName	Examples: - accessnet			No	string
	Pod network interface device used for external communication.				
lbExtDevice	Examples: - net2			No	string
	MTU for pod network interface device used for external communication. Range is 1280-9216. Default is to not set the MTU on the interface.				
mtu	Examples: - 9008		min: 1280 max: 9216	No	integer

pod-ulb deployment config deploymentGroups frontEnd

Description

Type of frontEnd to use for the deployment group

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
hostMapped	Host Mapped Frontend				
	Examples:			No	object
	- OrderedDict({'lbEthDevice': 'ens3', 'lbExtDevice': 'ens6', 'networkMode': 'hostPort'})				
externalLb	External Load Balancer Frontend.				
	Examples:			No	object
	- OrderedDict({'empty': 'true'})				
multus	Multus frontend.				
	Examples:			No	object
	- OrderedDict({'networkName': 'accessnet', 'lbExtDevice': 'net2'})				
cppe	CPPE Frontend				
	Examples:			No	object
	- OrderedDict({'lbExtDevice': 'veth1'})				

pod-ulb deployment config deploymentGroups frontEnd hostMapped

Description

Host Mapped Frontend

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
lbEthDevice	Pod network interface device used for internal communication (eth0 is used if this value is not specified).				
	Examples:			No	string
	- ens3				
lbExtDevice	Pod network interface device used for external communication. This field is mandatory in case networkMode is hostNetwork.				
	Examples:			No	string
	- ens6				
networkMode	Network mode .				
	Examples:			No	string
	- hostPort - hostNetwork				

pod-ulb deployment config deploymentGroups frontEnd externalLb

Description

External Load Balancer Frontend.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
	Empty field to select externalLb mode.				
empty	Examples: - true			No	boolean

pod-ulb deployment config deploymentGroups frontEnd multus

Description

Multus frontEnd.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	AdditionalNetwork name which is already defined.				
networkName	Examples: - accessnet			No	string
	Pod network interface device used for external communication.				
lbExtDevice	Examples: - net2			No	string
	MTU for pod network interface device used for external communication. Range is 1280-9216. Default is to not set the MTU on the interface.				
mtu	Examples: - 9008		min: 1280 max: 9216	No	integer

pod-ulb deployment config deploymentGroups frontEnd cppe

Description

CPPE Frontend

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Pod network interface device used for external communication. This field is mandatory.				
lbExtDevice	Examples: - veth1			No	string

pod-cdpln

Description

Common dataplane microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable common dataplane microservice				
enabled	Examples: - true	false		No	boolean

pod-lb_ppe

Description

LB PPE microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable LB PPE microservice	false		No	boolean
	Examples: - true				
rbacEnabled	Configuring rbacEnabled to true will create clusterrolebinding. Configuring rbacEnabled to false, clusterrolebinding will not be created.	true		No	boolean
	Examples: - false				
clusterRole	clusterrole and PSP for is created as a part of fed-rbac. clusterrole options are restricted-cr, permissive-network-cr, permissive-full-cr	permissive-full-cr		No	string
	Examples: - permissive-full-cr				
serviceAccountName	serviceAccountName configuration is used to create serviceaccount per pod	ppe-serviceaccount		No	string
	Examples: - ppe-serviceaccount				
ppeFirstWorker	First core dataplane that will be allowed to use. This is not a physical core number; it is a core number within the range allocated to the pod. I.e if a dataplane pod is allocated 10 cores, the first core has to be in the 0-9 range	1		No	string
	Examples: - 1				
ppeNumWorkers	Number of cores allocated to dataplane, including the first core. E.g. if first core is 2 and ppeNumWorkers is 7, then cores 2,3,4,5,6,7,8,9 will be allocated to dataplane	2		No	string
	Examples: - 2				
ppeloScaling	Dataplane I/O resource distribution. Options: 1. grouped: all ports' rx queues are handled by a single I/O core. 2. shared-cores: there are as many I/O cores as rx-queues on each interfaces. The Xth queue of each interfaces share the Xth I/O core. 3. separated-cores: there are as many I/O cores as there rx-queues total. Each rx-queue is placed on an individual I/O core	separated-cores		No	string
	Examples: - separated-cores				
vlanStripping	Enable/disable vlan stripping on dataplane ports	false		No	boolean
	Examples: - true				
enableJumboFrames	Enable/disable jumbo frame support	false		No	boolean
	Examples: - true				
deployment	Deployment parameters			No	object
resources	The Resources Schema			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
guaranteedScheduling	Define CPU & memory limits for 3 containers: ppe, infra and ulb. All 3 need to follow the config presented in https://kubernetes.io/docs/tasks/configure-pod-container/quality-service-pod/#create-a-pod-that-gets-assigned-a-qos-class-of-guaranteed Note: If a Container specifies its own memory limit, but does not specify a memory request, Kubernetes automatically assigns a memory request that matches the limit. Similarly, if a Container specifies its own CPU limit, but does not specify a CPU request, Kubernetes automatically assigns a CPU request that matches the limit. Don't specify requests.			No	object
sriov	SRIOV parameters			No	array
netAttachDefs	Networking attachment configuration for the VM node. Supported drivers are Intel and Mellanox			No	object
tracing	Tracing parameters			No	object

pod-lb_ppe deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count Examples: - 1	1		No	integer
strategy	Deployment Update strategy			No	object
deployCaptureAgent	Enable/disable capture-agent deployment Examples: - true	false		No	boolean
podAntiAffinityEnabled	Enable/disable pod anti-affinity. Ensure only a single replica is allowed on a node. Examples: - true	false		No	boolean
config	List configs related to deployments of LB PPE			No	object

pod-lb_ppe deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-lb_ppe deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	0		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	1		No	string

pod-lb_ppe deployment config

Description

List configs related to deployments of LB PPE

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
deploymentGroups	List of deployment groups for LB PPE			No	array

[pod-lb_ppe deployment config deploymentGroups](#)

Description

List of deployment groups for LB PPE

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Name of the deployment group				
name	Examples: - external-ips			Yes	string
	Endpoints info				
endpoints	Examples: - [OrderedDict({'ips': ['10.163.68.34'], 'defaultGw': '10.163.68.1', 'sctp': OrderedDict({'enabled': True, 'ports': [36412, 38412]}), 'udp': OrderedDict({'enabled': True, 'ports': [8000, 8010]}))}]			Yes	array

[pod-lb_ppe deployment config deploymentGroups endpoints](#)

Description

Endpoints info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	List of Endpoint IP addresses (IPv4/IPv6)				
ips	Examples: - ['10.163.68.34', '2275:0:ca:12b:3e94:d505:14e2:8ff0']			Yes	array
	Default Gateway IP				
defaultGw	Examples: - 10.163.68.1 - 2275:0:ca:12b::1			No	string
sctp	SCTP protocol			No	object
udp	UDP protocol			No	object

[pod-lb_ppe deployment config deploymentGroups endpoints sctp](#)

Description

SCTP protocol

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable SCTP protocol for the endpoint				
enabled	Examples: - true	false		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
ports	List of open ports for peer initiated associations.			No	array

pod-lb_ppe deployment config deploymentGroups endpoints udp

Description

UDP protocol

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable UDP protocol for the endpoint				
enabled	Examples: - true	false		No	boolean
ports	List of udp ports			No	array

pod-lb_ppe resources

Description

The Resources Schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Huge pages type				
hugepagesType	Examples: - 2Mi	2Mi		No	string
	LB PPE container CPU usage threshold				
ppeCpuRequests	Examples: - 1500m	1100m		No	string
	LB PPE container CPU usage maximum Limit				
ppeCpuLimits	Examples: - 2000m	2000m		No	string
	LB ULB container CPU usage threshold				
ulbCpuRequests	Examples: - 1500m	1000m		No	string
	Allocated memory for LB PPE container				
ppeMemory	Examples: - 4Gi	2Gi		No	string
	Huge pages size. More information here - https://wiki.debian.org/Hugepages				
ppeHugepagesSize	Examples: - 4Gi	4Gi		No	string

pod-lb_ppe guaranteedScheduling

Description

Define CPU & memory limits for 3 containers: ppe, infra and ulb. All 3 need to follow the config presented in <https://kubernetes.io/docs/tasks/configure-pod-container/quality-service-pod/#create-a-pod-that-gets-assigned-a-qos-class-of-guaranteed> Note: If a Container specifies its own memory limit, but does not specify a memory request, Kubernetes automatically assigns a memory request that matches the limit. Similarly, if a Container specifies its own CPU limit, but does not specify a CPU request, Kubernetes automatically assigns a CPU request that matches the limit. Don't specify requests.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable guaranteedScheduling for LB PPE microservice	true		No	boolean
	Examples:				
	- true				
infraCpuLimit	Infra container CPU usage maximum Limit	100m		No	string
	Examples:				
	- 100m				
infraMemoryLimit	Infra container memory usage maximum Limit	256Mi		No	string
	Examples:				
	- 2Gi				
ulbCpuLimit	ULB container CPU usage maximum Limit	3000m		No	string
	Examples:				
	- 1000m				
ulbMemoryLimit	ULB container memory usage maximum Limit	2Gi		No	string
	Examples:				
	- 2Gi				
ppeCpuLimit	LB PPE container CPU usage maximum Limit	2000m		No	string
	Examples:				
	- 2000m				
ppeMemoryLimit	LB PPE container memory usage maximum Limit	8Gi		No	string
	Examples:				
	- 2Gi				

pod-lb_ppe sriov

Description

SRIOV parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
labels	SRIOV label names configured on cluster			Yes	string
	Examples:				
	- label1				
nbIfc	Number of interfaces/NICs on n3 or n6	1		Yes	string
	Examples:				
	- 1				

pod-lb_ppe netAttachDefs

Description

Networking attachment configuration for the VM node. Supported drivers are Intel and Mellanox

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable non-default network driver. The default driver is intel. Intel needs this disabled.	false		No	boolean
	Examples:				
	- true				
annotation	SR-IOV network driver parameters	sriov-net1, sriov-net2		No	string
	Examples:				
	- sriov-net1, sriov-net2				

pod-lb_ppe tracing

Description

Tracing parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable tracing	false		No	boolean
	Examples: - false				
samplerType	Sampler type. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration	probabilistic	Enumerations: - const - probabilistic - ratelimiting - remote	No	string
	Examples: - probabilistic				
samplerParam	Sampler parameter. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration	1.0		No	string
agentPort	UDP port exposed by jaeger-agent	6831		No	string
	Examples: - 6831				
logEnabled	Enable/disable jaeger logging	false	Enumerations: - true - false	No	string
	Examples: - false				

CRDS Helm Documentation

CRDS values

Contents

- [Global Parameters](#)

global

Description

Global Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
registry	PaaS registry associations			No	object
monitoring	PaaS Monitoring associations			No	object

[global](#) registry

Description

PaaS registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

[global](#) [registry](#) docker

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string
imagePullSecret	Pull an image from a private registry			No	string
username	Username for private docker registry			No	string
password	Password for private docker registry			No	string

[global](#) monitoring

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association			No	object

[global](#) [monitoring](#) prometheus

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable prometheus monitoring	true		No	boolean

ETCD Helm Documentation

ETCD Helm Values.

Contents

- [Global parameters.](#)
- [The pod-db_etcd schema](#)
- [The pod-etcd_operator schema](#)

[global](#)

Description

Global parameters.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enableSCC	If running on OCP cluster, please set enableSCC to true	false		No	boolean
registry	PaaS container registry associations			No	object
deployment	node affinity deployment			No	object
envVars_ServiceRegistryNamespace	Serviceregistry namespace.			No	string
kargoProfileTag	This enables collection of etcd data by kargo			No	string
ingressNetworkPolicy	network policies configuration			No	object
logging	PaaS logging association.			No	object
grafana	PaaS Grafana association			No	object
monitoring	PaaS Monitoring associations			No	object
envVars	Environment variables.			No	object
overrides	Override Variables.			No	object
istio	Istio related configurations			No	object
mesh	PaaS service mesh associations			No	object

global registry

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

global registry docker

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string
imagePullSecret	Pull an image from a private registry			No	string
username	Username for private docker registry			No	string
password	Password for private docker registry			No	string

global deployment

Description

node affinity deployment

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
nodeDataplaneAffinity	Flag to enable/disable node affinity	false		No	string

global ingressNetworkPolicy

Description

network policies configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabled network policy	true		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressTrafficNamespaces	Namespaces which are required to be allowed for ingress traffic			No	array

global logging

Description

PaaS logging association.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable logging association.				
enabled	Examples: - false	false		No	boolean
fluentd	fluentd configurations.			No	object
elastic	Elasticsearch association.			No	object
	Enable/disable additional destinations.				
enableAddITargets	Examples: - false	false		No	boolean
addITargets	Additional logging output destination configuration			No	array
alerts	Elastalert association			No	object

global logging fluentd

Description

fluentd configurations.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	fluentd buffer configurations.			No	object

global logging fluentd buffer

Description

fluentd buffer configurations.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Total buffer size. Maximum amount of buffer space each fluentd thread would use to keep logs. After this space is exhausted, fluentd would start deleting oldest logs to make room for new logs.	32m		No	string
retryWait	Interval(seconds) at which the buffer flush is retried in case of failure.	10s		No	string
maxRetries	Max number of retries to flush a buffer chunk. After this is exhausted, fluentd would delete the chunk.	1		No	integer

global logging elastic

Description

Elasticsearch association.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
IP	Elasticsearch IP address			No	string
Port	Elasticsearch port	9200		No	integer

global logging addITargets

Description

Additional logging output destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			No	object

[global logging addlTargets](#) forward

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
host	Hostname or IP Address of the forward server				
	Examples:				
	- 192.168.1.1 - forward-server.com			No	string
port	Port of the forward server				
	Examples:	24224		No	integer
	- 24224				

[global logging alerts](#)

Description

Elastalert association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable event based alerts				
	Examples:				
	- false - true	false		No	boolean
host	Elastalert IP address				
	Examples:			No	string
	- 10.15.16.64				
port	Elastalert port number	3030		No	integer
realert	Alerts will be repeated after the realert duration			No	object
receivers	The platform on which alerts can be sent			No	array

[global logging alerts](#) realert

Description

Alerts will be repeated after the realert duration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minutes	Alerts will be repeated after the realert duration	1		No	integer

global logging alerts receivers

Description

The platform on which alerts can be sent

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
slack	Slack channel			No	object
post	Configuration for HTTP post			No	object
email	Configuration for email receiver			No	object

global logging alerts receivers slack

Description

Slack channel

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
webhookurl	Webhook url of the receiver slack channel			No	string

global logging alerts receivers post

Description

Configuration for HTTP post

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
http_post_url	HTTP post URL			No	string

global logging alerts receivers email

Description

Configuration for email receiver

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
to_address	Receiver email address			No	string
smtp_host	The smtp host ip			No	string
smtp_port	The smtp port number			No	string
smtp_ssl	This should be disabled	false		No	boolean
from_addr	Sender address			No	string

global grafana

Description

PaaS Grafana association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association	true		No	boolean
url	Exposed grafana URL			No	string
prometheusinfo	Prometheus server association.			No	object

global grafana prometheusinfo

Description

Prometheus server association.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
url	Prometheus server URL.	http://prometheus.fed-prometheus:9090		No	string

global monitoring

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association			No	object

global monitoring prometheus

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable prometheus monitoring	true		No	boolean

global envVars

Description

Environment variables.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
fedType	Fed Type.				
	Examples:	paas		No	string
	- paas				
fedUniqueName	Fed Unique Name.				
	Examples:	etcd-default		No	string
	- etcd-default				

global overrides

Description

Override Variables.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
preDeleteEnabled	Enable/Disable pre delete scripts.	false		No	boolean

global istio

Description

Istio related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtls	Istio mutual TLS related configuration			No	object

global istio mtlS

Description

Istio mutual TLS related configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable istio mutual TLS	false		No	boolean

global mesh

Description

PaaS service mesh associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio service mesh association			No	object

global mesh istio

Description

Istio service mesh association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtlsEnabled	Enable/disable istio mutual TLS	false		No	boolean

pod-db_etcd

Description

Pod DB ETCD values.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
deployment	Deployment configuration for pod-db_etcd			No	object

pod-db_etcd deployment

Description

Deployment configuration for pod-db_etcd

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ap5gc	ap5gc deployment flag configuration for pod-db_etcd			No	object

pod-db_etcd deployment ap5gc

Description

ap5gc deployment flag configuration for pod-db_etcd

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable deployment	false		No	boolean
rbacEnabled	RBAC enable/disable	true		No	boolean
serviceAccount	Service Account			No	object
HBinterval	HeartBeat interval between pods in ms	400		No	integer
healthTimer	ETCD health timer in ms	500		No	integer

Parameter	Description	Default	Value/Range	Mandatory	Type
resources	Resource limits and requests			No	object
etcd	ETCD port values			No	object

pod-db_etcd deployment ap5gc serviceAccount

Description

Service Account

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Service account name			No	string

pod-db_etcd deployment ap5gc resources

Description

Resource limits and requests

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
limits	Resource limits			No	object
requests	Resource Requests			No	object

pod-db_etcd deployment ap5gc resources limits

Description

Resource limits

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	CPU limits			No	string
memory	Memory limits			No	string

pod-db_etcd deployment ap5gc resources requests

Description

Resource Requests

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	CPU requests			No	string
memory	Memory requests			No	string

pod-db_etcd deployment ap5gc etcd

Description

ETCD port values

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
serverPortName	Server port name			No	string
clientPortName	Client port name			No	string
udpPortName	UDP port name			No	string
httpPortName	HTTP port name			No	string

pod-etcd_operator

Description

ETCD values.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rbacEnabled	rbac enable/disable	true		No	boolean
serviceAccount	Service Account			No	object
loadBalancerService	loadBalancerService			No	object
	etcd-operator.				
etcdOperator	Examples: - OrderedDict({'image': OrderedDict({'ramMode': False})})			No	object
etcdCluster	ETCD member cluster.			No	object
	Single node cluster config - if enabled 1 pod etcd managed by k8s will be deployed				
singlenodecluster	Examples: - OrderedDict({'enable': False})			No	object
	EtcdDefrag will schedule cron jobs to clean fragmented data in the database.				
etcdDefrag	Examples: - OrderedDict({'enable': True, 'schedule': '*/*/* * * *', 'jobHistory': 5})			No	object

[pod-etcd_operator serviceAccount](#)

Description

Service Account

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
etcdOperatorServiceAccount	etcdOperatorServiceAccount			No	object
backupOperatorServiceAccount	backupOperatorServiceAccount			No	object
restoreOperatorServiceAccount	restoreOperatorServiceAccount			No	object

[pod-etcd_operator serviceAccount etcdOperatorServiceAccount](#)

Description

etcdOperatorServiceAccount

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
create	Create	true		No	boolean
name	etcdOperatorServiceAccount	etcdoperator-sa		No	string

[pod-etcd_operator serviceAccount backupOperatorServiceAccount](#)

Description

backupOperatorServiceAccount

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
create	Create	false		No	boolean
name	backupoperator-sa	backupoperator-sa		No	string

[pod-etcd_operator serviceAccount restoreOperatorServiceAccount](#)

Description

restoreOperatorServiceAccount

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
create	Create	false		No	boolean
name	restoreOperatorServiceAccount	restoreoperator-sa		No	string

pod-etcd_operator loadBalancerService

Description

loadBalancerService

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable load-balancer	false		No	boolean
loadBalancerIP	loadBalancerIP			No	string
loadBalancerFQDN	loadBalancerFQDN			No	string
loadBalancerSharingKey	loadBalancerSharingKey			No	string
port	Port number	31379		No	integer
serviceAnnotations	serviceAnnotations			No	object

pod-etcd_operator loadBalancerService serviceAnnotations

Description

serviceAnnotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	azure-load-balancer-internal	true		No	string
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	azure-load-balancer-internal-subnet	none		No	string

pod-etcd_operator etcdOperator

Description

etcd-operator.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
image	ETCD data storage mode - memory/disk.			No	object
commandArgs	Common Arguments to be passed to the operator			No	object

pod-etcd_operator etcdOperator image

Description

ETCD data storage mode - memory/disk.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ramMode	Enabling will force ETCD to write data to Node Memory.	false		No	boolean

pod-etcd_operator etcdOperator commandArgs

Description

Common Arguments to be passed to the operator

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
disaster-recovery	Set this flag to bring up etcd-cluster when majority of etcd-cluster pods goes down or when all the etcd-cluster pods are dead.	true		No	string
	Examples:				
	- false - true				

pod-etcd_operator etcdCluster

Description

ETCD member cluster.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
size	Number of replicas of etcd cluster pods.	3		No	integer
	Examples:				
	- 3				
podDisruptionBudget	Configuration for pod disruption budget for pod-etcd_operator			No	object
pod	ETCD member attributes.			No	object

pod-etcd_operator etcdCluster podDisruptionBudget

Description

Configuration for pod disruption budget for pod-etcd_operator

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable pod disruption budgets(PDB) for etcd-cluster pods	true		No	boolean

pod-etcd_operator etcdCluster pod

Description

ETCD member attributes.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
resources	Resources for etcd pods.			No	object

pod-etcd_operator etcdCluster pod resources

Description

Resources for etcd pods.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
requests	Requests.			No	object
limits	Limits.			No	object

pod-etcd_operator etcdCluster pod resources requests

Description

Requests.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	CPU.				
	Examples:	500m		No	string
	- 500m				
memory	Memory.				
	Examples:	256Mi		No	string
	- 256Mi				

pod-etcd_operator etcdCluster pod resources limits

Description

Limits.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	CPU.				
	Examples:	2		No	string
	- 100m				
memory	Memory.				
	Examples:	8Gi		No	string
	- 4Gi				

pod-etcd_operator singlenodecluster

Description

Single node cluster config - if enabled 1 pod etcd managed by k8s will be deployed

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable flag.	false		No	boolean

pod-etcd_operator etcdDefrag

Description

EtcdDefrag will schedule cron jobs to clean fragmented data in the database.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable flag.	true		No	boolean
schedule	nix style cron job syntax to schedule the clean up	* / 30 * * * *		No	string
jobHistory	Number of previous failed/success jobs to store	5		No	integer

Elastalert Helm Documentation

fed-elastalert values

Contents

- [Global Parameters](#)
- [Pod-elastalert parameters](#)
- [Pod-istio_gw parameters](#)

global

Description

Global Scoped Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
defaultRbacEnabled	Default rbac flag	false		No	boolean
	Examples:				
	- false				
	- true				
authType	Authentication type for elastalert. Use local to enable keycloak.	haloe		No	string
adminPassword	Generic password for all PaaS Component			No	string
vault	Vault secret configuration			No	object
istio	Istio related configurations			No	object
secretNames	PaaS Vault Secret Names			No	object
mesh	Istio mesh configuration			No	object
logging	PaaS logging association			No	object
fileservers	PaaS fileservers associations			No	object
registry	PaaS container registry associations			No	object
envVars	Environment variables			No	object
loadBalancerSourceRanges	loadBalancerSourceRanges			No	string
deployment	Deployment option for fed-elastalert			No	object
overrides	overrides			No	object

[global vault](#)

Description

Vault secret configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enables vault to get secret	false		No	boolean
	Examples:				
	- false				
	- true				
hashicorpVault	hashicorpVault secret configuration			No	object
azureKeyVault	azureKeyVault secret configuration			No	object

[global vault hashicorpVault](#)

Description

hashicorpVault secret configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enables hashicorpVault to get secret	false		No	boolean
	Examples:				
	- false				
	- true				

global vault azureKeyVault

Description

azureKeyVault secret configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enables azureKeyVault to get secret	false		No	boolean
	Examples:				
	- false				
	- true				
aksCluster	Is it AKS cluster	false		No	boolean
	Examples:				
	- false				
	- true				
keyVaultName	key vault name			No	string
tenantID	tenant id where akv created			No	string
userManagerId	User manager ID			No	string
workloadIdentity	is it Workloadidentity	true		No	boolean
	Examples:				
	- false				
	- true				

global istio

Description

Istio related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtls	Istio mutual TLS related configuration			No	object

global istio mtls

Description

Istio mutual TLS related configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable istio mutual TLS	false		No	boolean

global secretNames

Description

PaaS Vault Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
elastalert	elastalert Secret Names			No	object
ingressgw	ingressgw Secret Names			No	object

global secretNames elastalert

Description

elastalert Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Name of User key in Vault					
username	Examples: - username	OrderedDict()		No	string
Name of password key in Vault					
password	Examples: - password	OrderedDict()		No	string

[global secretNames egressgw](#)

Description

ingressgw Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
userprovided	Userprovided Secret			No	object

[global secretNames egressgw userprovided](#)

Description

Userprovided Secret

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Name of Tlsrct secret in Vault					
tlsrctSecretName	Examples: - tlsrct	OrderedDict()		No	string
Name of tlskey secret in Vault					
tlskeySecretName	Examples: - tlskey	OrderedDict()		No	string
Name of cacert secret in Vault					
cacertSecretName	Examples: - cacert	OrderedDict()		No	string

[global mesh](#)

Description

Istio mesh configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio configuration			No	object

[global mesh istio](#)

Description

Istio configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtlsEnabled	Enable/disable istio mutual TLS	false		No	boolean
	Istio egress gateway FQDN				
egressGwFQDN	Examples: - elastalert.com	elastalert.com		No	string
egressGwTLS	Istio egress gateway TLS			No	object
	loadBalancerSharingKey				
loadBalancerSharingKey	Examples: -			No	string

[global mesh istio egressGwTLS](#)

Description

Istio egress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/Disable Istio egress gateway TLS				
enabled	Examples: - true - false	false		No	boolean
mode	Istio ingress gateway TLS mode.	MUTUAL		No	string
certManager	certManager configuration to use auto-generated certificates			No	object
userProvided	Configure user provided certificates			No	object
userProvidedVault	An explanation about the purpose of this instance.			No	object

[global mesh istio egressGwTLS certManager](#)

Description

certManager configuration to use auto-generated certificates

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable to generate certificates using certManager	false		No	boolean
certDuration	Duration of certificate validity	10h		No	string
renewBefore	Duration before which we must renew the certificates.	1h		No	string
organization	organization	affirmednetworks		No	string
issuerName	certificate issuer name	affirmed-clusterissuer		No	string
	Algorithm for PKI certs -RSA or ECDSA				
pkiAlgorithm	Examples: - RSA - ECDSA	RSA		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
pkiKeySize	PKI Key size for certs, if Alogirthm is RSA, valid inputs are 2048,4096,8192. If Alogrithm is ECDSA, valid input is 256	4096		No	string
	Examples:				
	- 256				
	- 2048				
	- 4096				
	- 8192				

global mesh istio egressGwTLS userProvided

Description

Configure user provided certificates

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable to use user provided certificates	true		No	boolean
	Examples:				
	- true				
cacert	- false			No	string
	Congifure cacert. Copy and Paste End User generated cacert				
	Examples:				
tlscrt	- Copy and Paste End User generated Certificate			No	string
	An explanation about the purpose of this instance.				
	Examples:				
tlskey	- Copy and Paste End User generated Certificate			No	string
	An explanation about the purpose of this instance.				
	Examples:				
	- Copy and Paste End User generated Certificate				

global mesh istio egressGwTLS userProvidedVault

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	enabled to use secrets from AKV	false		No	boolean
	Examples:				
	- false				

global logging

Description

PaaS logging association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable logging association	false		No	boolean
	Examples:				
	- false				
fluentd	Fluentd-Configurations			No	object
elastic	Elasticsearch association			No	object
enableAddlTargets	Enable/disable additional destinations	false		No	boolean
addlTargets	Additional logging output destination configuration			No	array
alerts	Alerts configuration			No	object

global logging fluentd

Description

Fluentd-Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	Fluentd-Buffer Configurations			No	object

global logging fluentd buffer

Description

Fluentd-Buffer Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Total buffer size. Maximum amount of buffer space each fluentd thread would use to keep logs. After this space is exhausted, fluentd would start deleting oldest logs to make room for new logs.	32m		No	string
retryWait	Interval(seconds) at which the buffer flush is retried in case of failure.	10s		No	string
maxRetries	Max number of retries to flush a buffer chunk. After this is exhausted, fluentd would delete the chunk.	1		No	integer

global logging elastic

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ip	Elasticsearch IP address			No	string
	Examples:				
	- 10.15.16.64				
Port	Elasticsearch port	9200		No	integer

global logging addlTargets

Description

Additional logging output destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			No	object

[global logging addlTargets](#) forward

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
host	Hostname or IP Address of the forward server for sending logs to additional targets in parallel with elastic			No	string
port	Port of the forward server	24224		No	integer

[global logging](#) alerts

Description

Alerts configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable event alerts				
enabled	Examples: - true	false		No	boolean
	Elasticsearch IP address or host				
host	Examples: - 10.15.10.161			No	string
port	Elasticsearch port	3030		No	integer
realert	Re-alert Info			No	object
	Alert receivers.				
receivers	Examples: - [OrderedDict({'slack': OrderedDict({'webhookurl': ''})}), OrderedDict({'post': OrderedDict({'http_post_url': ''})})]			No	array

[global logging alerts](#) realert

Description

Re-alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Interval in minutes to re-send an alert				
minutes	Examples: - 2	1		No	integer

[global logging alerts](#) receivers

Description

Alert receivers.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
0	The first anyOf schema.				
	Examples:			No	object
	- OrderedDict({'slack': OrderedDict({'webhookurl': ''})})				
1	The second anyOf schema.				
	Examples:			No	object
	- OrderedDict({'post': OrderedDict({'http_post_url': ''})})				
2	The third anyOf schema				
	Examples:			No	object
	- OrderedDict({'email': OrderedDict({'to_address': '', 'smtp_host': '', 'smtp_port': '', 'smtp_ssl': False, 'from_addr': ''})})				

global logging alerts receivers 0

Description

The first anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
slack	Slack receiver details.				
	Examples:			No	object
	- OrderedDict({'webhookurl': ''})				

global logging alerts receivers 0 slack

Description

Slack receiver details.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
webhookurl	The webhook URL that includes your auth data and the ID of the channel (room) you want to post to.				
	Examples:			No	string
	-				

global logging alerts receivers 1

Description

The second anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
post	HTTP post alert receiver details.				
	Examples:			No	object
	- OrderedDict({'http_post_url': ''})				

global logging alerts receivers 1 post

Description

HTTP post alert receiver details.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	URL for HTTP post.				
http_post_url	Examples: -			No	string

global logging alerts receivers 2

Description

The third anyOf schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Mail alert receiver Info.				
email	Examples: - OrderedDict({'to_address': '', 'smtp_host': '', 'smtp_port': '', 'smtp_ssl': False, 'from_addr': ''})			No	object

global logging alerts receivers 2 email

Description

Mail alert receiver Info.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	An address or list of addresses to sent the alert to.				
to_address	Examples: - user1@example.com	user1@example.com		No	string
	SMTP host details.				
smtp_host	Examples: - 1.1.1.1	1.1.1.1		No	string
	SMTP port info				
smtp_port	Examples: - 25	25		No	string
	Enable/disable SSL to SMTP server.				
smtp_ssl	Examples: - false	false		No	boolean
	This sets the from header in the email. By default, the from address is ElastAlert@ and the domain will be set by the smtp server				
from_addr	Examples: - user2@example.com	user2@example.com		No	string

global fileserver

Description

PaaS fileserver associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
nfs	NFS fileserver association			No	object

global fileserver nfs

Description

NFS fileserver association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Fileserver remote host address				
remoteHost	Examples: - 1.1.1.100			No	string
	Fileserver remote file path				
remotePath	Examples: - /filestore	/filestore		No	string
remotePort	Fileserver remote host port	85		No	string

global registry

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

global registry docker

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string
imagePullSecret	Pull an image from a private registry			No	string
username	Username for private docker registry			No	string
password	Password for private docker registry			No	string

global envVars

Description

Environment variables

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Federation type				
fedType	Examples: - paas	paas		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
	Federation unique name				
fedUniqueName	Examples: - elastalert-default	elastalert-default		No	string

global deployment

Description

Deployment option for fed-elastalert

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
nodeDataplaneAffinity	Enables node affinity for the fed-elastalert pods. If set to 'true' all the pods belonging to fed-elastalert will be deployed on nodes with no dataplane label.	false		No	string

global overrides

Description

overrides

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	postInstalEnabled				
postInstallEnabled	Examples: - false - true	false		No	boolean
	preDeleteEnabled				
preDeleteEnabled	Examples: - false - true	false		No	boolean

pod-elastalert

Description

Pod-elastalert parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rbacEnabled	Configuring rbacEnabled to true will create role and rolebinding. Configuring rbacEnabled to false, Elastalert pod will not come up Examples: - true - false	true		No	boolean
serviceAccountName	serviceAccountName configuration is used to create serviceaccount per pod.	elastalert-serviceaccount		No	string
readinessProbe	Readiness probe ensures that traffic is only routed when the pods are ready			No	object
livenessProbe	Liveliness probe to detect and redeem broken state of the pod by restarting them			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
elastalertExtIP	Elastalert external IP				
	Examples:			No	string
	- 10.15.16.64				
debug	Debug				
	Examples:	false		No	boolean
	- false - true				
paasSelectorElasticsearchName	paasSelelctorElasticsearchName, Ip address were elasticsearch is running				
	Examples:			No	string
	- 10.15.16.64				
paasSelectorElasticsearchRestPort	Elasticsearch port	9200		No	string
paasSelectorElasticsearchUsername	Elasticsearch username				
	Examples:	admin		No	string
	- admin				
security	secure data information			No	object
receivers	When egress gateway is enabled, we must add the receiver IP and port to which we must securely send the alert payload. Also please ensure the certificates are signed by the same CA and cacert, tlscert and tlskey have been configured. once that is done, add the reciever server IP and port as a list item.			No	array
service	Service			No	object
storage	Storage option to store alert rules			No	object
runEverySeconds	runEverySeconds	60		No	string

pod-elastalert readinessProbe

Description

Readiness probe ensures that traffic is only routed when the pods are ready

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
failureThreshold	When a probe fails, Kubernetes will try failureThreshold times before giving up	10		No	integer
initialDelaySeconds	Number of seconds after the container has started before liveness or readiness probes are initiated. Defaults to 0 seconds	60		No	integer
periodSeconds	How often (in seconds) to perform the probe. Default to 10 seconds. Minimum value is 1.	5		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer
timeoutSeconds	Number of seconds after which the probe times out. Defaults to 1 second.	30		No	integer

pod-elastalert livenessProbe

Description

Liveliness probe to detect and redeem broken state of the pod by restarting them

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
failureThreshold	When a probe fails, Kubernetes will try failureThreshold times before giving up	10		No	integer
initialDelaySeconds	Number of seconds after the container has started before liveness or readiness probes are initiated. Defaults to 0 seconds	60		No	integer
periodSeconds	How often (in seconds) to perform the probe. Default to 10 seconds. Minimum value is 1.	5		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer
timeoutSeconds	Number of seconds after which the probe times out.	30		No	integer

pod-elastalert security

Description

secure data information

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Elasticsearch password path				
credPath	Examples: - /vault/secrets	/vault/secrets		No	string

pod-elastalert receivers

Description

When egress gateway is enabled, we must add the receiver IP and port to which we must securely send the alert payload. Also please ensure the certificates are signed by the same CA and cacert, tlsert and tlskey have been configured. once that is done, add the reciever server IP and port as a list item.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Add server ip and port				
0	Examples: - OrderedDict({'server': '10.163.207.161', 'port': 443})			No	object

pod-elastalert receivers 0

Description

Add server ip and port

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Alert receiver server IP				
server	Examples: - 10.163.207.161			No	string
	Alert receiver server port				
port	Examples: - 443	443		No	integer

pod-elastalert service

Description

Service

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
loadBalancer	Service type of Elastalert will be LoadBalancer when loadBalancer.enabled=true, otherwise service type=ClusterIP.Metallb will automatically assign EXTERNAL-IP for service type=LoadBalancer.			No	object

pod-elastalert service loadBalancer

Description

Service type of Elastalert will be LoadBalancer when loadBalancer.enabled=true, otherwise service type=ClusterIP.Metallb will automatically assign EXTERNAL-IP for service type=LoadBalancer.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable for LoadBalancer				
	Examples:				
	- true	true		No	boolean
	- false				
loadBalancerIP	loadBalancerIP				
	Examples:			No	string
	-				
loadBalancerFQDN	loadBalancerFQDN				
	Examples:			No	string
	-				
loadBalancerSharingKey	loadBalancerSharingKey	paas		No	string
serviceAnnotations	Service annotations			No	object

pod-elastalert service loadBalancer serviceAnnotations

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	Azure Load-Balancer Internal	true		No	string
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

pod-elastalert storage

Description

Storage option to store alert rules

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
type	Three storage type can be configured. Those are local, remote or rook				
	Examples:				
	- nfs	nfs		No	string
	- remote				
	- rook				

Parameter	Description	Default	Value/Range	Mandatory	Type
storageClassName	Set any convenient value Storage class name if stoare type is local or remote. But if storage type is rook, mandatorily set it to the storage class name of File system storage that gets deployed with fed-rook-ceph. Default value is rook-cephfs				
	Examples:				
	- elasticsearch-local	elasticsearch-local		No	string
	- rook-cephfs				
alertStorageSize	- elasticsearch-remote				
	AlertStorageSize is storage limit	1Gi		No	string
	External Storage provisioner. Configure this field only if storage type is remote. Any file system storage provisioner can be configured.				
	Examples:			No	string
provisioner	- kubernetes.io/azure-file				
	PersistentVolumes that are dynamically created by a StorageClass will have the reclaim policy specified in the reclaimPolicy field				
	Examples:				
	- Delete	Delete		No	string
reclaimPolicy	- Retain				
	External storage specific parameters. By default azure-file parameters are given. Any other key/value pair can be configured by modifying values.yaml			No	object

pod-elastalert storage parameters

Description

External storage specific parameters. By default azure-file parameters are given. Any other key/value pair can be configured by modifying values.yaml

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
customParameters	Both key/value pair can be configured. Since any filesystem type provisioner can be configured, it's corresponding parameters can be set under this section. By default azure-file parameters are given			No	object

pod-elastalert storage parameters customParameters

Description

Both key/value pair can be configured. Since any filesystem type provisioner can be configured, it's corresponding parameters can be set under this section. By default azure-file parameters are given

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
skuName	Azure storage account Sku tier. Default is empty			No	string
location	Azure storage account location. Default is empty.			No	string
storageAccount	Azure storage account name. Default is empty. If a storage account is not provided, all storage accounts associated with the resource group are searched to find one that matches skuName and location			No	string

pod-istio_gw

Description

Pod-istio_gw parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable pod-istio-gw	true		No	boolean
	Examples:				
	- true - false				
rbacEnabled	Enable/Disable RBAC. if RBAC is disabled then serviceAccountName needs to be provided.	true		No	boolean
	Examples:				
	- true - false				
istioNspace	configure the namespace in which istio is deployed	fed-istio		No	string
ingressGateway	Ingress gateway configurations			No	object
egressGateway	Egress gateway configurations			No	object

pod-istio_gw [ingressGateway](#)

Description

Ingress gateway configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable ingress gateway configurations	false		No	boolean
	Examples:				
	- false - true				
ingressGatewayServiceAccountName	Ingress gateway ServiceAccountName	istio-ingressgateway-service-account		No	string

pod-istio_gw [egressGateway](#)

Description

Egress gateway configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable egress gateway configurations	true		No	boolean
	Examples:				
	- true - false				
egressGatewayServiceAccountName	Ingress gateway ServiceAccountName	istio-egressgateway-service-account		No	string

Elastic Helm Documentation

fed-elastic values

Contents

- [Global Parameters](#)
- [The pod-istio_gw schema](#)
- [Pod-elastic parameters](#)

global

Description

Global Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
defaultRbacEnabled	defaultRbacEnabled Flag				
	Examples:				
	- false	false		No	boolean
	- true				
defaultClusterRole	defaultClusterRole configuration is to configure the clusterrole in clusterrolebinding	permissive-network-cr		No	string
defaultServiceAccountName	Default service account for elasticsearch	fed-elastic-serviceaccount		No	string
authType	Default authorisation type for elasticsearch	haloe		No	string
adminPassword	Default password for elasticsearch			No	string
logging	PaaS logging association			No	object
vault	vault			No	object
secretNames	PaaS Vault Secret Names			No	object
kargoProfileTag	This enables collection of elastic server statistics data by kargo			No	string
mesh	Istio mesh configuration			No	object
ingressNetworkPolicy	An explanation about the purpose of this instance.				
	Examples:				
	- OrderedDict({'enabled': True, 'ingressTrafficNamespaces': ['fed-paas-helpers', 'fed-jaeger', 'fed-kubedb-operator', 'fed-prometheus']})			No	object
grafana	PaaS Grafana association			No	object
metricsScrapeInterval	Metrics scrape interval in ServiceMonitors. Setting a lower value would result in faster refreshes of metrics at the cost of more overhead for both prometheus and the application.	1m		No	string
elasticVersion	elastic Search version	xpack-8.14.1		No	string
registry	PaaS container registry associations			No	object
envVars	Environment variables			No	object
loadBalancerSourceRanges	loadBalancerSourceRanges			No	string
overrides	overrides			No	object

global logging

Description

PaaS logging association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable logging association				
	Examples:				
	- false	false		No	boolean
	- true				
fluentd	Fluentd-Configurations			No	object
elastic	Elasticsearch association			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
enableAddlTargets	Enable/disable additional destinations	false		No	boolean
addlTargets	Additional logging output destination configuration			No	array
alerts	Elastalert association			No	object

global logging fluentd

Description

Fluentd-Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	Fluentd-Buffer Configurations			No	object

global logging fluentd buffer

Description

Fluentd-Buffer Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Total buffer size. Maximum amount of buffer space each fluentd thread would use to keep logs. After this space is exhausted, fluentd would start deleting oldest logs to make room for new logs.	32m		No	string
retryWait	Interval(seconds) at which the buffer flush is retried in case of failure.	10s		No	string
maxRetries	Max number of retries to flush a buffer chunk. After this is exhausted, fluentd would delete the chunk.	1		No	integer

global logging elastic

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ip	Elasticsearch IP address				
	Examples:			No	string
	- 10.15.10.161				
Port	Elasticsearch port	9200		No	integer

global logging addlTargets

Description

Additional logging output destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			No	object

global logging addlTargets forward

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
host	Hostname or IP Address of the forward server for sending logs to additional targets in parallel with elastic			No	string
port	Port of the forward server	24224		No	integer

global logging alerts

Description

Elastalert association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable event based alerts				
	Examples:				
	- false	false		No	boolean
	- true				
host	Elastalert IP address				
	Examples:			No	string
	- 10.15.16.64				
port	Elastalert port number	3030		No	integer
realert	Alerts will be repeated after the realert duration			No	object
receivers	The platform on which alerts can be sent			No	array

global logging alerts realert

Description

Alerts will be repeated after the realert duration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minutes	Alerts will be repeated after the realert duration	1		No	integer

global logging alerts receivers

Description

The platform on which alerts can be sent

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
slack	Slack channel			No	object
post	Configuration for HTTP post			No	object
email	Configuration for email receiver			No	object

global logging alerts receivers slack

Description

Slack channel

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
webhookurl	Webhook url of the receiver slack channel			No	string

[global logging alerts receivers](#) post

Description

Configuration for HTTP post

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
http_post_url	HTTP post URL			No	string

[global logging alerts receivers](#) email

Description

Configuration for email receiver

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
to_address	Receiver email address			No	string
smtp_host	The smtp host ip			No	string
smtp_port	The smtp port number			No	string
smtp_ssl	This should be disabled	false		No	boolean
from_addr	Sender address			No	string

[global](#) vault

Description

vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	vault Enabled				
enabled	Examples:				
	- false	false		No	boolean
	- true				
hashicorpVault	hashicorpVault			No	object
azureKeyVault	azureKeyVault			No	object

[global vault](#) hashicorpVault

Description

hashicorpVault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	hashicorpVault Enabled				
enabled	Examples:				
	- false	false		No	boolean
	- true				
service	Vault Service	https://fed-vault-svc-internal.fed-vault:8200		No	string

[global azure](#) azureKeyVault

Description

azureKeyVault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	azureKeyVault Enabled	false		No	boolean
	Examples:				
	- false				
	- true				
aksCluster	Is it AKS cluster	false		No	boolean
	Examples:				
	- false				
	- true				
keyVaultName	key vault name			No	string
tenantID	tenant id where akv created			No	string
userManagedId	User manager ID			No	string

global secretNames

Description

PaaS Vault Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
elastic	grafana Secret Names			No	object
ingressgw	ingressgw Secret Names			No	object

global secretNames elastic

Description

grafana Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
user	Name of User key in Vault	OrderedDict()		No	string
	Examples:				
	- username				
password	Name of password key in Vault	OrderedDict()		No	string
	Examples:				
	- password				

global secretNames ingressgw

Description

ingressgw Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
userprovided	Userprovided Secret			No	object

global secretNames ingressgw userprovided

Description

Userprovided Secret

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Name of Tlsrct secret in Vault					
tlsrctSecretName	Examples: - tlsrct	OrderedDict()		No	string
Name of tlskey secret in Vault					
tlskeySecretName	Examples: - tlskey	OrderedDict()		No	string
Name of cacert secret in Vault					
cacertSecretName	Examples: - cacert	OrderedDict()		No	string

global mesh

Description

Istio mesh configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio configuration			No	object

global mesh istio

Description

Istio configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGwTLS	Istio ingress gateway TLS			No	object
mtlsEnabled	Enable/disable istio mutual TLS	false		No	boolean

global mesh istio ingressGwTLS

Description

Istio ingress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Enabling Istio ingress gateway TLS					
enabled	Examples: - true	false		No	boolean
Istio ingress gateway TLS mode.					
mode	Examples: - SIMPLE	SIMPLE		No	string
certManager	An explanation about the purpose of this instance.			No	object
userProvided	An explanation about the purpose of this instance.			No	object
userProvidedVault	An explanation about the purpose of this instance.			No	object

global mesh istio ingressGwTLS certManager

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
An explanation about the purpose of this instance.					
enabled	Examples: - true	false		No	boolean
An explanation about the purpose of this instance.					
certDuration	Examples: - 10h	10h		No	string
An explanation about the purpose of this instance.					
renewBefore	Examples: - 1h	1h		No	string
An explanation about the purpose of this instance.					
organization	Examples: - affirmednetworks	affirmednetworks		No	string
An explanation about the purpose of this instance.					
issuerName	Examples: - affirmed-clusterissuer	affirmed-clusterissuer		No	string
issuer type					
issuerType	Examples: - vault			No	string

global mesh istio ingressGwTLS userProvided

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
An explanation about the purpose of this instance.					
enabled	Examples: - false	false		No	boolean
An explanation about the purpose of this instance.					
cacert	Examples: - Copy and Paste End User generated Certificate			No	string
An explanation about the purpose of this instance.					
tlscrt	Examples: - Copy and Paste End User generated Certificate			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
tlskey	An explanation about the purpose of this instance.				
	Examples:			No	string
	- Copy and Paste End User generated Certificate				

global mesh istio ingressGwTLS userProvidedVault

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	An explanation about the purpose of this instance.				
	Examples:	false		No	boolean
	- false				

global ingressNetworkPolicy

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	An explanation about the purpose of this instance.				
	Examples:	false		No	boolean
	- true				
ingressTrafficNamespaces	An explanation about the purpose of this instance.				
	Examples:			No	array
	- ['fed-paas-helpers', 'fed-jaeger']				

global ingressNetworkPolicy ingressTrafficNamespaces

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	An explanation about the purpose of this instance.				
	Examples:			No	string
	- fed-paas-helpers				
	- fed-jaeger				

global grafana

Description

PaaS Grafana association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association	true		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
url	Exposed grafana URL				
	Examples:			No	string
	- https://1.1.1.1:3000				
prometheusinfo	Prometheus server association			No	object

[global grafana](#) prometheusinfo

Description

Prometheus server association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
url	Prometheus server URL				
	Examples:	https://prometheus.fed-prometheus:9090		No	string
	- https://prometheus.fed-prometheus:9090				

[global registry](#)

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

[global registry](#) docker

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string

[global envVars](#)

Description

Environment variables

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
fedType	Federation type				
	Examples:	paas		No	string
	- paas				
fedUniqueName	Federation unique name				
	Examples:	elastic-default		No	string
	- elastic-default				

[global overrides](#)

Description

overrides

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
postInstallEnabled					
Examples:					
postInstallEnabled	- false	false		No	boolean
	- true				
preDeleteEnabled					
Examples:					
preDeleteEnabled	- false	false		No	boolean
	- true				
fedIstioEnabled					
Examples:					
fedIstioEnabled	- false	false		No	boolean
	- true				

pod-istio_gw

Description

Pod istio gateway , configuration for ingress and egress gateways

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
pod istio gateway flag					
Examples:					
enabled	- true	false		No	boolean
	- false				

pod-elastic

Description

Pod-elastic parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
singleNodeElastic	bring up elastic on a single node i.e., master, data, and client on single pod			No	object
replicas	Replicas			No	object
externalStorage	externalStorage option			No	object
resources	resource requirements for each type of pod			No	object
rbacEnabled	rbac Enabled Flag. Configuring rbacEnabled to true will create customrole, customrolebinding. Configuring rbacEnabled to false, customrole,customrolebinding will not be created.	true		No	boolean
serviceAccountName	serviceAccountName configuration is used to create serviceaccount per pod.	elastic-serviceaccount		No	string
service	Service			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
terminationPolicy	Termination Policy	Delete		No	string
	Examples:				
	- Delete				
threadPoolBulkQueueSize	threadPoolBulkQueueSize	10000		No	integer
	Examples:				
	- 10000				
healthCheck	healthCheck configuration			No	object
redeployer	Redeployer configuration			No	object
curator	Curator Configuration for purging old logs			No	object

pod-elastic singleNodeElastic

Description

bring up elastic on a single node i.e., master, data, and client on single pod

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable Single node elastic	false		No	boolean
	Examples:				
	- true				
	- false				
resources	resource requirements for pod			No	object

pod-elastic singleNodeElastic resources

Description

resource requirements for pod

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
request	Request resource			No	object
limit	Resource limit			No	object

pod-elastic singleNodeElastic resources request

Description

Request resource

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
memory	Request memory	1Gi		No	string
	Examples:				
	- 1Gi				
cpu	Request cpu	450m		No	string
	Examples:				
	- 450m				

pod-elastic singleNodeElastic resources limit

Description

Resource limit

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Resource memory limit					
memory	Examples: - 1Gi	1Gi		No	string
Resource cpu limit					
cpu	Examples: - 1100m	1100m		No	string

pod-elastic replicas

Description

Replicas

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Number of Master node replicas					
master	Examples: - 3	3		No	integer
Number of Data node replicas					
data	Examples: - 3	3		No	integer
Number of Client node replicas					
client	Examples: - 2	2		No	integer

pod-elastic externalStorage

Description

externalStorage option

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Three storage type can be configured. Those are local, remote or rook.					
type	Examples:	local		No	string
	- local				
	- remote				
	- rook				

Parameter	Description	Default	Value/Range	Mandatory	Type
storageClassName	currently supported external storages are cinder, AzureDisk, AzureFile and rook-ceph.				
	Examples:				
	- cinder-class	cinder-class		No	string
	- azure-disk				
	- azure-file				
provisioner	- rook-cephfs				
	External storage provisioner. See example for available storage provisioners. If any other storage provisioner is set other than cinder and azure-disk. Then set that provisioner's parameters under customParameters.				
	Examples:	kubernetes.io/cinder		No	string
	- kubernetes.io/cinder				
	- kubernetes.io/azure-disk				
parameters	External storage specific parameters. To deploy federation with external storage other than cinder, provide configuration in values.yaml and deploy it.			No	object
reclaimPolicy	PersistentVolumes that are dynamically created by a StorageClass will have the reclaim policy specified in the reclaimPolicy field				
	Examples:	Delete		No	string
	- Delete				
	- Retain				
allowVolumeExpansion	Allow volume expansion				
volumeBindingMode	Examples:	true		No	boolean
	- true				
	- false				
storageSize	PersistentVolumes that are dynamically created by a StorageClass will have the volumeBindingMode specified in the volumeBindingMode field				
	Examples:	WaitForFirstConsumer		No	string
	- WaitForFirstConsumer				
	- Immediate				
storageSize	storage allocation for each type of elastic pod, Data pod stores data so more Size should be specified. The storage size of data nodes would also depend on the number of replicas configured per index as part of fed-paas-helpers, If replica is set to 1, the storage requirement becomes double as ES would maintain a duplicate set of data			No	object

pod-elastic externalStorage parameters

Description

External storage specific parameters. To deploy federation with external storage other than cinder, provide configuration in values.yaml and deploy it.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cinder	Parameters for cinder external storage			No	object
azureDisk	Parameters to configure Azure disk storage. To add any other parameter related to Azure disk, edit values.yaml during deployment			No	object

pod-elastic externalStorage parameters cinder

Description

Parameters for cinder external storage

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
type	VM disk type	ceph		No	string
availability	Availability Zone	nova		No	string
fsType	fsType	ext4		No	string

pod-elastic externalStorage parameters azureDisk

Description

Parameters to configure Azure disk storage. To add any other parameter related to Azure disk, edit values.yaml during deployment

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
storageaccounttype	Azure storage account name. If a storage account is provided, it must reside in the same resource group as the cluster			No	string
kind	Possible values are shared (default), dedicated, and managed	shared		No	string

pod-elastic externalStorage storageSize

Description

storage allocation for each type of elastic pod, Data pod stores data so more Size should be specified. The storage size of data nodes would also depend on the number of replicas configured per index as part of fed-paas-helpers, If replica is set to 1, the storage requirement becomes double as ES would maintain a duplicate set of data

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Master Node Allocation					
master	Examples: - 8Gi	8Gi		No	string
Client Node Allocation					
client	Examples: - 8Gi	8Gi		No	string
Data Node Allocation					
data	Examples: - 150Gi	150Gi		No	string

pod-elastic resources

Description

resource requirements for each type of pod

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
master	Master			No	object
client	Client			No	object
data	Data			No	object

pod-elastic resources master

Description

Master

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
request	request			No	object
limit	Limit			No	object

[pod-elastic resources master request](#)

Description

request

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
memory	memory				
	Examples:	8Gi		No	string
	- 8Gi				
cpu	CPU				
	Examples:	1		No	string
	- 1				

[pod-elastic resources master limit](#)

Description

Limit

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
memory	memory				
	Examples:	15Gi		No	string
	- 15Gi				
cpu	CPU				
	Examples:	3		No	string
	- 3				

[pod-elastic resources client](#)

Description

Client

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
request	Request			No	object
limit	Limit			No	object

[pod-elastic resources client request](#)

Description

Request

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
Memory					
memory	Examples: - 8Gi	8Gi		No	string
CPU					
cpu	Examples: - 2	2		No	string

pod-elastic resources client limit

Description

Limit

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Memory					
memory	Examples: - 15Gi	15Gi		No	string
CPU					
cpu	Examples: - 5	5		No	string

pod-elastic resources data

Description

Data

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
request	request			No	object
limit	Limit			No	object

pod-elastic resources data request

Description

request

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
memory					
memory	Examples: - 10Gi	10Gi		No	string
CPU					
cpu	Examples: - 2	2		No	string

pod-elastic resources data limit

Description

Limit

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
memory					
memory	Examples: - 20Gi	20Gi		No	string
CPU					
cpu	Examples: - 5	5		No	string

pod-elastic service

Description

Service

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
exposedport					
exposedPort	Examples: - 9200	9200		No	integer
loadBalancer	Service type of elastic will be LoadBalancer when loadBalancer.enabled=true, otherwise service type=ClusterIP.Metallb will automatically assign EXTERNAL-IP for service type=LoadBalancer.			No	object

pod-elastic service loadBalancer

Description

Service type of elastic will be LoadBalancer when loadBalancer.enabled=true, otherwise service type=ClusterIP.Metallb will automatically assign EXTERNAL-IP for service type=LoadBalancer.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
loadBalancerIP					
loadBalancerIP	Examples: -			No	string
loadBalancerFQDN					
loadBalancerFQDN	Examples: -			No	string
loadBalancerSharingKey	loadBalancerSharingKey	paas		No	string
serviceAnnotations	Service annotations			No	object

pod-elastic service loadBalancer serviceAnnotations

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	Azure Load-Balancer Internal	true		No	string
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

pod-elastic healthCheck

Description

healthCheck configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
failureThreshold	Number of failures healthCheck tolerates	3		No	integer
	Examples:				
	- 3				
periodSeconds	Time interval in seconds for healthCheck loop to run	10		No	integer
	Examples:				
	- 10				
timeoutSeconds	Number of timeouts healthCheck tolerates	10		No	integer
	Examples:				
	- 10				

pod-elastic redeployer

Description

Redeployer configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	redeployer enable/disable flag	true		No	boolean
	Examples:				
	- true				
	- false				
periodSeconds	Time interval in seconds for redeployer loop to run	60		No	integer
	Examples:				
	- 10000				
failureThreshold	Number of failures redeployer tolerates	5		No	integer
	Examples:				
	- 5				

pod-elastic curator

Description

Curator Configuration for purging old logs

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cron	Cron			No	object
config	Config			No	object

pod-elastic curator cron

Description

Cron

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
schedule	Cron Scheduler				
	Examples:	"*/10 *		No	string
	- "*/10 * * * *	* * *			
startingDeadLineSeconds	After Helm deployment, curator will start after mentioned seconds. In mentioned seconds it is expected that elastic deployed successfully				
	Examples:	300		No	integer
	- 300				

pod-elastic curator config

Description

Config

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
deleteLogs	Delete Logs			No	object

pod-elastic curator config deleteLogs

Description

Delete Logs

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
timeBased	Deletion of logs based on time			No	object
sizeBased	Deletion of logs based on Size			No	object

pod-elastic curator config deleteLogs timeBased

Description

Deletion of logs based on time

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
unitForLogs	Unit of Time				
	Examples:	days		No	string
	- days				
unitCountForLogs	Unit of Count of Time.Deletes the elastic indices which are older than the mentioned unitForLogs with pattern fluentd* which is used for logs sent by fluentd				
	Examples:	3		No	integer
	- 3				
unitForJaegerSpan	The Unit for JaegerSpan				
	Examples:	days		No	string
	- days				

Parameter	Description	Default	Value/Range	Mandatory	Type
unitCountForJaegerSpan	Unit of Count of Time.Deletes the elastic indices which are older than the mentioned unitForJaegerSpan with pattern jaeger-span* which is used for spans sent by jaeger Examples: - 3	3		No	integer

pod-elastic curator config deleteLogs sizeBased

Description

Deletion of logs based on Size

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
totalDiskUsage	Delete indices matching the prefix fluentd, jaeger-span, jaeger-service in excess of configured disk size threshold, starting with the oldest indices, based on index creation_date. Examples: - 800	800		No	integer
sizeLogs	Deletes fluentd logs indices so that total disk size is within the mentioned sizeLogs Gi Examples: - 200	200		No	integer
sizeJaegerSpan	Deletes jaegerspan indices so that total disk size is within the mentioned sizeLogs Gi Examples: - 200	200		No	integer

Grafana Helm Documentation

fed-grafana values

Contents

- [Global Parameters](#)
- [Pod-grafana parameters](#)
- [The pod-istio_gw schema](#)

global

Description

Global Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enableSCC	If running on OCP cluster, please set enableSCC to true	false		No	boolean
enableUserProvidedSCC	If running on OCP cluster and SCC are given by the user, please set enableUserProvidedSCC to true	false		No	boolean
vault	vault			No	object
secretNames	PaaS Vault Secret Names			No	object
logging	PaaS logging association			No	object
kargoProfileTag	This enables creation of specific kargo-default-profile for fed-grafana			No	string
ingressNetworkPolicy	network policies configuration			No	object
grafana	PaaS Grafana association			No	object
authType	Authentication type for grafana, allowed types are local and haloe	haloe		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
adminPassword	Grafana password			No	string
monitoring	PaaS Monitoring associations			No	object
metricsScrapeInterval	Metrics scrape interval in ServiceMonitors. Setting a lower value would result in faster refreshes of metrics at the cost of more overhead for both prometheus and the application.	1m		No	string
registry	PaaS container registry associations			No	object
envVars	Environment variables			No	object
istio	Istio related configurations			No	object
mesh	Istio mesh configuration			No	object
loadBalancerSourceRanges	loadBalancerSourceRanges			No	string
overrides	overrides			No	object

global vault

Description

vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	vault Enabled				
enabled	Examples: - false - true	false		No	boolean
hashicorpVault	hashicorpVault			No	object
azureKeyVault	azureKeyVault			No	object

global vault hashicorpVault

Description

hashicorpVault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	hashicorpVault Enabled				
enabled	Examples: - false - true	false		No	boolean
service	vault Service	http: //fed-vault-svc-internal.fed-vault:8200		No	string

global azure azureKeyVault

Description

azureKeyVault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	azureKeyVault Enabled	false		No	boolean
	Examples:				
	- false				
	- true				
aksCluster	Is it AKS cluster	false		No	boolean
	Examples:				
	- false				
	- true				
keyVaultName	key vault name			No	string
tenantID	tenant id where akv created			No	string
userManagerId	User manager ID			No	string
workloadIdentity	is it Workloadidentity	true		No	boolean
	Examples:				
	- false				
	- true				

global secretNames

Description

PaaS Vault Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
grafana	grafana Secret Names			No	object
ingressgw	ingressgw Secret Names			No	object

global secretNames grafana

Description

grafana Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
user	Name of User key in Vault	OrderedDict()		No	string
	Examples:				
	- username				
password	Name of password key in Vault	OrderedDict()		No	string
	Examples:				
	- password				

global secretNames ingressgw

Description

ingressgw Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
userprovided	Userprovided Secret			No	object

global secretNames ingressgw userprovided

Description

Userprovided Secret

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Name of Tlsctrl secret in Vault				
tlsctrlSecretName	Examples: - tlsctrl	OrderedDict()		No	string
	Name of tlskey secret in Vault				
tlskeySecretName	Examples: - tlskey	OrderedDict()		No	string
	Name of cacert secret in Vault				
cacertSecretName	Examples: - cacert	OrderedDict()		No	string

global logging

Description

PaaS logging association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable logging association				
enabled	Examples: - false - true	false		No	boolean
fluentd	Fluentd-Configurations			No	object
elastic	Elasticsearch association			No	object
enableAddlTargets	Enable/disable additional destinations	false		No	boolean
addlTargets	Additional logging output destination configuration			No	array
alerts	Alerts configuration			No	object

global logging fluentd

Description

Fluentd-Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	Fluentd-Buffer Configurations			No	object

global logging fluentd buffer

Description

Fluentd-Buffer Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Total buffer size. Maximum amount of buffer space each fluentd thread would use to keep logs. After this space is exhausted, fluentd would start deleting oldest logs to make room for new logs.	32m		No	string
retryWait	Interval(seconds) at which the buffer flush is retried in case of failure.	10s		No	string
maxRetries	Max number of retries to flush a buffer chunk. After this is exhausted, fluentd would delete the chunk.	1		No	integer

global logging elastic

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Elasticsearch IP address				
ip	Examples: - 10.15.10.161			No	string
Port	Elasticsearch port	9200		No	integer

global logging addITargets

Description

Additional logging output destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			No	object

global logging addITargets forward

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
host	Hostname or IP Address of the forward server for sending logs to additional targets in parallel with elastic			No	string
port	Port of the forward server	24224		No	integer

global logging alerts

Description

Alerts configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable event alerts				
enabled	Examples: - true	false		No	boolean
	Elasticsearch IP address or host				
host	Examples: - 10.15.10.161			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
port	Elasticsearch port	3030		No	integer
realert	Re-alert Info			No	object
	Alert receivers.				
receivers	Examples: - [OrderedDict({'slack': OrderedDict({'webhookurl': ''})}), OrderedDict({'post': OrderedDict({'http_post_url': ''})})]			No	array

global logging alerts realert

Description

Re-alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Interval in minutes to re-send an alert				
minutes	Examples: - 2	1		No	integer

global logging alerts receivers

Description

Alert receivers.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	The first anyOf schema.				
0	Examples: - OrderedDict({'slack': OrderedDict({'webhookurl': ''})})			No	object
	The second anyOf schema.				
1	Examples: - OrderedDict({'post': OrderedDict({'http_post_url': ''})})			No	object
	The third anyOf schema				
2	Examples: - OrderedDict({'email': OrderedDict({'to_address': '', 'smtp_host': '', 'smtp_port': '', 'smtp_ssl': False, 'from_addr': ''})})			No	object

global logging alerts receivers 0

Description

The first anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Slack receiver details.				
slack	Examples: - OrderedDict({'webhookurl': ''})			No	object

global logging alerts receivers 0 slack

Description

Slack receiver details.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	The webhook URL that includes your auth data and the ID of the channel (room) you want to post to.				
webhookurl	Examples: -			No	string

global logging alerts receivers 1

Description

The second anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	HTTP post alert receiver details.				
post	Examples: - OrderedDict({'http_post_url': ''})			No	object

global logging alerts receivers 1 post

Description

HTTP post alert receiver details.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	URL for HTTP post.				
http_post_url	Examples: -			No	string

global logging alerts receivers 2

Description

The third anyOf schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Mail alert receiver Info.				
email	Examples: - OrderedDict({'to_address': '', 'smtp_host': '', 'smtp_port': '', 'smtp_ssl': False, 'from_addr': ''})			No	object

global logging alerts receivers 2 email

Description

Mail alert receiver Info.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
to_address	An address or list of addresses to sent the alert to.	user1@example.com		No	string
	Examples: - user1@example.com				
smtp_host	SMTP host details.	1.1.1.1		No	string
	Examples: - 1.1.1.1				
smtp_port	SMTP port info	25		No	string
	Examples: - 25				
smtp_ssl	Enable/disable SSL to SMTP server.	false		No	boolean
	Examples: - false				
from_addr	This sets the from header in the email. By default, the from address is ElastAlert@ and the domain will be set by the smtp server	user2@example.com		No	string
	Examples: - user2@example.com				

[global](#) ingressNetworkPolicy

Description

network policies configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabled network policy	true		No	boolean
ingressTrafficNamespaces	Namespaces which are required to be allowed for ingress traffic			No	array

[global](#) grafana

Description

PaaS Grafana association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association	true		No	boolean
url	Exposed grafana URL			No	string
	Examples: - http: //1.1.1.1:3000				
prometheusinfo	Prometheus server association			No	object

[global](#) [grafana](#) prometheusinfo

Description

Prometheus server association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
Prometheus server URL					
url	Examples: - http: //prometheus.fed-prometheus:9090	http: //prometheus.fed-prometheus:9090		No	string

global monitoring

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association			No	object

global monitoring prometheus

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable prometheus monitoring	true		No	boolean

global registry

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

global registry docker

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string
imagePullSecret	Pull an image from a private registry			No	string
username	Username for private docker registry			No	string
password	Password for private docker registry			No	string

global envVars

Description

Environment variables

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
fedType	Federation type				
	Examples:	paas		No	string
	- paas				
fedUniqueName	Federation unique name				
	Examples:	grafana-default		No	string
	- grafana-default				

global istio

Description

Istio related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtls	Istio mutual TLS related configuration			No	object

global istio mtls

Description

Istio mutual TLS related configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable istio mutual TLS	false		No	boolean

global mesh

Description

Istio mesh configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio configuration			No	object

global mesh istio

Description

Istio configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtlsEnabled	Enable/disable istio mutual TLS	false		No	boolean
ingressGwIP	Istio ingress gateway IP				
	Examples:			No	string
	-				
ingressGwFQDN	Istio ingress gateway FQDN				
	Examples:	grafana.com		No	string
	- grafana.com				
serviceAnnotations	Service Annotations			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGwPort	Istio ingress gateway service port	3000		No	integer
	Examples:				
	- 3000				
ingressGwTLS	Istio ingress gateway TLS			No	object
loadBalancerSharingKey	Istio ingress gateway service loadbalancer sharing key.	paas		No	string
	Examples:				
	- paas				

global mesh istio serviceAnnotations

Description

Service Annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	Azure Load-Balancer Internal	true		No	string
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Azure Load-Balancer Internal subnet	none		No	string

global mesh istio ingressGwTLS

Description

Istio ingress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio ingress gateway TLS	false		No	boolean
	Examples:				
	- true				
mode	Istio ingress gateway TLS mode.	SIMPLE		No	string
	Examples:				
	- SIMPLE				
certManager	An explanation about the purpose of this instance.			No	object
userProvided	An explanation about the purpose of this instance.			No	object
userProvidedVault	An explanation about the purpose of this instance.			No	object

global mesh istio ingressGwTLS certManager

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	An explanation about the purpose of this instance.	false		No	boolean
	Examples:				
	- true				

Parameter	Description	Default	Value/Range	Mandatory	Type
certDuration	An explanation about the purpose of this instance.	10h		No	string
	Examples:				
	- 10h				
renewBefore	An explanation about the purpose of this instance.	1h		No	string
	Examples:				
	- 1h				
organization	An explanation about the purpose of this instance.	affirmednetworks		No	string
	Examples:				
	- affirmednetworks				
issuerName	An explanation about the purpose of this instance.	affirmed-clusterissuer		No	string
	Examples:				
	- affirmed-clusterissuer				
issuerType	Type of the certificate issuer			No	string
	Examples:				
	- vault				
pkiAlgorithm	Algorithm for PKI certs -RSA or ECDSA	RSA		No	string
	Examples:				
	- RSA				
	- ECDSA				
pkiKeySize	PKI Key size for certs, if Alogirthm is RSA, valid inputs are 2048,4096,8192. If Alogrithm is ECDSA, valid input is 256	4096		No	string
	Examples:				
	- 256				
	- 2048				
	- 4096				
	- 8192				

global mesh istio ingressGwTLS userProvided

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	An explanation about the purpose of this instance.	false		No	boolean
	Examples:				
	- false				
cacert	An explanation about the purpose of this instance.			No	string
	Examples:				
	- Copy and Paste End User generated Certificate				

Parameter	Description	Default	Value/Range	Mandatory	Type
tls crt	An explanation about the purpose of this instance.				
	Examples:				
	- Copy and Paste End User generated Certificate				
tls key	An explanation about the purpose of this instance.				
	Examples:				
	- Copy and Paste End User generated Certificate				

global mesh istio ingressGwTLS userProvidedVault

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	An explanation about the purpose of this instance.				
	Examples:				
	- false				

global overrides

Description

overrides

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
preDeleteEnabled	preDeleteEnabled				
	Examples:				
	- false				
postInstallEnabled	postInstalEnabled				
	Examples:				
	- false				

pod-grafana

Description

Pod-grafana parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
debug	to enable debug-level logs	false		No	boolean
enabled	Enable/Disable flag	true		No	boolean
rbacEnabled	RBAC Enabled flag	true		No	boolean
serviceAccountName	Service Account Name	grafana-serviceaccount		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
readinessProbe	Readiness probe ensures that traffic is only routed when the pods are ready			No	object
livenessProbe	Liveness probe to detect and redeem broken state of the pod by restarting them			No	object
ao5gcBasic	AO5GC Basic dashboard enable or disable setting			No	object

[pod-grafana](#) readinessProbe

Description

Readiness probe ensures that traffic is only routed when the pods are ready

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
failureThreshold	When a probe fails, Kubernetes will try failureThreshold times before giving up	10		No	integer
initialDelaySeconds	Number of seconds after the container has started before liveness or readiness probes are initiated. Defaults to 0 seconds	60		No	integer
periodSeconds	How often (in seconds) to perform the probe. Default to 10 seconds. Minimum value is 1.	5		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer
timeoutSeconds	Number of seconds after which the probe times out. Defaults to 1 second.	30		No	integer

[pod-grafana](#) livenessProbe

Description

Liveness probe to detect and redeem broken state of the pod by restarting them

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
failureThreshold	When a probe fails, Kubernetes will try failureThreshold times before giving up	10		No	integer
initialDelaySeconds	Number of seconds after the container has started before liveness or readiness probes are initiated. Defaults to 0 seconds	60		No	integer
periodSeconds	How often (in seconds) to perform the probe. Default to 10 seconds. Minimum value is 1.	5		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer
timeoutSeconds	Number of seconds after which the probe times out.	30		No	integer

[pod-grafana](#) ao5gcBasic

Description

AO5GC Basic dashboard enable or disable setting

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable flag	false		No	boolean
influxUrl	Influx Db Url	http: //fed-influx-cluster.fed-influx-cluster:8086		No	string
dbName	Influx DB Telegraf db name	telegraf		No	string

[pod-istio_gw](#)

Description

Pod istio gateway , configuration for ingress and egress gateways

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
istioNamespace	Istio namespace				
	Examples:			No	string
	- fed-istio				
istioRevision	Istio revision				
	Examples:			No	string
	- 1-8-2				
egressGateway	Istio egress gateway				
	Examples:			No	object
	- OrderedDict({'enabled': False})				

pod-istio_gw egressGateway

Description

Istio egress gateway

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Istio egress gateway flag				
	Examples:	false		No	boolean
	- false				

The fed-istio values schema

The fed-istio values schema

Contents

- [The fed-istio global values](#)
- [The Istio components configuration](#)
- [The Redis configuration values](#)
- [The pod-istio_gw schema](#)

global

Description

Global configuration values for fed-istio.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
multusDeployed	Set to true if deploying along with fed-upf, fed-agf and fed-n3iwf. In case of fed-amf, fed-mme and fed-amf-mme, set to true if those feds use multus for providing services. In all other cases, set to false.	false		No	boolean
enableSCC	Set to true on OCP clusters to enable support for Security-Context-Constraints (SCC)	false		No	boolean
ingressNetworkPolicy	network policies configuration			No	object
registry	PaaS container registry associations			No	object
envVars	Environment variables used by fed-istio applications.				
	Examples:			No	object
	- OrderedDict({'fedType': 'paas-istio', 'fedUniqueName': 'default'})				
monitoring_prometheus_ns	Prometheus namespace.	fed-prometheus		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
metricsScrapelInterval	Metric scraping interval.	1m		No	string
logging	Logging schema.			No	object
grafana	The grafana schema.			No	object
monitoring	PaaS Monitoring associations			No	object
disablePolicyChecks	Boolean to disable Istio policy checks.	false		No	boolean
telemetry	Telemetry collection control.				
	Examples: - OrderedDict({'telemetryEnabled': 'true'})			No	object
mesh	Istio mesh configuration			No	object
loadBalancerSourceRanges	The loadBalancerSourceRanges.				
	Examples: - []			No	array
overrides	Helm override values.			No	object
topologySpreadConstraints	Pod topology spread constraints control how pods of given microservice type are spread across the cluster among failure-domains such as regions, zones, nodes, and other user-defined topology domains. This can help to achieve high availability as well as efficient resource utilization.			No	object

global ingressNetworkPolicy

Description

network policies configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabled network policy	true		No	boolean
ingressTrafficNamespaces	Namespaces which are required to be allowed for ingress traffic			No	array

global registry

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

global registry docker

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string
imagePullSecret	Pull an image from a private registry			No	string
username	Username for private docker registry			No	string
password	Password for private docker registry			No	string

global envVars

Description

Environment variables used by fed-istio applications.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
fedType	Federation Type.	paas-istio		No	string
fedUniqueName	Federation unique name.	default		No	string

global logging

Description

Logging schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Boolean to enable logging, true/false.				
	Examples:				
	- false	false		No	boolean
	- true				
fluentd	Fluentd logging configuration.			No	object
elastic	The Elastic configuration parameters.			No	object
enableAddlTargets	Enable additional logging targets.				
	Examples:				
	- false	false		No	boolean
	- true				
addlTargets	An array of additional logging targets.			No	array

global logging fluentd

Description

Fluentd logging configuration.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	Buffer configuration.			No	object

global logging fluentd buffer

Description

Buffer configuration.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Buffer limit size.	32m		No	string
retryWait	Retry wait time.	10s		No	string
maxRetries	Maximum retry attempts.	1		No	integer

global logging elastic

Description

The Elastic configuration parameters.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
IP	The elastic IpAddress.			No	string
Port	The elastic IpPort.	9200		No	integer

global logging addITargets

Description

An array of additional logging targets.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			No	object

global logging addITargets forward

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
host	Hostname or IP Address of the forward server for sending logs to additional targets in parallel with elastic				
	Examples:			No	string
	- 192.168.1.1 - forward-server.com				
port	The IpPort of the forward server	24224		No	integer

global grafana

Description

The grafana schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Grafana enabled boolean.	true		No	boolean
url	The grafana url.			No	string
prometheusinfo	The grafana's prometheus configuration.			No	object

global grafana prometheusinfo

Description

The grafana's prometheus configuration.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
url	The prometheus URL.	http://prometheus.fed-prometheus:9090		No	string

global monitoring

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association			No	object

[global monitoring](#) prometheus

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable prometheus monitoring	true		No	boolean

[global telemetry](#)

Description

Telemetry collection control.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
telemetryEnabled	The telemetryEnabled string to enable to disable. Not a boolean.	true		No	string

[global mesh](#)

Description

Istio mesh configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio configuration			No	object

[global mesh istio](#)

Description

Istio configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGwIP	Istio ingress gateway IP				
	Examples:			No	string
	-				
ingressGwFQDN	Istio ingress gateway FQDN				
	Examples:	istio.com		No	string
	- istio.com				
ingressGwPort	Istio ingress gateway service port	20001		No	integer
ingressGwTLS	Istio ingress gateway TLS			No	object
loadBalancerSharingKey	Istio ingress gateway service loadbalancer sharing key.				
	Examples:	paas		No	string
	- paas				
serviceAnnotations	Service Annotations			No	object

[global mesh istio](#) ingressGwTLS

Description

Istio ingress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio ingress gateway TLS				
	Examples:				
	- true	true		No	boolean
	- false				
mode	Istio ingress gateway TLS mode.				
	Examples:				
	- SIMPLE	SIMPLE		No	string
certManager	certManager Configuration			No	object
userProvided	userProvided CERTIFICATES			No	object

[global mesh istio ingressGwTLS](#) certManager

Description

certManager Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for certManager configuration				
	Examples:				
	- true	true		No	boolean
	- false				
certDuration	certDuration Configuration	10h		No	string
renewBefore	renewBefore Configuration	1h		No	string
organization	organization Configuration				
	Examples:				
	- affirmednetworks	affirmednetworks		No	string
issuerName	issuerName				
	Examples:				
	- affirmed-clusterissuer	affirmed-clusterissuer		No	string

[global mesh istio ingressGwTLS](#) userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Enable/Disable Flag for userProvided Certificates					
enabled	Examples:	false		No	boolean
	- false				
	- true				

Parameter	Description	Default	Value/Range	Mandatory	Type
cacert	cacert Configuration				
	Examples:			No	string
	- Copy and Paste End User generated Certificate				
tlsCRT	An explanation about the purpose of this instance.				
	Examples:	tlsCRT configuration		No	string
	- Copy and Paste End User generated Certificate				
tlskey	tlskey configuration				
	Examples:			No	string
	- Copy and Paste End User generated Certificate				

global mesh istio serviceAnnotations

Description

Service Annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	Azure Load-Balancer Internal				
	Examples:	true		No	string
	- true				
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Azure Load-Balancer Subnet				
	Examples:	none		No	string
	- none				

global overrides

Description

Helm override values.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
preDeleteEnabled	Boolean to enable Helm preDelete scripts.				
	Examples:	false	No	boolean	
	- false				

global topologySpreadConstraints

Description

Pod topology spread constraints control how pods of given microservice type are spread across the cluster among failure-domains such as regions, zones, nodes, and other user-defined topology domains. This can help to achieve high availability as well as efficient resource utilization.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable pod topology spread constraints	true		No	boolean
	Examples:				
	- false				
	- true				
constraints	List of pod topology spread constraints to be applied.			No	array

global topologySpreadConstraints constraints

Description

List of pod topology spread constraints to be applied.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Definition of pod topology spread constraint to be applied to the pod specification.			No	object

global topologySpreadConstraints constraints 0

Description

Definition of pod topology spread constraint to be applied to the pod specification.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxSkew	Describes the degree to which pods may be unevenly distributed. It's the maximum permitted difference between the number of matching pods in any two topology domains of a given topology type. It must be greater than zero.	1		No	integer
	Examples:				
	- 1				
topologyKey	Its the key of node labels. If two nodes are labelled with this key and have identical values for that label, the Kubernetes scheduler treats both nodes as being in the same topology. The scheduler tries to place a balanced number of Pods into each topology domain.	kubernetes.io/hostname		No	string
	Examples:				
	- kubernetes.io/hostname				
whenUnsatisfiable	Indicates how to deal with a pod if it doesn't satisfy the defined pod topology spread constraint.	ScheduleAnyway		No	string
	Examples:				
	- ScheduleAnyway				
	- DoNotSchedule				

pod-istio

Description

Istio components configuration.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istioinit	Configuration parameters that affect the deployment of the istio-init init container.			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
istioproxy	Provide configuration for istio-proxy containers used by auto-injection.				
	Examples: - OrderedDict({'accessLogFile': '/dev/stdout', 'accessLogEncoding': 'TEXT', 'includeIPRanges': '10.96.0.0/12,192.168.0.0/16', 'excludeOutboundPorts': ''})			No	object
istiopilot	Provides additional configuration of the Istio-Pilot pod.				
	Examples: - OrderedDict({'istiodReplicas': 2, 'discovery': OrderedDict({'requestCpu': '100m', 'traceSampling': '0.01'})})			No	object
paasSelector	Configuration parameters specific to the Istio pods.				
	Examples: - OrderedDict({'jaegerHostName': '10.15.10.211', 'grafanaHostName': '10.15.10.161'})			No	object
istioOperator	Configuration parameters specific to the Istio operator pods.				
	Examples: - OrderedDict({'renewDeadline': '20s', 'resourceTimeout': '10s'})			No	object

pod-istio istioinit

Description

Configuration parameters that affect the deployment of the istio-init init container.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
useMaistraUbi8Image	This string selects the alternative UBI8 image that MUST be used on all RedHat based host nodes. Set to string "true" for RedHat hosts. This is driven by adoption differences between nftables and iptables in various Linux kernal variants.	true		No	boolean

pod-istio istioproxy

Description

Provide configuration for istio-proxy containers used by auto-injection.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtlsEnabled	Flag for enabling custom excludeOutbound and excludeInbound ports while encryption is enabled. Needs to be set to true if encryption enabled				
	Examples: - true - false	false		No	boolean
accessLogFile	Set to /dev/stdout to enable logs, or null string to disable logs.				
	Examples: - /dev/stdout			No	string
accessLogEncoding	May be TEXT or JSON				
	Examples: - TEXT	TEXT		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
includeIPRanges	Defines the subnets to be included within the Istio Service Mesh.	10.96.0.0/12,192.168.0.0/16		No	string
	Examples:				
	- 10.96.0.0/12,192.168.0.0/16				
excludeOutboundPorts	Defines the ports used in outbound traffic that shall be excluded from the Service Mesh.			No	string

pod-istio istipilot

Description

Provides additional configuration of the Istio-Pilot pod.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istiodReplicas	Number of replicas of istiod pod.	3		No	integer
	Examples:				
	- 2				
discovery	IstioPilot configuration.			No	object

pod-istio istipilot discovery

Description

IstioPilot configuration.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
requestCpu	K8s requestCpu for this container application.	100m		No	string
	Examples:				
	- 100m				

pod-istio paasSelector

Description

Configuration parameters specific to the Istio pods.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
jaegerHostName	The Jaeger host IpAddress.			No	string
	Examples:				
	- 10.15.10.211				
grafanaHostName	The Grafana host IpAddress.			No	string
	Examples:				
	- 10.15.10.161				

pod-istio istioOperator

Description

Configuration parameters specific to the Istio operator pods.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
renewDeadline	The timeout for the leader election of istio operator.	20s		No	string
	Examples: - 20s				
resourceTimeout	The timeout which Istio Operator uses for istio resources i.e, istio-proxy sidecar and gateways to become ready	10s		No	string
	Examples: - 10s				

pod-redis

Description

Redis configuration parameters.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Redis enabled true/false.	true		No	boolean
	Examples: - true				

pod-istio_gw

Description

Pod istio gateway , configuration for ingress and egress gateways

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
egressGateway	Istio egress gateway			No	object
	Examples: - OrderedDict({'enabled': False})				

[pod-istio_gw](#) egressGateway

Description

Istio egress gateway

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Istio egress gateway flag	false		No	boolean
	Examples: - false				

Jaeger Helm Documentation

fed-jaeger values

Contents

- [Global Parameters](#)
- [Pod-jaeger parameters](#)
- [The pod-istio_gw schema](#)

global

Description

Global Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
defaultRbacEnabled	Default RBAC Enabled flag	false		No	boolean
	Examples:				
	- false				
	- true				
metricsScrapeInterval	Metrics scrape interval in ServiceMonitors. Setting a lower value would result in faster refreshes of metrics at the cost of more overhead for both prometheus and the application.	1m		No	string
authType	Authentication type for jaeger	haloe		No	string
adminPassword	Default password for elasticsearch			No	string
logging	PaaS logging association			No	object
vault	vault			No	object
secretNames	PaaS Vault Secret Names			No	object
ingressNetworkPolicy	network policies configuration			No	object
grafana	PaaS Grafana association			No	object
registry	PaaS container registry associations			No	object
envVars	Environment variables			No	object
istio	Istio related configurations			No	object
mesh	Istio mesh configuration			No	object
monitoring	PaaS Monitoring associations			No	object
loadBalancerSourceRanges	loadBalancerSourceRanges			No	string
overrides	overrides			No	object

global logging

Description

PaaS logging association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable logging association	false		No	boolean
	Examples:				
	- false				
	- true				
fluentd	Fluentd-Configurations			No	object
elastic	Elasticsearch association			No	object
enableAddlTargets	Enable/disable additional destinations	false		No	boolean
addlTargets	Additional logging output destination configuration			No	array
alerts	Alerts configuration			No	object

global logging fluentd

Description

Fluentd-Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	Fluentd-Buffer Configurations			No	object

global logging fluentd buffer

Description

Fluentd-Buffer Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Total buffer size. Maximum amount of buffer space each fluentd thread would use to keep logs. After this space is exhausted, fluentd would start deleting oldest logs to make room for new logs.	32m		No	string
retryWait	Interval(seconds) at which the buffer flush is retried in case of failure.	10s		No	string
maxRetries	Max number of retries to flush a buffer chunk. After this is exhausted, fluentd would delete the chunk.	1		No	integer

global logging elastic

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Elasticsearch IP address				
IP	Examples: - 10.15.10.161			No	string
Port	Elasticsearch port	9200		No	integer

global logging addITargets

Description

Additional logging output destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			No	object

global logging addITargets forward

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
host	Hostname or IP Address of the forward server for sending logs to additional targets in parallel with elastic			No	string
port	Port of the forward server	24224		No	integer

global logging alerts

Description

Alerts configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable event alerts	false		No	boolean
	Examples:				
	- true				
host	Elasticsearch IP address or host			No	string
	Examples:				
	- 10.15.10.161				
port	Elasticsearch port	3030		No	integer
realert	Re-alert Info			No	object
receivers	Alert receivers.			No	array
	Examples:				
	- [OrderedDict({'slack': OrderedDict({'webhookurl': ''})}), OrderedDict({'post': OrderedDict({'http_post_url': ''})})]				

global logging alerts realert

Description

Re-alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minutes	Interval in minutes to re-send an alert	1		No	integer
	Examples:				
	- 2				

global logging alerts receivers

Description

Alert receivers.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	The first anyOf schema.			No	object
	Examples:				
	- OrderedDict({'slack': OrderedDict({'webhookurl': ''})})				
1	The second anyOf schema.			No	object
	Examples:				
	- OrderedDict({'post': OrderedDict({'http_post_url': ''})})				
2	The third anyOf schema			No	object
	Examples:				
	- OrderedDict({'email': OrderedDict({'to_address': '', 'smtp_host': '', 'smtp_port': '', 'smtp_ssl': False, 'from_addr': ''})})				

global logging alerts receivers 0

Description

The first anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Slack receiver details.				
slack	Examples: - OrderedDict({'webhookurl': ''})			No	object

global logging alerts receivers 0 slack

Description

Slack receiver details.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	The webhook URL that includes your auth data and the ID of the channel (room) you want to post to.				
webhookurl	Examples: -			No	string

global logging alerts receivers 1

Description

The second anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	HTTP post alert receiver details.				
post	Examples: - OrderedDict({'http_post_url': ''})			No	object

global logging alerts receivers 1 post

Description

HTTP post alert receiver details.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	URL for HTTP post.				
http_post_url	Examples: -			No	string

global logging alerts receivers 2

Description

The third anyOf schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Mail alert receiver Info.				
email	Examples: - OrderedDict({'to_address': '', 'smtp_host': '', 'smtp_port': '', 'smtp_ssl': False, 'from_addr': ''})			No	object

global logging alerts receivers 2 email

Description

Mail alert receiver Info.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
to_address	An address or list of addresses to sent the alert to.	user1@example.com		No	string
	Examples:				
	- user1@example.com				
smtp_host	SMTP host details.	1.1.1.1		No	string
	Examples:				
	- 1.1.1.1				
smtp_port	SMTP port info	25		No	string
	Examples:				
	- 25				
smtp_ssl	Enable/disable SSL to SMTP server.	false		No	boolean
	Examples:				
	- false				
from_addr	This sets the from header in the email. By default, the from address is ElastAlert@ and the domain will be set by the smtp server	user2@example.com		No	string
	Examples:				
	- user2@example.com				

global vault

Description

vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	vault Enabled	false		No	boolean
	Examples:				
	- false				
	- true				
hashicorpVault	hashicorpVault			No	object
azureKeyVault	azureKeyVault			No	object

global vault hashicorpVault

Description

hashicorpVault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	hashicorpVault Enabled	false		No	boolean
	Examples:				
	- false				
	- true				

Parameter	Description	Default	Value/Range	Mandatory	Type
service	vault Service	http: //fed-vault-svc-internal.fed-vault:8200		No	string

global azure azureKeyVault

Description

azureKeyVault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	azureKeyVault Enabled				
	Examples:				
	- false	false		No	boolean
	- true				
aksCluster	Is it AKS cluster				
	Examples:				
	- false	false		No	boolean
	- true				
keyVaultName	key vault name			No	string
tenantID	tenant id where akv created			No	string
userManagerId	User manager ID			No	string

global secretNames

Description

PaaS Vault Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
jaeger	jaeger Secret Names			No	object
ingressgw	ingressgw Secret Names			No	object
egressgw	egressgw Secret Names			No	object

global secretNames jaeger

Description

jaeger Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
elasticUsername	Name of User key in Vault				
	Examples:	OrderedDict()		No	string
	- username				
elasticPassword	Name of password key in Vault				
	Examples:	OrderedDict()		No	string
	- password				
username	Name of User key in Vault				
	Examples:	OrderedDict()		No	string
	- username				

Parameter	Description	Default	Value/Range	Mandatory	Type
	Name of User key in Vault				
password	Examples: - password	OrderedDict()		No	string

[global secretNames ingressgw](#)

Description

ingressgw Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
userprovided	Userprovided Secret			No	object

[global secretNames ingressgw userprovided](#)

Description

Userprovided Secret

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Name of Tls crt secret in Vault				
tls crtSecretName	Examples: - tls crt	OrderedDict()		No	string
	Name of tls key secret in Vault				
tls keySecretName	Examples: - tls key	OrderedDict()		No	string
	Name of cacert secret in Vault				
cacertSecretName	Examples: - cacert	OrderedDict()		No	string

[global secretNames egressgw](#)

Description

egressgw Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
userprovided	Userprovided Secret			No	object

[global secretNames egressgw userprovided](#)

Description

Userprovided Secret

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Name of Tls crt secret in Vault				
tls crtSecretName	Examples: - tls crt	OrderedDict()		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
Name of tlskey secret in Vault					
tlskeySecretName	Examples: - tlskey	OrderedDict()		No	string
Name of cacert secret in Vault					
cacertSecretName	Examples: - cacert	OrderedDict()		No	string

[global](#) ingressNetworkPolicy

Description

network policies configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabled network policy	true		No	boolean
ingressTrafficNamespaces	Namespaces which are required to be allowed for ingress traffic			No	array

[global](#) grafana

Description

PaaS Grafana association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association	true		No	boolean
url	Exposed grafana URL			No	string
prometheusinfo	Prometheus server association			No	object

[global](#) grafana prometheusinfo

Description

Prometheus server association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
url	Prometheus server URL	http: //prometheus.fed-prometheus:9090		No	string

[global](#) registry

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

[global](#) registry docker

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string
imagePullSecret	Pull an image from a private registry			No	string
username	Username for private docker registry			No	string
password	Password for private docker registry			No	string

global envVars

Description

Environment variables

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Federation type				
fedType	Examples: - paas	paas		No	string
	Federation unique name				
fedUniqueName	Examples: - jaeger-default	jaeger-default		No	string

global istio

Description

Istio related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtls	Istio mutual TLS related configuration			No	object

global istio mtls

Description

Istio mutual TLS related configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable istio mutual TLS	false		No	boolean

global mesh

Description

Istio mesh configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio configuration			No	object

global mesh istio

Description

Istio configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
mtlsEnabled	Enable/disable istio mutual TLS	false		No	boolean
ingressGwIP	Istio ingress gateway IP				
	Examples: -			No	string
ingressGwFQDN	Istio ingress gateway FQDN				
	Examples: - jaeger.com	jaeger.com		No	string
ingressGwPort	Istio ingress gateway service port				
	Examples: - 16686	16686		No	integer
ingressGwTLS	Istio ingress gateway TLS			No	object
egressGwTLS	Istio egress gateway TLS			No	object
ingressGwAdditionalServices	Ingress Gw Additional Services				
	Examples: - [OrderedDict({'ingressGwIP': '', 'ingressGwFQDN': 'jaeger.com', 'ingressGw': 'jaeger-ingress', 'ingressGwPort': 4318, 'mtlsEnabled': False, 'ingressGwTLS': OrderedDict({'enabled': True, 'mode': 'SIMPLE'}), 'serviceAnnotations': OrderedDict({'service.beta.kubernetes.io/azure-load-balancer-internal': 'true', 'service.beta.kubernetes.io/azure-load-balancer-internal-subnet': 'none'})}), OrderedDict({'ingressGwIP': '', 'ingressGwFQDN': 'jaeger.com', 'ingressGw': 'jaeger-ingress', 'ingressGwPort': 4318, 'mtlsEnabled': False, 'ingressGwTLS': OrderedDict({'enabled': True, 'mode': 'SIMPLE'}), 'serviceAnnotations': OrderedDict({'service.beta.kubernetes.io/azure-load-balancer-internal': 'true', 'service.beta.kubernetes.io/azure-load-balancer-internal-subnet': 'none'})})]			No	array
loadBalancerSharingKey	Istio ingress gateway service loadbalancer sharing key.				
	Examples: - paas	paas		No	string
serviceAnnotations	Service Annotations			No	object

global mesh istio ingressGwTLS

Description

Istio ingress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio ingress gateway TLS				
	Examples: - true	false		No	boolean
mode	Istio ingress gateway TLS mode.				
	Examples: - SIMPLE	SIMPLE		No	string
certManager	An explanation about the purpose of this instance.			No	object
userProvided	An explanation about the purpose of this instance.			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
userProvidedVault	An explanation about the purpose of this instance.			No	object

global mesh istio ingressGwTLS certManager

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	An explanation about the purpose of this instance.				
enabled	Examples: - true	false		No	boolean
	An explanation about the purpose of this instance.				
certDuration	Examples: - 10h	10h		No	string
	An explanation about the purpose of this instance.				
renewBefore	Examples: - 1h	1h		No	string
	An explanation about the purpose of this instance.				
organization	Examples: - affirmednetworks	affirmednetworks		No	string
	An explanation about the purpose of this instance.				
issuerName	Examples: - affirmed-clusterissuer	affirmed-clusterissuer		No	string
	issuer type				
issuerType	Examples: - vault			No	string
	Algorithm for PKI certs -RSA or ECDSA				
pkiAlgorithm	Examples: - RSA - ECDSA	RSA		No	string
	PKI Key size for certs, if Alogirthm is RSA, valid inputs are 2048,4096,8192. If Alogrithm is ECDSA, valid input is 256				
pkiKeySize	Examples: - 256 - 2048 - 4096 - 8192	4096		No	string

global mesh istio ingressGwTLS userProvided

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	An explanation about the purpose of this instance.	false		No	boolean
	Examples: - false				
cacert	An explanation about the purpose of this instance.			No	string
	Examples: - Copy and Paste End User generated Certificate				
tls crt	An explanation about the purpose of this instance.			No	string
	Examples: - Copy and Paste End User generated Certificate				
tls key	An explanation about the purpose of this instance.			No	string
	Examples: - Copy and Paste End User generated Certificate				

global mesh istio ingressGwTLS userProvidedVault

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	enabled to use secrets from AKV	false		No	boolean
	Examples: - false				

global mesh istio egressGwTLS

Description

Istio egress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio egress gateway TLS	false		No	boolean
	Examples:				
	- true - false				
mode	Istio egress gateway TLS mode.	MUTUAL		No	string
	Examples: - MUTUAL				
certManager	certManager Configuration			No	object
userProvided	userProvided CERTIFICATES			No	object
userProvidedVault	An explanation about the purpose of this instance.			No	object

global mesh istio egressGwTLS certManager

Description

certManager Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for certManager configuration	true		No	boolean
	Examples:				
	- true				
	- false				
certDuration	certDuration Configuration	10h		No	string
renewBefore	renewBefore Configuration	1h		No	string
organization	organization Configuration	affirmednetworks		No	string
	Examples:				
	- affirmednetworks				
issuerName	issuerName	affirmed-clusterissuer		No	string
	Examples:				
	- affirmed-clusterissuer				
pkiAlgorithm	Algorithm for PKI certs -RSA or ECDSA	RSA		No	string
	Examples:				
	- RSA				
	- ECDSA				
pkiKeySize	PKI Key size for certs, if Alogirthm is RSA, valid inputs are 2048,4096,8192. If Alogirthm is ECDSA, valid input is 256	4096		No	string
	Examples:				
	- 256				
	- 2048				
	- 4096				
	- 8192				

global mesh istio egressGwTLS userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvided Certificates	false		No	boolean
	Examples:				
	- false				
	- true				
cacert	cacert Configuration			No	string
	Examples:				
	- Copy and Paste End User generated Certificate				
tls crt	tls crt configuration			No	string
	Examples:				
	- Copy and Paste End User generated Certificate				

Parameter	Description	Default	Value/Range	Mandatory	Type
	tlskey configuration				
tlskey	Examples: - Copy and Paste End User generated Certificate			No	string

global mesh istio egressGwTLS userProvidedVault

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	enabled to use secrets from AKV				
enabled	Examples: - false	false		No	boolean

global mesh istio ingressGwAdditionalServices

Description

Ingress Gw Additional Services

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Array element				
	Examples:				
0	- OrderedDict({'ingressGwIP': '', 'ingressGwFQDN': 'jaeger.com', 'ingressGw': 'jaeger-ingress', 'ingressGwPort': 4318, 'mtlsEnabled': False, 'ingressGwTLS': OrderedDict({'enabled': True, 'mode': 'SIMPLE'}), 'serviceAnnotations': OrderedDict({'service.beta.kubernetes.io/azure-load-balancer-internal': True, 'service.beta.kubernetes.io/azure-load-balancer-internal-subnet': 'none'})})			No	object
	Array element				
	Examples:				
1	- OrderedDict({'ingressGwIP': '', 'ingressGwFQDN': 'jaeger.com', 'ingressGw': 'jaeger-ingress', 'ingressGwPort': 4318, 'mtlsEnabled': False, 'ingressGwTLS': OrderedDict({'enabled': True, 'mode': 'SIMPLE'}), 'serviceAnnotations': OrderedDict({'service.beta.kubernetes.io/azure-load-balancer-internal': 'true', 'service.beta.kubernetes.io/azure-load-balancer-internal-subnet': 'none'})})			No	object

global mesh istio ingressGwAdditionalServices 0

Description

Array element

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Ingress Gw IP				
ingressGwIP	Examples: -			No	string
	The ingress Gw FQDN				
ingressGwFQDN	Examples: - jaeger.com	jaeger.com		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGw	Ingress gateway name Examples: - jaeger-ingress	jaeger-ingress		No	string
ingressGwPort	The ingress Gw Port. Examples: - 4318	4318		No	integer
mtlsEnabled	MTLS flag. Examples: - false	false		No	boolean
ingressGwTLS	Ingress gateway TLS. Examples: - OrderedDict({'enabled': True, 'mode': 'SIMPLE'})			No	object
serviceAnnotations	Service Annotations Examples: - OrderedDict({'service.beta.kubernetes.io/azure-load-balancer-internal': 'true', 'service.beta.kubernetes.io/azure-load-balancer-internal-subnet': 'none'})			No	object

global mesh istio ingressGwAdditionalServices 0 ingressGwTLS

Description

Ingress gateway TLS.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Ingress Gateway TLS flag. Examples: - true	false		No	boolean
mode	Ingress Gw TLS mode. Examples: - SIMPLE			No	string

global mesh istio ingressGwAdditionalServices 0 serviceAnnotations

Description

Service Annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	Azure Loadbalancer Internal	true		No	string
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Azure Loadbalancer Internal subnet	none		No	string

global mesh istio ingressGwAdditionalServices 0

Description

Array element

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGwIP	Ingress Gw IP				
	Examples:			No	string
	-				
ingressGwFQDN	The ingress Gw FQDN				
	Examples:	jaeger.com		No	string
	- jaeger.com				
ingressGw	Ingress gateway name				
	Examples:	jaeger-ingress		No	string
	- jaeger-ingress				
ingressGwPort	The ingress Gw Port.				
	Examples:	4318		No	integer
	- 4318				
mtlsEnabled	MTLS flag.				
	Examples:	false		No	boolean
	- false				
ingressGwTLS	Ingress gateway TLS.				
	Examples:			No	object
	- OrderedDict({'enabled': True, 'mode': 'SIMPLE'})				
serviceAnnotations	Service Annotations				
	Examples:			No	object
	- OrderedDict({'service.beta.kubernetes.io/azure-load-balancer-internal': True, 'service.beta.kubernetes.io/azure-load-balancer-internal-subnet': 'none'})				

global mesh istio ingressGwAdditionalServices 0 ingressGwTLS

Description

Ingress gateway TLS.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Ingress Gateway TLS flag.				
	Examples:	false		No	boolean
	- true				
mode	Ingress Gw TLS mode.				
	Examples:			No	string
	- SIMPLE				

global mesh istio ingressGwAdditionalServices 0 serviceAnnotations

Description

Service Annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	Azure loadbalancer Internal	true		No	string
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Azure Loadbalancer Internal subnet	none		No	string

global mesh istio serviceAnnotations

Description

Service Annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	Azure Load-Balancer Internal	false		No	string
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Azure Load-Balancer Internal subnet	none		No	string

global monitoring

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association			No	object

global monitoring prometheus

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable prometheus monitoring	true		No	boolean

global overrides

Description

overrides

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	preDeleteEnabled				
	Examples:				
preDeleteEnabled	- false	false		No	boolean
	- true				
	postInstalEnabled				
	Examples:				
postInstallEnabled	- false	false		No	boolean
	- true				

pod-jaeger

Description

Pod-jaeger parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
storage	Storage			No	object
rbacEnabled	rbac Enabled flag.Configuring rbacEnabled to true will create custom clusterrole, clusterrolebinding for jaeger-collector and jaeger-query. Configuring rbacEnabled to false, clusterrole, clusterrolebinding will not be created. Examples: - true - false	true		No	boolean
serviceAccountNameCollector	serviceAccountNameCollector configuration is used to create serviceaccount for jaeger-collector. Examples: - jaeger-collector-sa	jaeger-collector-sa		No	string
serviceAccountNameQuery	serviceAccountNameQuery configuration is used to create serviceaccount for jaeger-query. Examples: - jaeger-query-sa	jaeger-query-sa		No	string
readinessProbe	Readiness probe ensures that traffic is only routed when the pods are ready			No	object
livenessProbe	Liveliness probe to detect and redeem broken state of the pod by restarting them			No	object
collector	On deployment of collector please change enabled flag to true and change other required parameters			No	object
query	On deployment of query please change the enabled flag to true and change other required parameters			No	object
keycloak	Deploy with keycloak, enable to true if keycloak needs to be deployed			No	object

pod-jaeger storage

Description

Storage

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
type	Storage type	elasticsearch		No	string
elasticsearch	Elasticsearch			No	object

pod-jaeger storage elasticsearch

Description

Elasticsearch

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
scheme	Scheme	http		No	string
host	Host Examples: - 10.15.10.161			No	string
port	Port	9200		No	integer
shards	Shards: Buckets which Elasticsearch maintains per index. Default values is 5. More shards are better for greater distribution, faster indexing and searching data, but with some maintenance overhead.	5		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Replica: Duplicate index/data/shard maintained by Elasticsearch for HA and redundancy. A values of 1 means, ES would maintain 1 duplicate copy of the data in a different node (need to have sufficient data nodes).	1		No	string

pod-jaeger readinessProbe

Description

Readiness probe ensures that traffic is only routed when the pods are ready

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
failureThreshold	When a probe fails, Kubernetes will try failureThreshold times before giving up	10		No	integer
initialDelaySeconds	Number of seconds after the container has started before liveness or readiness probes are initiated. Defaults to 0 seconds	10		No	integer
periodSeconds	How often (in seconds) to perform the probe. Minimum value is 1.	5		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer
timeoutSeconds	Number of seconds after which the probe times out. Defaults to 1 second.	30		No	integer

pod-jaeger livenessProbe

Description

Liveness probe to detect and redeem broken state of the pod by restarting them

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
failureThreshold	When a probe fails, Kubernetes will try failureThreshold times before giving up	10		No	integer
initialDelaySeconds	Number of seconds after the container has started before liveness or readiness probes are initiated. Defaults to 0 seconds	10		No	integer
periodSeconds	How often (in seconds) to perform the probe. Default to 10 seconds. Minimum value is 1.	5		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer
timeoutSeconds	Number of seconds after which the probe times out. Defaults to 1 second.	30		No	integer

pod-jaeger collector

Description

On deployment of collector please change enabled flag to true and change other required parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabled flag				
	Examples:				
	- true	true		No	boolean
	- false				
replicaCount	Replica count	1		No	integer
log	Log-Information			No	object
service	Service			No	object
resources	Resource			No	object

pod-jaeger collector log

Description

Log-Information

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
level	Log-level	info		No	string

pod-jaeger collector service

Description

Service

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
exposedExternalIP	Exposed External IP				
	Examples:			No	string
	- 10.15.10.161				
tchannelPort	tchannelPort: used by jaeger-agent to send spans in jaeger.thrift format	14267		No	integer
loadBalancer	If you want to enable metal lb loadbalancer change loadbalancer enabled to true			No	object

pod-jaeger collector service loadBalancer

Description

If you want to enable metal lb loadbalancer change loadbalancer enabled to true

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable for LoadBalancer	true		No	boolean
loadBalancerIP	loadBalancerIP				
	Examples:			No	string
	-				
loadBalancerFQDN	loadBalancerFQDN				
	Examples:			No	string
	-				
loadBalancerSharingKey	sharing key is for having single loadbalancer IP shared among multiple paas components.	paas		No	string
serviceAnnotations	Service Annotations			No	object

pod-jaeger collector service loadBalancer serviceAnnotations

Description

Service Annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	Azure Load-Balancer Internal	false		No	string
service.beta.kubernetes.io/azure-load-balancer-internalli-subnet	Azure Load-Balancer Internal subnet	none		No	string

pod-jaeger collector resources

Description

Resource

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
requests	requests			No	object

pod-jaeger collector resources requests

Description

requests

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	CPU	500m		No	string
memory	Memory	1Gi		No	string

pod-jaeger query

Description

On deployment of query please change the enabled flag to true and change other required parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag				
	Examples:				
	- true	true		No	boolean
	- false				
replicaCount	Replica Count	1		No	integer
service	Service			No	object
resources	resources			No	object

pod-jaeger query service

Description

Service

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
queryPort	queryPort: externally accessible port for UI and API	16686		No	integer
loadBalancer	If you want to enable metal lb loadbalancer change loadbalancer enabled to true			No	object

pod-jaeger query service loadBalancer

Description

If you want to enable metal lb loadbalancer change loadbalancer enabled to true

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable for LoadBalancer	true		No	boolean
loadBalancerIP	loadBalancerIP				
	Examples:			No	string
	-				
loadBalancerFQDN	loadBalancerFQDN				
	Examples:			No	string
	-				

Parameter	Description	Default	Value/Range	Mandatory	Type
loadBalancerSharingKey	loadBalancerSharingKey	paas		No	string
serviceAnnotations	Service Annotations			No	object

pod-jaeger query service loadBalancer serviceAnnotations

Description

Service Annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	Azure Load-Balancer Internal	false		No	string
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Azure Load-Balancer Internal subnet	none		No	string

pod-jaeger query resources

Description

resources

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
requests	requests			No	object

pod-jaeger query resources requests

Description

requests

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	CPU	256m		No	string
memory	Memory	128Mi		No	string

pod-jaeger keycloak

Description

Deploy with keycloak, enable to true if keycloak needs to be deployed

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag				
	Examples:				
	- true	true		No	boolean
	- false				
service	Service			No	object

pod-jaeger keycloak service

Description

Service

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
loadBalancer	If you want to enable metal lb loadbalancer change loadbalancer enabled to true			No	object

pod-jaequer keycloak service loadBalancer

Description

If you want to enable metal lb loadbalancer change loadbalancer enabled to true

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable for LoadBalancer	true		No	boolean
	loadBalancerIP				
loadBalancerIP	Examples: -			No	string
	loadBalancerFQDN				
loadBalancerFQDN	Examples: -			No	string
loadBalancerSharingKey	loadBalancerSharingKey	paas		No	string
serviceAnnotations	Service Annotations			No	object

pod-jaeger keycloak service loadBalancer serviceAnnotations

Description

Service Annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	Azure Load-Balancer Internal	false		No	string
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Azure Load-Balancer Internal subnet	none		No	string

pod-istio_gw

Description

Pod istio gateway , configuration for ingress and egress gateways

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Istio egress gateway				
egressGateway	Examples: - OrderedDict({'enabled': False})			No	object

pod-istio_gw egressGateway

Description

Istio egress gateway

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Istio namespace				
istioNspace	Examples: - fed-istio	fed-istio		No	string
	Istio egress gateway flag				
enabled	Examples: - false	false		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
egressGateway	Egress gateway parameters			No	object
externalHosts	ExternalHosts Configurations			No	array
paasSelector	PAAS parameters			No	object

[pod-istio_gw](#) egressGateway

Description

Egress gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable egress gateway				
enabled	Examples: - false	false		No	boolean

[pod-istio_gw](#) externalHosts

Description

ExternalHosts Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	The second anyOf schema.			No	object

[pod-istio_gw](#) externalHosts [0](#)

Description

The second anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
host	host is '.com'			No	string
server	istio-ingressGW IP of fed-elastic			No	string
ports	Port and Scheme Configurations for fed-elastic ingressGw			No	array

[pod-istio_gw](#) externalHosts [0](#) [ports](#)

Description

Port and Scheme Configurations for fed-elastic ingressGw

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	The first anyOf schema.			No	object

[pod-istio_gw](#) externalHosts anyOf/[0](#) [ports](#) [0](#)

Description

The first anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
number	Number is the port serving traffic on the istio-ingressGW of fed-elastic	80		No	integer
scheme	scheme is http/https. It dictates whether TLS is used for fed-elastic connections. If TLS is not enabled, scheme is http. If TLS is enabled, scheme is https.	http		No	string

pod-istio_gw paasSelector

Description

PAAS parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Jaeger host (IP or FQDN)					
Examples:					
jaegerHostName	- 10.10.10.10	fqdn.com		No	string
	- fqdn.com				

Kafka Helm Documentation

fed-kafka_strimzi values

Contents

- [Enable/Disable Flag](#)
- [Global Parameters](#)

enabled

Description

Enable/Disable Flag

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

global

Description

Global Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
registry	PaaS container registry associations			No	object
logging	PaaS logging association			No	object
mesh	PaaS service mesh associations			No	object

global registry

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

global registry docker

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string

global logging

Description

PaaS logging association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable logging association	false		No	boolean
	Examples:				
	- false - true				
fluentd	fluentd configurations			No	object
elastic	Elasticsearch association			No	object
enableAddlTargets	Enable/disable additional destinations	false		No	boolean
	Examples:				
	- true - false				
addlTargets	Additional logging output destination configuration			No	array
alerts	Alerts configuration			No	object

global logging fluentd

Description

fluentd configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	fluentd buffer configurations			No	object

global logging fluentd buffer

Description

fluentd buffer configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Total buffer size. Maximum amount of buffer space each fluentd thread would use to keep logs. After this space is exhausted, fluentd would start deleting oldest logs to make room for new logs.	32m		No	string
retryWait	Interval(seconds) at which the buffer flush is retried in case of failure.	10s		No	string
maxRetries	Max number of retries to flush a buffer chunk. After this is exhausted, fluentd would delete the chunk.	1		No	integer

global logging elastic

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ip	Elasticsearch IP address	No			string
	Examples:				
	- 10.15.10.161				

Parameter	Description	Default	Value/Range	Mandatory	Type
Port	Elasticsearch port	9200		No	integer

[global logging](#) addITargets

Description

Additional logging output destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			No	object

[global logging](#) addITargets forward

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
	Hostname or IP Address of the forward server for sending logs to additional targets in parallel with elastic				
host	Examples: - 192.168.1.1 - forward-server.com			No	string
	Port of the forward server				
port	Examples: - 24224	24224		No	integer

[global logging](#) alerts

Description

Alerts configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable event alerts				
enabled	Examples: - true	false		No	boolean
	Elasticsearch IP address or host				
host	Examples: - 10.15.10.161			No	string
port	Elasticsearch port	3030		No	integer
realert	Re-alert Info			No	object
	Alert receivers.				
receivers	Examples: - [OrderedDict({'slack': OrderedDict({'webhookurl': ''})}), OrderedDict({'post': OrderedDict({'http_post_url': ''})})]			No	array

[global logging](#) alerts realert

Description

Re-alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Interval in minutes to re-send an alert				
minutes	Examples: - 2	1		No	integer

global logging alerts receivers

Description

Alert receivers.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	The first anyOf schema.				
0	Examples: - OrderedDict({'slack': OrderedDict({'webhookurl': ''})})			No	object
	The second anyOf schema.				
1	Examples: - OrderedDict({'post': OrderedDict({'http_post_url': ''})})			No	object
	The third anyOf schema				
2	Examples: - OrderedDict({'email': OrderedDict({'to_address': '', 'smtp_host': '', 'smtp_port': '', 'smtp_ssl': False, 'from_addr': ''})})			No	object

global logging alerts receivers 0

Description

The first anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Slack receiver details.				
slack	Examples: - OrderedDict({'webhookurl': ''})			No	object

global logging alerts receivers 0 slack

Description

Slack receiver details.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	The webhook URL that includes your auth data and the ID of the channel (room) you want to post to.				
webhookurl	Examples: -			No	string

global logging alerts receivers 1

Description

The second anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
post	HTTP post alert receiver details.				
	Examples:			No	object
	- OrderedDict({'http_post_url': ''})				

global logging alerts receivers 1 post

Description

HTTP post alert receiver details.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
http_post_url	URL for HTTP post.				
	Examples:			No	string
	-				

global logging alerts receivers 2

Description

The third anyOf schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
email	Mail alert receiver Info.				
	Examples:			No	object
	- OrderedDict({'to_address': '', 'smtp_host': '', 'smtp_port': '', 'smtp_ssl': False, 'from_addr': ''})				

global logging alerts receivers 2 email

Description

Mail alert receiver Info.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
to_address	An address or list of addresses to sent the alert to.				
	Examples:	user1@example.com		No	string
	- user1@example.com				
smtp_host	SMTP host details.				
	Examples:	1.1.1.1		No	string
	- 1.1.1.1				
smtp_port	SMTP port info				
	Examples:	25		No	string
	- 25				

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable SSL to SMTP server.				
smtp_ssl	Examples: - false	false		No	boolean
	This sets the from header in the email. By default, the from address is ElastAlert@ and the domain will be set by the smtp server				
from_addr	Examples: - user2@example.com	user2@example.com		No	string

global mesh

Description

PaaS service mesh associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio service mesh association			No	object

global mesh istio

Description

Istio service mesh association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Service mesh ingress gateway				
ingressGw	Examples: - ingress-gateway			No	string
	Specific IP requested for Ingress Gateway LoadBalancer service				
ingressGwIP	Examples: -			No	string
	Http max concurrent steams per connections for Ingress Gateway.				
ingressGwMaxConcurrentStreams	Calculated as TPS*Latency/Number of connections, eg: for 72k TPS, 120 connections, 3 sec latency we get 1800 streams	1536	No	integer	
	HTTP initial flow-control window size per stream for Ingress Gateway.				
ingressGwInitialStreamWindowSize	Value is in octets.	262144	No	integer	
	FQDN to be added as annotation to the Ingress Gateway LoadBalancer service				
ingressGwFQDN	Examples: -	smf.com		No	string
	Enable/disable istio mutual TLS	false		No	boolean
mtlsEnabled					
ingressGwTLS	Istio ingress gateway TLS			No	object

global mesh istio ingressGwTLS

Description

Istio ingress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio ingress gateway TLS	false		No	boolean
	Examples:				
	- true				
	- false				
mode	Istio ingress gateway TLS mode.	MUTUAL		No	string
	Examples:				
	- MUTUAL				
certManager	certManager Configuration			No	object
userProvided	userProvided CERTIFICATES			No	object

global mesh istio ingressGwTLS certManager

Description

certManager Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for certManager configuration	true		No	boolean
	Examples:				
	- true				
	- false				
certDuration	certDuration Configuration	2160h		No	string
renewBefore	renewBefore Configuration	648h		No	string
organization	organization Configuration	affirmednetworks		No	string
	Examples:				
	- affirmednetworks				
issuerName	issuerName	affirmed-clusterissuer-sbi		No	string
	Examples:				
	- affirmed-clusterissuer-sbi				
issuerType	issuerType	vault		No	string
	Examples:				
	- vault				

global mesh istio ingressGwTLS userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvided Certificates	false		No	boolean
	Examples:				
	- false				
cacert	cacert Configuration			No	string
	Examples:				
	- Copy and Paste End User generated Certificate				
tls crt	tls crt configuration			No	string
	Examples:				
	- Copy and Paste End User generated Certificate				
tls key	tls key configuration			No	string
	Examples:				
	- Copy and Paste End User generated Certificate				

Kibana Helm Documentation

fed-kibana values

Contents

- [Global Parameters](#)
- [The pod-istio_gw schema](#)
- [Pod-kibana parameters](#)

global

Description

Global Scoped Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
defaultRbacEnabled	Default Rbac Enabled flag	false		No	boolean
defaultClusterRole	defaultClusterRole configuration is to configure the clusterrole in clusterrolebinding	permissive-network-cr		No	string
defaultServiceAccountName	Default service account for kibana	fed-kibana-serviceaccount		No	string
authType	Default authorisation type for elasticsearch	haloe		No	string
adminPassword	Default password for elasticsearch			No	string
vault	vault			No	object
secretNames	PaaS Vault Secret Names			No	object
azureEntra	Authenticate to Kibana using Azure login			No	object
ingressNetworkPolicy	network policies configuration			No	object
logging	PaaS logging association			No	object
grafana	PaaS Grafana association			No	object
monitoring	PaaS Monitoring associations			No	object
metricsScrapeInterval	Metrics scrape interval in ServiceMonitors. Setting a lower value would result in faster refreshes of metrics at the cost of more overhead for both prometheus and the application.	1m		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
registry	PaaS container registry associations			No	object
envVars	Environment variables			No	object
mesh	Istio mesh configuration			No	object
loadBalancerSourceRanges	loadBalancerSourceRanges			No	string
overrides	overrides			No	object

[global vault](#)

Description

vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Vault Enabled				
	Examples:				
enabled	- false	false		No	boolean
	- true				
hashicorpVault	HashicorpVault			No	object
azureKeyVault	AzureKeyVault			No	object

[global vault hashicorpVault](#)

Description

HashicorpVault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	HashicorpVault Enabled				
	Examples:				
enabled	- false	false		No	boolean
	- true				
service	Vault Service	http: //fed-vault-svc-internal.fed-vault:8200		No	string

[global azure azureKeyVault](#)

Description

AzureKeyVault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	AzureKeyVault Enabled				
	Examples:				
enabled	- false	false		No	boolean
	- true				
	Is it AKS cluster				
	Examples:				
aksCluster	- false	false		No	boolean
	- true				

Parameter	Description	Default	Value/Range	Mandatory	Type
keyVaultName	key vault name			No	string
tenantID	tenant id where akv created			No	string
userManagedId	User manager ID			No	string
	is it Workloadidentity				
	Examples:				
workloadIdentity	- false	true		No	boolean
	- true				

global secretNames

Description

PaaS Vault Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
oauth2Proxy	AAD keycloak client ID and Client secret			No	object
kibana	kibana Secret Names			No	object
ingressgw	ingressgw Secret Names			No	object

global secretNames oauth2Proxy

Description

AAD keycloak client ID and Client secret

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
clientId	AAD keycloak client ID			No	string
clientSecret	AAD keycloak clientSecret			No	string

global secretNames kibana

Description

kibana Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Name of User key in Vault				
username	Examples: - username	OrderedDict()		No	string
	Name of password key in Vault				
password	Examples: - password	OrderedDict()		No	string

global secretNames ingressgw

Description

ingressgw Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
userprovided	Userprovided Secret			No	object

global secretNames ingressgw userprovided

Description

Userprovided Secret

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
tlsrctSecretName	Name of Tlsrct secret in Vault				
	Examples:	OrderedDict()		No	string
	- tlsrct				
tlskeySecretName	Name of tlskey secret in Vault				
	Examples:	OrderedDict()		No	string
	- tlskey				
cacertSecretName	Name of cacert secret in Vault				
	Examples:	OrderedDict()		No	string
	- cacert				

global azureEntra

Description

Authenticate to Kibana using Azure login

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Set this to true to authenticate to Kibana using Azure login	false		No	boolean
keycloakip	Configure fed-aad_keycloak loadbalancer IP			No	string

global ingressNetworkPolicy

Description

network policies configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabled network policy	true		No	boolean
ingressTrafficNamespaces	Namespaces which are required to be allowed for ingress traffic			No	array

global logging

Description

PaaS logging association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable logging association				
	Examples:	false		No	boolean
	- false				
	- true				
fluentd	Fluentd-Configurations			No	object
elastic	Elasticsearch association			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
enableAddlTargets	Enable/disable additional destinations	false		No	boolean
addlTargets	Additional logging output destination configuration			No	array
alerts	Alerts configuration			No	object

global logging fluentd

Description

Fluentd-Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	Fluentd-Buffer Configurations			No	object

global logging fluentd buffer

Description

Fluentd-Buffer Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Total buffer size. Maximum amount of buffer space each fluentd thread would use to keep logs. After this space is exhausted, fluentd would start deleting oldest logs to make room for new logs.	32m		No	string
retryWait	Interval(seconds) at which the buffer flush is retried in case of failure.	10s		No	string
maxRetries	Max number of retries to flush a buffer chunk. After this is exhausted, fluentd would delete the chunk.	1		No	integer

global logging elastic

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ip	Elasticsearch IP address				
	Examples:			No	string
	- 10.15.16.64				
Port	Elasticsearch port	9200		No	integer

global logging addlTargets

Description

Additional logging output destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			No	object

global logging addlTargets forward

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
host	Hostname or IP Address of the forward server for sending logs to additional targets in parallel with elastic			No	string
port	Port of the forward server	24224		No	integer

global logging alerts

Description

Alerts configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable event alerts				
enabled	Examples: - true	false		No	boolean
	Elasticsearch IP address or host				
host	Examples: - 10.15.10.161			No	string
port	Elasticsearch port	3030		No	integer
realert	Re-alert Info			No	object
	Alert receivers.				
receivers	Examples: - [OrderedDict({'slack': OrderedDict({'webhookurl': ''})}), OrderedDict({'post': OrderedDict({'http_post_url': ''})})]			No	array

global logging alerts realert

Description

Re-alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Interval in minutes to re-send an alert				
minutes	Examples: - 2	1		No	integer

global logging alerts receivers

Description

Alert receivers.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	The first anyOf schema.				
0	Examples: - OrderedDict({'slack': OrderedDict({'webhookurl': ''})})			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
1	The second anyOf schema.				
	Examples:			No	object
	- OrderedDict({'post': OrderedDict({'http_post_url': ''})})				
2	The third anyOf schema				
	Examples:			No	object
	- OrderedDict({'email': OrderedDict({'to_address': '', 'smtp_host': '', 'smtp_port': '', 'smtp_ssl': False, 'from_addr': ''})})				

global logging alerts receivers 0

Description

The first anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
slack	Slack receiver details.				
	Examples:			No	object
	- OrderedDict({'webhookurl': ''})				

global logging alerts receivers 0 slack

Description

Slack receiver details.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
webhookurl	The webhook URL that includes your auth data and the ID of the channel (room) you want to post to.				
	Examples:			No	string
	-				

global logging alerts receivers 1

Description

The second anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
post	HTTP post alert receiver details.				
	Examples:			No	object
	- OrderedDict({'http_post_url': ''})				

global logging alerts receivers 1 post

Description

HTTP post alert receiver details.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
	URL for HTTP post.				
http_post_url	Examples: -			No	string

global logging alerts receivers 2

Description

The third anyOf schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Mail alert receiver Info.				
email	Examples: - OrderedDict({'to_address': '', 'smtp_host': '', 'smtp_port': '', 'smtp_ssl': False, 'from_addr': ''})			No	object

global logging alerts receivers 2 email

Description

Mail alert receiver Info.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	An address or list of addresses to sent the alert to.				
to_address	Examples: - user1@example.com	user1@example.com		No	string
	SMTP host details.				
smtp_host	Examples: - 1.1.1.1	1.1.1.1		No	string
	SMTP port info				
smtp_port	Examples: - 25	25		No	string
	Enable/disable SSL to SMTP server.				
smtp_ssl	Examples: - false	false		No	boolean
	This sets the from header in the email. By default, the from address is ElastAlert@ and the domain will be set by the smtp server				
from_addr	Examples: - user2@example.com	user2@example.com		No	string

global grafana

Description

PaaS Grafana association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association	true		No	boolean
	Examples:				
	- true				
url	Exposed grafana URL			No	string
	Examples:				
	- http: //1.1.1.1:3000				
prometheusinfo	Prometheus server association			No	object

[global grafana](#) prometheusinfo

Description

Prometheus server association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
url	Prometheus server URL	http: //prometheus.fed-prometheus:9090		No	string
	Examples:				
	- http: //prometheus.fed-prometheus:9090				

[global monitoring](#)

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association			No	object

[global monitoring](#) prometheus

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable prometheus monitoring	true		No	boolean

[global registry](#)

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

[global registry](#) docker

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string

global envVars

Description

Environment variables

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Federation type				
fedType	Examples: - paas	paas		No	string
	Federation unique name				
fedUniqueName	Examples: - kibana-default	kibana-default		No	string

global mesh

Description

Istio mesh configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio configuration			No	object

global mesh istio

Description

Istio configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Istio ingress gateway IP				
ingressGwIP	Examples: -			No	string
	Istio ingress gateway FQDN				
ingressGwFQDN	Examples: - kibana.com	kibana.com		No	string
	Istio ingress gateway service port				
ingressGwPort	Examples: - 5601	5601		No	integer
ingressGwTLS	Istio ingress gateway TLS			No	object
	Istio ingress gateway service loadbalancer sharing key.				
loadBalancerSharingKey	Examples: - paas	paas		No	string
serviceAnnotations	Service Annotations			No	object

global mesh istio ingressGwTLS

Description

Istio ingress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio ingress gateway TLS	false		No	boolean
	Examples:				
	- true				
mode	Istio ingress gateway TLS mode.	SIMPLE		No	string
	Examples:				
	- SIMPLE				
certManager	An explanation about the purpose of this instance.			No	object
userProvided	An explanation about the purpose of this instance.			No	object
userProvidedVault	An explanation about the purpose of this instance.			No	object

global mesh istio ingressGwTLS certManager

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	An explanation about the purpose of this instance.	false		No	boolean
	Examples:				
	- true				
certDuration	An explanation about the purpose of this instance.	10h		No	string
	Examples:				
	- 10h				
renewBefore	An explanation about the purpose of this instance.	1h		No	string
	Examples:				
	- 1h				
organization	An explanation about the purpose of this instance.	affirmednetworks		No	string
	Examples:				
	- affirmednetworks				
issuerName	An explanation about the purpose of this instance.	affirmed-clusterissuer		No	string
	Examples:				
	- affirmed-clusterissuer				
issuerType	issuerType			No	string
	Examples:				
	- vault				

Parameter	Description	Default	Value/Range	Mandatory	Type
pkiAlgorithm	Algorithm for PKI certs -RSA or ECDSA	RSA		No	string
	Examples:				
	- RSA				
	- ECDSA				
pkiKeySize	PKI Key size for certs, if Alogirthm is RSA, valid inputs are 2048,4096,8192. If Alogrithm is ECDSA, valid input is 256	4096		No	string
	Examples:				
	- 256				
	- 2048				
	- 4096				
	- 8192				

global mesh istio ingressGwTLS userProvided

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	An explanation about the purpose of this instance.	false		No	boolean
	Examples:				
	- false				
cacert	An explanation about the purpose of this instance.			No	string
	Examples:				
	- Copy and Paste End User generated Certificate				
tlscrt	An explanation about the purpose of this instance.			No	string
	Examples:				
	- Copy and Paste End User generated Certificate				
tlskey	An explanation about the purpose of this instance.			No	string
	Examples:				
	- Copy and Paste End User generated Certificate				

global mesh istio ingressGwTLS userProvidedVault

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	An explanation about the purpose of this instance.	false		No	boolean
	Examples:				
	- false				

global mesh istio serviceAnnotations

Description

Service Annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	Azure Load-Balancer Internal	false		No	string
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Azure Load-Balancer Internal subnet	none		No	string

global overrides

Description

overrides

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	preDeleteEnabled				
	Examples:				
preDeleteEnabled	- false	true		No	boolean
	- true				
	postInstalEnabled				
	Examples:				
postInstallEnabled	- false	false		No	boolean
	- true				
preUpgradeEnabled	preUpgradeEnabled	true		No	boolean
preRollbackEnabled	preRollbackEnabled	true		No	boolean

pod-istio_gw

Description

Pod istio gateway , configuration for ingress and egress gateways

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
egressGateway	Istio egress gateway			No	object

pod-istio_gw egressGateway

Description

Istio egress gateway

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Istio egress gateway flag				
	Examples:				
enabled	- true	false		No	boolean
	- false				

pod-kibana

Description

Pod-kibana parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
kibanaPort	Kibana Port	5601		No	integer
resources	resource requirements for pod			No	object
readinessProbe	Readiness probe ensures that traffic is only routed when the pods are ready			No	object
livenessProbe	Liveliness probe to detect and redeem broken state of the pod by restarting them			No	object
upgrade	Kibana-Upgrade configuration			No	object
deployment	Kibana deployment specifications			No	object
rbacEnabled	rbac Enabled Flag. Configuring rbacEnabled to true will create clusterrole, clusterrolebinding. Configuring rbacEnabled to false, clusterrole, clusterrolebinding will not be created.	true		No	boolean
serviceAccountName	serviceAccountName configuration is used to create serviceaccount per pod	kibana-serviceaccount		No	string

pod-kibana pod-kibana resources

Description

resource requirements for pod

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
request	Request resource			No	object
limit	Resource limit			No	object

pod-kibana pod-kibana resources request

Description

Request resource

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
memory	Request memory				
	Examples:	100Mi		No	string
	- 1Gi				
cpu	Request cpu				
	Examples:	100m		No	string
	- 450m				

pod-kibana resources limit

Description

Resource limit

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
memory	Resource memory limit				
	Examples:	1Gi		No	string
	- 1Gi				
cpu	Resource cpu limit				
	Examples:	800m		No	string
	- 1100m				

pod-kibana readinessProbe

Description

Readiness probe ensures that traffic is only routed when the pods are ready

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
failureThreshold	When a probe fails, Kubernetes will try failureThreshold times before giving up	10		No	integer
initialDelaySeconds	Number of seconds after the container has started before liveness or readiness probes are initiated. Defaults to 120 seconds	120		No	integer
periodSeconds	How often (in seconds) to perform the probe. Default to 5 seconds. Minimum value is 1	5		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer
timeoutSeconds	Number of seconds after which the probe times out. Defaults to 10 second.	10		No	integer

pod-kibana livenessProbe

Description

Liveliness probe to detect and redeem broken state of the pod by restarting them

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
failureThreshold	When a probe fails, Kubernetes will try failureThreshold times before giving up	10		No	integer
initialDelaySeconds	Number of seconds after the container has started before liveness or readiness probes are initiated. Defaults to 120 seconds	120		No	integer
periodSeconds	How often (in seconds) to perform the probe. Default to 5 seconds. Minimum value is 1.	5		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer
timeoutSeconds	Number of seconds after which the probe times out.	10		No	integer

pod-kibana upgrade

Description

Kibana-Upgrade configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
version	This values must be changed and it must be unique for every for every upgrade	kibana		No	string

pod-kibana deployment

Description

Kibana deployment specifications

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Replicas	1		No	integer
resources	resource requirements for pod			No	object

pod-kibana pod-kibana resources

Description

resource requirements for pod

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
request	Request resource			No	object
limit	Resource limit			No	object

[pod-kibana pod-kibana resources request](#)

Description

Request resource

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Request memory				
memory	Examples: - 1Gi	100Mi		No	string
	Request cpu				
cpu	Examples: - 450m	100m		No	string

[pod-kibana resources limit](#)

Description

Resource limit

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Resource memory limit				
memory	Examples: - 1Gi	1Gi		No	string
	Resource cpu limit				
cpu	Examples: - 1100m	800m		No	string

fed-kube_addons Helm Documentation

fed-kube_addons values

Contents

- [Global Parameters](#)
- [pod-descheduler Configuration](#)
- [pod-conntrack_clean Configuration](#)
- [pod-cert_exporter Configuration](#)

global

Description

Global Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
registry	PaaS container registry associations			No	object
vault	Details for Vault configuration			No	object
grafana	PaaS Grafana association			No	object

[global registry](#)

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker-Registry path			No	object

[global registry docker](#)

Description

Docker-Registry path

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	repoPath	<registry_docker_path>		No	string
imagePullSecrets				No	array

[global registry docker imagePullSecrets](#)

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Image Pull Secets Array			No	object

[global registry docker imagePullSecrets 0](#)

Description

Image Pull Secets Array

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	AS number to use for the local end of the session			No	string

[global vault](#)

Description

Details for Vault configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	To enable or disable Vault	false		No	boolean
hashicorpVault	Hashicorp Vault configuration			No	object

[global vault hashicorpVault](#)

Description

Hashicorp Vault configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	To enable or disable hashicorpVault	true		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
serverUrl	Address of Vault Server				
	Examples:	http: //fed-hc-vault-test-svc-internal.fed-hc-vault-		No	string
	- http: //fed-hc-vault-test-svc-internal.fed-hc-vault-test:8200	test:8200			

global grafana

Description

PaaS Grafana association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association	true		No	boolean
url	Exposed grafana URL				
	Examples:			No	string
	- https: //1.1.1.1:3000				
prometheusinfo	Prometheus server association			No	object

global grafana prometheusinfo

Description

Prometheus server association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
url	Prometheus server URL				
	Examples:	https: //prometheus.fed-prometheus:9090		No	string
	- https: //prometheus.fed-prometheus:9090				

pod-descheduler

Description

pod-descheduler Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type	
enabled	Use this flag to enable or disable descheduler feature	true		No	boolean	
logVerbosity	Use this variable to change the verbosity of logs of descheduler pod. The range of this variable is between [0,9], where 0 means very less or no verbosity of logs and 9 means trace level verbosity of pod logs which displays HTTP request contents without truncation of contents	3	Enumerations:			
			- 0			
			- 1			
			- 2			
			- 3			
			- 4		No	
			- 5			
			- 6			
			- 7			
			- 8			
			- 9			
					string	

Parameter	Description	Default	Value/Range	Mandatory	Type
nodeSelector	List of all the nodes which are to be processed for descheduler. If kept empty, then all the nodes on cluster will be considered for descheduler processing.			No	array
evictFailedBarePods	If set to true, allow eviction of pods without owner references and in failed phase	true		No	boolean
evictLocalStoragePods	If set to true then it allow eviction of pods with local storage	false		No	boolean
evictSystemCriticalPods	If set to true, allows eviction of system critical pods	false		No	boolean
maxNoOfPodsToEvictPerNode	Maximum number of pod evitions allowed by descheduler for each node	100		No	integer
policy	Policy configuration for descheduler			No	object

pod-descheduler policy

Description

Policy configuration for descheduler

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
removeDuplicates	RemoveDuplicates Strategy's configuration			No	object
removePodsViolatingInterPodAntiAffinity	RemovePodsViolatingInterPodAntiAffinity Strategy's configuration			No	object
removePodsViolatingNodeAffinity	RemovePodsViolatingNodeAffinity Strategy's configuration			No	object
removePodsViolatingTopologySpreadConstraint	RemovePodsViolatingTopologySpreadConstraint Strategy's configuration			No	object
removePodsViolatingTopologySpreadConstraintSmf	removePodsViolatingTopologySpreadConstraintSmf Strategy's configuration			No	object
removePodsHavingTooManyRestarts	RemovePodsHavingTooManyRestarts Strategy's configuration			No	object

pod-descheduler policy removeDuplicates

Description

RemoveDuplicates Strategy's configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	enabled	true		No	boolean
namespacesIncluded	Namespaces which are required to be allowed for removeDuplicates strategy			No	array
nodefit	Nodefit	true		No	boolean
thresholdPriorityClassName	Classname of threshold priority. If left empty then by default it will be set to system-cluster-critical			No	string

pod-descheduler policy removePodsViolatingInterPodAntiAffinity

Description

RemovePodsViolatingInterPodAntiAffinity Strategy's configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	enabled	true		No	boolean
namespacesIncluded	Namespaces which are required to be allowed for removePodsViolatingInterPodAntiAffinity strategy			No	array
nodefit	Nodefit	true		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
thresholdPriorityClassName	Classname of threshold priority. If left empty then by default it will be set to system-cluster-critical			No	string

pod-descheduler policy removePodsViolatingNodeAffinity

Description

RemovePodsViolatingNodeAffinity Strategy's configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	enabled	true		No	boolean
nodeAffinityType	Node affinity type			No	array
namespacesIncluded	Namespaces which are required to be allowed for removePodsViolatingNodeAffinity strategy			No	array
nodefit	Nodefit	true		No	boolean
thresholdPriorityClassName	Classname of threshold priority. If left empty then by default it will be set to system-cluster-critical			No	string

pod-descheduler policy removePodsViolatingTopologySpreadConstraint

Description

RemovePodsViolatingTopologySpreadConstraint Strategy's configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	enabled	true		No	boolean
includeSoftConstraints	Set to true if SoftConstraints are to required for eviction criteria	true		No	boolean
namespacesIncluded	Namespaces which are required to be allowed for removePodsViolatingTopologySpreadConstraint strategy			No	array
nodefit	Nodefit	true		No	boolean
topologyBalanceNodeFit	topologyBalanceNodeFit	true		No	boolean
thresholdPriorityClassName	Classname of threshold priority. If left empty then by default it will be set to system-cluster-critical			No	string

pod-descheduler policy removePodsViolatingTopologySpreadConstraintSmf

Description

removePodsViolatingTopologySpreadConstraintSmf Strategy's configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	enabled	true		No	boolean
includeSoftConstraints	Set to true if SoftConstraints are to required for eviction criteria	true		No	boolean
namespacesIncluded	Namespaces which are required to be allowed for removePodsViolatingTopologySpreadConstraintSmf strategy			No	array
nodefit	Nodefit	true		No	boolean
topologyBalanceNodeFit	topologyBalanceNodeFit	true		No	boolean
thresholdPriorityClassName	Classname of threshold priority. If left empty then by default it will be set to system-cluster-critical			No	string

pod-descheduler policy removePodsHavingTooManyRestarts

Description

RemovePodsHavingTooManyRestarts Strategy's configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	enabled	true		No	boolean
includingInitContainers	If set to true, then restart count of init containers will also be consider for eviction criteria	false		No	boolean
podRestartThreshold	Threshold count for pod restarts upto which the pod won't be considered for eviction by descheduler	20		No	integer
namespacesIncluded	Namespaces which are required to be allowed for removePodsHavingTooManyRestarts strategy			No	array
nodefit	Nodefit	true		No	boolean
thresholdPriorityClassName	Classname of threshold priority. If left empty then by default it will be set to system-cluster-critical			No	string

pod-conntrack_clean

Description

pod-conntrack_clean Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Use this flag to enable or disable conntrack-cleaner feature	true		No	boolean
udpCleaningEnabled	Enable cleanup of UDP conntrack entries	true		No	boolean
tcpCleaningEnabled	Enable cleanup of TCP conntrack entries	false		No	boolean

pod-cert_exporter

Description

pod-cert_exporter Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Use this flag to enable or disable cert_exporter feature	true		No	boolean
prometheusRules	PrometheusRules configuration for cert_exporter			No	object

[pod-cert_exporter](#) prometheusRules

Description

PrometheusRules configuration for cert_exporter

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
create	Use this flag to control deployment of prometheusRules	true		No	boolean
warningDaysLeft	Configure the number of days before certificate expiry date when a warning alert would be raised	28		No	integer
criticalDaysLeft	Configure the number of days before certificate expiry date when a critical alert would be raised	14		No	integer

kube-prom Helm Documentation

fed-kube-prom values

Contents

- [Global Parameters](#)
- [pod-kube_prom parameters](#)
- [The pod-istio_gw schema](#)

Description

Global Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
registry	PaaS container registry associations			No	object
envVars	Environment variables			No	object
authType	Authentication type for PaaS components, allowed values are local and haloe	haloe		No	string
adminPassword	Generic password for all PaaS components			No	string
metricsScrapeInterval	Prometheus metrics scrape interval. Default value set to 30 seconds.So, prometheus will scrape the metrics for every 30 seconds.	30s		No	string
kargoProfileTag	This enables creation of specific kargo-default-profile for fed-kube-prom			No	string
logging	PaaS logging association			No	object
grafanaDatasource	PaaS Grafana Datasource association			No	object
vault	vault			No	object
secretNames	PaaS Vault Secret Names			No	object
monitoring	PaaS Monitoring associations			No	object
istio	Istio related configurations			No	object
mesh	Istio mesh configuration			No	object

[global registry](#)

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

[global registry docker](#)

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string
imagePullSecret	Pull an image from a private registry			No	string
username	Username for private docker registry			No	string
password	Password for private docker registry			No	string

[global envVars](#)

Description

Environment variables

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Federation type				
fedType	Examples: - kube-prom	kube-prom		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
	Federation unique name				
fedUniqueName	Examples: - default	default		No	string

global logging

Description

PaaS logging association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable logging association				
enabled	Examples: - false - true	false		No	boolean
fluentd	Fluentd-Configurations			No	object
elastic	Elasticsearch association			No	object
enableAddlTargets	Enable/disable additional destinations	false		No	boolean
addlTargets	Additional logging output destination configuration			No	array

global logging fluentd

Description

Fluentd-Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	Fluentd-Buffer Configurations			No	object

global logging fluentd buffer

Description

Fluentd-Buffer Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Total buffer size. Maximum amount of buffer space each fluentd thread would use to keep logs. After this space is exhausted, fluentd would start deleting oldest logs to make room for new logs.	32m		No	string
retryWait	Interval(seconds) at which the buffer flush is retried in case of failure.	10s		No	string
maxRetries	Max number of retries to flush a buffer chunk. After this is exhausted, fluentd would delete the chunk.	1		No	integer

global logging elastic

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
IP	Elasticsearch IP address				
	Examples:			No	string
	- 10.15.10.161				
Port	Elasticsearch port	9200		No	integer

[global logging addITargets](#)

Description

Additional logging output destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			No	object

[global logging addITargets forward](#)

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
host	Hostname or IP Address of the forward server for sending logs to additional targets in parallel with elastic			No	string
port	Port of the forward server	24224		No	integer

[global grafanaDatasource](#)

Description

PaaS Grafana Datasource association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association	true		No	boolean
url	Exposed grafana URL				
	Examples:			No	string
	- http: //1.1.1.1:3000				
prometheusinfo	Prometheus server association			No	object

[global grafanaDatasource prometheusinfo](#)

Description

Prometheus server association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
url	Prometheus server URL	http: //prometheus-k8s.fed-kube-prom:9099		No	string

[global vault](#)

Description

vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	vault Enabled				
	Examples:				
	- false	false		No	boolean
	- true				
hashicorpVault	hashicorpVault			No	object
azureKeyVault	azureKeyVault			No	object

global vault hashicorpVault

Description

hashicorpVault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	hashicorpVault Enabled				
	Examples:				
	- false	false		No	boolean
	- true				

global azure azureKeyVault enabled

Description

azureKeyVault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	azureKeyVault Enabled				
	Examples:				
	- false	false		No	boolean
	- true				
aksCluster	Is it AKS cluster				
	Examples:				
	- false	false		No	boolean
	- true				
keyVaultName	key vault name			No	string
tenantID	tenant id where akv created			No	string
userManagerId	User manager ID			No	string
workloadIdentity	is it Workloadidentity				
	Examples:				
	- false	true		No	boolean
	- true				

global secretNames

Description

PaaS Vault Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
grafana	grafana Secret Names			No	object
ingressgw	ingressgw Secret Names			No	object

global secretNames grafana

Description

grafana Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Name of User key in Vault				
username	Examples: - username	OrderedDict()		No	string
	Name of password key in Vault				
password	Examples: - password	OrderedDict()		No	string

global secretNames ingressgw

Description

ingressgw Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
userprovided	Userprovided Secret			No	object

global secretNames ingressgw userprovided

Description

Userprovided Secret

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Name of Tlsrct secret in Vault				
tlsrctSecretName	Examples: - tlsrct	OrderedDict()		No	string
	Name of tlskey secret in Vault				
tlskeySecretName	Examples: - tlskey	OrderedDict()		No	string
	Name of cacert secret in Vault				
cacertSecretName	Examples: - cacert	OrderedDict()		No	string

global monitoring

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association			No	object

[global monitoring](#) prometheus

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable prometheus monitoring	true		No	boolean

[global](#) istio

Description

Istio related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtls	Istio mutual TLS related configuration			No	object

[global istio](#) mtls

Description

Istio mutual TLS related configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable istio mutual TLS	false		No	boolean

[global](#) mesh

Description

Istio mesh configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio configuration			No	object

[global mesh](#) istio

Description

Istio configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtlsEnabled	Enable/disable istio mutual TLS	false		No	boolean
ingressGwIP	Istio ingress gateway IP			No	string
	Examples: -				
ingressGwFQDN	Istio ingress gateway FQDN			No	string
	Examples: - kubepromgrafana.com	kubepromgrafana.com			
ingressGwPort	Istio ingress gateway service port	3000		No	integer

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGwTLS	Istio ingress gateway TLS			No	object
ingressGwAdditionalServices	Ingress Gw Additional Services				
	Examples: - [OrderedDict({'ingressGwIP': '', 'ingressGwFQDN': 'kubepromalertmanager.com', 'ingressGw': 'kubepromalertmanager-ingress', 'ingressGwPort': 9093, 'mtlsEnabled': False, 'ingressGwTLS': OrderedDict({'enabled': True, 'mode': 'SIMPLE'}), 'serviceAnnotations': OrderedDict({'service.beta.kubernetes.io/azure-load-balancer-internal': 'true', 'service.beta.kubernetes.io/azure-load-balancer-internal-subnet': 'none'})}), OrderedDict({'ingressGwIP': '', 'ingressGwFQDN': 'kubeprom.com', 'ingressGw': 'kubeprom-ingress', 'ingressGwPort': 9099, 'mtlsEnabled': False, 'ingressGwTLS': OrderedDict({'enabled': True, 'mode': 'SIMPLE'}), 'serviceAnnotations': OrderedDict({'service.beta.kubernetes.io/azure-load-balancer-internal': 'true', 'service.beta.kubernetes.io/azure-load-balancer-internal-subnet': 'none'})})]			No	array
loadBalancerSharingKey	Istio ingress gateway service loadbalancer sharing key.				
	Examples: - kube_prom	kube_prom		No	string
serviceAnnotations	Service Annotations			No	object

global mesh istio ingressGwTLS

Description

Istio ingress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio ingress gateway TLS				
	Examples: - true - false	true		No	boolean
mode	Istio ingress gateway TLS mode.				
	Examples: - SIMPLE	SIMPLE		No	string
certManager	certManager Configuration			No	object
userProvided	userProvided CERTIFICATES			No	object
userProvidedVault	An explanation about the purpose of this instance.			No	object

global mesh istio ingressGwTLS certManager

Description

certManager Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for certManager configuration	true		No	boolean
	Examples:				
	- true				
certDuration	- false				
certDuration	certDuration Configuration	10h		No	string
renewBefore	renewBefore Configuration	1h		No	string
organization	organization Configuration	affirmednetworks		No	string
	Examples:				
	- affirmednetworks				
issuerName	issuerName	affirmed-clusterissuer		No	string
	Examples:				
	- affirmed-clusterissuer				
issuerType	issuerType			No	string
	Examples:				
	- vault				
pkiAlgorithm	Algorithm for PKI certs -RSA or ECDSA	RSA		No	string
	Examples:				
	- RSA				
pkiKeySize	- ECDSA	4096		No	string
	PKI Key size for certs, if Alogirthm is RSA, valid inputs are 2048,4096,8192. If Alogrithm is ECDSA, valid input is 256				
	Examples:				
	- 256				
pkiKeySize	- 2048				
	- 4096				
	- 8192				

global mesh istio ingressGwTLS userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvided Certificates	false		No	boolean
	Examples:				
	- false				
cacert	- true				
	cacert Configuration				
cacert	Examples:			No	string
	- Copy and Paste End User generated Certificate				

Parameter	Description	Default	Value/Range	Mandatory	Type
tls crt	tls crt configuration				
	Examples:			No	string
	- Copy and Paste End User generated Certificate				
tls key	tls key configuration				
	Examples:			No	string
	- Copy and Paste End User generated Certificate				

global mesh istio ingressGwTLS userProvidedVault

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	An explanation about the purpose of this instance.				
	Examples:	false		No	boolean
	- false				

global mesh istio ingressGwAdditionalServices

Description

Ingress Gw Additional Services

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Array element				
	Examples:				
	- OrderedDict({'ingressGwIP': '', 'ingressGwFQDN': 'kubepromalertmanager.com', 'ingressGw': 'kubepromalertmanager-ingress', 'ingressGwPort': 9093, 'mtlsEnabled': False, 'ingressGwTLS': OrderedDict({'enabled': True, 'mode': 'SIMPLE'}), 'serviceAnnotations': OrderedDict({'service.beta.kubernetes.io/azure-load-balancer-internal': True, 'service.beta.kubernetes.io/azure-load-balancer-internal-subnet': 'none'})})			No	object
1	Array element				
	Examples:				
	- OrderedDict({'ingressGwIP': '', 'ingressGwFQDN': 'kubeprom.com', 'ingressGw': 'kubeprom-ingress', 'ingressGwPort': 9099, 'mtlsEnabled': False, 'ingressGwTLS': OrderedDict({'enabled': True, 'mode': 'SIMPLE'}), 'serviceAnnotations': OrderedDict({'service.beta.kubernetes.io/azure-load-balancer-internal': 'true', 'service.beta.kubernetes.io/azure-load-balancer-internal-subnet': 'none'})})			No	object

global mesh istio ingressGwAdditionalServices 0

Description

Array element

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGwIP	Ingress Gw IP				
	Examples:			No	string
	-				

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGwFQDN	The ingress Gw FQDN	kubepromalertmanager.com		No	string
	Examples: - kubepromalertmanager.com				
ingressGw	Ingress gateway name	kubepromalertmanager-ingress		No	string
	Examples: - kubepromalertmanager-ingress				
ingressGwPort	The ingress Gw Port.	9093		No	integer
	Examples: - 9093				
mtlsEnabled	MTLS flag.	false		No	boolean
	Examples: - false				
ingressGwTLS	Ingress gateway TLS.			No	object
	Examples: - OrderedDict({'enabled': True, 'mode': 'SIMPLE'})				
serviceAnnotations	Service Annotations			No	object
	Examples: - OrderedDict({'service.beta.kubernetes.io/azure-load-balancer-internal': 'true', 'service.beta.kubernetes.io/azure-load-balancer-internal-subnet': 'none'})				

global mesh istio ingressGwAdditionalServices 0 ingressGwTLS

Description

Ingress gateway TLS.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Ingress Gateway TLS flag.	false		No	boolean
	Examples: - true				
mode	Ingress Gw TLS mode.			No	string
	Examples: - SIMPLE				

global mesh istio ingressGwAdditionalServices 0 serviceAnnotations

Description

Service Annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	Azure Loadbalancer Internal	true		No	string
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Azure Loadbalancer Internal subnet	none		No	string

global mesh istio ingressGwAdditionalServices 0

Description

Array element

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGwIP	Ingress Gw IP				
	Examples:			No	string
	-				
ingressGwFQDN	The ingress Gw FQDN				
	Examples:	kubeprom.com		No	string
	- kubeprom.com				
ingressGw	Ingress gateway name				
	Examples:	kubeprom-ingress		No	string
	- kubeprom-ingress				
ingressGwPort	The ingress Gw Port.				
	Examples:	9099		No	integer
	- 9099				
mtlsEnabled	MTLS flag.				
	Examples:	false		No	boolean
	- false				
ingressGwTLS	Ingress gateway TLS.				
	Examples:			No	object
	- OrderedDict({'enabled': True, 'mode': 'SIMPLE'})				
serviceAnnotations	Service Annotations				
	Examples:			No	object
	- OrderedDict({'service.beta.kubernetes.io/azure-load-balancer-internal': True, 'service.beta.kubernetes.io/azure-load-balancer-internal-subnet': 'none'})				

global mesh istio ingressGwAdditionalServices 0 ingressGwTLS

Description

Ingress gateway TLS.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Ingress Gateway TLS flag.				
	Examples:	false		No	boolean
	- true				
mode	Ingress Gw TLS mode.				
	Examples:			No	string
	- SIMPLE				

global mesh istio ingressGwAdditionalServices 0 serviceAnnotations

Description

Service Annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	Azure loadbalancer Internal	true		No	string
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Azure Loadbalancer Internal subnet	none		No	string

[global mesh istio](#) serviceAnnotations

Description

Service Annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	Azure Load-Balancer Internal	true		No	string
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Azure Load-Balancer Internal subnet	none		No	string

pod-kube_prom

Description

pod-kube_prom parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus Configuration			No	object
probesCheck	Liveliness and Readiness Probe Checks for Prometheus, Alertmanager and Thanos			No	object
alertmanager	Alert-Manager Configuration			No	object

[pod-kube_prom](#) prometheus

Description

Prometheus Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Replicas configuration	2		No	integer
storage	Storage			No	object

[pod-kube_prom](#) prometheus storage

Description

Storage

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Three storage type can be configured. Those are local, remote or rook. Examples:				
type	- local - remote - rook			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
storageClassName	currently supported external storages are cinder, AzureDisk and rook-ceph.				
	Examples:				
	- cinder-class	cinder-class		No	string
	- azure-disk				
provisioner	- rook-cephbp				
	External storage provisioner. See example for available storage provisioners. If any other storage provisioner is set other than cinder and azure-disk. Then set that provisioner's parameters under customParameters.				
	Examples:	kubernetes.io/cinder		No	string
	- kubernetes.io/cinder				
parameters	- kubernetes.io/azure-disk				
	External storage specific parameters. To deploy federation with external storage other than cinder, provide configuration in values.yaml and deploy it.			No	object
	PersistentVolumes that are dynamically created by a StorageClass will have the reclaim policy specified in the reclaimPolicy field				
	Examples:				
reclaimPolicy	- Delete	Delete		No	string
	- Retain				
	Allow volume expansion				
	Examples:				
allowVolumeExpansion	- true	true		No	boolean
	- false				
	PersistentVolumes that are dynamically created by a StorageClass will have the volumeBindingMode specified in the volumeBindingMode field				
	Examples:				
volumeBindingMode	- WaitForFirstConsumer	WaitForFirstConsumer		No	string
	- Immediate				
	Resource Requirements			No	object

pod-kube_prom prometheus storage parameters

Description

External storage specific parameters. To deploy federation with external storage other than cinder, provide configuration in values.yaml and deploy it.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cinder	Parameters for cinder external storage			No	object
azureDisk	Parameters to configure Azure disk storage. To add any other parameter related to Azure disk, edit values.yaml during deployment			No	object

pod-kube_prom prometheus storage parameters cinder

Description

Parameters for cinder external storage

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
type	VM disk type	ceph		No	string
availability	Availability Zone	nova		No	string
fsType	fsType	ext4		No	string

pod-kube_prom prometheus storage parameters azureDisk

Description

Parameters to configure Azure disk storage. To add any other parameter related to Azure disk, edit values.yaml during deployment

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
storageaccounttype	Azure storage account name. If a storage account is provided, it must reside in the same resource group as the cluster			No	string
kind	Possible values are shared (default), dedicated, and managed	shared		No	string

pod-kube_prom prometheus storage resource

Description

Resource Requirements

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Request Resource				
request	Examples: - 100Gi	100Gi		No	string

pod-kube_prom probesCheck

Description

Liveliness and Readiness Probe Checks for Prometheus, Alertmanager and Thanos

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
liveliness	Liveliness probe to detect and redeem broken state of the pod by restarting them			No	object
readiness	Readiness probe ensures that traffic is only routed when the pods are ready			No	object

pod-kube_prom probesCheck liveliness

Description

Liveliness probe to detect and redeem broken state of the pod by restarting them

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
failureThreshold	When a probe fails, Kubernetes will try failureThreshold times before giving up	120		No	integer
initialDelaySeconds	Number of seconds after the container has started before liveness or readiness probes are initiated. Defaults to 0 seconds	30		No	integer
periodSeconds	How often (in seconds) to perform the probe. Default to 10 seconds. Minimum value is 1.	60		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer
timeoutSeconds	Number of seconds after which the probe times out. Defaults to 1 second.	5		No	integer

pod-kube_prom probesCheck readiness

Description

Readiness probe ensures that traffic is only routed when the pods are ready

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
failureThreshold	When a probe fails, Kubernetes will try failureThreshold times before giving up	120		No	integer
initialDelaySeconds	Number of seconds after the container has started before liveness or readiness probes are initiated. Defaults to 0 seconds	30		No	integer
periodSeconds	How often (in seconds) to perform the probe. Default to 10 seconds. Minimum value is 1.	60		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer
timeoutSeconds	Number of seconds after which the probe times out. Defaults to 1 second.	5		No	integer

pod-kube_prom alertmanager

Description

Alert-Manager Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Replicas Configuration	3		No	integer
config	Alertmanager Configuration parameters			No	object

podkube_prom alertmanager config

Description

Alertmanager Configuration parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
global	global scoped configurations			No	object
route	A route block defines a node in a routing tree and its children. Its optional configuration parameters are inherited from its parent node if not set.			No	object
receivers	Alert Receiver Configuration			No	array

pod-kube_prom alertmanager config global

Description

global scoped configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	resolve_timeout				
resolve_timeout	Examples: - 5m	5m		No	string

pod-kube_prom alertmanager config route

Description

A route block defines a node in a routing tree and its children. Its optional configuration parameters are inherited from its parent node if not set.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
group_wait	How long to initially wait to send a notification for a group of alerts	30s		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
group_interval	Duration of time to wait to send notification for the alerts that are already added	2m		No	string
repeat_interval	Duration of time to wait, before sending the notification again	2m		No	string
receiver	Provide receiver name to send alerts to, slackreceiver for slack, emailreceiver for email, postreceiver for HTTP POST	null		No	string

pod-kube_prom alertmanager config receivers

Description

Alert Receiver Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Default Null receiver			No	object
1	HTTP POST receiver			No	object
2	Add Email receiver			No	object
3	Add slack receiver			No	object

pod-kube_prom alertmanager config receivers 0

Description

Default Null receiver

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Default Null receiver	null		No	string

pod-kube_prom alertmanager config receivers 1

Description

HTTP POST receiver

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Add a name to the HTTP POST webhook receiver				
name	Examples: - postreceiver	postreceiver		No	string
webhook_configs	Configure Webhook			No	array

pod-kube_prom alertmanager config receivers 1 webhook_configs

Description

Configure Webhook

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Configure Webhook			No	object

pod-kube_prom alertmanager config receivers 1 webhook_configs 0

Description

Configure Webhook

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
	Reciever webhook				
url	Examples: - http: //XXXX	http: //XXXX		No	string
http_config	HTTP Configuration			No	object

[pod-kube_prom alertmanager config receivers 1 webhook_configs 0 http_config](#)

Description

HTTP Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
tls_config	TLS configuration			No	object

[pod-kube_prom alertmanager config receivers 1 webhook_configs 0 http_config](#) [tls_config](#)

Description

TLS configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	skip tls verify flag				
	Examples:				
insecure_skip_verify	- true	true		No	boolean
	- false				

[pod-kube_prom alertmanager config receivers 2](#)

Description

Add Email receiver

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Add a name to the email receiver				
name	Examples: - emailreceiver	emailreceiver		No	string
email_configs	Provide required email details			No	array

[pod-kube_prom alertmanager config receivers 2 email_configs](#)

Description

Provide required email details

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Provide email configurations			No	object

[pod-kube_prom alertmanager config receivers 2 email_configs 0](#)

Description

Provide email configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
to	Email To address				
	Examples:	user1@example.com		No	string
	- user1@example.com				
from	Email From address				
	Examples:	user2@example.com		No	string
	- user2@example.com				
smarthost	Mail server IP along with the port				
	Examples:	XXXX:80		No	string
	- XXXX:80				
auth_username	Mail server authentication Username				
	Examples:	user@example.com		No	string
	- user@example.com				
auth_password	Mail server authentication password				
	Examples:	password		No	string
	- password				
require_tls	enable/disable TLS authentication				
	Examples:	false		No	boolean
	- false				
headers	Email header section			No	object

pod-kube_prom alertmanager config receivers 2 email_configs 0 headers

Description

Email header section

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Subject	Add subject to the mail	Alert from: {{ .CommonLabels.alertname }}		No	string

pod-kube_prom alertmanager config receivers 3

Description

Add slack receiver

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Add a name to the slack receiver				
	Examples:	slackreceiver		No	string
	- slackreceiver				
slack_configs	Slack configurations			No	array

pod-kube_prom alertmanager config receivers 3 slack_configs

Description

Slack configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Add slack configuration			No	object

pod-kube_prom alertmanager config receivers 3 slack_configs 0

Description

Add slack configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
channel	Name of the slack channel				
	Examples:	#channel_name		No	string
	- #channel_name				
api_url	Provide webhook url	http: //XXXX		No	string
text	Add message text.	summary: {{ .CommonAnnotations.summary }}			
description: {{ .CommonAnnotations.description }}		No			string
title	Add title for the slack message	Alert from: {{ .CommonLabels.alertname }}		No	string

pod-istio_gw

Description

Pod istio gateway , configuration for ingress and egress gateways

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
egressGateway	Istio egress gateway				
	Examples:			No	object
	- OrderedDict({'enabled': False})				

pod-istio_gw egressGateway

Description

Istio egress gateway

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Istio egress gateway flag				
	Examples:	false		No	boolean
	- false				

Kubedb_operator Helm Documentation

fed-kubedb_operator values

Contents

- [Global Parameters](#)
- [mesh parameters](#)
- [pod-kubedb_catalog parameters](#)
- [Pod-kubedb_operator parameters](#)
- [Pod-kubedb_autosc parameters](#)
- [Pod-kubedb_enterp parameters](#)

global

Description

Global Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
defaultRbacEnabled	defaultRbacEnabled Flag				
	Examples:				
	- false	false		No	boolean
	- true				
defaultClusterRole	defaultClusterRole configuration is to configure the clusterrole in clusterrolebinding	permissive-network-cr		No	string
defaultServiceAccountName	Default service account for kubedb operator	fed-kubedb-operator-serviceaccount		No	string
enableSCC	If running on OCP cluster, please set enableSCC to true	false		No	boolean
logging	PaaS logging association			No	object
grafana	PaaS Grafana association			No	object
monitoring	PaaS Monitoring associations			No	object
metricsScrapeInterval	Metrics scrape interval in ServiceMonitors. Setting a lower value would result in faster refreshes of metrics at the cost of more overhead for both prometheus and the application.	1m		No	string
registry	PaaS container registry associations			No	object
envVars	Environment variables			No	object
overrides	overrides			No	object

[global logging](#)

Description

PaaS logging association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable logging association				
	Examples:				
	- false	false		No	boolean
	- true				
fluentd	Fluentd-Configurations			No	object
elastic	Elasticsearch association			No	object
enableAddlTargets	Enable/disable additional destinations	false		No	boolean
addlTargets	Additional logging output destination configuration			No	array

[global logging fluentd](#)

Description

Fluentd-Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	Fluentd-Buffer Configurations			No	object

global logging fluentd buffer

Description

Fluentd-Buffer Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Total buffer size. Maximum amount of buffer space each fluentd thread would use to keep logs. After this space is exhausted, fluentd would start deleting oldest logs to make room for new logs.	512m		No	string
retryWait	Interval(seconds) at which the buffer flush is retried in case of failure.	180s		No	string
maxRetries	Max number of retries to flush a buffer chunk. After this is exhausted, fluentd would delete the chunk.	10		No	integer

global logging elastic

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ip	Elasticsearch IP address				
	Examples:			No	string
	- 10.15.10.161				
Port	Elasticsearch port	9200		No	integer

global logging addITargets

Description

Additional logging output destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			No	object

global logging addITargets forward

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
host	Hostname or IP Address of the forward server for sending logs to additional targets in parallel with elastic			No	string
port	Port of the forward server	24224		No	integer

global grafana

Description

PaaS Grafana association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association	true		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
url	Exposed grafana URL				
	Examples:			No	string
	- http: //1.1.1.1:3000				
prometheusinfo	Prometheus server association			No	object

[global grafana](#) prometheusinfo

Description

Prometheus server association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
url	Prometheus server URL				
	Examples:	http: //prometheus.fed-prometheus:9090		No	string
	- http: //prometheus.fed-prometheus:9090				

[global monitoring](#)

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association			No	object

[global monitoring](#) prometheus

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable prometheus monitoring	true		No	boolean

[global registry](#)

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

[global registry](#) docker

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string

[global envVars](#)

Description

Environment variables

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
fedType	Federation type				
	Examples:	paas		No	string
	- paas				
fedUniqueName	Federation unique name				
	Examples:	kubedb-default		No	string
	- kubedb-default				

global overrides

Description

overrides

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
preInstallEnabled	Enabling/Disabling preInstall Helm hook. Currently it is disabled but any pre install script could be executed using this tpl file				
	Examples:	false		No	boolean
	- false				
postInstallEnabled	Enabling/Disabling postInstall Helm hook. Currently it is disabled but any pre install script could be executed using this tpl file				
	Examples:	false		No	boolean
	- false				
preUpgradeEnabled	Enabling/Disabling preUpgrade Helm hook. Currently it is disabled but any pre upgrade script could be executed using this tpl file				
	Examples:	false		No	boolean
	- false				
postUpgradeEnabled	Enabling/Disabling postUpgrade Helm hook. Currently it is disabled but any post upgrade script could be executed using this tpl file				
	Examples:	false		No	boolean
	- false				
fedIstioEnabled	fedIstioEnabled				
	Examples:	false		No	boolean
	- false				
fedIstioEnabled	Examples:				
	- false				
	- true				

global mesh

Description

Istio mesh configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio configuration			No	object

[global mesh](#) istio

Description

Istio configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtlsEnabled	Enable/disable istio mutual TLS	false		No	boolean

pod-kubedb_catalog

Description

Pod-kubedb_catalog parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enabling/Disabling performance related command execution				
	Examples:				
enablePerf	- false	false		No	boolean
	- true				

pod-kubedb_operator

Description

Pod-kubedb_operator parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
operator	operator parameters			No	object
imagePullPolicy	Image pull policy	IfNotPresent		No	string
criticalAddon	Installs KubeDB operator as critical addon. https://kubernetes.io/docs/tasks/administer-cluster/guaranteed-scheduling-critical-addon-pods/	false		No	boolean
logLevel	log-Level	5		No	integer
rbacEnabled	RBAC configurations	true		No	boolean
serviceAccount	Service-Account Configurations			No	object
monitoring	Monitoring Configuration			No	object

[pod-kubedb_operator](#) operator

Description

operator parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
resources	Resources for operator pod			No	object

[pod-kubedb_operator](#) operator resources

Description

Resources for operator pod

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
requests	Resource requests			No	object
limits	Resource limits			No	object

pod-kubedb_operator operator resources requests

Description

Resource requests

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	CPU requests	100m		No	string
memory	Memory requests	100Mi		No	string

pod-kubedb_operator operator resources limits

Description

Resource limits

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	CPU limits	500m		No	string
memory	Memory limits	1Gi		No	string

pod-kubedb_operator serviceAccount

Description

Service-Account Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
create	Specifies whether a ServiceAccount should be created	true		No	boolean
name	The name of the ServiceAccount to use. If not set and create is true, a name is generated using the fullname template	kubedb-operator-sa		No	string

pod-kubedb_operator monitoring

Description

Monitoring Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	specify whether to monitor KubeDB operator	false		No	boolean
agent	specify monitoring agent either prometheus.io/builtin or prometheus.io/coreos-operator	none		No	string
serviceMonitor	service monitor configuration			No	object

pod-kubedb_operator monitoring serviceMonitor

Description

service monitor configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
labels	servce monitor labels			No	object

pod-kubedb_operator monitoring prometheus labels

Description

sercive monitor labels

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-kubedb_autosc

Description

Pod-kubedb_autosc parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
updateInterval	Interval between each autoscaler loop	1m		No	string
storageAutoscaler	Storage Autoscaling configurations			No	object
operator	operator parameters			No	object
imagePullPolicy	Image pull policy	IfNotPresent		No	string
criticalAddon	Installs KubeDB operator as critical addon. https://kubernetes.io/docs/tasks/administer-cluster/guaranteed-scheduling-critical-addon-pods/	false		No	boolean
logLevel	log-Level	5		No	integer
rbacEnabled	RBAC configurations	true		No	boolean
serviceAccount	Service-Account Configurations			No	object
monitoring	Monitoring Configuration			No	object

pod-kubedb_autosc storageAutoscaler

Description

Storage Autoscaling configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Autoscaler Prometheus configuration			No	object

pod-kubedb_autosc storageAutoscaler prometheus

Description

Autoscaler Prometheus configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
address	Interval between each autoscaler loop			No	string
bearerToken	Bearer token for prometheus server			No	string
caCert	CA cert for prometheus server TLS connections			No	string

pod-kubedb_autosc operator

Description

operator parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
resources	Resources for operator pod			No	object

pod-kubedb_autosc operator resources

Description

Resources for operator pod

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
requests	Resource requests			No	object
limits	Resource limits			No	object

pod-kubedb_autosc operator resources requests

Description

Resource requests

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	CPU requests	100m		No	string
memory	Memory requests	100Mi		No	string

pod-kubedb_autosc operator resources limits

Description

Resource limits

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	CPU limits	500m		No	string
memory	Memory limits	1Gi		No	string

pod-kubedb_autosc serviceAccount

Description

Service-Account Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
create	Specifies whether a ServiceAccount should be created	true		No	boolean
name	The name of the ServiceAccount to use. If not set and create is true, a name is generated using the fullname template	kubedb-operator-sa		No	string

pod-kubedb_autosc monitoring

Description

Monitoring Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	specify whether to monitor KubeDB operator	false		No	boolean
agent	specify monitoring agent either prometheus.io/builtin or prometheus.io/coreos-operator	none		No	string
serviceMonitor	service monitor configuration			No	object

pod-kubedb_autosc monitoring serviceMonitor

Description

service monitor configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
labels	sercive monitor labels			No	object

pod-kubedb_autosc monitoring prometheus labels

Description

sercive monitor labels

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-kubedb_enterp

Description

Pod-kubedb_enterp parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
operator	operator parameters			No	object
imagePullPolicy	Image pull policy	IfNotPresent		No	string
criticalAddon	Installs KubeDB operator as critical addon. https://kubernetes.io/docs/tasks/administer-cluster/guaranteed-scheduling-critical-addon-pods/	false		No	boolean
logLevel	log-Level	5		No	integer
rbacEnabled	RBAC configurations	true		No	boolean
serviceAccount	Service-Account Configurations			No	object
monitoring	Monitoring Configuration			No	object

pod-kubedb_enterp operator

Description

operator parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
resources	Resources for operator pod			No	object

pod-kubedb_enterp operator resources

Description

Resources for operator pod

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
requests	Resource requests			No	object
limits	Resource limits			No	object

pod-kubedb_enterp operator resources requests

Description

Resource requests

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	CPU requests	100m		No	string
memory	Memory requests	100Mi		No	string

pod-kubedb_enterp operator resources limits

Description

Resource limits

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	CPU limits	500m		No	string
memory	Memory limits	1Gi		No	string

pod-kubedb_enterp serviceAccount

Description

Service-Account Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
create	Specifies whether a ServiceAccount should be created	true		No	boolean
name	The name of the ServiceAccount to use. If not set and create is true, a name is generated using the fullname template	kubedb-operator-sa		No	string

pod-kubedb_enterp monitoring

Description

Monitoring Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	specify whether to monitor KubeDB operator	false		No	boolean
agent	specify monitoring agent either prometheus.io/builtin or prometheus.io/coreos-operator	none		No	string
serviceMonitor	service monitor configuration			No	object

pod-kubedb_enterp monitoring serviceMonitor

Description

service monitor configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
labels	sercive monitor labels			No	object

pod-kubedb_enterp monitoring prometheus labels

Description

sercive monitor labels

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Metal LB Helm Documentation

fed-metallb values

Contents

- [Global Parameters](#)
- [Pod-metallb Parameters](#)

global

Description

Global Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
registry	PaaS registry associations			No	object
	Create an Openshift SCC resource instead of a K8s PSP.				
enableSCC	Examples: - false	false		No	boolean

[global registry](#)

Description

PaaS registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

[global registry docker](#)

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string
imagePullSecret	Pull an image from a private registry			No	string
username	Username for private docker registry			No	string
password	Password for private docker registry			No	string

pod-metallb

Description

Pod-metallb parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bgp	BGP parameters			No	object
controller	MetalLB controller			No	object
fullNameOverride	Pod-metallb full name override			No	string
ipAddressPools				No	array
layer2	Layer 2 parameters			No	object
loadBalancerClass	Load balancer class			No	string
nameOverride	Name override			No	string
prometheus	Prometheus			No	object
	Create MetalLB RBAC resources				
rbacEnabled	Examples: - true	true		No	boolean
speaker	MetalLB speaker			No	object

[pod-metallb bgp](#)

Description

BGP parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
advertisements				No	array
bfd	BFD parameters			No	object
communities	BGP communities			No	object
peers				No	array

pod-metallb bgp advertisements

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	BGP advertisement			No	object

pod-metallb bgp advertisements 0

Description

BGP advertisement

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
aggregationLength	IPv4 Aggregation length	32		No	integer
aggregationLengthV6	IPv6 Aggregation length	128		No	integer
ipAddressPoolSelectors				No	array
ipAddressPools				No	array
localPref	BGP LOCAL_PREF attribute			No	integer
name	BGP advertisement name	default-bgp-advertisement		No	string
nodeSelectors				No	array
peers				No	array

pod-metallb bgp advertisements 0 ipAddressPoolSelectors

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	A label selector is a label query over a set of resources. The result of matchLabels and matchExpressions are ANDed. An empty label selector matches all objects. A null label selector matches no objects.			No	object

pod-metallb bgp advertisements 0 ipAddressPoolSelectors 0

Description

A label selector is a label query over a set of resources. The result of matchLabels and matchExpressions are ANDed. An empty label selector matches all objects. A null label selector matches no objects.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
matchExpressions	matchExpressions is a list of label selector requirements. The requirements are ANDed.			No	['array', 'null']

Parameter	Description	Default	Value/Range	Mandatory	Type
matchLabels	matchLabels is a map of {key,value} pairs. A single {key,value} in the matchLabels map is equivalent to an element of matchExpressions, whose key field is "key", the operator is "In", and the values array contains only "value". The requirements are ANDed.			No	['object', 'null']

pod-metallb bgp advertisements 0 ipAddressPools

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	IP address pool for BGP advertisement			No	string

pod-metallb bgp advertisements 0 nodeSelectors

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	A node selector represents the union of the results of one or more label queries over a set of nodes; that is, it represents the OR of the selectors represented by the node selector terms.			No	object

pod-metallb bgp advertisements 0 nodeSelectors 0

Description

A node selector represents the union of the results of one or more label queries over a set of nodes; that is, it represents the OR of the selectors represented by the node selector terms.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
nodeSelectorTerms	Required. A list of node selector terms. The terms are ORed.			No	['array', 'null']

pod-metallb bgp advertisements 0 peers

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	BGP advertisement peer			No	string

pod-metallb bgp bfd

Description

BFD parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable BFD				
enabled	Examples: - false	false		No	boolean
profiles				No	array

pod-metallb bgp bfd profiles

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	BFD profile			No	object

pod-metallb bgp bfd profiles 0

Description

BFD profile

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
detectMultiplier	Detection multiplier to determine packet loss. The remote transmission interval will be multiplied by this value to determine the connection loss detection timer			No	integer
echoInterval	Minimal echo receive transmission interval that this system is capable of handling in ms	50		No	integer
	Enable BFD echo mode. Not supported on multi hops setups.				
echoMode	Examples: - false	false		No	boolean
minimumTtl	For multi hop sessions, configure the minimum expected TTL for an incoming BFD control packet			No	integer
name	BFD profile name	default-profile		No	string
	Mark session as passive: a passive session will not attempt to start the connection and will wait for control packets from peer before it begins replying.				
passiveMode	Examples: - false	false		No	boolean
receiveInterval	Minimum interval that this system is capable of receiving control packets in ms	300		No	integer
transmitInterval	Minimum transmission interval (less jitter) that this system wants to use to send BFD control packets in ms.	300		No	integer

pod-metallb bgp bfd communities

Description

BGP communities

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
aliases				No	array
name	BGP communities name	my-communities		No	string

pod-metallb bgp bfd communities aliases

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	BGP community alias			No	object

pod-metallb bgp bfd communities aliases 0

Description

BGP community alias

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	BGP community alias name			No	string
value	BGP community alias ASNs			No	string

pod-metallb bgp peers

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	BGP peer			No	object

pod-metallb bgp peers 0

Description

BGP peer

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bfdProfile	BFD profile for peer	default-profile		No	string
	For FRR mode only, set if the BGPPeer is multi-hops away				
ebgpMultiHop	Examples: - false	false		No	boolean
holdTime	Requested BGP hold time, per RFC4271			No	integer
keepaliveTime	Requested BGP keepalive time, per RFC4271			No	integer
	AS number to use for the local end of the session				
myASN	Examples: - 64500			No	string
name	BGP peer name	leaf-1		No	string
nodeSelectors				No	array
password	BGP peer password			No	string
passwordSecret	BGP peer password secret			No	string
	AS number to expect from the remote end of the session				
peerASN	Examples: - 64501			No	string
peerAddress	Address to dial when establishing the session			No	string
peerPort	Port to dial when establishing the session			No	integer
routerID	BGP peer router id			No	string
sourceAddress	BGP peer source address			No	string

pod-metallb bgp peers 0 nodeSelectors

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	A node selector represents the union of the results of one or more label queries over a set of nodes; that is, it represents the OR of the selectors represented by the node selector terms.			No	object

pod-metallb bgp peers 0 nodeSelectors 0

Description

A node selector represents the union of the results of one or more label queries over a set of nodes; that is, it represents the OR of the selectors represented by the node selector terms.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
nodeSelectorTerms	Required. A list of node selector terms. The terms are ORed.			No	['array', 'null']

pod-metallb/controller

Description

MetalLB controller

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
affinity	Controller affinity rules			No	object
	Enable the MetalLB controller				
enabled	Examples: - true	true		No	boolean
image	MetalLB controller image			No	object
livenessProbe	Controller liveness probe			No	object
logLevel	Controller log level	info		No	string
nodeSelector	Controller node selector			No	object
podAnnotations	Controller pod annotations			No	object
priorityClassName	Controller priority class name			No	string
readinessProbe	Controller readiness probe			No	object
resources	Controller resources			No	object
runtimeClassName	Controller runtime class name			No	string
securityContext	Controller security context			No	object
serviceAccount	Controller service account			No	object
tolerations				No	array

pod-metallb/controller affinity

Description

Controller affinity rules

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-metallb/controller image

Description

MetalLB controller image

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
pullPolicy	Controller image pull policy			No	string

pod-metallb/controller livenessProbe

Description

Controller liveness probe

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable the controller liveness probe	true		No	boolean
	Examples:				
	- true				
failureThreshold	When a probe fails, Kubernetes will try failureThreshold times before giving up	3		No	integer
initialDelaySeconds	Number of seconds after the container has started before liveness or readiness probes are initiated	10		No	integer
periodSeconds	Number of seconds after the container has started before liveness or readiness probes are initiated	10		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer
timeoutSeconds	Number of seconds after which the probe times out	1		No	integer

pod-metallb/controller nodeSelector

Description

Controller node selector

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-metallb/controller podAnnotations

Description

Controller pod annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-metallb/controller readinessProbe

Description

Controller readiness probe

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable the controller readiness probe	true		No	boolean
	Examples:				
	- true				
failureThreshold	Readiness probe failure threshold	3		No	integer
initialDelaySeconds	Readiness probe initial delay seconds	10		No	integer
periodSeconds	Readiness probe period seconds	10		No	integer
successThreshold	Readiness probe success threshold	1		No	integer
timeoutSeconds	Readiness probe timeout seconds	1		No	integer

pod-metallb/controller resources

Description

Controller resources

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-metallb/controller securityContext

Description

Controller security context

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
fsGroup	Controller security context fsGroup	65534		No	integer
	Run controller as non-root				
runAsNonRoot	Examples: - true	true		No	boolean
runAsUser	Controller security context runAsUser	65534		No	integer

pod-metallb/controller serviceAccount

Description

Controller service account

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
annotations	Controller service account annotations			No	object
	Enable the controller readiness probe				
create	Examples: - true	true		No	boolean
name	Controller service account name			No	string

pod-metallb/controller serviceAccount annotations

Description

Controller service account annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-metallb/controller tolerations

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	The pod this Toleration is attached to tolerates any taint that matches the triple <key,value,effect> using the matching operator .			No	object

pod-metallb/controller tolerations 0

Description

The pod this Toleration is attached to tolerates any taint that matches the triple <key,value,effect> using the matching operator .

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
effect	Effect indicates the taint effect to match. Empty means match all taint effects. When specified, allowed values are NoSchedule, PreferNoSchedule and NoExecute.			No	['string', 'null']
key	Key is the taint key that the toleration applies to. Empty means match all taint keys. If the key is empty, operator must be Exists; this combination means to match all values and all keys.			No	['string', 'null']

Parameter	Description	Default	Value/Range	Mandatory	Type
operator	Operator represents a key's relationship to the value. Valid operators are Exists and Equal. Defaults to Equal. Exists is equivalent to wildcard for value, so that a pod can tolerate all taints of a particular category.			No	['string', 'null']
tolerationSeconds	TolerationSeconds represents the period of time the toleration (which must be of effect NoExecute, otherwise this field is ignored) tolerates the taint. By default, it is not set, which means tolerate the taint forever (do not evict). Zero and negative values will be treated as 0 (evict immediately) by the system.			No	['integer', 'null']
value	Value is the taint value the toleration matches to. If the operator is Exists, the value should be empty, otherwise just a regular string.			No	['string', 'null']

pod-metallb/ipAddressPools

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	IP address pool			No	object

pod-metallb/ipAddressPools 0

Description

IP address pool

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
addressesList	A list of IP address ranges over which MetalLB has authority. You can list multiple ranges in a single pool, they will all share the same settings. Each range can be either a CIDR prefix, or an explicit start-end range of IPs.			No	array
name	IP address pool name	default-pool		No	string
poolLabels	IP address pool labels			No	object

pod-metallb ipAddressPools 0 addressesList

Description

A list of IP address ranges over which MetalLB has authority. You can list multiple ranges in a single pool, they will all share the same settings. Each range can be either a CIDR prefix, or an explicit start-end range of IPs.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	A single IP address range that can either be a CIDR prefix, or an explicit start-end range of IPs			No	string

pod-metallb/ipAddressPools 0 poolLabels

Description

IP address pool labels

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-metallb/layer2

Description

Layer 2 parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
advertisements				No	array

pod-metallb layer2 advertisements

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Layer 2 advertisement			No	object

pod-metallb/layer2 advertisements 0

Description

Layer 2 advertisement

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ipAddressPoolSelectors				No	array
ipAddressPools				No	array
name		default-layer2-advertisement		No	string
nodeSelectors				No	array

pod-metallb layer2 advertisements 0 ipAddressPoolSelectors

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	A label selector is a label query over a set of resources. The result of matchLabels and matchExpressions are ANDed. An empty label selector matches all objects. A null label selector matches no objects.			No	object

pod-metallb layer2 advertisements 0 ipAddressPoolSelectors 0

Description

A label selector is a label query over a set of resources. The result of matchLabels and matchExpressions are ANDed. An empty label selector matches all objects. A null label selector matches no objects.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
matchExpressions	matchExpressions is a list of label selector requirements. The requirements are ANDed.			No	['array', 'null']
matchLabels	matchLabels is a map of {key,value} pairs. A single {key,value} in the matchLabels map is equivalent to an element of matchExpressions, whose key field is "key", the operator is "In", and the values array contains only "value". The requirements are ANDed.			No	['object', 'null']

pod-metallb layer2 advertisements 0 ipAddressPools

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	IP address pool name	default-pool		No	string

pod-metallb layer2 advertisements 0 nodeSelectors

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
0	A node selector represents the union of the results of one or more label queries over a set of nodes; that is, it represents the OR of the selectors represented by the node selector terms.			No	object

pod-metallb layer2 advertisements items0 nodeSelectors 0

Description

A node selector represents the union of the results of one or more label queries over a set of nodes; that is, it represents the OR of the selectors represented by the node selector terms.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
nodeSelectorTerms	Required. A list of node selector terms. The terms are ORed.			No	['array', 'null']

pod-metallb/prometheus

Description

Prometheus

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
metricsPort	Port both controller and speaker will listen on for metrics	7472		No	integer
namespace	Prometheus namespace	fed-prometheus		No	string
podMonitor	Prometheus PodMonitor			No	object
serviceMonitor	Prometheus ServiceMonitor			No	object
prometheusRule	Prometheus rules			No	object
Add the Prometheus scrape annotations to pods					
scrapeAnnotations	Examples: - false	false		No	boolean
serviceAccount	Prometheus service account			No	string

pod-metallb/prometheus podMonitor

Description

Prometheus PodMonitor

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
additionalLabels	Prometheus PodMonitor labels			No	object
annotations	Prometheus PodMonitor annotations			No	object
Enable the Prometheus operator PodMonitors					
enabled	Examples: - false	false		No	boolean
interval	Scrape interval. If not set, the Prometheus default scrape interval is used			No	string
jobLabel	Job label for scrape target	app.kubernetes.io/name		No	string
metricRelabelings				No	array
relabelings				No	array

pod-metallb/prometheus podMonitor additionalLabels

Description

Prometheus PodMonitor labels

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-metallb/prometheus podMonitor annotations

Description

Prometheus PodMonitor annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-metallb/prometheus serviceMonitor

Description

Prometheus ServiceMonitor

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
speaker	Prometheus ServiceMonitor for speaker			No	object
controller	Prometheus ServiceMonitor for controller			No	object
Enable the Prometheus operator ServiceMonitor					
enabled	Examples: - false	false		No	boolean
interval	Scrape interval. If not set, the Prometheus default scrape interval is used			No	string
jobLabel	Job label for scrape target	app.kubernetes.io/name		No	string
metricRelabelings				No	array
relabelings				No	array

pod-metallb/prometheus serviceMonitor speaker

Description

Prometheus ServiceMonitor for speaker

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
additionalLabels	Prometheus ServiceMonitor speaker labels			No	object
annotations	Prometheus ServiceMonitor speaker annotations			No	object
tlsConfig	Prometheus ServiceMonitor speaker TLS configuration			No	object

pod-metallb/prometheus serviceMonitor speaker additionalLabels

Description

Prometheus ServiceMonitor speaker labels

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-metallb/prometheus serviceMonitor speaker annotations

Description

Prometheus ServiceMonitor speaker annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-metallb/prometheus serviceMonitor speaker tlsConfig

Description

Prometheus ServiceMonitor speaker TLS configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Skip certificate verification				
insecureSkipVerify	Examples: - true	true		No	boolean

pod-metallb/prometheus serviceMonitor controller

Description

Prometheus ServiceMonitor for controller

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
additionalLabels	Prometheus ServiceMonitor controller labels			No	object
annotations	Prometheus ServiceMonitor controller annotations			No	object
tlsConfig	Prometheus ServiceMonitor controller TLS configuration			No	object

pod-metallb/prometheus serviceMonitor controller additionalLabels

Description

Prometheus ServiceMonitor controller labels

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-metallb/prometheus serviceMonitor controller annotations

Description

Prometheus ServiceMonitor controller annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-metallb/prometheus serviceMonitor controller tlsConfig

Description

Prometheus ServiceMonitor controller TLS configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Skip certificate verification				
insecureSkipVerify	Examples: - true	true		No	boolean

pod-metallb/prometheus prometheusRule

Description

Prometheus rules

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
additionalLabels	PrometheusRule labels			No	object
addressPoolExhausted	AddressPoolExhausted alert rule			No	object
addressPoolUsage	AddressPoolUsage alert rule			No	object
annotations	Prometheus alert rule annotations			No	object
bgpSessionDown	BgpSessionDown alert rule			No	object
configNotLoaded	ConfigNotLoaded alert rule			No	object
	Enable the Prometheus alertmanager alerts				
enabled	Examples: - false	false		No	boolean
extraAlerts				No	array
staleConfig	StaleConfig alert rule			No	object

[pod-metallb/prometheus prometheusRule additionalLabels](#)

Description

PrometheusRule labels

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

[pod-metallb/prometheus prometheusRule addressPoolExhausted](#)

Description

AddressPoolExhausted alert rule

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable the addressPoolExhausted alert rule				
enabled	Examples: - true	true		No	boolean
labels	AddressPoolExhausted alert rule labels			No	object

[pod-metallb/prometheus prometheusRule addressPoolExhausted labels](#)

Description

AddressPoolExhausted alert rule labels

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
severity	addressPoolExhausted alert rule severity	alert		No	string

[pod-metallb/prometheus prometheusRule addressPoolUsage](#)

Description

AddressPoolUsage alert rule

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable the addressPoolUsage alert rule				
enabled	Examples: - true	true		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
thresholds				No	array

pod-metallb/prometheus prometheusRule addressPoolUsage thresholds

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	AddressPoolUsage alert rule threshold			No	object

pod-metallb/prometheus prometheusRule addressPoolUsage thresholds 0

Description

AddressPoolUsage alert rule threshold

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
labels	AddressPoolUsage alert rule threshold labels			No	object
percent	AddressPoolUsage alert rule threshold percent			No	integer

pod-metallb/prometheus prometheusRule addressPoolUsage thresholds 0 labels

Description

AddressPoolUsage alert rule threshold labels

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
severity	addressPoolUsage alert rule severity	alert		No	string

pod-metallb/prometheus prometheusRule annotations

Description

Prometheus alert rule annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-metallb/prometheus prometheusRule bgpSessionDown

Description

BgpSessionDown alert rule

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable the bgpSessionDown alert rule				
enabled	Examples: - true	true		No	boolean
labels	BgpSessionDown alert rule labels			No	object

pod-metallb/prometheus prometheusRule bgpSessionDown labels

Description

BgpSessionDown alert rule labels

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
severity	bgpSessionDown alert rule severity	alert		No	string

pod-metallb/prometheus prometheusRule configNotLoaded

Description

ConfigNotLoaded alert rule

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable the configNotLoaded alert rule				
enabled	Examples: - true	true		No	boolean
labels	ConfigNotLoaded alert rule labels			No	object

pod-metallb/prometheus prometheusRule configNotLoaded labels

Description

ConfigNotLoaded alert rule labels

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
severity	configNotLoaded alert rule severity	warning		No	string

pod-metallb/prometheus prometheusRule staleConfig

Description

StaleConfig alert rule

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable the staleConfig alert rule				
enabled	Examples: - true	true		No	boolean
labels	StaleConfig alert rule labels			No	object

pod-metallb/prometheus prometheusRule staleConfig labels

Description

StaleConfig alert rule labels

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
severity	staleConfig alert rule severity	warning		No	string

pod-metallb/speaker

Description

MetalLB speaker

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
affinity	Speaker affinity			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable the MetalLB speaker	true		No	boolean
	Examples:				
	- true				
frr	Speaker FRR mode			No	object
image	Speaker image			No	object
livenessProbe	Speaker liveness probe			No	object
logLevel	Speaker log level	info		No	string
memberlist	Speaker member list			No	object
nodeSelector	Speaker node selector			No	object
podAnnotations	Speaker pod annotations			No	object
priorityClassName	Speaker priority class name			No	string
readinessProbe	Speaker readiness probe			No	object
resources	Speaker resources			No	object
runtimeClassName	Speaker runtime class name			No	string
serviceAccount	Speaker service account			No	object
tolerateMaster	Whether speakers tolerate control plane nodes	true		No	boolean
	Examples:				
	- true				
tolerations				No	array

pod-metallb/speaker affinity

Description

Speaker affinity

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-metallb/speaker frr

Description

Speaker FRR mode

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable speaker FRR mode	false		No	boolean
	Examples:				
	- false				
image	FRR image			No	object
metricsPort	Port that FRR will listen on for metrics	7473		No	integer

pod-metallb/speaker frr image

Description

FRR image

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	FRR image name	frr:v7.5.1		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	FRR image repo path	frrouting		No	string
pullPolicy	FRR image pull policy			No	string

pod-metallb/speaker image

Description

Speaker image

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
pullPolicy	Speaker image pull policy			No	string

pod-metallb/speaker livenessProbe

Description

Speaker liveness probe

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable speaker liveness probe				
enabled	Examples: - true	true		No	boolean
failureThreshold	When a probe fails, Kubernetes will try failureThreshold times before giving up	3		No	integer
initialDelaySeconds	Number of seconds after the container has started before liveness or readiness probes are initiated	10		No	integer
periodSeconds	How often (in seconds) to perform the probe	10		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer
timeoutSeconds	Number of seconds after which the probe times out	1		No	integer

pod-metallb/speaker memberlist

Description

Speaker member list

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable the speaker member list				
enabled	Examples: - true	true		No	boolean
mlBindPort	Speaker member list bind port	7946		No	integer

pod-metallb/speaker nodeSelector

Description

Speaker node selector

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-metallb/speaker podAnnotations

Description

Speaker pod annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-metallb/speaker readinessProbe

Description

Speaker readiness probe

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Enable speaker readiness probe					
enabled	Examples: - true	true		No	boolean
failureThreshold	Readiness probe failure threshold	3		No	integer
initialDelaySeconds	Readiness probe initial delay seconds	10		No	integer
periodSeconds	Readiness probe period seconds	10		No	integer
successThreshold	Readiness probe success threshold	1		No	integer
timeoutSeconds	Readiness probe timeout seconds	1		No	integer

pod-metallb/speaker resources

Description

Speaker resources

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
limits	Speaker resource limits			No	object

pod-metallb/speaker resources limits

Description

Speaker resource limits

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	Speaker CPU limit	100m		No	string
memory	Speaker memory limit	100Mi		No	string

pod-metallb/speaker serviceAccount

Description

Speaker service account

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
annotations	Speaker service account annotations			No	object
Create speaker service account					
create	Examples: - true	true		No	boolean
name	Speaker service account name			No	string

pod-metallb/speaker serviceAccount annotations

Description

Speaker service account annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-metallb speaker tolerations

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	The pod this Toleration is attached to tolerates any taint that matches the triple <key,value,effect> using the matching operator .			No	object

pod-metallb speaker tolerations 0

Description

The pod this Toleration is attached to tolerates any taint that matches the triple <key,value,effect> using the matching operator .

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
effect	Effect indicates the taint effect to match. Empty means match all taint effects. When specified, allowed values are NoSchedule, PreferNoSchedule and NoExecute.			No	['string', 'null']
key	Key is the taint key that the toleration applies to. Empty means match all taint keys. If the key is empty, operator must be Exists; this combination means to match all values and all keys.			No	['string', 'null']
operator	Operator represents a key's relationship to the value. Valid operators are Exists and Equal. Defaults to Equal. Exists is equivalent to wildcard for value, so that a pod can tolerate all taints of a particular category.			No	['string', 'null']
tolerationSeconds	TolerationSeconds represents the period of time the toleration (which must be of effect NoExecute, otherwise this field is ignored) tolerates the taint. By default, it is not set, which means tolerate the taint forever (do not evict). Zero and negative values will be treated as 0 (evict immediately) by the system.			No	['integer', 'null']
value	Value is the taint value the toleration matches to. If the operator is Exists, the value should be empty, otherwise just a regular string.			No	['string', 'null']

N3IWF Helm Documentation

fed-n3iwf values

Contents

- [Global Parameters](#)
- [File Server Parameters](#)
- [Configuration Manager Parameters](#)
- [Interface Manager Parameters](#)
- [PPE Parameters](#)
- [N3IWF Monitor Parameters](#)
- [N3IWF CC Parameters](#)
- [N3IWF N2 Parameters](#)
- [IKE MGR Parameters](#)
- [Routing Parameters](#)
- [L3rm Parameters](#)
- [Timer Parameters](#)

global

Description

Global parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
defaultRbacEnabled	Configuring defaultRbacEnabled to true will create clusterrolebinding. Configuring defaultRbacEnabled to false, clusterrolebinding will not be created. Examples: - false	true		No	boolean
defaultClusterRole	clusterrole and PSP for is created as a part of fed-rbac. defaultClusterRole options are restricted-cr, permissive-network-cr, permissive-full-cr Examples: - permissive-network-cr	permissive-network-cr		No	string
defaultServiceAccountName	serviceaccount will be created by default. defaultServiceAccountName configuration is used to create default serviceaccount per namespace Examples: - fed-n3iwf-serviceaccount	fed-n3iwf-serviceaccount		No	string
podPriorityEnabled	Support enabling pod priority in this federation; must be true in this federation Examples: - true - false	true		No	boolean
opentelemetry				No	object
ingressNetworkPolicy	network policies configuration			No	object
tabdb	PaaS Tabular database associations			No	object
fileservers	PaaS fileserver associations			No	object
mesh	PaaS service mesh associations			No	object
monitoring	PaaS Monitoring associations			No	object
grafana	PaaS Grafana association			No	object
logging	PaaS logging association			No	object
registry	PaaS container registry associations			No	object
license	PaaS License Server Selector			No	object
envVars	Environment variables			No	object
fileCheckPath	Need to set only while using Mellanox NIC. Directory where multus config file is present on local node Examples: - /etc/cni/net.d	/etc/cni/net.d		No	string
fileCheckFile	Need to set only while using Mellanox NIC. Name of the multus config file on local node Examples: - 00-multus.conf			No	string
loadBalancerSourceRanges	Comma separated IP ranges that are allowed to access the load balancer. More info here - https://kubernetes.io/docs/tasks/access-application-cluster/configure-cloud-provider-firewall/#restrict-access-for-loadbalancer-service Examples: - 130.211.204.1/32	[]		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
resource	Default limits and request for each container			No	object

global opentelemetry

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable opentelemetry	true		No	boolean
tlsEnabled	Enable mTLS on opentelemetry	false		No	boolean
tracing	Configuration options for opentelemetry traces			No	object

global opentelemetry tracing

Description

Configuration options for opentelemetry traces

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable opentelemetry tracing	true		No	boolean
host	opentelemetry fqdn			No	string
port	opentelemetry port	80		No	integer

global ingressNetworkPolicy

Description

network policies configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabled network policy	true		No	boolean
ingressTrafficNamespaces	Namespaces which are required to be allowed for ingress traffic			No	array

global tabdb

Description

PaaS Tabular database associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
etcd	Etcd database association			No	object

global tabdb etcd

Description

Etcd database association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Etcd db instance name	etcd-server		No	string
	Tab-DB service path				
svc	Examples: - etcd-cluster-client.fed-db-etcd.svc.cluster.local	etcd-cluster-client.fed-db-etcd.svc.cluster.local		No	string
port	Tab-DB service port	2379		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
targetPort	Tab-DB service target port	31869		No	string

global fileserver

Description

PaaS fileserver associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
nfs	NFS fileserver association			No	object
cephfs	CephFS configuration - CephFS is an actual mountable POSIX-compliant filesystem layered on top of a Ceph storage cluster			No	object

global fileserver nfs

Description

NFS fileserver association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Fileserver remote host address				
remoteHost	Examples: - 1.1.1.100			No	string
remotePort	Fileserver remote host port	85		No	string

global fileserver cephfs

Description

CephFS configuration - CephFS is an actual mountable POSIX-compliant filesystem layered on top of a Ceph storage cluster

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable CephFS				
enabled	Examples: - true	false		No	boolean

global mesh

Description

PaaS service mesh associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio service mesh association			No	object

global mesh istio

Description

Istio service mesh association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtlsEnabled	Enable/disable istio mutual TLS	false		No	boolean

global monitoring

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association			No	object

global monitoring prometheus

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Monitoring namespace				
namespace	Examples: - fed-prometheus	fed-prometheus		No	string
enabled	Enable/disable prometheus monitoring	true		No	boolean

global grafana

Description

PaaS Grafana association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association	true		No	boolean
	Exposed grafana URL				
url	Examples: - http: //1.1.1.1:3000			No	string
prometheusinfo	Prometheus server association			No	object

global grafana prometheusinfo

Description

Prometheus server association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Prometheus server URL				
url	Examples: - http: //prometheus.fed-prometheus:9090	http: //prometheus.fed-prometheus:9090		No	string

global logging

Description

PaaS logging association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable logging association				
enabled	Examples: - false	false		No	boolean
elastic	Elasticsearch association			No	object
alerts	Alerts configuration			No	object

[global logging elastic](#)

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Elasticsearch IP address				
ip	Examples: - 10.15.10.161			No	string
Port	Elasticsearch port	9200		No	integer

[global logging alerts](#)

Description

Alerts configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable event alerts				
enabled	Examples: - true	false		No	boolean
	Elasticsearch IP address				
ip	Examples: - 10.15.10.161			No	string
port	Elasticsearch port	3030		No	integer
realert	Re-alert Info			No	object
	Receiver type to send alerts, Currently supported are slack as 'slack', email as 'email' and HTTP-POST as 'post'				
type	Examples: - mail	slack		No	string
slack	Slack alert Info			No	object
mail	Mail alert Info			No	object
http_post	HTTP post alert Info			No	object

[global logging alerts realert](#)

Description

Re-alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
	Interval in minutes to re-send an alert				
minutes	Examples: - 2	1		No	integer

[global logging alerts slack](#)

Description

Slack alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	The webhook URL that includes your auth data and the ID of the channel (room) you want to post to.				
webhookurl	Examples: - xxxx	xxxx		No	string

[global logging alerts mail](#)

Description

Mail alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	An address or list of addresses to sent the alert to				
email	Examples: - user1@example.com	user1@example.com		No	string
	SMTP host info				
smtp_host	Examples: - 1.1.1.1	1.1.1.1		No	string
	SMTP port info				
smtp_port	Examples: - 25	25		No	integer
	Enable/disable SSL to SMTP server				
smtp_ssl	Examples: - true	false		No	boolean
	This sets the from header in the email. By default, the from address is ElastAlert@ and the domain will be set by the smtp server				
from_addr	Examples: - user2@example.com	user2@example.com		No	string

[global logging alerts http_post](#)

Description

HTTP post alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
url	URL for HTTP post				
	Examples:	XXXX		No	string
	- XXXX				

global registry

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

global registry docker

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string

global license

Description

PaaS License Server Selector

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
flexera	Flexera license server information			No	object

global license flexera

Description

Flexera license server information

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
remoteHost	Flexera license server host				
	Examples:			No	string
	- 10.163.67.251				
remotePort	Flexera license server port				
	Examples:			No	string
	- 7070				

global envVars

Description

Environment variables

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
fedType	Federation type		Enumerations: - amf - smf		
	Examples:	n3iwf	- upf - nrf - nssf - n3iwf	No	string
	- n3iwf				
fedUniqueName	Federation unique name				
	Examples: - n3iwf	default		No	string
serviceRegistryNamespace	Service registry namespace				
	Examples: - fed-service-reg	fed- service- reg		No	string
configDataEncryptionEnable	Enable config JSON file encryption. When true, also requires injection of encryption key as kubernetes secret or it won't encrypt.				
	Examples:	false		No	boolean
	- true - false				

global resource

Description

Default limits and request for each container

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
defaultlimit	Default CPU & memory limits for each container			No	object
defaultrequest	Default CPU & memory request for each container			No	object

global resource defaultlimit

Description

Default CPU & memory limits for each container

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	Default CPU limits for each container	2		No	integer
	Examples:				
	- 1				
memory	Default memory limits for each container	2Gi		No	string
	Examples:				
	- 4Gi				

global resource defaultrequest

Description

Default CPU & memory request for each container

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	Default CPU request for each container	10m		No	string
	Examples:				
	- 10m				
memory	Default memory request for each container	10Mi		No	string
	Examples:				
	- 10Mi				

pod-fileserver

Description

PaaS Fileserver microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable fileserver	true		No	boolean
	Examples:				
	- false				
deployment	Deployment parameters			No	object
pvc	Persistent Volume Claim (PVC) configuration			No	object

[pod-fileserver](#) deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer

[pod-fileserver](#) pvc

Description

Persistent Volume Claim (PVC) configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
web	PVC web configuration			No	object
cfg	PVC cfg configuration			No	object

[pod-fileserver](#) pvc web

Description

PVC web configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
requestsStorage	Requests storage for pvc	5Gi		No	string
	Examples:				
	- 25Gi				

Parameter	Description	Default	Value/Range	Mandatory	Type
	Storage class name for pvc				
storageClassName	Examples: - rook-cephfs	web		No	string

pod-fileserver pvc cfg

Description

PVC cfg configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Requests storage for pvc				
requestsStorage	Examples: - 25Gi	5Gi		No	string
	Storage class name for pvc				
storageClassName	Examples: - rook-cephfs	cfg		No	string

pod-cfgmgr

Description

Config Manager microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable cfgmgr				
enabled	Examples: - false	true		No	boolean
	Configuring rbacEnabled to true will create clusterrolebinding. Configuring rbacEnabled to false, clusterrolebinding will not be created.				
rbacEnabled	Examples: - false	true		No	boolean
	clusterrole and PSP for is created as a part of fed-rbac. clusterrole options are restricted-cr, permissive-network-cr, permissive-full-cr				
clusterRole	Examples: - permissive-full-cr	permissive-full-cr		No	string
	serviceAccountName configuration is used to create serviceaccount per pod				
serviceAccountName	Examples: - cfgmgr-serviceaccount	cfgmgr-serviceaccount		No	string
deployment	Deployment parameters			No	object
service	Service parameters			No	object

pod-cfgmgr deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer

pod-cfgmgr service

Description

Service parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
loadBalancerIP	Load Balancer IP address				
	Examples:			No	string
	- 10.1.1.101				
loadBalancerFQDN	If specified, this is added as an annotation to the cfgmgr service. Other applications can then query to find the FQDN through which external peers can reach this application				
	Examples:			No	string
	- cfgmgr.n3iwf.affirmed.com				

pod-interface_mgr

Description

Interface Manager microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable Interface Manager microservice				
	Examples:	true		No	boolean
	- false				
deployment	Deployment parameters			No	object

pod-interface_mgr deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count				
	Examples:	1		No	integer
	- 1				

pod-n3iwf_ppe

Description

N3IWF PPE microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable N3IWF PPE microservice				
	Examples:	true		No	boolean
	- false				

Parameter	Description	Default	Value/Range	Mandatory	Type
rbacEnabled	Configuring rbacEnabled to true will create clusterrolebinding. Configuring rbacEnabled to false, clusterrolebinding will not be created. Examples: - false	true		No	boolean
clusterRole	clusterrole and PSP for is created as a part of fed-rbac. clusterrole options are restricted-cr, permissive-network-cr, permissive-full-cr Examples: - permissive-full-cr	permissive-full-cr		No	string
serviceAccountName	serviceAccountName configuration is used to create serviceaccount per pod Examples: - ppe-serviceaccount	ppe-serviceaccount		No	string
ppeFirstWorker	First core dataplane that will be allowed to use. This is not a physical core number; it is a core number within the range allocated to the pod. I.e if a dataplane pod is allocated 10 cores, the first core has to be in the 0-9 range Examples: - 1	1		No	string
ppeNumWorkers	Number of cores allocated to dataplane, including the first core. E.g. if first core is 2 and ppeNumWorkers is 7, then cores 2,3,4,5,6,7,8,9 will be allocated to dataplane Examples: - 2	2		No	string
ppeloScaling	Dataplane I/O resource distribution. Options: 1. grouped: all ports' rx queues are handled by a single I/O core. 2. shared-cores: there are as many I/O cores as rx-queues on each interfaces. The Xth queue of each interfaces share the Xth I/O core. 3. separated-cores: there are as many I/O cores as there rx-queues total. Each rx-queue is placed on an individual I/O core Examples: - separated-cores	separated-cores	Enumerations: - grouped - shared-cores - separated-cores	No	string
vlanStripping	Enable/disable vlan stripping on dataplane ports Examples: - true	false		No	boolean
enableJumboFrames	Enable/disable jumbo frame support Examples: - true	false		No	boolean
sessionPersistenceEnabled	Enable/disable session preservation across PPE failures. Examples: - true	false		No	boolean
deployment	Deployment parameters			No	object
resources	The Resources Schema			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
guaranteedScheduling	Define CPU & memory limits for 4 containers: ppe, infra and istio-proxy and proxy-init. All 3 need to follow the config presented in https://kubernetes.io/docs/tasks/configure-pod-container/quality-service-pod/#create-a-pod-that-gets-assigned-a-qos-class-of-guaranteed Note: If a Container specifies its own memory limit, but does not specify a memory request, Kubernetes automatically assigns a memory request that matches the limit. Similarly, if a Container specifies its own CPU limit, but does not specify a CPU request, Kubernetes automatically assigns a CPU request that matches the limit. Don't specify requests.			No	object
sriov	SRIOV parameters			No	array
netAttachDefs	Networking attachment configuration for the VM node. Supported drivers are Intel and Mellanox			No	object
tracing	Tracing parameters			No	object

[pod-n3iwf_ppe](#) deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer

[pod-n3iwf_ppe](#) resources

Description

The Resources Schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Huge pages type				
hugepagesType	Examples: - 2Mi	2Mi		No	string
	PPE container CPU usage threshold				
ppeCpuRequests	Examples: - 3	3		No	integer
	PPE container CPU usage maximum Limit				
ppeCpuLimits	Examples: - 3	3		No	integer
	Allocated memory for PPE container				
ppeMemory	Examples: - 4Gi	4Gi		No	string
	Huge pages size. More information here - https://wiki.debian.org/Hugepages				
ppeHugepagesSize	Examples: - 4Gi	4Gi		No	string

[pod-n3iwf_ppe](#) guaranteedScheduling

Description

Define CPU & memory limits for 4 containers: ppe, infra and istio-proxy and proxy-init. All 3 need to follow the config presented in <https://kubernetes.io/docs/tasks/configure-pod-container/quality-service-pod/#create-a-pod-that-gets-assigned-a-qos-class-of-guaranteed> Note: If a Container specifies its own memory limit, but does not specify a memory request, Kubernetes automatically assigns a memory request that matches the limit. Similarly, if a Container specifies its own CPU limit, but does not specify a CPU request, Kubernetes automatically assigns a CPU request that matches the limit. Don't specify requests.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable guaranteedScheduling for PPE microservice	false		No	boolean
	Examples: - true				
infraCpuLimit	Infra container CPU usage maximum Limit	100m		No	string
	Examples: - 100m				
infraMemoryLimit	Infra container memory usage maximum Limit	256Mi		No	string
	Examples: - 2Gi				
kafkaCpuLimit	Kafka container CPU usage maximum Limit	100m		No	string
	Examples: - 100m				
kafkaMemoryLimit	Kafka container memory usage maximum Limit	256Mi		No	string
	Examples: - 2Gi				
proxyCPULimit	Proxy container CPU usage maximum Limit	200m		No	string
	Examples: - 200m				
proxyMemoryLimit	Proxy container memory usage maximum Limit	256Mi		No	string
	Examples: - 2Gi				
proxyInitCPULimit	Proxy-Init container CPU usage maximum Limit	100m		No	string
	Examples: - 100m				
proxyInitMemoryLimit	Proxy-Init container memory usage maximum Limit	128Mi		No	string
	Examples: - 2Gi				
ppeCpuLimit	PPE container CPU usage maximum Limit	3		No	integer
	Examples: - 3				
ppeMemoryLimit	PPE container memory usage maximum Limit	2Gi		No	string
	Examples: - 2Gi				

pod-n3iwf_ppe sriov

Description

SRIOV parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
labels	SRIOV label names configured on cluster				
	Examples:			Yes	string
	- label1				
nblfc	Number of interfaces/NICs on n3 or n6				
	Examples:	1		Yes	string
	- 1				

pod-n3iwf_ppe netAttachDefs

Description

Networking attachment configuration for the VM node. Supported drivers are Intel and Mellanox

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable non-default network driver. The default driver is intel. Intel needs this disabled.				
	Examples:	false		No	boolean
	- true				
annotation	SR-IOV network driver parameters				
	Examples:	sriov-net1, sriov-net2		No	string
	- sriov-net1, sriov-net2				

pod-n3iwf_ppe tracing

Description

Tracing parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable tracing				
	Examples:	false		No	boolean
	- false				
samplerType	Sampler type. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration				
	Examples:	probabilistic	Enumerations: - const - probabilistic - ratelimiting - remote	No	string
	- probabilistic				

Parameter	Description	Default	Value/Range	Mandatory	Type
samplerParam	Sampler parameter. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration	1.0		No	string
	Examples: - 1.0				
agentPort	UDP port exposed by jaeger-agent	6831		No	string
	Examples: - 6831				
logEnabled	Enable/disable jaeger logging	false		No	string
	Examples: - false				

pod-n3iwf_monitor

Description

N3IWF Monitor microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable N3IWF Monitor microservice	true		No	boolean
	Examples: - false				
deployment	Deployment parameters			No	object

[pod-n3iwf_monitor deployment](#)

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer
	Examples: - 1				

pod-n3iwf_cc

Description

N3IWF CC microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable N3IWF CC microservice	true		No	boolean
	Examples: - false				
deployment	Deployment parameters			No	object

[pod-n3iwf_cc deployment](#)

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer

pod-n3iwf_n2

Description

N3IWF N2 microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable N3IWF N2 microservice				
enabled	Examples: - false	true		No	boolean
deployment	Deployment parameters			No	object

[pod-n3iwf_n2 deployment](#)

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer

pod-ike_mgr

Description

IKE MGR microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable IKE MGR microservice				
enabled	Examples: - false	true		No	boolean
deployment	Deployment parameters			No	object

[pod-ike_mgr deployment](#)

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer

pod-routing

Description

Routing microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable Routing microservice				
enabled	Examples: - false	true		No	boolean
deployment	Deployment parameters			No	object

[pod-routing](#) deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer

pod-l3rm

Description

L3rm microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable L3rm microservice				
enabled	Examples: - false	true		No	boolean
deployment	Deployment parameters			No	object

[pod-l3rm](#) deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer

pod-timer

Description

Timer microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable timer microservice				
enabled	Examples: - false	true		No	boolean
deployment	Deployment parameters			No	object

[pod-timer deployment](#)

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer

NRF Helm Documentation

fed-nrf values

Contents

- [Global Parameters](#)
- [Configuration Manager Parameters](#)
- [Istio Gateway Parameters](#)
- [Timer Parameters](#)
- [NF Inventory Manager Microservice](#)
- [NF Selector Microservice](#)
- [Oauth Token Microservice](#)
- [NRF Monitor Microservice](#)

global

Description

Global parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
vault	Vault Related attributes			No	object
secretNames	Name of secrets to be pulled from AKV			No	object
defaultRbacEnabled	Configuring defaultRbacEnabled to true will create clusterrolebinding. Configuring defaultRbacEnabled to false, clusterrolebinding will not be created. Examples: - false	true		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
defaultClusterRole	clusterrole and PSP for is created as a part of fed-rbac. defaultClusterRole options are restricted-cr, permissive-network-cr, permissive-full-cr Examples: - permissive-network-cr	permissive-network-cr		No	string
defaultServiceAccountName	serviceaccount will be created by default. defaultServiceAccountName configuration is used to create default serviceaccount per namespace Examples: - fed-nrf-serviceaccount	fed-nrf-serviceaccount		No	string
enableNfEgressCommunication	Configuration to enable NF external communication through Istio Egress Gateway for use cases like mTLS communication. Examples: - false	false		No	boolean
enableLivenessProbe	Support Liveness Probe in this federation; must be true in this federation Examples: - true - false	true		No	boolean
podPriorityEnabled	Support pod priority in this federation; must be true in this federation Examples: - true - false	true		No	boolean
destinationSubsetsEnabled	Controls whether subsets and weights in Destination rule and Virtual services are enabled or not. Examples: - true - false	false		No	boolean
kargoProfileTag	This enables creation of specific kargo-default-profile for fed-nrf			No	string
ingressNetworkPolicy	network policies configuration			No	object
metricsScrapeInterval:	Configure the default metrics scrape interval to 1m. Configure the metrics scraping interval Examples: - 1m	1m		No	string
tabdb	PaaS Tabular database associations			No	object
opentelemetry				No	object
fileserv	PaaS fileserv associations			No	object
istio	Istio related configurations			No	object
mesh	PaaS service mesh associations			No	object
monitoring	PaaS Monitoring associations			No	object
registry	PaaS container registry associations			No	object
envVars	Environment variables			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
grafana	PaaS grafana association			No	object
logging	PaaS logging association			No	object
prometheus	Prometheus association			No	object
topologySpreadConstraints	Pod topology spread constraints control how pods of given microservice type are spread across the cluster among failure-domains such as regions, zones, nodes, and other user-defined topology domains. This can help to achieve high availability as well as efficient resource utilization.			No	object
issu	ISSU parameters			No	object

[global vault](#)

Description

Vault Related attributes

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/Disable Vault feature				
	Examples:				
enabled	- false	false		No	boolean
	- true				
azureKeyVault	AzureKeyVault related configurations			No	object

[global azure azureKeyVault](#)

Description

AzureKeyVault related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	AzureKeyVault Enable/Disable flag				
	Examples:				
enabled	- false	false		No	boolean
	- true				
tenantID	Tenant ID of Customer where AzureKeyVault is deployed			No	string
keyVaultName	KeyVault of Customer where secrets are stored			No	string
	Azure Kuberetes Cluster				
	Examples:				
aksCluster	- false	true		No	boolean
	- true				
userManagedId	ClientID of User managed ID			No	string
	workload Identity				
	Examples:				
workloadIdentity	- false	true		No	boolean
	- true				

[global secretNames](#)

Description

Name of secrets to be pulled from AKV

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cfgmgr	Name of secrets used by configuration manager			No	object
ingressgw	Ingress GW			No	object
egressgw	Engress GW			No	object

global secretNames [cfgmgr](#)

Description

Name of secrets used by configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
confdKey	Vault Secret Name for confd AES key			No	string
encryptConfigKeySecretName	Vault Secret Name for Encyrpt Config key			No	string
adminDomainCAkeySecretName	Vault Secret Name for Admin Domain CA key			No	string
maintDomainCAkeySecretName	Vault Secret Name for Maint domain CA key			No	string
rootDomainCAkeySecretName	Vault Secret Name for root domain CA key			No	string
rootPasswdSecretName	Vault Secret Name for root password			No	string
rootPubkeySecretName	Vault Secret Name for root public key			No	string
adminUsers	List of Admin users for configuration manager			No	array
operUsers	List of Oper users for configuration manager			No	array
readonlyUsers	List of read-only users for configuration manager			No	array
userProvided	Secret Name of certificates used by RESTCONF			No	object

global secretNames [cfgmgr](#) [adminUsers](#)

Description

List of Admin users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

global secretNames [cfgmgr](#) [operUsers](#)

Description

List of Oper users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

global secretNames [cfgmgr](#) [readonlyUsers](#)

Description

List of read-only users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

global secretNames cfmgr userProvided

Description

Secret Name of certificates used by RESTCONF

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
tls crtSecretName	Secret Name of server TLS certificate			No	string
tls keySecretName	Secret Name of server TLS key			No	string
ca certSecretName	Secret Name of CA certificate			No	string

global secretNames ingressgw

Description

Ingress GW

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
userProvided	userProvided CERTIFICATES			No	object

global secretNames ingressgw/userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ca certSecretName	ca certSecretName Configuration				
	Examples:			No	string
tls crtSecretName	ca certSecretName configuration				
	Examples:			No	string
tls keySecretName	ca certSecretName configuration				
	Examples:			No	string

global secretNames egressgw

Description

Egress GW

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
userProvided	userProvided CERTIFICATES			No	object

global secretNames egressgw/userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cacertSecretName	cacert Configuration				
	Examples:			No	string
tls crtSecretName	tls crtSecretName configuration				
	Examples:			No	string
tlskeySecretName	tlskeySecretName configuration				
	Examples:			No	string

global ingressNetworkPolicy

Description

network policies configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabled network policy	true		No	boolean
ingressTrafficNamespaces	Namespaces which are required to be allowed for ingress traffic			No	array

global tabddb

Description

PaaS Tabular database associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
etcd	Etcd database association			No	object

global tabddb etcd

Description

Etcd database association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Etcd db instance name				
	Examples:	etcd-server		No	string
	- etcd-server				
svc	Tab-DB service path				
	Examples:	etcd-cluster-client.fed-db-etcd.svc.cluster.local		No	string
	- etcd-cluster-client.fed-db-etcd.svc.cluster.local				
port	Tab-DB service port	2379		No	string
targetPort	Tab-DB service target port	31869		No	string

global opentelemetry

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable opentelemetry	true		No	boolean
tlsEnabled	Enable mTLS on opentelemetry	false		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
tracing	Configuration options for opentelemetry traces			No	object

global opentelemetry tracing

Description

Configuration options for opentelemetry traces

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable opentelemetry tracing	true		No	boolean
host	opentelemetry fqdn			No	string
port	opentelemetry port	80		No	integer

global fileserver

Description

PaaS fileserver associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ui	Fileserver UI association			No	object
nfs	NFS fileserver association			No	object

global fileserver ui

Description

Fileserver UI association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
loadBalancerPort	Fileserver UI load balancer port	85		No	string
serviceAnnotations	Service annotations			No	object

global fileserver ui serviceAnnotations

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

global fileserver nfs

Description

NFS fileserver association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Fileserver remote host address				
remoteHost	Examples: - 1.1.1.100			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
remotePath	Fileserver remote file path	/filestore		No	string
	Examples:				
	- /filestore				
remotePort	Fileserver remote host port	85		No	string

global istio

Description

Istio related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtls	Istio mutual TLS related configuration			No	object

global istio mtls

Description

Istio mutual TLS related configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable istio mutual TLS	false		No	boolean

global mesh

Description

PaaS service mesh associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio service mesh association			No	object

global mesh istio

Description

Istio service mesh association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGw	Service mesh ingress gateway			No	string
	Examples:				
	- ingress-gateway				
ingressGwIP	Specific IP requested for Ingress Gateway LoadBalancer service			No	string
	Examples:				
	-				
ingressGwFQDN	FQDN to be added as annotation to the Ingress Gateway LoadBalancer service	nrf.com		No	string
	Examples:				
	-				
mtlsEnabled	Enable/disable istio mutual TLS	false		No	boolean
egressGwTLS	Istio egress gateway TLS			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGwTLS	Istio ingress gateway TLS			No	object
serviceAnnotations	Service Annotations			No	object

global mesh istio egressGwTLS

Description

Istio egress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio egress gateway TLS				
	Examples:				
	- true	false		No	boolean
	- false				
mode	Istio egress gateway TLS mode.				
	Examples:	MUTUAL		No	string
	- MUTUAL				
certManager	certManager Configuration			No	object
userProvided	userProvided CERTIFICATES			No	object

global mesh istio egressGwTLS certManager

Description

certManager Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for certManager configuration				
	Examples:				
	- true	true		No	boolean
	- false				
certDuration	certDuration Configuration	10h		No	string
renewBefore	renewBefore Configuration	1h		No	string
organization	organization Configuration				
	Examples:	affirmednetworks		No	string
	- affirmednetworks				
issuerName	issuerName				
	Examples:	affirmed-clusterissuer		No	string
	- affirmed-clusterissuer				
issuerType	Type of the certificate issuer				
	Examples:			No	string
	- vault				

global mesh istio egressGwTLS userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvided Certificates	false		No	boolean
	Examples:				
	- false				
cacert	- true				
	cacert Configuration				
	Examples:				
tlscrt	- Copy and Paste End User generated Certificate			No	string
	tlscrt configuration				
	Examples:				
tlskey	- Copy and Paste End User generated Certificate				
	tlskey configuration				
	Examples:				
tlskey	- Copy and Paste End User generated Certificate			No	string

global mesh istio ingressGwTLS

Description

Istio ingress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio ingress gateway TLS	false		No	boolean
	Examples:				
	- true				
mode	- false				
	Istio ingress gateway TLS mode.				
	Examples:				
certManager	- MUTUAL	MUTUAL		No	string
certManager	certManager Configuration			No	object
userProvided	userProvided CERTIFICATES			No	object

global mesh istio ingressGwTLS certManager

Description

certManager Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for certManager configuration	true		No	boolean
	Examples:				
	- true				
certDuration	- false				
	certDuration Configuration				
certDuration		10h		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
renewBefore	renewBefore Configuration	1h		No	string
	organization Configuration				
organization	Examples: - affirmednetworks	affirmednetworks		No	string
	issuerName				
issuerName	Examples: - affirmed-clusterissuer	affirmed-clusterissuer		No	string
	Type of the certificate issuer				
issuerType	Examples: - vault			No	string

global mesh istio ingressGwTLS userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/Disable Flag for userProvided Certificates				
enabled	Examples: - false - true	false		No	boolean
	cacert Configuration				
cacert	Examples: - Copy and Paste End User generated Certificate			No	string
	tlsCRT configuration				
tlsCRT	Examples: - Copy and Paste End User generated Certificate			No	string
	tlskey configuration				
tlskey	Examples: - Copy and Paste End User generated Certificate			No	string

global mesh istio serviceAnnotations

Description

Service Annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	Azure Load-Balancer Internal	false		No	string
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Azure Load-Balancer Internal subnet	none		No	string

global monitoring

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association			No	object

[global monitoring](#) prometheus

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Monitoring namespace				
namespace	Examples: - fed-prometheus			No	string
enabled	Enable/disable prometheus monitoring	true		No	boolean

[global registry](#)

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

[global registry](#) docker

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string
imagePullSecret	Pull an image from a private registry			No	string
username	Username for private docker registry			No	string
password	Password for private docker registry			No	string

[global envVars](#)

Description

Environment variables

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
			Enumerations: - amf - smf - upf - nrf - nssf		
fedType	Federation type Examples: - smf	nrf		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
fedUniqueName	Federation unique name				
	Examples: - FED-NRF-1			No	string
configDataEncryptionEnable	Enable config JSON file encryption. When true, also requires injection of encryption key as kubernetes secret or it won't encrypt.				
	Examples:				
	- true - false	false		No	boolean

global grafana

Description

PaaS grafana association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association	true		No	boolean
url	Exposed grafana URL				
	Examples: - http: //1.1.1.1:3000			No	string
prometheusinfo	Prometheus server association			No	object

global grafana prometheusinfo

Description

Prometheus server association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
url	Prometheus server URL				
	Examples: - http: //prometheus.fed-prometheus:9090	http: //prometheus.fed-prometheus:9090		No	string

global logging

Description

PaaS logging association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable logging association				
	Examples: - false	false		No	boolean
fluentd	fluentd configurations			No	object
elastic	Elasticsearch association			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
enableAddlTargets	Enable/disable additional destinations	false		No	boolean
	Examples:				
	- true				
	- false				
addlTargets	Additional logging output destination configuration			No	array
alerts	Elastalert association			No	object

global logging fluentd

Description

fluentd configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	fluentd buffer configurations			No	object

global logging fluentd buffer

Description

fluentd buffer configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Total buffer size. Maximum amount of buffer space each fluentd thread would use to keep logs. After this space is exhausted, fluentd would start deleting oldest logs to make room for new logs.	512m		No	string
retryWait	Interval(seconds) at which the buffer flush is retried in case of failure.	180s		No	string
maxRetries	Max number of retries to flush a buffer chunk. After this is exhausted, fluentd would delete the chunk.	10		No	integer

global logging elastic

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ip	Elasticsearch IP address			No	string
	Examples:				
	- 10.15.10.161				
Port	Elasticsearch port	9200		No	integer

global logging addlTargets

Description

Additional logging output destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			No	object

global logging addlTargets forward

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
	Hostname or IP Address of the forward server				
	Examples:				
host	- 192.168.1.1			No	string
	- forward-server.com				
	Port of the forward server				
port	Examples:	24224		No	integer
	- 24224				

global logging alerts

Description

Elastalert association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable event based alerts				
	Examples:				
enabled	- false	false		No	boolean
	- true				
	Elastalert IP address				
host	Examples:			No	string
	- 10.15.16.64				
port	Elastalert port number	3030		No	integer
realert	Alerts will be repeated after the realert duration			No	object
receivers	The platform on which alerts can be sent			No	array

global logging alerts realert

Description

Alerts will be repeated after the realert duration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minutes	An explanation about the purpose of this instance.	1		No	integer

global logging alerts receivers

Description

The platform on which alerts can be sent

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
slack	Slack channel			No	object
post	Configuration for HTTP post			No	object
email	Configuration for email receiver			No	object

global logging alerts receivers slack

Description

Slack channel

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
webhookurl	Webhook url of the receiver slack channel			No	string

global logging alerts receivers post

Description

Configuration for HTTP post

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
http_post_url	HTTP post URL			No	string

global logging alerts receivers email

Description

Configuration for email receiver

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
to_address	Receiver email address			No	string
smtp_host	The smtp host ip			No	string
smtp_port	The smtp port number			No	string
smtp_ssl	This should be disabled	false		No	boolean
from_addr	Sender address			No	string

global prometheus

Description

Prometheus association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Association name				
	Examples:			No	string
	- prometheustest				
url	Prometheus URL				
	Examples:			No	string
	- http: //prometheus.fed-prometheus:9090				

global topologySpreadConstraints

Description

Pod topology spread constraints control how pods of given microservice type are spread across the cluster among failure-domains such as regions, zones, nodes, and other user-defined topology domains. This can help to achieve high availability as well as efficient resource utilization.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable pod topology spread constraints	true		No	boolean
	Examples:				
	- false				
	- true				
constraints	List of pod topology spread constraints to be applied.			No	array

global topologySpreadConstraints constraints

Description

List of pod topology spread constraints to be applied.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Definition of pod topology spread constraint to be applied to the pod specification.			No	object

global topologySpreadConstraints constraints 0

Description

Definition of pod topology spread constraint to be applied to the pod specification.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxSkew	Describes the degree to which pods may be unevenly distributed. It's the maximum permitted difference between the number of matching pods in any two topology domains of a given topology type. It must be greater than zero. Examples: - 1	1		No	integer
topologyKey	Its the key of node labels. If two nodes are labelled with this key and have identical values for that label, the Kubernetes scheduler treats both nodes as being in the same topology. The scheduler tries to place a balanced number of Pods into each topology domain. Examples: - kubernetes.io/hostname	kubernetes.io/hostname		No	string
whenUnsatisfiable	Indicates how to deal with a pod if it doesn't satisfy the defined pod topology spread constraint. Examples: - ScheduleAnyway - DoNotSchedule	ScheduleAnyway		No	string

global issu

Description

ISSU parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
preUpgrade	Pre-upgrade parameters			No	object
postUpgrade	Post-upgrade parameters			No	object
preRollback	Pre-rollback parameters			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
postRollback	Post-rollback parameters			No	object
test	helm test parameters			No	object
nrfKpis	KPIs to be validated for NRF			No	array

global issu preUpgrade

Description

Pre-upgrade parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
validatePods	Validate pods status			No	boolean
validateKpis	Validate KPIs			No	boolean
validateNfState	Validate NF state			No	boolean

global issu postUpgrade

Description

Post-upgrade parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
validatePods	Validate pods status			No	boolean
validateKpis	Validate KPIs			No	boolean
validateNfState	Validate NF state			No	boolean

global issu preRollback

Description

Pre-rollback parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
validatePods	Validate pods status			No	boolean
validateKpis	Validate KPIs			No	boolean
validateNfState	Validate NF state			No	boolean

global issu postRollback

Description

Post-rollback parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
validatePods	Validate pods status			No	boolean
validateKpis	Validate KPIs			No	boolean
validateNfState	Validate NF state			No	boolean

global issu test

Description

helm test parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
validatePods	Validate pods status			No	boolean
validateKpis	Validate KPIs			No	boolean
validateNfState	Validate NF state			No	boolean

global issu nrfKpis

Description

KPIs to be validated for NRF

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the KPI			Yes	string
threshold	Threshold value for the KPI			Yes	number
minimumThreshold	Minimum threshold value forincoming message rate of update request KPI	0		No	number

pod-cfgmgr

Description

Config manager microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable cfgmgr microservice				
enabled	Examples: - true	true		No	boolean
confd	Conf d parameters			No	object
	Configuring rbacEnabled to true will create clusterrolebinding. Configuring rbacEnabled to false, clusterrolebinding will not be created.				
rbacEnabled	Examples: - false	true		No	boolean
	clusterrole and PSP for is created as a part of fed-rbac. clusterrole options are restricted-cr, permissive-network-cr, permissive-full-cr				
clusterRole	Examples: - permissive-full-cr	permissive-full-cr		No	string
	serviceAccountName configuration is used to create serviceaccount per pod				
serviceAccountName	Examples: - cfgmgr-serviceaccount	cfgmgr-serviceaccount		No	string
deployment	Deployment parameters			No	object
service	Service parameters			No	object

pod-cfgmgr confd

Description

Conf d parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
aes256cfb128Key	encoded confd aes256cfb128Key, echo f9c4065f6592b38cc3dbaf2033f73b6c54751c4425faf688857704004306d65a	base64		No	

pod-cfgmgr deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer

pod-cfgmgr service

Description

Service parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
portPrefix	Service port prefix	304	min: 301 max: 309	No	number
loadBalancerIP	Load Balancer IP address Examples: - 10.1.1.101			No	string
loadBalancerFQDN	If specified, this is added as an annotation to the cfgmgr service. Other applications can then query to find the FQDN through which external peers can reach this application Examples: - cfgmgr.nrf.affirmed.com			No	string
serviceAnnotations	Service Annotations			No	object

pod-cfgmgr service serviceAnnotations

Description

Service Annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	Azure Load-Balancer Internal	false		No	string
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Azure Load-Balancer Internal subnet	none		No	string

pod-istio_gw

Description

Istio gateway microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable istio gateway microservice				
enabled	Examples: - true	true		No	boolean
deployment	Deployment parameters			No	object

pod-istio_gw deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer
	Examples:				
	- 1				
istioNspace	Istio namespace	fed-istio		No	string
	Examples:				
	- fed-istio				
istioGwNspace	Istio gateway namespace	fed-nrf		No	string
	Examples:				
	- fed-nrf				
egressGateway	Egress gateway parameters			No	object
ingressGateway	Ingress gateway parameters			No	object

pod-istio_gw egressGateway

Description

Egress gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable egress gateway	true		No	boolean
	Examples:				
	- true				
	- false				
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

pod-istio_gw egressGateway hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable egress gateway HPA	true		No	boolean
	Examples:				
	- false				
workerCpuRequests	CPU request egress application	800m		No	string
	Examples:				
	- 800m				

Parameter	Description	Default	Value/Range	Mandatory	Type
Specify the minimum replica count for egress gateway					
minReplicas	Examples: - 3	1		No	integer
Specify the maximum replica count for egress gateway					
maxReplicas	Examples: - 5	5		No	integer
Specify the target CPU utilization level when hpa would trigger					
averageUtilization	Examples: - 80	80		No	integer

pod-istio_gw ingressGateway

Description

Ingress gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Enable/disable ingress gateway					
enabled	Examples: - true - false	true		No	boolean
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

pod-istio_gw ingressGateway hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Enable/disable ingress gateway HPA					
enabled	Examples: - false	true		No	boolean
CPU request ingress application					
workerCpuRequests	Examples: - 800m	800m		No	string
Specify the minimum replica count for ingress gateway					
minReplicas	Examples: - 3	1		No	integer

Parameter	Description	Default	Value/Range	Mandatory	Type
maxReplicas	Specify the maximum replica count for ingress gateway	5		No	integer
	Examples:				
	- 5				
averageUtilization	Specify the target CPU utilization level when hpa would trigger	80		No	integer
	Examples:				
	- 80				

pod-timer

Description

Timer microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable timer microservice	true		No	boolean
	Examples:				
	- true				
strategy	Deployment Update strategy			No	object
deployment	Deployment parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

[pod-timer deployment strategy](#)

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

[pod-timer deployment strategy rollingUpdate](#)

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	25%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	25%		No	string

[pod-timer deployment](#)

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count				
	Examples:	3		No	integer
	- 3				
Enumerations:					
logLevel	Set log level	DEBUG	- DEBUG - INFO	No	string

pod-timer hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA				
	Examples:	false		No	boolean
	- false				
infraCpuRequests	Infra container CPU request				
	Examples:	10m		No	string
	- 10m				
workerCpuRequests	Worker container CPU request				
	Examples:	390m		No	string
	- 390m				
workerCpuLimits	Worker container CPU limits				
	Examples:	1000m		No	string
	- 1000m				
maxReplicas	Pod maximum replicas setting				
	Examples:	6		No	integer
	- 6				
minReplicas	Pod minimum replicas setting				
	Examples:	1		No	integer
	- 1				
averageUtilization	Average CPU utilization for HPA criteria				
	Examples:	80		No	integer
	- 80				

pod-nf_inv_mgr

Description

Pod-nf_inv_mgr Schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable slice inventory manager microservice	false		No	boolean
	Examples: - true				
deployment	Deployment schema			No	object
upgrade	Upgrade schema			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

pod-nf_inv_mgr deployment

Description

Deployment schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Number of Replicas	1		No	integer
	Examples: - 1				
logLevel	Log level			No	string
	Examples: - DEBUG				
strategy	Deployment Update strategy			No	object

pod-nf_inv_mgr deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-nf_inv_mgr deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

pod-nf_inv_mgr upgrade

Description

Upgrade schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable canary				
	Examples:	false		No	boolean
	- false				
canaryVersWeight	Canary version weight				
	Examples:	0		No	integer
	- 0				
stableVersWeight	Stable version weight				
	Examples:	0		No	integer
	- 0				
stableVersion	Stable version				
	Examples:			No	string
	- 0.0.0				

pod-nf_inv_mgr hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA				
	Examples:	false		No	boolean
	- true				
infraCpuRequests	Infra conatiner CPU request value				
	Examples:			No	string
	- 20m				
workerCpuRequests	Worker container CPU request value				
	Examples:			No	string
	- 100m				
workerCpuLimits	Worker container CPU limits				
	Examples:			No	string
	- 1000m				
maxReplicas	Maximum number of replicas				
	Examples:	1		No	integer
	- 5				
minReplicas	Minimum number of replicas				
	Examples:	1		No	integer
	- 1				

Parameter	Description	Default	Value/Range	Mandatory	Type
	Average utilization value				
averageUtilization	Examples: - 80	0		No	integer

pod-nf_selector

Description

Pod-nf_selector Schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable NF selector microservice				
enabled	Examples: - true	false		No	boolean
upgrade	Upgrade schema			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
deployment	Deployment parameters			No	object

[pod-nf_selector upgrade](#)

Description

Upgrade schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable canary				
canary	Examples: - false	false		No	boolean
	Canary version weight				
canaryVersWeight	Examples: - 0	0		No	integer
	Stable version weight				
stableVersWeight	Examples: - 0	0		No	integer
	Stable version				
stableVersion	Examples: - 0.0.0			No	string

[pod-nf_selector hpa](#)

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA	false		No	boolean
	Examples:				
	- true				
infraCpuRequests	Infra container HPA CPU requests			No	string
	Examples:				
	- 20m				
workerCpuRequests	Worker container HPA CPU requests			No	string
	Examples:				
	- 100m				
workerCpuLimits	Worker container HPA CPU limits			No	string
	Examples:				
	- 1000m				
maxReplicas	Pod maximum number of replicas	1		No	integer
	Examples:				
	- 5				
minReplicas	Pod minimum number of replicas	1		No	integer
	Examples:				
	- 1				
averageUtilization	Pod average utilization	0		No	integer
	Examples:				
	- 80				

pod-nf_selector deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer
	Examples:				
	- 1				
logLevel	Log level			No	string
	Examples:				
	- DEBUG				
strategy	Deployment Update strategy			No	object

pod-nf_selector deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

[pod-nf_selector deployment strategy](#) [rollingUpdate](#)

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

[pod-oauth_token](#)

Description

Pod-oauth_token Schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable Oauth Token microservice				
enabled	Examples: - true	false		No	boolean
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
deployment	Deployment parameters			No	object

[pod-oauth_token](#) [hpa](#)

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable HPA				
enabled	Examples: - true	false		No	boolean
	Infra container HPA CPU requests				
infraCpuRequests	Examples: - 20m			No	string
	Worker container HPA CPU requests				
workerCpuRequests	Examples: - 100m			No	string
	Worker container HPA CPU limits				
workerCpuLimits	Examples: - 1000m			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
maxReplicas	Pod maximum number of replicas				
	Examples:	1		No	integer
	- 5				
minReplicas	Pod minimum number of replicas				
	Examples:	1		No	integer
	- 1				
averageUtilization	Pod average utilization				
	Examples:	0		No	integer
	- 80				

pod-oauth_token deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count				
	Examples:	1		No	integer
	- 1				
logLevel	Log level				
	Examples:			No	string
	- DEBUG				
strategy	Deployment Update strategy			No	object

pod-oauth_token deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-oauth_token deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

pod-nrf_monitor

Description

Pod-nrf_monitor Schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
upgrade	Upgrade Schema			No	object
deployment	Deployment schema			No	object

pod-nrf_monitor upgrade

Description

Upgrade Schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable canary				
canary	Examples: - false	false		No	boolean
	Number of replicas during canary				
canaryReplicas	Examples: - 3	0		No	integer
	Stable replicas				
stableReplicas	Examples: - 1	0		No	integer
	Canary version weight				
canaryVersWeight	Examples: - 80	0		No	integer
	Stable version weight schema				
stableVersWeight	Examples: - 20	0		No	integer
	Stable version weight				
stableVersion	Examples: - 1.0.0			No	string

pod-nrf_monitor deployment

Description

Deployment schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Number of replicas				
replicas	Examples: - 1	1		No	integer
	Log level				
logLevel	Examples: - DEBUG			No	string

fed-nssf values

Contents

- [Global Parameters](#)
- [Configuration Manager Microservice Parameters](#)
- [Istio Gateway Microservice Parameters](#)
- [Timer Microservice Parameters](#)
- [Sub Analyzer Microservice Parameters](#)
- [Slice Inventory Manager Microservice Parameters](#)
- [Slice Selector Microservice Parameters](#)
- [NRF Agent Microservice Parameters](#)
- [NSSF Monitor Microservice Parameters](#)

global

Description

Global parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
vault	Vault Related attributes			No	object
secretNames	Name of secrets to be pulled from AKV			No	object
defaultRbacEnabled	Configuring defaultRbacEnabled to true will create clusterrolebinding. Configuring defaultRbacEnabled to false, clusterrolebinding will not be created. Examples: - false	true		No	boolean
enableNfEgressCommunication	Configuration to enable NF external communication through Istio Egress Gateway for use cases like mTLS communication Examples: - true	false		No	boolean
enableStaticNfEgressCommunication	Configuration to enable statically configured NF external communication through Istio Egress Gateway for use cases like mTLS communication Examples: - true	false		No	boolean
defaultClusterRole	clusterrole and PSP for is created as a part of fed-rbac. defaultClusterRole options are restricted-cr, permissive-network-cr, permissive-full-cr Examples: - permissive-network-cr	permissive-network-cr		No	string
defaultServiceAccountName	serviceaccount will be created by default. defaultServiceAccountName configuration is used to create default serviceaccount per namespace Examples: - fed-nssf-serviceaccount	fed-nssf-serviceaccount		No	string
enableLivenessProbe	Support Liveness Probe in this federation; must be true in this federation Examples: - true - false	true		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
podPriorityEnabled	Support pod priority in this federation; must be true in this federation	true		No	boolean
	Examples:				
	- true - false				
kargoProfileTag	This enables creation of specific kargo-default-profile for fed-nssf			No	string
opentelemetry				No	object
ingressNetworkPolicy	network policies configuration			No	object
metricsScrapeInterval:	Configure the default metrics scrape interval to 1m. Configure the metrics scraping interval	1m		No	string
	Examples:				
	- 1m				
tabdb	PaaS Tabular database associations			No	object
fileserver	PaaS fileserver associations			No	object
istio	Istio related configurations			No	object
mesh	PaaS service mesh associations			No	object
monitoring	PaaS Monitoring associations			No	object
registry	PaaS container registry associations			No	object
envVars	Environment variables			No	object
destinationSubsetsEnabled	Controls whether subsets and weights in Virtual services and Destination rules are enabled or not.	false		No	boolean
	Examples:				
	- true - false				
grafana	PaaS Grafana association			No	object
logging	PaaS logging association			No	object
prometheus	Prometheus association			No	object
topologySpreadConstraints	Pod topology spread constraints control how pods of given microservice type are spread across the cluster among failure-domains such as regions, zones, nodes, and other user-defined topology domains. This can help to achieve high availability as well as efficient resource utilization.			No	object
issu	ISSU parameters			No	object

[global vault](#)

Description

Vault Related attributes

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Vault feature	false		No	boolean
	Examples:				
	- false - true				
azureKeyVault	AzureKeyVault related configurations			No	object

global azure azureKeyVault

Description

AzureKeyVault related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	AzureKeyVault Enable/Disable flag	false		No	boolean
	Examples:				
	- false				
	- true				
tenantID	Tenant ID of Customer where AzureKeyVault is deployed			No	string
keyVaultName	KeyVault of Customer where secrets are stored			No	string
aksCluster	Azure Kuberetes Cluster	true		No	boolean
	Examples:				
	- false				
	- true				
userManagedId	ClientID of User managed ID			No	string
workloadIdentity	workload Identity	true		No	boolean
	Examples:				
	- false				
	- true				

global secretNames

Description

Name of secrets to be pulled from AKV

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cfgmgr	Name of secrets used by configuration manager			No	object
ingressgw	Ingress GW			No	object
egressgw	Engress GW			No	object

global secretNames cfgmgr

Description

Name of secrets used by configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
confdKey	Vault Secret Name for confd AES key			No	string
encryptConfigKeySecretName	Vault Secret Name for Encyrpt Config key			No	string
adminDomainCAkeySecretName	Vault Secret Name for Admin Domain CA key			No	string
maintDomainCAkeySecretName	Vault Secret Name for Maint domain CA key			No	string
rootDomainCAkeySecretName	Vault Secret Name for root domain CA key			No	string
rootPasswdSecretName	Vault Secret Name for root password			No	string
rootPubkeySecretName	Vault Secret Name for root public key			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
adminUsers	List of Admin users for configuration manager			No	array
operUsers	List of Oper users for configuration manager			No	array
readonlyUsers	List of read-only users for configuration manager			No	array
userProvided	Secret Name of certificates used by RESTCONF			No	object

global secretNames cfgmgr adminUsers

Description

List of Admin users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

global secretNames cfgmgr operUsers

Description

List of Oper users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

global secretNames cfgmgr readonlyUsers

Description

List of read-only users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

global secretNames cfgmgr userProvided

Description

Secret Name of certificates used by RESTCONF

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
tlscrtSecretName	Secret Name of server TLS certificate			No	string
tlskeySecretName	Secret Name of server TLS key			No	string
cacertSecretName	Secret Name of CA certificate			No	string

global secretNames ingressgw

Description

Ingress GW

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
userProvided	userProvided CERTIFICATES			No	object

[global secretNames](#) ingressgw/userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cacertSecretName	cacertSecretName Configuration				
	Examples:			No	string
tls crtSecretName	cacertSecretName configuration				
	Examples:			No	string
tlskeySecretName	cacertSecretName configuration				
	Examples:			No	string

[global secretNames](#) egressgw

Description

Engress GW

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
userProvided	userProvided CERTIFICATES			No	object

[global secretNames](#) egressgw/userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cacertSecretName	cacert Configuration				
	Examples:			No	string
tls crtSecretName	tls crtSecretName configuration				
	Examples:			No	string
tlskeySecretName	tlskeySecretName configuration				
	Examples:			No	string

[global](#) opentelemetry

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable opentelemetry	true		No	boolean
tlsEnabled	Enable mTLS on opentelemetry	false		No	boolean
tracing	Configuration options for opentelemetry traces			No	object

[global opentelemetry](#) tracing

Description

Configuration options for opentelemetry traces

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable opentelemetry tracing	true		No	boolean
host	opentelemetry fqdn			No	string
port	opentelemetry port	80		No	integer

[global](#) ingressNetworkPolicy

Description

network policies configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabled network policy	true		No	boolean
ingressTrafficNamespaces	Namespaces which are required to be allowed for ingress traffic			No	array

[global](#) tabdb

Description

PaaS Tabular database associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
etcd	Etcd database association			No	object

[global](#) [tabdb](#) etcd

Description

Etcd database association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Etcd db instance name				
name	Examples: - etcd-server	etcd-server		No	string
	Tab-DB service path				
svc	Examples: - etcd-cluster-client.fed-db-etcd.svc.cluster.local	etcd-cluster-client.fed-db-etcd.svc.cluster.local		No	string
port	Tab-DB service port	2379		No	string
targetPort	Tab-DB service target port	31869		No	string

[global](#) fileserver

Description

PaaS fileserver associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ui	Fileserver UI association			No	object
nfs	NFS fileserver association			No	object

global fileserver ui

Description

Fileserver UI association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
loadBalancerPort	Fileserver UI load balancer port	85		No	string
serviceAnnotations	Service annotations			No	object

global fileserver ui serviceAnnotations

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

global fileserver nfs

Description

NFS fileserver association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Fileserver remote host address				
remoteHost	Examples: - 1.1.1.100			No	string
	Fileserver remote file path				
remotePath	Examples: - /filestore	/filestore		No	string
remotePort	Fileserver remote host port	85		No	string

global istio

Description

Istio related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtls	Istio mutual TLS related configuration			No	object

global istio mtls

Description

Istio mutual TLS related configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable istio mutual TLS	false		No	boolean

global mesh

Description

PaaS service mesh associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio service mesh association			No	object

[global mesh istio](#)

Description

Istio service mesh association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Service mesh ingress gateway				
ingressGw	Examples: - ingress-gateway			No	string
	Specific IP requested for Ingress Gateway LoadBalancer service				
ingressGwIP	Examples: -			No	string
	FQDN to be added as annotation to the Ingress Gateway LoadBalancer service				
ingressGwFQDN	Examples: -	nssf.com		No	string
mtlsEnabled	Enable/disable istio mutual TLS	false		No	boolean
egressGwTLS	Istio egress gateway TLS			No	object
ingressGwTLS	Istio ingress gateway TLS			No	object

[global mesh istio egressGwTLS](#)

Description

Istio egress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enabling Istio egress gateway TLS				
enabled	Examples: - true - false	false		No	boolean
	Istio egress gateway TLS mode.				
mode	Examples: - MUTUAL	MUTUAL		No	string
certManager	certManager Configuration			No	object
userProvided	userProvided CERTIFICATES			No	object

[global mesh istio egressGwTLS certManager](#)

Description

certManager Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for certManager configuration				
	Examples:				
	- true	true		No	boolean
	- false				
certDuration	certDuration Configuration	10h		No	string
renewBefore	renewBefore Configuration	1h		No	string
organization	organization Configuration				
	Examples:				
	- affirmednetworks	affirmednetworks		No	string
issuerName	issuerName				
	Examples:				
	- affirmed-clusterissuer	affirmed-clusterissuer		No	string
issuerType	Type of the certificate issuer				
	Examples:				
	- vault			No	string

global mesh istio egressGwTLS userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvided Certificates				
	Examples:				
	- false	false		No	boolean
	- true				
cacert	cacert Configuration				
	Examples:				
	- Copy and Paste End User generated Certificate			No	string
tlsCRT	tlsCRT configuration				
	Examples:				
	- Copy and Paste End User generated Certificate			No	string
tlskey	tlskey configuration				
	Examples:				
	- Copy and Paste End User generated Certificate			No	string

global mesh istio ingressGwTLS

Description

Istio ingress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio ingress gateway TLS	false		No	boolean
	Examples:				
	- true				
mode	Istio ingress gateway TLS mode.	MUTUAL		No	string
	Examples:				
	- MUTUAL				
certManager	certManager Configuration			No	object
userProvided	userProvided CERTIFICATES			No	object

global mesh istio ingressGwTLS certManager

Description

certManager Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for certManager configuration	true		No	boolean
	Examples:				
	- true				
certDuration	certDuration Configuration	10h		No	string
	Examples:				
	- 10h				
renewBefore	renewBefore Configuration	1h		No	string
	Examples:				
	- 1h				
organization	organization Configuration	affirmednetworks		No	string
	Examples:				
	- affirmednetworks				
issuerName	issuerName	affirmed-clusterissuer		No	string
	Examples:				
	- affirmed-clusterissuer				
issuerType	Type of the certificate issuer			No	string
	Examples:				
	- vault				

global mesh istio ingressGwTLS userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvided Certificates	false		No	boolean
	Examples:				
	- false				
	Examples:				
	- true				

Parameter	Description	Default	Value/Range	Mandatory	Type
cacert Configuration					
cacert	Examples: - Copy and Paste End User generated Certificate			No	string
tlsrct configuration					
tlsrct	Examples: - Copy and Paste End User generated Certificate			No	string
tlskey configuration					
tlskey	Examples: - Copy and Paste End User generated Certificate			No	string

global monitoring

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association			No	object

global monitoring prometheus

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Monitoring namespace					
namespace	Examples: - fed-prometheus			No	string
enabled	Enable/disable prometheus monitoring	true		No	boolean

global registry

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

global registry docker

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string
imagePullSecret	Pull an image from a private registry			No	string

global envVars

Description

Environment variables

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
fedType	Federation type Examples: - nssf	nssf	Enumerations:	No	string
			- amf		
			- smf		
			- upf		
			- nrf		
			- nssf		
fedUniqueName	Federation unique name			No	string
	Examples: - FED-NSSF-1				
configDataEncryptionEnable	Enable config JSON file encryption. When true, also requires injection of encryption key as kubernetes secret or it won't encrypt.	false		No	boolean
	Examples:				
	- true - false				

global grafana

Description

PaaS Grafana association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association	true		No	boolean
url	Exposed grafana URL			No	string
	Examples:				
	- http: //1.1.1.1:3000				
prometheusinfo	Prometheus server association			No	object

global grafana prometheusinfo

Description

Prometheus server association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
url	Prometheus server URL	http: //prometheus.fed-prometheus:9090		No	string
	Examples:				
	- http: //prometheus.fed-prometheus:9090				

global logging

Description

PaaS logging association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable logging association	false		No	boolean
	Examples:				
	- false				
fluentd	fluentd configurations			No	object
elastic	Elasticsearch association			No	object
enableAddITargets	Enable/disable additional destinations	false		No	boolean
	Examples:				
	- true				
addITargets	- false				
	Additional logging output destination configuration				
alerts	Elastalert association			No	object

[global logging](#) [fluentd](#)

Description

fluentd configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	fluentd buffer configurations			No	object

[global logging](#) [fluentd](#) [buffer](#)

Description

fluentd buffer configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Total buffer size. Maximum amount of buffer space each fluentd thread would use to keep logs. After this space is exhausted, fluentd would start deleting oldest logs to make room for new logs.	512m		No	string
retryWait	Interval(seconds) at which the buffer flush is retried in case of failure.	180s		No	string
maxRetries	Max number of retries to flush a buffer chunk. After this is exhausted, fluentd would delete the chunk.	10		No	integer

[global logging](#) [elastic](#)

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
IP	Elasticsearch IP address			No	string
	Examples:				
	- 10.15.10.161				
Port	Elasticsearch port	9200		No	integer

[global logging](#) [addITargets](#)

Description

Additional logging output destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			No	object

[global logging addTargets](#) forward

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
Hostname or IP Address of the forward server					
Examples:					
host	- 192.168.1.1			No	string
	- forward-server.com				
Port of the forward server					
port	Examples:	24224		No	integer
	- 24224				

[global logging alerts](#)

Description

Elastalert association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Enable/disable event based alerts					
Examples:					
enabled	- false	false		No	boolean
	- true				
Elastalert IP address					
host	Examples:			No	string
	- 10.15.16.64				
port	Elastalert port number	3030		No	integer
realert	Alerts will be repeated after the realert duration			No	object
receivers	The platform on which alerts can be sent			No	array

[global logging alerts](#) realert

Description

Alerts will be repeated after the realert duration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minutes	An explanation about the purpose of this instance.	1		No	integer

[global logging alerts](#) receivers

Description

The platform on which alerts can be sent

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
slack	Slack channel			No	object
post	Configuration for HTTP post			No	object
email	Configuration for email receiver			No	object

global logging alerts receivers slack

Description

Slack channel

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
webhookurl	Webhook url of the receiver slack channel			No	string

global logging alerts receivers post

Description

Configuration for HTTP post

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
http_post_url	HTTP post URL			No	string

global logging alerts receivers email

Description

Configuration for email receiver

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
to_address	Receiver email address			No	string
smtp_host	The smtp host ip			No	string
smtp_port	The smtp port number			No	string
smtp_ssl	This should be disabled	false		No	boolean
from_addr	Sender address			No	string

global prometheus

Description

Prometheus association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Association name			No	string
	Examples: - prometheustest				
url	Prometheus URL			No	string
	Examples: - http: //prometheus.fed-prometheus:9090				

global topologySpreadConstraints

Description

Pod topology spread constraints control how pods of given microservice type are spread across the cluster among failure-domains such as regions, zones, nodes, and other user-defined topology domains. This can help to achieve high availability as well as efficient resource utilization.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable pod topology spread constraints	true		No	boolean
	Examples:				
	- false				
	- true				
constraints	List of pod topology spread constraints to be applied.			No	array

global topologySpreadConstraints constraints

Description

List of pod topology spread constraints to be applied.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Definition of pod topology spread constraint to be applied to the pod specification.			No	object

global topologySpreadConstraints constraints 0

Description

Definition of pod topology spread constraint to be applied to the pod specification.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxSkew	Describes the degree to which pods may be unevenly distributed. It's the maximum permitted difference between the number of matching pods in any two topology domains of a given topology type. It must be greater than zero.	1		No	integer
	Examples: - 1				
topologyKey	Its the key of node labels. If two nodes are labelled with this key and have identical values for that label, the Kubernetes scheduler treats both nodes as being in the same topology. The scheduler tries to place a balanced number of Pods into each topology domain.	kubernetes.io/hostname		No	string
	Examples: - kubernetes.io/hostname				
whenUnsatisfiable	Indicates how to deal with a pod if it doesn't satisfy the defined pod topology spread constraint.	ScheduleAnyway		No	string
	Examples:				
	- ScheduleAnyway - DoNotSchedule				

global issu

Description

ISSU parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
preUpgrade	Pre-upgrade parameters			No	object
postUpgrade	Post-upgrade parameters			No	object
preRollback	Pre-rollback parameters			No	object
postRollback	Post-rollback parameters			No	object
test	helm test parameters			No	object
nssfKpis	KPIs to be validated for NSSF			No	array

[global issu](#) preUpgrade

Description

Pre-upgrade parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
validatePods	Validate pods status			No	boolean
validateKpis	Validate KPIs			No	boolean
validateNfState	Validate NF state			No	boolean

[global issu](#) postUpgrade

Description

Post-upgrade parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
validatePods	Validate pods status			No	boolean
validateKpis	Validate KPIs			No	boolean
validateNfState	Validate NF state			No	boolean

[global issu](#) preRollback

Description

Pre-rollback parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
validatePods	Validate pods status			No	boolean
validateKpis	Validate KPIs			No	boolean
validateNfState	Validate NF state			No	boolean

[global issu](#) postRollback

Description

Post-rollback parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
validatePods	Validate pods status			No	boolean
validateKpis	Validate KPIs			No	boolean
validateNfState	Validate NF state			No	boolean

[global issu](#) test

Description

helm test parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
validatePods	Validate pods status			No	boolean
validateKpis	Validate KPIs			No	boolean
validateNfState	Validate NF state			No	boolean

global issu nssfKpis

Description

KPIs to be validated for NSSF

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the KPI			Yes	string
threshold	Threshold value for the KPI			Yes	number

pod-cfgmgr

Description

pod-cfgmgr parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable Config Manager microservice	true		No	boolean
	Examples: - true				
confd	Conf parameters			No	object
rbacEnabled	Configuring rbacEnabled to true will create clusterrolebinding. Configuring rbacEnabled to false, clusterrolebinding will not be created.	true		No	boolean
	Examples: - false				
clusterRole	clusterrole and PSP for is created as a part of fed-rbac. clusterrole options are restricted-cr, permissive-network-cr, permissive-full-cr	permissive-full-cr		No	string
	Examples: - permissive-full-cr				
serviceAccountName	serviceAccountName configuration is used to create serviceaccount per pod	cfgmgr-serviceaccount		No	string
	Examples: - cfgmgr-serviceaccount				
deployment	Deployment parameters			No	object
service	Service parameters			No	object

pod-cfgmgr confd

Description

Conf parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
aes256cfb128Key	encoded confd aes256cfb128Key, echo f9c4065f6592b38cc3dbaf2033f73b6c54751c4425faf688857704004306d65a	base64			No

pod-cfgmgr deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer

pod-cfgmgr service

Description

Service parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
portPrefix	Service port prefix	305	min: 301 max: 309	No	number
loadBalancerIP	Load Balancer IP address Examples: - 10.1.1.101			No	string
loadBalancerFQDN	If specified, this is added as an annotation to the cfgmgr service. Other applications can then query to find the FQDN through which external peers can reach this application Examples: - cfgmgr.nssf.affirmed.com			No	string
serviceAnnotations	Service annotations			No	object

pod-cfgmgr service/propoerties/serviceAnnotations

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

pod-istio_gw

Description

pod-istio_gw parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable Timer microservice	true		No	boolean
	Examples:				
	- true				
deployment	Deployment parameters			No	object

pod-istio_gw deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer
	Examples:				
	- 1				
istioNspace	Istio namespace	fed-istio		No	string
	Examples:				
	- fed-istio				
istioGwNspace	Istio Gateway namespace	fed-nssf		No	string
	Examples:				
	- fed-nssf				
egressGateway	Egress gateway parameters			No	object
ingressGateway	Ingress gateway parameters			No	object

pod-istio_gw egressGateway

Description

Egress gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable egress gateway	true		No	boolean
	Examples:				
	- true				
	- false				
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

pod-istio_gw egressGateway hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable egress gateway HPA	true		No	boolean
	Examples:				
	- false				
workerCpuRequests	CPU request egress application	800m		No	string
	Examples:				
	- 800m				
minReplicas	Specify the mininum replica count for egress gateway	1		No	integer
	Examples:				
	- 3				
maxReplicas	Specify the maximum replica count for egress gateway	5		No	integer
	Examples:				
	- 5				
averageUtilization	Specify the target CPU utilization level when hpa would trigger	80		No	integer
	Examples:				
	- 80				

pod-istio_gw ingressGateway

Description

Ingress gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable ingress gateway	true		No	boolean
	Examples:				
	- true				
	- false				
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

pod-istio_gw ingressGateway hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable ingress gateway HPA	true		No	boolean
	Examples:				
	- false				

Parameter	Description	Default	Value/Range	Mandatory	Type
workerCpuRequests	CPU request ingress application	800m		No	string
	Examples: - 800m				
minReplicas	Specify the mininum replica count for ingress gateway	1		No	integer
	Examples: - 3				
maxReplicas	Specify the maximum replica count for ingress gateway	5		No	integer
	Examples: - 5				
averageUtilization	Specify the target CPU utilization level when hpa would trigger	80		No	integer
	Examples: - 80				

pod-timer

Description

pod-timer parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable Timer microservice	true		No	boolean
	Examples: - true				
strategy	Deployment Update strategy			No	object
deployment	Deployment parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

pod-timer deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-timer deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

pod-timer deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 3	3		No	integer

pod-timer hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable HPA				
enabled	Examples: - false	false		No	boolean
	Infra container CPU request				
infraCpuRequests	Examples: - 10m	20m		No	string
	Worker container CPU requests				
workerCpuRequests	Examples: - 100m	100m		No	string
	Worker container CPU limits				
workerCpuLimits	Examples: - 1000m	1000m		No	string
	Pod maximum number of replicas				
maxReplicas	Examples: - 5	5		No	integer
	Pod minimum number of replicas				
minReplicas	Examples: - 1	1		No	integer
	Average CPU utilization for HPA criteria				
averageUtilization	Examples: - 80	80		No	integer

pod-sub_analyzer

Description

pod-sub_analyzer parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable Sub Analyzer microservice	true		No	boolean
	Examples: - true				
deployment	Deployment parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

pod-sub_analyzer deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer
	Examples: - 1				
strategy	Deployment Update strategy			No	object
injectIstioProxy	Enable/Disable istio-proxy	false		No	boolean
	Examples: - true - false				
logLevel	Loglevel parameters			No	string
	Examples: - DEBUG				

pod-sub_analyzer deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-sub_analyzer deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

pod-sub_analyzer hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA	false		No	boolean
	Examples:				
	- true				
infraCpuRequests	Infra container CPU requests	20m		No	string
	Examples:				
	- 20m				
workerCpuRequests	Worker container CPU requests	200m		No	string
	Examples:				
	- 200m				
workerCpuLimits	Worker container CPU limits	1000m		No	string
	Examples:				
	- 1000m				
maxReplicas	Pod maximum number of replicas	5		No	integer
	Examples:				
	- 5				
minReplicas	Pod minimum number of replicas	1		No	integer
	Examples:				
	- 1				
averageUtilization	Average CPU utilization for HPA criteria	80		No	integer
	Examples:				
	- 80				

pod-slice_inv_mgr

Description

Pod-slice_inv_mgr parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable Slice Inventory Manager microservice	true		No	boolean
	Examples:				
	- true				
deployment	Deployment parameters			No	object
upgrade	Upgrade Schema			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
destinationRule	Istio destination rule			No	object

pod-slice_inv_mgr deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Deployment replica count					
replicas	Examples: - 1	1		No	integer
strategy	Deployment Update strategy			No	object

pod-slice_inv_mgr deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-slice_inv_mgr deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

pod-slice_inv_mgr upgrade

Description

Upgrade Schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Enable/disable Canary					
canary	Examples: - false	false		No	boolean
Canary version weight					
canaryVersWeight	Examples: - 0	0		No	integer
Stable version weight					
stableVersWeight	Examples: - 0	0		No	integer
Stable version					
stableVersion	Examples: - 0.0.0			No	string

pod-slice_inv_mgr hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA	false		No	boolean
	Examples:				
	- true				
infraCpuRequests	Infra container CPU request			No	string
	Examples:				
	- 20m				
workerCpuRequests	Worker container CPU requests			No	string
	Examples:				
	- 100m				
workerCpuLimits	Worker container CPU limits			No	string
	Examples:				
	- 1000m				
maxReplicas	Pod maximum number of replicas	5		No	integer
	Examples:				
	- 5				
minReplicas	Pod minimum number of replicas	1		No	integer
	Examples:				
	- 1				
averageUtilization	Average CPU utilization for HPA criteria	0		No	integer
	Examples:				
	- 80				

pod-slice_inv_mgr destinationRule

Description

Istio destination rule

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
tlsEnabled	Enable/disable Transport Layer Security (TLS)	false		No	boolean
	Examples:				
	- false				

pod-slice_selector

Description

Pod-slice_selector parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable Slice Selector microservice	false		No	boolean
	Examples: - true				
deployment	Deployment parameters			No	object
upgrade	Upgrade Schema			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
destinationRule	Istio destinationrule rule			No	object

pod-slice_selector deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer
	Examples: - 1				
logLevel	Log level			No	string
	Examples: - DEBUG				
strategy	Deployment Update strategy			No	object

pod-slice_selector deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-slice_selector deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

pod-slice_selector upgrade

Description

Upgrade Schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable Canary				
	Examples:	false		No	boolean
	- false				
canaryVersWeight	Canary version weight				
	Examples:	0		No	integer
	- 0				
stableVersWeight	Stable version weight				
	Examples:	0		No	integer
	- 0				
stableVersion	Stable version				
	Examples:			No	string
	- 0.0.0				

pod-slice_selector hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA				
	Examples:	false		No	boolean
	- true				
infraCpuRequests	Infra container CPU requests				
	Examples:			No	string
	- 20m				
workerCpuRequests	Worker container CPU requests				
	Examples:			No	string
	- 100m				
workerCpuLimits	Worker container CPU limits				
	Examples:			No	string
	- 1000m				
maxReplicas	Pod maximum number of replicas				
	Examples:	5		No	integer
	- 5				
minReplicas	Pod minimum number of replicas				
	Examples:	1		No	integer
	- 1				

Parameter	Description	Default	Value/Range	Mandatory	Type
	Average CPU utilization for HPA criteria				
averageUtilization	Examples: - 80	0		No	integer

pod-slice_selector destinationRule

Description

Istio destinationrule rule

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable Transport Layer Security (TLS)				
tlsEnabled	Examples: - false	false		No	boolean

pod-nrf_agent

Description

pod-nrf_agent parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable NRF agent				
enabled	Examples: - true	true		No	boolean
deployment	Deployment parameters			No	object
upgrade	Upgrade Schema			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

pod-nrf_agent deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer
strategy	Deployment Update strategy			No	object
	Enable/Disable istio-proxy				
injectIstioProxy	Examples: - true - false	false		No	boolean

pod-nrf_agent deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

[pod-nrf_agent deployment strategy](#) rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	10%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	10%		No	string

[pod-nrf_agent](#) upgrade

Description

Upgrade Schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable Canary				
	Examples:	false		No	boolean
	- false				
canaryVersWeight	Canary version weight				
	Examples:	0		No	integer
	- 0				
stableVersWeight	Stable version weight				
	Examples:	0		No	integer
	- 0				
stableVersion	Stable version				
	Examples:			No	string
	- 0.0.0				

[pod-nrf_agent](#) hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA				
	Examples:	false		No	boolean
	- true				

Parameter	Description	Default	Value/Range	Mandatory	Type
infraCpuRequests	Infra container HPA CPU requests	20m		No	string
	Examples:				
	- 20m				
workerCpuRequests	Worker container HPA CPU requests	100m		No	string
	Examples:				
	- 100m				
workerCpuLimits	Worker container HPA CPU limits	1000m		No	string
	Examples:				
	- 1000m				
maxReplicas	Pod maximum number of replicas	3		No	integer
	Examples:				
	- 3				
minReplicas	Pod minimum number of replicas	1		No	integer
	Examples:				
	- 1				
averageUtilization	Average CPU utilization for HPA criteria	80		No	integer
	Examples:				
	- 80				

pod-nssf_monitor

Description

Pod-nssf_monitor parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable NSSF Monitor microservice	false		No	boolean
	Examples:				
	- true				
deployment	Deployment parameters			No	object

[pod-nssf_monitor](#) deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer
	Examples:				
	- 1				

fed-opa values

Contents

- [Global Parameters](#)
- [stream-server Configuration](#)
- [Pod-opa parameters](#)
- [pod-opa_gatekeeper parameters](#)

global

Description

Global Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
defaultRbacEnabled	Default Rbac enabled flag				
	Examples:				
	- true	true		No	boolean
	- false				
defaultClusterRole	defaultClusterRole configuration				
	Examples:	permissive- full-cr		No	string
	- permissive-full-cr				
defaultServiceAccountName	defaultServiceAccountName Configuration				
	Examples:	fed-opa- serviceaccount		No	string
	- fed-opa-serviceaccount				
podPriorityEnabled	global flag to enable/disable pod priority				
	Examples:				
	- true	true		No	boolean
	- false				
deployPolicies	global flag to enable/disable deployment of gatekeeper constraintTemplates				
	Examples:				
	- true	true		No	boolean
	- false				
topologySpreadConstraints	Pod topology spread constraints control how pods of given microservice type are spread across the cluster among failure-domains such as regions, zones, nodes, and other user-defined topology domains. This can help to achieve high availability as well as efficient resource utilization.			No	object
logging	PaaS logging association			No	object
grafana	PaaS Grafana association			No	object
monitoring	PaaS Monitoring associations			No	object
registry	PaaS container registry associations			No	object
envVars	Environment variables			No	object
deployment	Deployment options for opa pods.			No	object

[global topologySpreadConstraints](#)

Description

Pod topology spread constraints control how pods of given microservice type are spread across the cluster among failure-domains such as regions, zones, nodes, and other user-defined topology domains. This can help to achieve high availability as well as efficient resource utilization.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable pod topology spread constraints	true		No	boolean
	Examples:				
	- false				
	- true				
constraints	List of pod topology spread constraints to be applied.			No	array

global topologySpreadConstraints constraints

Description

List of pod topology spread constraints to be applied.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Definition of pod topology spread constraint to be applied to the pod specification.			No	object

global topologySpreadConstraints constraints 0

Description

Definition of pod topology spread constraint to be applied to the pod specification.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxSkew	Describes the degree to which pods may be unevenly distributed. It's the maximum permitted difference between the number of matching pods in any two topology domains of a given topology type. It must be greater than zero.	1		No	integer
	Examples:				
	- 1				
topologyKey	Its the key of node labels. If two nodes are labelled with this key and have identical values for that label, the Kubernetes scheduler treats both nodes as being in the same topology. The scheduler tries to place a balanced number of Pods into each topology domain.	kubernetes.io/hostname		No	string
	Examples:				
	- kubernetes.io/hostname				
whenUnsatisfiable	Indicates how to deal with a pod if it doesn't satisfy the defined pod topology spread constraint.	ScheduleAnyway		No	string
	Examples:				
	- ScheduleAnyway				
	- DoNotSchedule				

global logging

Description

PaaS logging association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable logging association				
enabled	Examples: - false - true	false		No	boolean
fluentd	Fluentd-Configurations			No	object
elastic	Elasticsearch association			No	object
	Enable/disable additional destinations				
enableAddlTargets	Examples: - false - true	false		No	boolean
addlTargets	Additional logging output destination configuration			No	array

global logging fluentd

Description

Fluentd-Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	Fluentd-Buffer Configurations			No	object

global logging fluentd buffer

Description

Fluentd-Buffer Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Total buffer size. Maximum amount of buffer space each fluentd thread would use to keep logs. After this space is exhausted, fluentd would start deleting oldest logs to make room for new logs.	512m		No	string
retryWait	Interval(seconds) at which the buffer flush is retried in case of failure.	180s		No	string
maxRetries	Max number of retries to flush a buffer chunk. After this is exhausted, fluentd would delete the chunk.	10		No	integer

global logging elastic

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Elasticsearch IP address				
ip	Examples: - 10.15.10.161			No	string
Port	Elasticsearch port	9200		No	integer

global logging addlTargets

Description

Additional logging output destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			No	object

[global logging addTargets](#) forward

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
host	Hostname or IP Address of the forward server for sending logs to additional targets in parallel with elastic			No	string
port	Port of the forward server	24224		No	integer

[global grafana](#)

Description

PaaS Grafana association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association	true		No	boolean
url	Exposed grafana URL				
	Examples:			No	string
	- https://1.1.1.1:3000				
prometheusinfo	Prometheus server association			No	object

[global grafana prometheusinfo](#)

Description

Prometheus server association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
url	Prometheus server URL				
	Examples:	https://prometheus.fed-prometheus:9090		No	string
	- https://prometheus.fed-prometheus:9090				

[global monitoring](#)

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association			No	object

[global monitoring prometheus](#)

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable prometheus monitoring	true		No	boolean

global registry

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker-Registry path			No	object

global registry docker

Description

Docker-Registry path

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	repoPath	<registry_docker_path>		No	string

global envVars

Description

Environment variables

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
fedType	Federation type				
	Examples:	paas		No	string
	- paas				
fedUniqueName	Federation unique name				
	Examples:	opa-default		No	string
	- opa-default				

global deployment

Description

Deployment options for opa pods.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
nodeDataplaneAffinity	Enables node affinity for the opa pod. If set to 'true' opa pods will be deployed on nodes with no dataplane labels	false		No	string

stream-server

Description

stream-server Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
fqdn	fqdn	capture-stream-server-svc.fed-paas-helpers.svc.cluster.local:9890		No	string

pod-opa

Description

Pod-opa parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
kube_mgmt	Parameters related to kube-mgmt container			No	object
readinessProbe	Readiness probe ensures that traffic is only routed when the pods are ready			No	object
livenessProbe	Liveliness probe to detect and redeem broken state of the pod by restarting them			No	object
podPriority	Configuration for pod priority for pod-opa			No	object
podDisruptionBudget	Configuration for pod disruption budget for pod-opa			No	object
tolerations	Configuration for tolerationSeconds for pod-opa			No	object

[pod-opa](#) [kube_mgmt](#)

Description

Parameters related to kube-mgmt container

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
livenessProbe	Liveness probe ensures to restart kube-mgmt whenever there is OPA container restart to reload OPA policies			No	object

[pod-opa](#) [kube_mgmt](#) [livenessProbe](#)

Description

Liveness probe ensures to restart kube-mgmt whenever there is OPA container restart to reload OPA policies

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	enable liveness probe for kube-mgmt container	true		No	boolean

[pod-opa](#) [readinessProbe](#)

Description

Readiness probe ensures that traffic is only routed when the pods are ready

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
failureThreshold	When a probe fails, Kubernetes will try failureThreshold times before giving up	10		No	integer
initialDelaySeconds	Number of seconds after the container has started before readiness probes are initiated.	10		No	integer
periodSeconds	How often (in seconds) to perform the probe. Default to 10 seconds. Minimum value is 1.	5		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer
timeoutSeconds	Number of seconds after which the probe times out. Defaults to 1 second.	30		No	integer

[pod-opa](#) [livenessProbe](#)

Description

Liveliness probe to detect and redeem broken state of the pod by restarting them

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
failureThreshold	When a probe fails, Kubernetes will try failureThreshold times before giving up	10		No	integer
initialDelaySeconds	Number of seconds after the container has started before liveness probes are initiated.	10		No	integer

Parameter	Description	Default	Value/Range	Mandatory	Type
periodSeconds	How often (in seconds) to perform the probe. Default to 10 seconds. Minimum value is 1.	5		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer
timeoutSeconds	Number of seconds after which the probe times out.	30		No	integer

pod-opa podPriority

Description

Configuration for pod priority for pod-opa

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	enable to deploy pod-opa with the configured priorityClassName	true		No	boolean
priorityClassName	Name of the priority class that is to be used by pod-opa	uc-priority-1		No	string

pod-opa podDisruptionBudget

Description

Configuration for pod disruption budget for pod-opa

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable pod disruption budgets(PDB) for OPA pods	true		No	boolean

pod-opa tolerations

Description

Configuration for tolerationSeconds for pod-opa

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	enable to deploy pod-opa with the configured tolerationSeconds	true		No	boolean
tolerationSecondsUnreachable	Duration in seconds for tolerationSeconds for Unreachable taint	0		No	integer
tolerationsSecondsNotReady	Duration in seconds for tolerationSeconds for NotReady taint	0		No	integer

pod-opa_gatekeeper

Description

pod-opa_gatekeeper parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
deployOpaGatekeeper	Flag to enable/disable deployment of opa-gatekeeper	false		No	boolean
	Examples:				
	- true - false				
podPriority	Configuration for pod priority for pod-opa_gatekeeper			No	object
exemptedNamespaces	Namespaces which are to be excluded from admission control of opa-gatekeeper			No	array

pod-opa_gatekeeper podPriority

Description

Configuration for pod priority for pod-opa_gatekeeper

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	enable to deploy pod-opa_gatekeeper with the configured priorityClassName	true		No	boolean
priorityClassName	Name of the priority class that is to be used by pod-opa_gatekeeper	uc-priority-1		No	string

fed-opa-policies Helm Documentation

fed-opa-policies values

Contents

- [Global Parameters](#)

global

Description

Global Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
registry	registry associations			No	object
deployPolicies	Enable/disable OPA constraints	true		No	boolean

[global](#) registry

Description

registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

[global](#) [registry](#) docker

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string

OPM Helm DOcumentation

fed-opm values

Contents

- [Global Parameters](#)
- [Chart museum Parameters](#)
- [Docker registry Parameters](#)
- [OPM ambassador Parameters](#)

global

Description

Global Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
nfc	NF Configurator properties			No	object

global nfc

Description

NF Configurator properties

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Is NFC enabled	false		No	boolean

pod-chart_museum_ui

Description

Chart museum Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	An explanation about the purpose of this instance.				
chartMuseumlp	Examples: -			No	string

pod-opm_dreg

Description

Docker registry Parameters`

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	An explanation about the purpose of this instance.				
deployment	Examples: - OrderedDict({'dregWebImage': 'hyper/docker-registry-web:v0.1.2'})			No	object

pod-opm_dreg deployment

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-opm_ambassador

Description

OPM ambassadorrameters`

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Details of the certificates.				
certs	Examples:			No	object

pod-opm_ambassador certs

Description

Details of the certificates.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
fallback	Details of the fallback certificate.			No	object
	Examples:				

pod-opm_ambassador fallback

Description

Details of the fallback certificate.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
create	Flag to determine if the certs needs to be created.	true		No	boolean
tls crt	TLS fallback certificate			No	string
tls key	TLS fallback certificate key			No	string

OPM Helm DOcumentation

fed-opm values

Contents

- [Global Parameters](#)
- [Istio Gw Parameters](#)
- [pod istio parameters](#)
- [Docker registry Parameters](#)
- [Master Resource Manager Parameters](#)

global

Description

Global Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
defaultRbacEnabled	Configuring defaultRbacEnabled to true will create clusterrolebinding. Configuring defaultRbacEnabled to false, clusterrolebinding will not be created.	true		No	boolean
	Examples: - false				
defaultClusterRole	clusterrole and PSP for is created as a part of fed-rbac. defaultClusterRole options are restricted-cr, permissive-network-cr, permissive-full-cr	permissive-full-cr		No	string
	Examples: - permissive-full-cr				
defaultServiceAccountName	serviceaccount will be created by default. defaultServiceAccountName configuration is used to create default serviceaccount per namespace	unity-cloud-serviceaccount		No	string
	Examples: - unity-cloud-serviceaccount				
dbNoSqlRam	PaaS NO SQL RAM database associations			No	object
externalAuth	External Authentication			No	object
vault	Enable vault related configuration			No	object
secretNames	Name of secrets to be pulled from AKV or Hashicorp Vault			No	object
opm	opm association			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
fileserver	PaaS fileserver associations			No	object
registry	PaaS registry associations			No	object
logging	OPM logging configuration			No	object
envVars	Environment variables			No	object
mesh	OPM service mesh associations			No	object

global dbNoSqlRam

Description

PaaS NO SQL RAM database associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mongo	Mongo database association			No	object

global dbNoSqlRam mongo

Description

Mongo database association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
username	Database username			No	string
password	Database password			No	string
initUsername	Database init username			No	string
initPassword	Database init password			No	string
connectionString	Database Connection String	vnfmgr-db.vnfmgr:27017/		No	string

global externalAuth

Description

External Authentication

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable external Authentication	true		No	boolean

global vault

Description

Enable vault related configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable Vault configuration	false		No	boolean
hashicorpVault	Enable Hashicorp vault			No	object
azureKeyVault	Enable Azure Key vault			No	object

global vault hashicorpVault

Description

Enable Hashicorp vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable Hashicorp vault configuration	false		No	boolean
	Examples:				
	- false				
serverUrl	Address of Vault Server	http: //fed-hc-vault-test-svc-internal.fed-hc-vault-test:8200		No	string
	Examples:				
	- http: //fed-hc-vault-test-svc-internal.fed-hc-vault-test:8200				
role	JWT Role created on Vault Server			No	string
authMountPath	JWT mount path on Vault server			No	string
vaultNamespace	Vault Namespace configured on Vault server for multi-tenancy support			No	string

global vault azureKeyVault

Description

Enable Azure Key vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable Azure Key vault configuration	false		No	boolean
keyVaultName	Name of the Azure Key Vault			No	string
tenantID	Tenant ID where Azure Key Vault resides			No	string
secretName	Name of the k8s secret which contains SPN's ClientID and ClientSecret (required for On-prem)			No	string
aksCluster	Whether the cluster is running on AKS	false		No	boolean

global secretNames

Description

Name of secrets to be pulled from AKV or Hashicorp Vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
fedopmmulti	Name of secrets used by multi node opm			No	object

global secretNames fedopmmulti

Description

Name of secrets used by multi node opm

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
opmUsernameSecretName	Vault Secret Name for the OPM user	secrets/data/opmUsernameSecretName		No	string
opmPasswordSecretName	Vault Secret Name for the OPM user password	secrets/data/opmPasswordSecretName		No	string
mongoUsernameSecretName	Vault Secret Name for the Mongo db user	secrets/data/mongoUsernameSecretName		No	string
mongoPasswordSecretName	Vault Secret Name for the Mongo db password	secrets/data/mongoPasswordSecretName		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
mongoInitUsernameSecretName	Vault Secret Name for the Mongo init user	secrets/data/mongoInitUsernameSecretName		No	string
mongoInitPasswordSecretName	Vault Secret Name for the Mongo init password	secrets/data/mongoInitPasswordSecretName		No	string
mongoConnectionStringSecretName	Vault Secret Name for the Mongo connection string	secrets/data/mongoConnectionStringSecretName		No	string

global opm

Description

opm association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
username	opm username	admin		No	string
password	opm password	admin		No	string
mode	opm mode	multiNode		No	string
deployment	opm deployment	production		No	string
platform	opm platform	openstack		No	string
variant	opm platform variant	none		No	string
Configuring resiliency for vnfmgr pods					
resilient	Examples: - true	true		No	boolean
ao5gc					
ao5gc	Examples: - true	false		No	boolean
ratelimit	opm http ratelimit per ingress pod	100		No	integer
manageSecrets	opm to manage secrets for this chart	false		No	boolean

global fileserver

Description

PaaS fileserver associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
nfs	Fileserver NFS association			No	object
rookceph	NFS association for rookceph			No	object

global fileserver nfs

Description

Fileserver NFS association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
remoteHost	NFS server remote host			No	string

global fileserver rookceph

Description

NFS association for rookceph

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
pvc	Rookceph persistence volume configuration			No	object

[global fileserver rookceph pvc](#)

Description

Rookceph persistence volume configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
storageClassName	Rookceph storage class configuration			No	string

[global registry](#)

Description

PaaS registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
infraDreg	InfraDreg registry association			No	object
docker	Docker registry association			No	object

[global registry infraDreg](#)

Description

InfraDreg registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable InfraDreg	false		No	boolean
loadBalancerIP	Load balancer IP for InfraDreg			No	string
port	Port for InfraDreg	5005		No	integer
registryUrl	URL of the InfraDreg registry			No	string
secretName	Name of the secret for InfraDreg	infradreg-cert-manager		No	string
storageSize	Storage size for InfraDreg	200Gi		No	string
storageClass	Name of the storage class for InfraDreg	csi-sc-cinderplugin		No	string

[global registry docker](#)

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string
imagePullSecret	Pull an image from a private registry			No	string
username	Username for private docker registry			No	string
password	Password for private docker registry			No	string

[global logging](#)

Description

OPM logging configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable logging association				
enabled	Examples: - false	false		No	boolean
elastic	Elasticsearch association			No	object
alerts	Alerts configuration			No	object

global logging elastic

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
IP	Elasticsearch IP address			No	string
Port	Elasticsearch port	80		No	integer

global logging alerts

Description

Alerts configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable event alerts				
enabled	Examples: - true	false		No	boolean
realert	Re-alert Info			No	object
host	Host to forward the alerts			No	string

global logging alerts realert

Description

Re-alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Interval in minutes to re-send an alert				
minutes	Examples: - 2	1		No	integer

global envVars

Description

Environment variables

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Federation type				
fedType	Examples: - opm	opm		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
	Federation unique name				
fedUniqueName	Examples: - opm	default		No	string

global mesh

Description

OPM service mesh associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio service mesh association			No	object

global mesh istio

Description

Istio service mesh association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGw	Istio service mesh LI ingress GW	ingress-gateway		No	string
ingressGwIP	Specific IP requested for OPM Ingress Gateway LoadBalancer service			No	string
	fqdn requested for Ingress Gateway LoadBalancer service				
ingressGwFQDN	Examples: -	opm.unitycloud.com		No	string
serviceAnnotations	Service annotations			No	object
	Mutual TLS for Ingress Gateway communications				
mtlsEnabled	Examples: - true	true		No	boolean
ingressGwTLS	Service annotations			No	object

global mesh istio serviceAnnotations

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	use internal load balancer subnet	true		No	string
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

global mesh istio ingressGwTLS

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	tls enabled	true		No	boolean
mode	tls mode	SIMPLE		No	string

pod-istio_gw

Description

Istio Gw Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	An explanation about the purpose of this instance.	true		No	boolean
istioNspace	An explanation about the purpose of this instance.	fed-istio		No	string
egressGateway	egress gateway			No	object
paasSelector	paas selector.			No	object
ingressGateway	ingress gw			No	object

[pod-istio_gw egressGateway](#)

Description

egress gateway

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	An explanation about the purpose of this instance.	true		No	boolean
service	An explanation about the purpose of this instance.			No	object

[pod-istio_gw egressGateway service](#)

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
useMtlsPort	An explanation about the purpose of this instance.	true		No	boolean

[pod-istio_gw paasSelector](#)

Description

paas selector.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
jaegerHostName	jaeger host.	No	string		

[pod-istio_gw ingressGateway](#)

Description

ingress gw

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	An explanation about the purpose of this instance.	true		No	boolean
service	An explanation about the purpose of this instance.			No	object

[pod-istio_gw ingressGateway service](#)

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
useMtlsPort	An explanation about the purpose of this instance.	true		No	boolean

pod-istio

Description

pod istio parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istioproxy	An explanation about the purpose of this instance.			No	object

[pod-istio](#) [istioproxy](#)

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
accessLogFile	An explanation about the purpose of this instance.	istioAccessLog		No	string
accessLogEncoding	An explanation about the purpose of this instance.	TEXT		No	string
	An explanation about the purpose of this instance.				
includeIPRanges	Examples: - 10.96.0.0/12,192.168.0.0/16,10.15.19.160/27			No	string

pod-opm_dreg

Description

Docker registry Parameters`

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	An explanation about the purpose of this instance.				
deployment	Examples: - OrderedDict({'dregWebImage': 'hyper/docker-registry-web:v0.1.2'})			No	object

[pod-opm_dreg](#) [deployment](#)

Description

An explanation about the purpose of this instance.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
dregWebImage	Deployment Image of Docker registry.	hyper/docker-registry-web:v0.1.2		No	string

pod-opm_master_rm

Description

Master Resource Manager Parameters`

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
deployment	Deployment Image of MongoDB.			No	object

[pod-opm_master_rm](#) [deployment](#)

Description

Deployment Image of MongoDB.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mongoServerImage	Deployment Image of MongoDB.			No	string

fed-paas_helpers Helm Documentation

fed-paas_helpers values

Contents

- [Global Parameters](#)
- [Name](#)
- [Pod-grafana_operator Configurations](#)
- [pod-fluentd_operator related configurations](#)
- [pod-k8s_event_logger related configurations](#)
- [pod-cert_manager Configurations](#)
- [pod-istio_config Configurations](#)
- [pod-capture_mgr related Configuration](#)
- [pod-capture_ss related Configuration](#)
- [UDSF management operation configuration](#)
- [pod-kargo related configuration](#)
- [Elastalert operator Configuration](#)
- [Cores Mgr Configuration](#)
- [Oauth2 Proxy Configuration](#)

global

Description

Global Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
vault	Vault			No	object
secretNames	Name of secrets to be pulled from AKV or Hashicorp Vault			No	object
authType	Authentication type for PaaS components, allowed values are local and haloe	haloe		No	string
adminPassword	Generic password for all PAAS components is adminPassword			No	string
defaultRbacEnabled	Default Rbac enabled flag. Configuring defaultRbacEnabled to true will create clusterrolebinding. Configuring defaultRbacEnabled to false, clusterrolebinding will not be created. Examples: - true - false	true		No	boolean
defaultClusterRole	Default-Cluster-Role, defaultClusterRole configuration is to configure the clusterrole in clusterrolebinding.	permissive-network-cr		No	string
defaultServiceAccountName	Default-Service-Account-Name, defaultServiceAccountName configuration is used to create default serviceaccount per namespace.	fed-paas-helpers-serviceaccount		No	string
ingressNetworkPolicy	network policies configuration			No	object
enableSCC	If running on OCP cluster, please set enableSCC to true	false		No	boolean
enableUserProvidedSCC	Set this flag to enable the user to provide custom SCC for use in RBAC	false		No	boolean
opaInjectDisabled	Please set to true in case fed-opa is not deployed	false		No	boolean
logging	PaaS logging association			No	object
grafana	PaaS Grafana association			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
fileserv	PaaS Fileserver Selector			No	object
metricsScrapeInterval	Metrics scrape interval in ServiceMonitors. Setting a lower value would result in faster refreshes of metrics at the cost of more overhead for both prometheus and the application.	1m		No	string
monitoring	PaaS Monitoring associations			No	object
registry	PaaS container registry associations			No	object
envVars	Environment variables			No	object
loadBalancerSourceRanges	loadBalancerSourceRanges			No	string
overrides	overrides			No	object
deployment	Deployment option for fed-paas-helpers			No	object
kargo	PaaS Kargo association			No	object
istio	Istio related configurations			No	object
mesh	PaaS service mesh associations			No	object

global vault

Description

Vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Vault Enabled				
	Examples:				
enabled	- false	false		No	boolean
	- true				
hashicorpVault	HashicorpVault related configurations			No	object
azureKeyVault	AzureKeyVault related configurations			No	object

global vault hashicorpVault

Description

HashicorpVault related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	HashicorpVault Enable/Disable flag				
	Examples:				
enabled	- false	true		No	boolean
	- true				
	Address of Vault Server				
serverUrl	Examples: - http://fed-hc-vault-test-svc-internal.fed-hc-vault-test:8200	http://fed-hc-vault-test-svc-internal.fed-hc-vault-test:8200		No	string
role	JWT Role created on Vault Server			No	string
authMountPath	JWT mount path on Vault server			No	string
vaultNamespace	Vault Namespace configured on Vault server for multi-tenancy support			No	string

global azure azureKeyVault

Description

AzureKeyVault related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	AzureKeyVault Enable/Disable flag				
	Examples:				
	- false	false		No	boolean
	- true				
tenantID	Tenant ID of Customer where AzureKeyVault is deployed			No	string
keyVaultName	KeyVault of Customer where secrets are stored			No	string
aksCluster	Azure Kuberetes Cluster				
	Examples:				
	- false	false		No	boolean
	- true				
userManagerId	User manager ID			No	string
workloadIdentity	workload Identity				
	Examples:				
	- false	true		No	boolean
	- true				

global secretNames

Description

Name of secrets to be pulled from AKV or Hashicorp Vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
oidc	OIDC Secret Names			No	object

global secretNames oidc

Description

OIDC Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mountCSI	Enable mounting of OIDC secrets as CSI volumes	true		No	boolean
oidcClientIDSecretName	Name of OIDC Client ID key in Vault				
	Examples:	OrderedDict()		No	string
	- oidcClientID				
oidcClientSecretName	Name of OIDC Client Secret key in Vault				
	Examples:	OrderedDict()		No	string
	- oidcClientSecret				
caCertSecretName	Name of CA Cert key in Vault				
	Examples:	OrderedDict()		No	string
	- ca-crt				

global ingressNetworkPolicy

Description

network policies configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabled network policy	true		No	boolean
ingressTrafficNamespaces	Namespaces which are required to be allowed for ingress traffic			No	array

global logging

Description

PaaS logging association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable logging association				
enabled	Examples: - false - true	false		No	boolean
fluentd	Fluentd-Configurations			No	object
elastic	Elasticsearch association			No	object
	Enable/disable additional destinations				
enableAddlTargets	Examples: - false - true	false		No	boolean
addlTargets	Additional logging output destination configuration			No	array
alerts	Alerts configuration			No	object

global logging fluentd

Description

Fluentd-Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	Fluentd-Buffer Configurations			No	object

global logging fluentd buffer

Description

Fluentd-Buffer Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Total buffer size. Maximum amount of buffer space each fluentd thread would use to keep logs. After this space is exhausted, fluentd would start deleting oldest logs to make room for new logs.	32m		No	string
retryWait	Interval(seconds) at which the buffer flush is retried in case of failure.	10s		No	string
maxRetries	Max number of retries to flush a buffer chunk. After this is exhausted, fluentd would delete the chunk.	1		No	integer

global logging elastic

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
IP	Elasticsearch IP address				
	Examples:			No	string
	- 10.15.10.161				
Port	Elasticsearch port	9200		No	integer

global logging addITargets

Description

Additional logging output destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			No	object

global logging addITargets forward

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
host	Hostname or IP Address of the forward server for sending logs to additional targets in parallel with elastic			No	string
port	Port of the forward server	24224		No	integer

global logging alerts

Description

Alerts configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable event alerts				
	Examples:	false		No	boolean
	- true				
host	Elasticsearch IP address or host				
	Examples:			No	string
	- 10.15.10.161				
port	Elasticsearch port	3030		No	integer
realert	Re-alert Info			No	object
receivers	Alert receivers.				
	Examples:			No	array
	- [OrderedDict({'slack': OrderedDict({'webhookurl': ''})}), OrderedDict({'post': OrderedDict({'http_post_url': ''})})]				

global logging alerts realert

Description

Re-alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Interval in minutes to re-send an alert				
minutes	Examples: - 2	1		No	integer

global logging alerts receivers

Description

Alert receivers.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	The first anyOf schema.				
0	Examples: - OrderedDict({'slack': OrderedDict({'webhookurl': ''})})			No	object
	The second anyOf schema.				
1	Examples: - OrderedDict({'post': OrderedDict({'http_post_url': ''})})			No	object
	The third anyOf schema				
2	Examples: - OrderedDict({'email': OrderedDict({'to_address': '', 'smtp_host': '', 'smtp_port': '', 'smtp_ssl': False, 'from_addr': ''})})			No	object

global logging alerts receivers 0

Description

The first anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Slack receiver details.				
slack	Examples: - OrderedDict({'webhookurl': ''})			No	object

global logging alerts receivers 0 slack

Description

Slack receiver details.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
webhookurl	The webhook URL that includes your auth data and the ID of the channel (room) you want to post to.				
	Examples:			No	string
	-				

global logging alerts receivers 1

Description

The second anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
post	HTTP post alert receiver details.				
	Examples:			No	object
	- OrderedDict({'http_post_url': ''})				

global logging alerts receivers 1 post

Description

HTTP post alert receiver details.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
http_post_url	URL for HTTP post.				
	Examples:			No	string
	-				

global logging alerts receivers 2

Description

The third anyOf schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
email	Mail alert receiver Info.				
	Examples:			No	object
	- OrderedDict({'to_address': '', 'smtp_host': '', 'smtp_port': '', 'smtp_ssl': False, 'from_addr': ''})				

global logging alerts receivers 2 email

Description

Mail alert receiver Info.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
to_address	An address or list of addresses to sent the alert to.				
	Examples:	user1@example.com		No	string
	- user1@example.com				

Parameter	Description	Default	Value/Range	Mandatory	Type
smtp_host	SMTP host details.				
	Examples:	1.1.1.1		No	string
	- 1.1.1.1				
smtp_port	SMTP port info				
	Examples:	25		No	string
	- 25				
smtp_ssl	Enable/disable SSL to SMTP server.				
	Examples:	false		No	boolean
	- false				
from_addr	This sets the from header in the email. By default, the from address is ElastAlert@ and the domain will be set by the smtp server				
	Examples:	user2@example.com		No	string
	- user2@example.com				

global grafana

Description

PaaS Grafana association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association				
	Examples:	true		No	boolean
	- true				
url	Exposed grafana URL				
	Examples:			No	string
	- https: //10.15.10.161:3000				
prometheusinfo	Prometheus server association			No	object

global grafana prometheusinfo

Description

Prometheus server association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
url	Prometheus server URL				
	Examples:	http: //prometheus.fed-prometheus:9090		No	string
	- https: //prometheus.fed-prometheus:9090				

global fileserver

Description

PaaS Fileserver Selector

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
nfs	NFS configuration			No	object

[global fileserver](#) nfs

Description

NFS configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Remote-Host Configuration					
remoteHost	Examples: -			No	string
Remote path Configuration					
remotePath	Examples: - /filestore	/filestore		No	string
Remote-Port Configuration					
remotePort	Examples: - 85	85		No	string

[global monitoring](#)

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association			No	object

[global monitoring prometheus](#)

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable prometheus monitoring	true		No	boolean

[global registry](#)

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

[global registry docker](#)

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string
imagePullSecret	Pull an image from a private registry			No	string
username	Username for private docker registry			No	string
password	Password for private docker registry			No	string

global envVars

Description

Environment variables

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Federation type				
fedType	Examples: - paas	paas		No	string
	Federation unique name				
fedUniqueName	Examples: - paas-helpers	paas-helpers		No	string

global overrides

Description

overrides

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	postInstallEnabled				
postInstallEnabled	Examples: - false - true	false		No	boolean

global deployment

Description

Deployment option for fed-paas-helpers

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
nodeDataplaneAffinity	Enables node affinity for the fed-paas-helpers pods. If set to 'true' all the pods belonging to fed-paas-helpers will be deployed on nodes with no dataplane label.	false		No	string

global kargo

Description

PaaS Kargo association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable Kargo association				
	Examples:				
enabled	- true	true		No	boolean
	- false				

global istio

Description

Istio related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtls	Istio mutual TLS related configuration			No	object

global istio mtls

Description

Istio mutual TLS related configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable istio mutual TLS	false		No	boolean

global mesh

Description

PaaS service mesh associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio service mesh association			No	object

global mesh istio

Description

Istio service mesh association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtlsEnabled	Enable/disable istio mutual TLS	false		No	boolean

name

Description

Name

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-grafana_operator

Description

Pod-grafana_operator Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable Flag	true		No	boolean
	Examples:				
	- true				
	- false				
deployment	Deployment Configuration			No	object
livenessProbe	Liveliness probe to detect and redeem broken state of the pod by restarting those pods.			No	object

[pod-grafana_operator deployment](#)

Description

Deployment Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
authToProm	authToProm Configuration			No	object

[pod-grafana_operator deployment authToProm](#)

Description

authToProm Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
oAuth	oAuth Configuration			No	object

[pod-grafana_operator deployment authToProm oAuth](#)

Description

oAuth Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabled Flag	false	No		boolean
	Examples:				
	- false				
	- true				

[pod-grafana_operator livenessProbe](#)

Description

Liveliness probe to detect and redeem broken state of the pod by restarting those pods.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
initialDelaySeconds	Number of seconds after the container has started before liveness probes are initiated. Defaults to 0 seconds	20		No	integer
periodSeconds	How often (in seconds) to perform the probe. Default to 10 seconds. Minimum value is 1	30		No	integer
timeoutSeconds	Number of seconds after which the probe times out.	30		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer
failureThreshold	When the probe fails, Kubernetes will try failureThreshold times before giving up	10		No	integer

[pod-fluentd_operator](#)

Description

pod-fluentd_operator related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
logLevel	Control verbosity of log level for reloader container	warn		No	string
	Examples:				
	- fatal				
	- error				
	- warn				
	- warning				
	- info				
	- debug				
fluentdLogLevel	Control verbosity of log level for fluentd container. Possible values are fatal, error, warn or warning, info, debug, and trace.	error		No	string
	Examples:				
	- fatal				
	- error				
	- warn				
	- warning				
	- info				
	- debug				
prometheusEnabled	To specify whether Prometheus should be Enabled/Disabled	true		No	boolean
	Examples:				
	- true				
syslogEnabled	Enable/disable syslog association. By enabling this flag, additional fluentd instance will be deployed on master node to read syslogs on master node.	false		No	boolean
	Examples:				
	- false				
auditlogEnabled	Enable/disable Audit logs. By enabling this flag, additional fluentd instance will be deployed on master node	false		No	boolean
	Examples:				
	- false				
lilogsEnabled	Enable/disable lilogs association	false		No	boolean
	Examples:				
	- false				
	- true				

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable kubernetes event logging				
k8sEventLoggingEnabled	Examples: - false - true	false		No	boolean
fluentd	Fluentd related Configurations			No	object
closeWaitCleanup	Clean-up the close-wait sockets. Applicable only for additional targets apart from elastic.			No	object
livenessProbe	liveness health check for fluentd			No	object
rbacEnabled	rbac Enabled Flag for pod-fluentd_operator. Configuring rbacEnabled to true will create customrole, customrolebinding. Configuring rbacEnabled to false, customrole,customrolebinding will not be created. Examples: - true - false	true		No	boolean
serviceAccountName	serviceAccountName configuration is used to create serviceaccount per pod(pod-fluentd_operator)	fluentd-operator-serviceaccount		No	string
tolerations	fluentd pod tolerations			No	array

[pod-fluentd_operator](#) fluentd

Description

Fluentd related Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	To specify whether multi-Worker should be Enabled/Disabled				
multiWorkerEnabled	Examples: - true - false	true		No	boolean
numberOfWorkers	To specify the number of Workers	10		No	integer
elastic	Default elastic shard and replica configuration for fluentd created indices			No	object
resources	resource requirements for pod			No	object

[pod-fluentd_operator](#) fluentd elastic

Description

Default elastic shard and replica configuration for fluentd created indices

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
shards	Shards: Buckets which Elasticsearch maintains per index. Default values is 5. More shards are better for greater distribution, faster indexing and searching data, but with some maintenance overhead	5		No	integer
replicas	Replica: Duplicate index/data/shard maintained by Elasticsearch for HA and redundancy. A values of 1 means, ES would maintain 1 duplicate copy of the data in a different node (need to have sufficient data nodes). This comes with the storage tradeoff as double storage is needed to maintain the duplicate copy. The storage size of the data nodes in fed-elastic values file must be changed accordingly, if this value is changed	0		No	integer

pod-fluentd_operator fluentd resources

Description

resource requirements for pod

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
limits	Resource limit			No	object
requests	Request resource			No	object

pod-fluentd_operator fluentd resources limits

Description

Resource limit

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	Resource cpu limit	4		No	string
memory	Resource memory limit	6Gi		No	string

pod-fluentd_operator fluentd resources requests

Description

Request resource

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	Request cpu	1500m		No	string
memory	Request memory	2Gi		No	string

pod-fluentd_operator closeWaitCleanup

Description

Clean-up the close-wait sockets. Applicable only for additional targets apart from elastic.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	To specify whether Close-wait clean-up should be Enabled/Disabled				
	Examples:				
	- true	true		No	boolean
	- false				
scheduleJob	To specify the cronjob scheduling expression. By default cronjob runs once daily at midnight	"0 0 * * *		No	string
sleepDuration	To specify within the Job script will sleep for 120 seconds before killing the next PID	120		No	integer

pod-fluentd_operator livenessProbe

Description

liveness health check for fluentd

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
failureThreshold	When a probe fails, Kubernetes will try failureThreshold times before giving up	5		No	integer
initialDelaySeconds	Number of seconds after the container has started before liveness probe is initiated.	180		No	integer

Parameter	Description	Default	Value/Range	Mandatory	Type
periodSeconds	How often (in seconds) to perform the probe. Minimum value is 1	60		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer
timeoutSeconds	Number of seconds after which the probe times out	15		No	integer

pod-fluentd_operator tolerations

Description

fluentd pod tolerations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
effect	Effect of the toleration	NoSchedule		No	string
key	The taint which needs to be tolerated	node-role.kubernetes.io/control-plane		No	string

pod-k8s_event_logger

Description

pod-k8s_event_logger related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	enable to deploy Kubernetes event exporter. To visualise kubernetes event logs, Set logging.elastic.IP				
enabled	Examples: - true - false	true		No	boolean

pod-cert_manager

Description

pod-cert_manager Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/Disable Flag				
enabled	Examples: - true - false	true		No	boolean
issuerTypes	Issuer Types			No	object
	rbacEnabled true will create the upstream rbac				
rbacEnabled	Examples: - true - false	true		No	boolean
serviceAccount	Service-Account related Configuration			No	object

pod-cert_manager issuerTypes

Description

Issuer Types

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ca	ca related configuration			No	object
hashicorpVault	Hashicorp Vault PKI related configuration			No	object

pod-cert_manager issuerTypes ca

Description

ca related configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable flag	true		No	boolean
	Examples:				
	- true				
	- false				
issuerName	Issuer Name	affirmed-clusterissuer		No	string
crlDistributionPoints	crlDistributionPoints			No	string
	Examples:				
	-				
userProvided	User-Provided			No	object
userProvidedVault	User Provided CA Certificates stored in Azure KV			No	object

pod-cert_manager issuerTypes ca userProvided

Description

User-Provided

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	To specify whether userProvided has to be Enabled/Disabled	true		No	boolean
	Examples:				
	- false				
	- true				
rootCa	rootCa			No	object

pod-cert_manager issuerTypes ca userProvided rootCa

Description

rootCa

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
tls crt	tls crt configuration in plain text, i.e., without base64 encoding			No	string
	Examples:				
	- Copy and Paste End User generated Certificate				
tls key	tls key Configuration in plain text, i.e., without base64 encoding			No	string
	Examples:				
	- Copy and Paste End User generated Certificate				

pod-cert_manager issuerTypes ca userProvidedVault

Description

User Provided CA Certificates stored in Azure KV

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	To specify whether userProvidedVault has to be Enabled/Disabled	false		No	boolean
	Examples:				
	- false				
	- true				

pod-cert_manager issuerTypes hashicorpVault

Description

Hashicorp Vault PKI related configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable flag	false		No	boolean
	Examples:				
	- true				
	- false				
serviceAccount	ServiceAccount used by cert-manager for secretless authentication to Vault	vault-issuer		No	string
	Examples:				
	- vault-issuer				
namespace	Namespace on Hasicorp Vault for multi-tenancy support			No	string
	Examples:				
	- 5GMobility				
issuers	Hashicorp Vault Issuer configuration			No	array

pod-cert_manager issuerTypes vault issuers

Description

Hashicorp Vault Issuer configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
issuerName	cert-manager cluster issuer name	affirmed-clusterissuer		No	string
pkiPath	PKI path on Hashicorp Vault for issuing certificate			No	string
	Examples:				
	- pki/sign/alldomain-dot-com				
	- pki/test/private/int/sign/5g.private				
jwtRole	JWT role used by cert-manager for issuing certificate			No	string
	Examples:				
	- uc-cert-issuer-role				

Parameter	Description	Default	Value/Range	Mandatory	Type
	JWT Authentication path configured on Hashicorp Vault				
jwtMountPath	Examples: - /v1/auth/jwt			No	string

pod-cert_manager serviceAccount

Description

Service-Account related Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Specifies whether a service account should be created				
create	Examples: - true - false	true		No	boolean
	The name of the service account to use. If not set and create is true, a name is generated using the fullname template.				
name	Examples: - cert-manager-sa	cert-manager-sa		No	string

pod-istio_config

Description

pod-istio_config related Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Configuring rbacEnabled to true will create custom clusterrole, clusterrolebinding for jaeger-agent. Configuring rbacEnabled to false, clusterrole, clusterrolebinding will not be created.				
rbacEnabled	Examples: - true - false	true		No	boolean
	serviceAccountName configuration is used to create serviceaccount for jaeger-agent				
serviceAccountName	Examples: - istio-config-controller-sa	istio-config-controller-sa		No	string

pod-capture_mgr

Description

pod-capture_mgr related Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Specifies whether rbac should be Enabled/Disabled	true		No	boolean
	Examples:				
	- true - false				
rbacEnabled	Configuring rbacEnabled to true will create custom clusterrole, clusterrolebinding for jaeger-agent. Configuring rbacEnabled to false, clusterrole, clusterrolebinding will not be created.	true		No	boolean
	Examples:				
	- true - false				
serviceAccountName	serviceAccountName configuration is used to create serviceaccount for jaeger-agent	istio-config-controller-sa		No	string
	Examples:				
	- istio-config-controller-sa				

pod-capture_ss

Description

pod-capture_ss related Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Specifies whether rbac should be Enabled/Disabled	true		No	boolean
	Examples:				
	- true - false				

pod-udsf_mgmt_op

Description

Configuration for managing operations on the UDSF pod

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
udsfMetaSchemaConfig	Configuration for the UDSF meta-schema			No	object

[pod-udsf_mgmt_op](#) [udsfMetaSchemaConfig](#)

Description

Configuration for the UDSF meta-schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
hostToConfigMapping	For a redis cluster provide the : mapping. This field shows that redis cluster for the given is deployed on namespace and has a metaschema config map with name . This to provide the udsf_mgmt_operator with information about different redis instances and their configurations			No	object

[pod-udsf_mgmt_op](#) [udsfMetaSchemaConfig](#) [hostToConfigMapping](#)

Description

For a redis cluster provide the : mapping. This field shows that redis cluster for the given is deployed on namespace and has a metaschema config map with name . This to provide the udsf_mgmt_operator with information about different redis instances and their configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

pod-kargo

Description

pod-kargo related configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service	Service related configurations			No	object
logLevel	Log-level	info		No	string
cleaner	Garbage collector related configurations			No	object
resources	Resources related configurations			No	object
storage	Storage option to store kargo tar files			No	object
readinessProbe	Readiness probe ensures that traffic is only routed when the pods are ready			No	object
livenessProbe	Liveliness probe to detect and redeem broken state of the pod by restarting them			No	object

[pod-kargo service](#)

Description

Service related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
port	Port Configuration	5555		No	integer
loadBalancerIP	Load-Balancer IP			No	string
	Examples:				
	-				
serviceAnnotations	Service annotations			No	object
loadBalancerFQDN	Load-Balancer FQDN			No	string
	Examples:				
	-				
loadBalancerSharingKey	Load-Balancer			No	string
	Examples:	paas			
	- paas				

[pod-kargo service](#) [servicaAnnotations](#)

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

[pod-kargo cleaner](#)

Description

Garbage collector related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable garbage collector	true		No	boolean
retentionTime	Duration for which a file is not deleted by garbage collector	3h		No	string
retentionSizeGB	Size limit of kargo files directory after which old files get deleted by garbage collector	40		No	integer

pod-kargo resources

Description

Resources related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
limits	Set limits for CPU and memory			No	object
requests	Set requests for CPU and memory			No	object

pod-kargo resources limits

Description

Set limits for CPU and memory

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	Set the CPU limit for kargo pod	2		No	string
memory	Set the memory limit for kargo pod	8Gi		No	string

pod-kargo resources requests

Description

Set requests for CPU and memory

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	Set the CPU request for kargo pod	100m		No	string
memory	Set the memory request for kargo pod	100Mi		No	string

pod-kargo storage

Description

Storage option to store kargo tar files

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
type	Three storage type can be configured. Those are emptyDir, nfs, remote or rook	emptyDir		No	string
storageClassName	Set any convenient value Storage class name if stoare type is local or remote. But if storage type is rook, mandatorily set it to the storage class name of File system storage that gets deployed with fed-rook-ceph. Default value is rook-cephfs	kargo-vol		No	string
storageSize	A storageaize limit of your storage	5Gi		No	string
provisioner	External Storage provisioner. Configure this field only if storage type is remote. Any file system storage provisioner can be configured.			No	string
reclaimPolicy	PersistentVolumes that are dynamically created by a StorageClass will have the reclaim policy specified in the reclaimPolicy field	Delete		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
parameters	External storage specific parameters. By default azure-file parameters are given. Any other key/value pair can be configured by modifying values.yaml			No	object

[pod-kargo storage parameters](#)

Description

External storage specific parameters. By default azure-file parameters are given. Any other key/value pair can be configured by modifying values.yaml

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
customParameters	Both key/value pair can be configured. Since any filesystem type provisioner can be configured, it's corresponding parameters can be set under this section. By default azure-file parameters are given			No	object

[pod-kargo storage parameters customParameters](#)

Description

Both key/value pair can be configured. Since any filesystem type provisioner can be configured, it's corresponding parameters can be set under this section. By default azure-file parameters are given

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
skuName	Azure storage account Sku tier. Default is empty			No	string
location	Azure storage account location. Default is empty.			No	string
storageAccount	Azure storage account name. Default is empty. If a storage account is not provided, all storage accounts associated with the resource group are searched to find one that matches skuName and location			No	string

[pod-kargo readinessProbe](#)

Description

Readiness probe ensures that traffic is only routed when the pods are ready

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
failureThreshold	When a probe fails, Kubernetes will try failureThreshold times before giving up	5		No	integer
initialDelaySeconds	Number of seconds after the container has started before liveness or readiness probes are initiated. Defaults to 0 seconds	20		No	integer
periodSeconds	How often (in seconds) to perform the probe. Minimum value is 1.	60		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer
timeoutSeconds	Number of seconds after which the probe times out. Defaults to 1 second.	10		No	integer

[pod-kargo livenessProbe](#)

Description

Liveness probe to detect and redeem broken state of the pod by restarting them

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
failureThreshold	When a probe fails, Kubernetes will try failureThreshold times before giving up	5		No	integer
initialDelaySeconds	Number of seconds after the container has started before liveness or readiness probes are initiated. Defaults to 0 seconds	30		No	integer
periodSeconds	How often (in seconds) to perform the probe. Default to 10 seconds. Minimum value is 1.	60		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer

Parameter	Description	Default	Value/Range	Mandatory	Type
timeoutSeconds	Number of seconds after which the probe times out. Defaults to 1 second.	10		No	integer

pod-elastalert_cfg

Description

Pod-elastalert-parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
deployment	Deployment configuration			No	object
livenessProbe	Liveliness probe to detect and redeem broken state of the pod by restarting those pods.			No	object

pod-elastalert_cfg deployment

Description

Deployment configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	default value is 1, please configure to 3 or more for HA Mode	1		No	integer

pod-elastalert_cfg livenessProbe

Description

Liveliness probe to detect and redeem broken state of the pod by restarting those pods.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
initialDelaySeconds	Number of seconds after the container has started before liveness probes are initiated. Defaults to 0 seconds	20		No	integer
periodSeconds	How often (in seconds) to perform the probe. Default to 10 seconds. Minimum value is 1	30		No	integer
timeoutSeconds	Number of seconds after which the probe times out.	30		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer
failureThreshold	When the probe fails, Kubernetes will try failureThreshold times before giving up	10		No	integer

pod-cores_mgr

Description

pod-cores_mgr related configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Specifies whether the cores mgr pod will be created or not	true		No	boolean
	Examples:				
	- true - false				
kargoHTTPReqTimeout	Specifies the time(in seconds) after which connection with kargo server should be closed when calling kargo collect from cores-mgr	30		No	integer
	Examples: - 60				

Parameter	Description	Default	Value/Range	Mandatory	Type
rbacEnabled	Specifies whether rbac needs to be enabled for cores-mgr. Configuring rbacEnabled to false results in clusterrole, clusterrolebinding not getting created for the cores-mgr. Ensure that a valid serviceAccountName is configured for the cores-mgr functionality when rbacEnabled is set to false. Examples: - true - false	true		No	boolean
serviceAccountName	serviceAccountName configuration is used to create serviceaccount for cores-mgr	cores-mgr-sa		No	string
retentionPeriod	Defines the time period in seconds for which a generated core file is stored on the persistent storage before it is discarded to free up the storage space. Retention period of 0 seconds indicate that there is no time limit for a given core file for its presence. Examples: - 0	0		No	integer
retentionSize	Maximum size in bytes the stored core files on the persistent storage can consume before the retention policy is applied on them to free up the storage space. The type of retention policy is defined by the retentionPolicy parameter configuration. Retention size of -1 indicates that the management of the core files based on the consumed storage size is disabled. Examples: - 4294967296	-1		No	integer
retentionPolicy	This parameter defines when the retention size is reached, whether the oldest core files should be deleted or the newest to free up the storage space. Examples: - OLDEST - NEWEST	OLDEST		No	string
coresSourcePath	Defines the path on each K8s worker node where the ELF core files are generated when an application crashes. Examples: - /tmp	/var/local/tmp		No	string
coresUtilSourcePath	Defines the path on each K8s worker node where the cores generation utility, which will be used in the kernel core_pattern file, needs to be placed. Examples: - /bin	/bin		No	string
coresStorage	Defines the parameters for storage configuration related to the persistent storage used by cores-mgr to save the generated core files.			No	object
resources	Cores Mgr Resources Configuration			No	object

pod-cores_mgr coresStorage

Description

Defines the parameters for storage configuration related to the persistent storage used by cores-mgr to save the generated core files.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
type	Type of persistent filesystem storage for saving the generated core files. Supported types are nfs or any persistent volume type which supports dynamic provisioning through storage class				
	Examples:	nfs		No	string
	- nfs - rook-ceph				
storageClassName	Name of the storage class used by cores-mgr for the persistent storage.	cores-mgr-storage		No	string
requestStorage	The amount of storage allocated for the persistent storage to save the core files				
	Examples:	5Gi		No	string
	- 5Gi				
nfs	Defines the parameters related to NFS persistent volume			No	object

pod-cores_mgr coresStorage nfs

Description

Defines the parameters related to NFS persistent volume

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
capacityStorage	The amount of storage allocated to this volume.				
	Examples:	5Gi		No	string
	- 25Gi				
coresPath	The path that is exported by the NFS server.				
	Examples:	/filestore		No	string
	- /filestore				
remoteHost	The host name or IP address of the NFS server.				
	Examples:			No	string
	- 10.163.66.215				

pod-cores_mgr resources

Description

Cores Mgr Resources Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
limits	Configuration related to resource limits.				
	Examples:			No	object
	- OrderedDict({'cpu': '200m'})				

pod-cores_mgr resources limits

Description

Configuration related to resource limits.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
CPU Resource Limits.					
cpu	Examples: - 200m	200m		No	string

pod-oauth2_proxy

Description

pod-oauth2_proxy related configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
oauth2proxy	Oauth2 Proxy Configuration			No	object

[pod-oauth2_proxy](#) [oauth2proxy](#)

Description

Oauth2 Proxy Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
OIDC Issuer URL					
oidcIssuerUrl	Examples: - https: //accounts.google.com			No	string
OIDC Authorize URL					
oidcAuthorizeUrl	Examples: - https: //accounts.google.com/o/oauth2/auth			No	string
OIDC User Info URL					
oidcUserInfoUrl	Examples: - https: //accounts.google.com/o/oauth2/userinfo			No	string
OIDC Token URL					
oidcTokenUrl	Examples: - https: //accounts.google.com/o/oauth2/token			No	string
The time after which the 'cookie' will expire. The default value is '0' which means that the cookie will be a 'session-cookie' which will expire when the browser is closed. In case it's not required for the session to expire on browser close, then please set it to a non-zero value. The recommendation is to set this to the IDP's (e.g., Halo-E) 'Refresh-Token lifespan'					
Examples:					
cookieExpire	- 0 means no-expiry and it will be a session-cookie - 2h3m4s - 3h - 50m - 5s	0		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
cookieRefresh	OAuth2-proxy tries to refresh an Access-Token after this duration. The recommendation is to set this to the IDP's (e.g., Halo-E) 'Access-Token lifespan - 1m'				
	Examples:				
	- 2h3m4s	59m		No	string
	- 3h				
	- 50m				
	- 5s				

Prometheus Helm Documentation

fed-prometheus values

Contents

- [Global Parameters](#)
- [Istio Gateway Parameters](#)
- [Pod-prometheus parameters](#)

global

Description

Global Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
metricsScrapeInterval	Metrics scrape interval in ServiceMonitors. Setting a lower value would result in faster refreshes of metrics at the cost of more overhead for both prometheus and the application.	1m		No	string
defaultRbacEnabled	Default RBAC flag				
	Examples:				
	- false	false		No	boolean
	- true				
enableSCC	If running on OCP cluster, please set enableSCC to true	false		No	boolean
authType	Authentication type for prometheus	haloe		No	string
upgradeOrder	upgradeOrder with possible values of end or default.	default		No	string
kargoProfileTag	This enables creation of specific kargo-default-profile for fed-prometheus			No	string
ingressNetworkPolicy	network policies configuration			No	object
deployment	Deployment			No	object
logging	PaaS logging association			No	object
istio	Istio related configurations			No	object
mesh	Istio mesh configuration			No	object
grafana	PaaS Grafana association			No	object
monitoring	PaaS Monitoring associations			No	object
registry	PaaS registry associations			No	object
envVars	Environment variables			No	object
loadBalancerSourceRanges	loadBalancerSourceRanges			No	string
overrides	overrides			No	object

[global](#) ingressNetworkPolicy

Description

network policies configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabled network policy	true		No	boolean
ingressTrafficNamespaces	Namespaces which are required to be allowed for ingress traffic			No	array

global deployment

Description

Deployment

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable node affinity				
	Examples:				
nodeDataplaneAffinity	- false	false		No	string
	- true				

global logging

Description

PaaS logging association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable logging association				
	Examples:				
enabled	- false	false		No	boolean
	- true				
fluentd	Fluentd-Configurations			No	object
elastic	Elasticsearch association			No	object
enableAddlTargets	Enable/disable additional destinations	false		No	boolean
addlTargets	Additional logging output destination configuration			No	array
alerts	Elastalert association			No	object

global logging fluentd

Description

Fluentd-Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	Fluentd-Buffer Configurations			No	object

global logging fluentd buffer

Description

Fluentd-Buffer Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Total buffer size. Maximum amount of buffer space each fluentd thread would use to keep logs. After this space is exhausted, fluentd would start deleting oldest logs to make room for new logs.	32m		No	string
retryWait	Interval(seconds) at which the buffer flush is retried in case of failure.	10s		No	string
maxRetries	Max number of retries to flush a buffer chunk. After this is exhausted, fluentd would delete the chunk.	1		No	integer

global logging elastic

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Elasticsearch IP address				
ip	Examples: - 10.15.16.64			No	string
Port	Elasticsearch port	9200		No	integer

global logging addITargets

Description

Additional logging output destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			No	object

global logging addITargets forward

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
host	Hostname or IP Address of the forward server for sending logs to additional targets in parallel with elastic			No	string
port	Port of the forward server	24224		No	integer

global logging alerts

Description

Elastalert association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable event based alerts				
enabled	Examples: - false - true	false		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
host	Elastalert IP address				
	Examples:			No	string
	- 10.15.16.64				
port	Elastalert port number	3030		No	integer
realert	Alerts will be repeated after the realert duration			No	object
receivers	The platform on which alerts can be sent			No	array

global logging alerts realert

Description

Alerts will be repeated after the realert duration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minutes	An explanation about the purpose of this instance.	1		No	integer

global logging alerts receivers

Description

The platform on which alerts can be sent

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
slack	Slack channel			No	object
post	Configuration for HTTP post			No	object
email	Configuration for email receiver			No	object

global logging alerts receivers slack

Description

Slack channel

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
webhookurl	Webhook url of the receiver slack channel			No	string

global logging alerts receivers post

Description

Configuration for HTTP post

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
http_post_url	HTTP post URL			No	string

global logging alerts receivers email

Description

Configuration for email receiver

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
to_address	Receiver email address			No	string
smtp_host	The smtp host ip			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
smtp_port	The smtp port number			No	string
smtp_ssl	This should be disabled	false		No	boolean
from_addr	Sender address			No	string

global istio

Description

Istio related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtls	Istio mutual TLS related configuration			No	object

global istio mtls

Description

Istio mutual TLS related configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable istio mutual TLS	false		No	boolean

global mesh

Description

Istio mesh configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio configuration			No	object

global mesh istio

Description

Istio configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtlsEnabled	Enable/disable istio mutual TLS	false		No	boolean
ingressGwIP	Istio ingress gateway IP Examples: -			No	string
ingressGwFQDN	Istio ingress gateway FQDN Examples: - thanos.com	thanos.com		No	string
ingressSvcLabel	Istio ingress gateway service label for thanos Examples: - thanos	thanos		No	string
ingressGwPort	Istio ingress gateway service port	9090		No	integer
ingressGwTLS	Istio ingress gateway TLS			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGwAdditionalServices	Ingress Gw Additional Services				
	Examples: - [OrderedDict({'ingressGwIP': '', 'ingressGwFQDN': 'alertmanager.com', 'ingressGw': 'alertmanager-ingress', 'ingressGwPort': 9091, 'mtlsEnabled': False, 'ingressGwTLS': OrderedDict({'enabled': True, 'mode': 'SIMPLE'}), 'serviceAnnotations': OrderedDict({'service.beta.kubernetes.io/azure-load-balancer-internal': 'true', 'service.beta.kubernetes.io/azure-load-balancer-internal-subnet': 'none'})}), OrderedDict({'ingressGwIP': '', 'ingressGwFQDN': 'thanos-federate.com', 'ingressGw': 'thanos-federate-ingress', 'ingressGwPort': 9099, 'mtlsEnabled': False, 'ingressGwTLS': OrderedDict({'enabled': True, 'mode': 'SIMPLE'}), 'serviceAnnotations': OrderedDict({'service.beta.kubernetes.io/azure-load-balancer-internal': 'true', 'service.beta.kubernetes.io/azure-load-balancer-internal-subnet': 'none'})})]		No	array	
loadBalancerSharingKey	Istio ingress gateway service loadbalancer sharing key. Examples: - kube_prom	kube_prom		No	string
serviceAnnotations	Service Annotations			No	object

global mesh istio ingressGwTLS

Description

Istio ingress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio ingress gateway TLS				
	Examples: - true - false	true		No	boolean
mode	Istio ingress gateway TLS mode.				
	Examples: - SIMPLE	SIMPLE		No	string
certManager	certManager Configuration			No	object
userProvided	userProvided CERTIFICATES			No	object

global mesh istio ingressGwTLS certManager

Description

certManager Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for certManager configuration				
	Examples: - true - false	true		No	boolean
certDuration	certDuration Configuration	10h		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
renewBefore	renewBefore Configuration	1h		No	string
	organization Configuration				
organization	Examples: - affirmednetworks	affirmednetworks		No	string
	issuerName				
issuerName	Examples: - affirmed-clusterissuer	affirmed-clusterissuer		No	string
	issuerType				
issuerType	Examples: -			No	string
	Algorithm for PKI certs -RSA or ECDSA				
pkiAlgorithm	Examples: - RSA - ECDSA	RSA		No	string
	PKI Key size for certs, if Alogirthm is RSA, valid inputs are 2048,4096,8192. If Alogrithm is ECDSA, valid input is 256				
pkiKeySize	Examples: - 256 - 2048 - 4096 - 8192	4096		No	string

global mesh istio ingressGwTLS userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/Disable Flag for userProvided Certificates				
enabled	Examples: - false - true	false		No	boolean
	cacert Configuration				
cacert	Examples: - Copy and Paste End User generated Certificate			No	string
	tlsctx configuration				
tlsctx	Examples: - Copy and Paste End User generated Certificate			No	string
	tlskey configuration				
tlskey	Examples: - Copy and Paste End User generated Certificate			No	string

global mesh istio ingressGwAdditionalServices

Description

Ingress Gw Additional Services

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Array element				
	Examples: - OrderedDict({'ingressGwIP': '', 'ingressGwFQDN': 'alertmanager.com', 'ingressGw': 'alertmanager-ingress', 'ingressGwPort': 9091, 'mtlsEnabled': False, 'ingressGwTLS': OrderedDict({'enabled': True, 'mode': 'SIMPLE'}), 'serviceAnnotations': OrderedDict({'service.beta.kubernetes.io/azure-load-balancer-internal': 'true', 'service.beta.kubernetes.io/azure-load-balancer-internal-subnet': 'none'})})			No	object
1	Array element				
	Examples: - OrderedDict({'ingressGwIP': '', 'ingressGwFQDN': 'thanos-federate.com', 'ingressGw': 'thanos-federate-ingress', 'ingressGwPort': 9099, 'mtlsEnabled': False, 'ingressGwTLS': OrderedDict({'enabled': True, 'mode': 'SIMPLE'}), 'serviceAnnotations': OrderedDict({'service.beta.kubernetes.io/azure-load-balancer-internal': 'true', 'service.beta.kubernetes.io/azure-load-balancer-internal-subnet': 'none'})})			No	object

global mesh istio ingressGwAdditionalServices 0

Description

Array element

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGwIP	Ingress Gw IP				
	Examples: -			No	string
ingressGwFQDN	The ingress Gw FQDN				
	Examples: - alertmanager.com	alertmanager.com		No	string
ingressGw	Ingress gateway name				
	Examples: - alertmanager-ingress	alertmanager-ingress		No	string
ingressSvcLabel	The ingress Gw service label for alertmanager				
	Examples: - alertmanager	alertmanager		No	string
ingressGwPort	The ingress Gw Port.				
	Examples: - 9091	9091		No	integer
mtlsEnabled	MTLS flag.				
	Examples: - false	false		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGwTLS	Ingress gateway TLS.				
	Examples:			No	object
	- OrderedDict({'enabled': True, 'mode': 'SIMPLE'})				
serviceAnnotations	Service Annotations				
	Examples:			No	object
	- OrderedDict({'service.beta.kubernetes.io/azure-load-balancer-internal': 'true', 'service.beta.kubernetes.io/azure-load-balancer-internal-subnet': 'none'})				

global mesh istio ingressGwAdditionalServices 0 ingressGwTLS

Description

Ingress gateway TLS.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Ingress Gateway TLS flag.				
	Examples:	false		No	boolean
	- true				
mode	Ingress Gw TLS mode.				
	Examples:			No	string
	- SIMPLE				

global mesh istio ingressGwAdditionalServices 0 serviceAnnotations

Description

Service Annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	Azure Loadbalancer Internal	true		No	string
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Azure Loadbalancer Internal subnet	none		No	string

global mesh istio ingressGwAdditionalServices 0

Description

Array element

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGwIP	Ingress Gw IP				
	Examples:			No	string
	-				
ingressGwFQDN	The ingress Gw FQDN				
	Examples:	thanos-federate.com		No	string
	- thanos-federate.com				

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGw	Ingress gateway name				
	Examples:	thanos-federate-ingress		No	string
	- thanos-federate-ingress				
ingressSvcLabel	The ingress Gw service label for thanos federate				
	Examples:	thanos-federate-svc		No	string
	- thanos-federate-svc				
ingressGwPort	The ingress Gw Port.				
	Examples:	9099		No	integer
	- 9099				
mtlsEnabled	MTLS flag.				
	Examples:	false		No	boolean
	- false				
ingressGwTLS	Ingress gateway TLS.				
	Examples:			No	object
	- OrderedDict({'enabled': True, 'mode': 'SIMPLE'})				
serviceAnnotations	Service Annotations				
	Examples:			No	object
	- OrderedDict({'service.beta.kubernetes.io/azure-load-balancer-internal': 'true', 'service.beta.kubernetes.io/azure-load-balancer-internal-subnet': 'none'})				

global mesh istio ingressGwAdditionalServices 0 ingressGwTLS

Description

Ingress gateway TLS.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Ingress Gateway TLS flag.				
	Examples:	false		No	boolean
	- true				
mode	Ingress Gw TLS mode.				
	Examples:			No	string
	- SIMPLE				

global mesh istio ingressGwAdditionalServices 0 serviceAnnotations

Description

Service Annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	Azure Loadbalancer Internal	true		No	string
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Azure Loadbalancer Internal subnet	none		No	string

global mesh istio serviceAnnotations

Description

Service Annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal	Azure Load-Balancer Internal	true		No	string
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Azure Load-Balancer Internal subnet	none		No	string

global grafana

Description

PaaS Grafana association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association	true		No	boolean
url	Exposed grafana URL				
	Examples:			No	string
	- http: //1.1.1.1:3000				
prometheusinfo	Prometheus server association			No	object

global grafana prometheusinfo

Description

Prometheus server association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
url	Prometheus server URL				
	Examples:	http: //prometheus.fed-prometheus:9090		No	string
	- http: //prometheus.fed-prometheus:9090				

global monitoring

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association			No	object

global monitoring prometheus

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable prometheus monitoring	true		No	boolean

global registry

Description

PaaS registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

[global registry](#) **docker**

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string
imagePullSecret	Pull an image from a private registry			No	string
username	Username for private docker registry			No	string
password	Password for private docker registry			No	string

[global envVars](#)

Description

Environment variables

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Federation type				
fedType	Examples: - paas	paas		No	string
	Federation unique name				
fedUniqueName	Examples: - prometheus-default	prometheus-default		No	string

[global overrides](#)

Description

overrides

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	preDeleteEnabled				
preDeleteEnabled	Examples: - false - true	false		No	boolean
	postInstalEnabled				
postInstallEnabled	Examples: - false - true	false		No	boolean

pod-istio_gw

Description

Istio Gateway microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable istio-gw	true		No	boolean
	Examples:				
	- false				
istioNspace	Istio namespace	fed-istio		No	string
	Examples:				
	- fed-istio				
ingressGateway	Ingress gateway parameters			No	object
egressGateway	Egress gateway parameters			No	object
paasSelector	PAAS parameters			No	object

[pod-istio_gw](#) ingressGateway

Description

Ingress gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable ingress gateway	true		No	boolean
	Examples:				
	- false				
ingressGatewayServiceAccountName	Ingress gateway service account name	istio-ingressgateway-service-account		No	string
	Examples:				
	- istio-ingressgateway-service-account				

[pod-istio_gw](#) egressGateway

Description

Egress gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable egress gateway	true		No	boolean
	Examples:				
	- false				
egressGatewayServiceAccountName	Egress gateway service account name	istio-egressgateway-service-account		No	string
	Examples:				
	- istio-egressgateway-service-account				

[pod-istio_gw](#) paasSelector

Description

PAAS parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
	Jaeger host (IP or FQDN)				
	Examples:				
jaegerHostName	- 10.10.10.10	fqdn.com		No	string
	- fqdn.com				

pod-prometheus

Description

Pod-prometheus parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rbacEnabled	Configuring rbacEnabled to true will create psp, clusterrole and clusterrolebinding. Configure rbacEnabled to false, pods will not come up Examples: - true - false	true		No	boolean
serviceAccountNameOperator	serviceAccountName configuration is used to create serviceaccount per pod.	prometheus-operator-serviceaccount		No	string
serviceAccountNamePrometheus	serviceAccountName configuration is used to create serviceaccount per pod.	prometheus-serviceaccount		No	string
serviceAccountNameAlertmanager	serviceAccountName configuration is used to create serviceaccount per pod.	alertmanager-serviceaccount		No	string
serviceAccountNameThanos	serviceAccountName configuration is used to create serviceaccount per pod.	thanos-serviceaccount		No	string
config	Alertmanager Configuration parameters			No	object
name	prometheus Name Examples: - prometheus	prometheus		No	string
alertmanagerName	Alert Manager Name Examples: - prometheus-alerts	prometheus-alerts		No	string
serviceMonitor	Service monitor			No	object
prometheus	Prometheus Storage Configurations			No	object
thanosQuery	Thanos Query			No	object
thanos	Enable or Disable Thanos			No	object
probesCheck	Liveliness and Readiness Probe Checks for Prometheus, Alertmanager and Thanos			No	object
httpAlertsThreshold	Threshold configuration for HTTP metric based alerts			No	object
ao5GCBasic	Centralized Prometheus for aggregating and monitoring several clusters			No	object
promDataPurger	Prometheus metrics data purger			No	object

[pod-prometheus config](#)

Description

Alertmanager Configuration parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
global	global scoped configurations			No	object
route	A route block defines a node in a routing tree and its children. Its optional configuration parameters are inherited from its parent node if not set.			No	object
receivers	Alert Reciever configuration			No	array

pod-prometheus config global

Description

global scoped configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	resolve_timeout				
resolve_timeout	Examples: - 5m	5m		No	string

pod-prometheus config route

Description

A route block defines a node in a routing tree and its children. Its optional configuration parameters are inherited from its parent node if not set.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
group_wait	How long to initially wait to send a notification for a group of alerts	30s		No	string
group_interval	Duration of time to wait to send notification for the alerts that are already added	2m		No	string
repeat_interval	Duration of time to wait, before sending the notification again	2m		No	string
receiver	Provide receiver name to send alerts to, slackreceiver for slack, emailreceiver for email, postreceiver for HTTP POST	null		No	string

pod-prometheus config receivers

Description

Alert Reciever configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Default Null receiver			No	object
1	HTTP POST receiver			No	object
2	Add Email receiver			No	object
3	Add slack receiver			No	object

pod-prometheus config receivers 0

Description

Default Null receiver

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Default Null receiver	null		No	string

pod-prometheus config receivers 1

Description

HTTP POST receiver

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Add a name to the HTTP POST webhook receiver				
name	Examples: - postreceiver	postreceiver		No	string
webhook_configs	Configure Webhook			No	array

pod-prometheus config receivers 1 [webhook_configs](#)

Description

Configure Webhook

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Configure Webhook			No	object

pod-prometheus config receivers 1 [webhook_configs](#) [0](#)

Description

Configure Webhook

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Reciever webhook				
url	Examples: - http: //XXXX	http: //XXXX		No	string
http_config	HTTP Configuration			No	object

pod-prometheus config receivers 1 [webhook_configs](#) [0](#) [http_config](#)

Description

HTTP Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
tls_config	TLS configuration			No	object

pod-prometheus config receivers 1 [webhook_configs](#) [0](#) [http_config](#) [tls_config](#)

Description

TLS configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	skip tls verify flag				
insecure_skip_verify	Examples: - true - false	true		No	boolean

pod-prometheus config receivers 2

Description

Add Email receiver

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Add a name to the email receiver					
name	Examples: - emailreceiver	emailreceiver		No	string
email_configs	Provide required email details			No	array

pod-prometheus config receivers 2 email_configs

Description

Provide required email details

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Provide email configurations			No	object

pod-prometheus config receivers 2 email_configs 0

Description

Provide email configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Email To address					
to	Examples: - user1@example.com	user1@example.com		No	string
Email From address					
from	Examples: - user2@example.com	user2@example.com		No	string
Mail server IP along with the port					
smarthost	Examples: - XXXX:80	XXXX:80		No	string
Mail server authentication Username					
auth_username	Examples: - user@example.com	user@example.com		No	string
Mail server authentication password					
auth_password	Examples: - password	password		No	string
enable/disable TLS authentication					
require_tls	Examples: - false	false		No	boolean
headers	Email header section			No	object

pod-prometheus config receivers 2 email_configs 0 headers

Description

Email header section

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Subject	Add subject to the mail	Alert from: {{ .CommonLabels.alertname }}		No	string

pod-prometheus config receivers 3

Description

Add slack receiver

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Add a name to the slack receiver				
name	Examples: - slackreceiver	slackreceiver		No	string
slack_configs	Slack configurations			No	array

pod-prometheus config receivers 3 slack_configs

Description

Slack configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Add slack configuration			No	object

pod-prometheus config receivers 3 slack_configs 0

Description

Add slack configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Name of the slack channel				
channel	Examples: - #channel_name	#channel_name		No	string
api_url	Provide webhook url	http: //XXXX		No	string
text	Add message text.	summary: {{ .CommonAnnotations.summary }}			
description: {{ .CommonAnnotations.description }}		No			string
title	Add title for the slack message	Alert from: {{ .CommonLabels.alertname }}		No	string

pod-prometheus serviceMonitor

Description

Service monitor

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
	istio Namespace				
istioNamespace	Examples: - fed-istio	fed-istio		No	string

pod-prometheus prometheus

Description

Prometheus Storage Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
storage	Storage			No	object
remoteStorage	remoteStorage			No	object
	Retention period for prometheus scraped data				
retention	Examples: - 3d	3d		No	string
	Enable Admin API				
enableAdminAPI	Examples: - false - true	false		No	boolean
	Number of replicas of prometheus pods				
replicas	Examples: - 2	2		No	integer
	Number of shards of prometheus pods				
shards	Examples: - 2	1		No	integer
topologySpreadConstraints	Pod Topology Spread Constraints			No	object
resources	resource requirements			No	object

pod-prometheus prometheus storage

Description

Storage

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Three storage type can be configured. Those are local, remote or rook.				
	Examples:				
type	- local - remote - rook			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
storageClassName	currently supported external storages are cinder, AzureDisk and rook-ceph.				
	Examples:				
	- cinder-class	cinder-class		No	string
provisioner	- azure-disk				
	- rook-cephbp				
	External storage provisioner. See example for available storage provisioners. If any other storage provisioner is set other than cinder and azure-disk. Then set that provisioner's parameters under customParameters.				
provisioner	Examples:	kubernetes.io/cinder		No	string
	- kubernetes.io/cinder				
	- kubernetes.io/azure-disk				
parameters	External storage specific parameters. To deploy federation with external storage other than cinder, provide configuration in values.yaml and deploy it.			No	object
reclaimPolicy	PersistentVolumes that are dynamically created by a StorageClass will have the reclaim policy specified in the reclaimPolicy field				
	Examples:	Delete		No	string
	- Delete				
allowVolumeExpansion	- Retain				
	Allow volume expansion				
	Examples:	true		No	boolean
volumeBindingMode	- true				
	- false				
	PersistentVolumes that are dynamically created by a StorageClass will have the volumeBindingMode specified in the volumeBindingMode field				
volumeBindingMode	Examples:	WaitForFirstConsumer		No	string
	- WaitForFirstConsumer				
	- Immediate				
resource	Resource Requirements			No	object

pod-prometheus prometheus storage parameters

Description

External storage specific parameters. To deploy federation with external storage other than cinder, provide configuration in values.yaml and deploy it.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cinder	Parameters for cinder external storage			No	object
azureDisk	Parameters to configure Azure disk storage. To add any other parameter related to Azure disk, edit values.yaml during deployment			No	object

pod-prometheus prometheus storage parameters cinder

Description

Parameters for cinder external storage

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
type	VM disk type	ceph		No	string
availability	Availability Zone	nova		No	string
fsType	fsType	ext4		No	string

pod-prometheus prometheus storage parameters azureDisk

Description

Parameters to configure Azure disk storage. To add any other parameter related to Azure disk, edit values.yaml during deployment

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
storageaccounttype	Azure storage account name. If a storage account is provided, it must reside in the same resource group as the cluster			No	string
kind	Possible values are shared (default), dedicated, and managed	shared		No	string

pod-prometheus prometheus storage resource

Description

Resource Requirements

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Request Resource				
request	Examples: - 100Gi	100Gi		No	string

pod-prometheus prometheus remoteStorage

Description

remoteStorage

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable remote storage Option.				
enabled	Examples: - false - true	false		No	boolean
remoteWriteUrl	Remote write URL			No	string
remoteWriteTimeout	Remote write Timeout	30s		No	string
remoteReadUrl	Remote Read Url			No	string

pod-prometheus prometheus topologySpreadConstraints

Description

Pod Topology Spread Constraints

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Pod Topology Spread Constraints -enable or disable	true		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
constraints	Pod topology Spread Constraints			No	array

[pod-prometheus prometheus topologySpreadConstraints constraints](#)

Description

Pod topology Spread Constraints

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Pod topology Spread Constraints			No	object

[pod-prometheus prometheus topologySpreadConstraints constraints 0](#)

Description

Pod topology Spread Constraints

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxSkew	Maxskew	1		No	integer
topologyKey	topologyKey for pod topologySpreadConstraints	kubernetes.io/hostname		No	string
whenUnsatisfiable	whenUnsatisfiable value for pod topologySpreadConstraints	DoNotSchedule		No	string

[pod-prometheus prometheus resources](#)

Description

resource requirements

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
limits	Resource Limit			No	object
requests	Requested Resource			No	object

[pod-prometheus prometheus resources limits](#)

Description

Resource Limit

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu limit					
cpu	Examples: - 10	10		No	string
Memory Limit					
memory	Examples: - 25Gi	25Gi		No	string

[pod-prometheus prometheus resources requests](#)

Description

Requested Resource

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
Requested CPU					
cpu	Examples: - 1	1		No	string
Requested memory					
memory	Examples: - 4Gi	4Gi		No	string

pod-prometheus thanosQuery

Description

Thanos Query

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Thanos Query Name					
name	Examples: - thanos-query	thanos-query		No	string
deploy	Deploy			No	object
service	Service			No	object
hpa	hpa for thanos query			No	object

pod-prometheus thanosQuery deploy

Description

Deploy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Log level					
logLevel	Examples: - info	info		No	string
resources	resource requirements			No	object

pod-prometheus thanosQuery deploy resources

Description

resource requirements

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
limits	Resource Limit			No	object
requests	Requested Resource			No	object

pod-prometheus thanosQuery deploy resources limits

Description

Resource Limit

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu limit					
cpu	Examples: - 10	10		No	string
Memory Limit					
memory	Examples: - 25Gi	25Gi		No	string

pod-prometheus thanosQuery deploy resources requests

Description

Requested Resource

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Requested CPU					
cpu	Examples: - 1	1		No	string
Requested memory					
memory	Examples: - 4Gi	4Gi		No	string

pod-prometheus thanosQuery service

Description

Service

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Thanos Query External IP					
externalIpAddress	Examples: - 1.1.1.1			No	string

pod-prometheus thanosQuery hpa

Description

hpa for thanos query

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
HPA minimum replicas					
minReplicas	Examples: - 2	2		No	integer
HPA maximum replicas					
maxReplicas	Examples: - 6	6		No	integer

Parameter	Description	Default	Value/Range	Mandatory	Type
	HPA enabled or disabled				
enabled	Examples: - true	true		No	boolean

pod-prometheus thanos

Description

Enable or Disable Thanos

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable or Disable Thanos				
enabled	Examples: - true - false	true		No	boolean
longTermStorage	To store metrics for long term.			No	object

pod-prometheus thanos longTermStorage

Description

To store metrics for long term.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Flag to enable/disable long term storage with thanos.	false		No	boolean
type	Storage type for long term storage.	AZURE		No	string
config	Storage configuration for long term storage.			No	object

pod-prometheus thanos longTermStorage config

Description

Storage configuration for long term storage.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
storage_account	Storage account name.			No	string
storage_account_key	Storage account key.			No	string
container	Storage account container name.			No	string

pod-prometheus probesCheck

Description

Liveliness and Readiness Probe Checks for Prometheus, Alertmanager and Thanos

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
liveliness	Liveliness probe to detect and redeem broken state of the pod by restarting them			No	object
readiness	Readiness probe ensures that traffic is only routed when the pods are ready			No	object

pod-prometheus probesCheck liveliness

Description

Liveliness probe to detect and redeem broken state of the pod by restarting them

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
failureThreshold	When a probe fails, Kubernetes will try failureThreshold times before giving up	120		No	integer
initialDelaySeconds	Number of seconds after the container has started before liveness or readiness probes are initiated. Defaults to 0 seconds	30		No	integer
periodSeconds	How often (in seconds) to perform the probe. Default to 10 seconds. Minimum value is 1.	60		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer
timeoutSeconds	Number of seconds after which the probe times out. Defaults to 1 second.	5		No	integer

pod-prometheus probesCheck readiness

Description

Readiness probe ensures that traffic is only routed when the pods are ready

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
failureThreshold	When a probe fails, Kubernetes will try failureThreshold times before giving up	120		No	integer
initialDelaySeconds	Number of seconds after the container has started before liveness or readiness probes are initiated. Defaults to 0 seconds	30		No	integer
periodSeconds	How often (in seconds) to perform the probe. Default to 10 seconds. Minimum value is 1.	60		No	integer
successThreshold	Minimum consecutive successes for the probe to be considered successful after having failed	1		No	integer
timeoutSeconds	Number of seconds after which the probe times out. Defaults to 1 second.	5		No	integer

pod-prometheus httpAlertsThreshold

Description

Threshold configuration for HTTP metric based alerts

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio5xxErrorPercentage	Istio globall HTTP request failed with 5xx error percentage failure alert threshold.	25		No	integer
istio4xxErrorPercentage	Istio globall HTTP request failed with 4xx error percentage failure alert threshold.	25		No	integer
istioReqLatencySeconds	Istio globall HTTP request latency high alert threshold.	5		No	integer
httpSrvr5xxErrorPercentage	HTTP server request failed with 5xx error percentage failure alert threshold.	25		No	integer
httpSrvr4xxErrorPercentage	HTTP server request failed with 4xx error percentage failure alert threshold.	50		No	integer
httpClientRespRcvd5xxErrorPercentage	HTTP client response received failed with 5xx error percentage failure alert threshold.	25		No	integer
httpClientRespRcvd460N499ErrorPercentage	HTTP client response received failed with 460 and 499 error percentage failure alert threshold.	25		No	integer
httpSrvrReqRate	HTTP request rate high alert threshold.	500		No	integer
firingActiveAlertInterval	Firing active alerts interval from Prometheus.	2m		No	string

pod-prometheus ao5GCBasic

Description

Centralized Prometheus for aggregating and monitoring several clusters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	To enabled or disable ao5GCBasic	false		No	boolean
additionalScrapeConfigsPrometheus	IPs of Prometheus instances to be monitored			No	object
additionalScrapeConfigsKubeProm	IPs of Prometheus instances to be monitored			No	object
prometheusResources	resource requirements			No	object
thanosResources	resource requirements			No	object

[pod-prometheus ao5GCBasic additionalScrapeConfigsPrometheus](#)

Description

IPs of Prometheus instances to be monitored

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
static_configs	IPs of Prometheus instances to be monitored			No	array

[pod-prometheus ao5GCBasic additionalScrapeConfigsPrometheus static_configs](#)

Description

IPs of Prometheus instances to be monitored

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
targets	array of target IPs			No	array

[pod-prometheus ao5GCBasic additionalScrapeConfigsKubeProm](#)

Description

IPs of Prometheus instances to be monitored

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
static_configs	IPs of Prometheus instances to be monitored			No	array

[pod-prometheus ao5GCBasic additionalScrapeConfigsKubeProm static_configs](#)

Description

IPs of Prometheus instances to be monitored

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
targets	array of target IPs			No	array

[pod-prometheus ao5GCBasic prometheusResources](#)

Description

resource requirements

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
limits	Resource Limit			No	object
requests	Requested Resource			No	object

[pod-prometheus ao5GCBasic prometheusResources limits](#)

Description

Resource Limit

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	cpu limit				
	Examples:	7		No	string
	- 7				
Memory Limit					
memory	Examples:	10Gi		No	string
	- 10Gi				

pod-prometheus ao5GCBasic prometheusResources requests

Description

Requested Resource

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Requested CPU					
cpu	Examples:	700m		No	string
	- 700m				
Requested memory					
memory	Examples:	1Gi		No	string
	- 1Gi				

pod-prometheus ao5GCBasic thanosResources

Description

resource requirements

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
limits	Resource Limit			No	object
requests	Requested Resource			No	object

pod-prometheus ao5GCBasic thanosResources limits

Description

Resource Limit

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu limit					
cpu	Examples:	3		No	string
	- 3				
Memory Limit					
memory	Examples:	3Gi		No	string
	- 3Gi				

pod-prometheus ao5GCBasic thanosResources requests

Description

Requested Resource

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Requested CPU					
cpu	Examples: - 200m	200m		No	string
Requested memory					
memory	Examples: - 200Mi	200Mi		No	string

pod-prometheus promDataPurger

Description

Prometheus metrics data purger

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	To enabled or disable promDataPurger	false		No	boolean
deleteInNamespace	Delete metrics data in the specified namespace	fed-smf		No	string
deleteOlderInMinutes	Delete metrics data older than specified minutes	15		No	integer
periodSeconds	Delete metrics data every specified seconds	300s		No	string

RBAC Helm Documentation

RBAC values

Contents

- [Global Parameters](#)
- [Pod-rbac Parameters](#)
- [azurearc Parameters](#)
- [azuread Parameters](#)

global

Description

Global Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
registry	PaaS registry associations			No	object

[global](#) registry

Description

PaaS registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

[global](#) [registry](#) docker

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string
imagePullSecrets				No	array
imagePullSecret	Pull an image from a private registry			No	string
username	Username for private docker registry			No	string
password	Password for private docker registry			No	string

global registry docker imagePullSecrets

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Image Pull Secrets Array			No	object

global registry docker imagePullSecrets 0

Description

Image Pull Secrets Array

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	AS number to use for the local end of the session			No	string

pod-rbac

Description

Pod-rbac Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
podExec	Set to true if pod execution is allowed	true		No	boolean

azurearc

Description

azurearc Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Set this flag to true if the cluster is integrated with Azure AD for Authentication	false		No	boolean
limaintaadGroupObjectid	Please update value of limaintaadgroup with Objectid of Azure AD group of Li users			No	string
maintaadGroupObjectid	Please update value of maintaadgroup with Objectid of Azure AD group of Non-Li user			No	string

azuread

Description

azuread Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Set this flag to true if the cluster is integrated with Azure AD for Authentication	false		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
clusterrole	Cluster role to be bounded for Azure AD Proxy ServiceAccount	restricted-cr		No	string
aadproxysa	Azure AD Proxy ServiceAccount Name	azure-arc-kube-aad-proxy-sa		No	string
namespace	Namespace where all the Azure ARC pods are deployed	azure-arc		No	string

fed-redis_cluster Helm Documentation

fed-redis_cluster values

Contents

- [Global Parameters](#)
- [pod-redis_cluster parameters](#)

global

Description

Global Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
defaultRbacEnabled	defaultRbacEnabled Flag				
	Examples:				
	- false	false		No	boolean
	- true				
kargoProfileTag	This enables creation of specific kargo-default-profile for fed-redis_cluster			No	string
vault	vault			No	object
secretNames	Azure PaaS Key-Vault Secret Names			No	object
logging	PaaS logging association			No	object
grafana	PaaS Grafana association			No	object
monitoring	PaaS Monitoring associations			No	object
registry	PaaS container registry associations			No	object
envVars	Environment variables			No	object
podPriorityEnabled	Flag to enable/disable pod priority at a fed level				
	Examples:				
	- false	true		No	boolean
	- true				
constraints	Pod topology Spread Constraints			No	array
mesh	Istio mesh configuration			No	object

[global](#) vault

Description

vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	vault Enabled				
	Examples:				
	- false	false		No	boolean
	- true				
hashicorpVault	hashicorpVault			No	object
azureKeyVault	azureKeyVault			No	object

global vault hashicorpVault

Description

hashicorpVault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	hashicorpVault Enabled				
	Examples:				
	- false	false		No	boolean
	- true				
serverUrl	Address of Vault Server				
	Examples:				
	- https://test.vault.com:8200			No	string
role	JWT Role created on Vault Server			No	string
authMountPath	JWT mount path on Vault server			No	string
vaultNamespace	Vault Namespace configured on Vault server for multi-tenancy support			No	string

global azure azureKeyVault

Description

azureKeyVault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	azureKeyVault Enabled				
	Examples:				
	- false	false		No	boolean
	- true				
aksCluster	Is it AKS cluster				
	Examples:				
	- false	false		No	boolean
	- true				
keyVaultName	key vault name			No	string
tenantID	tenant id where akv created			No	string
userManagerId	User manager ID			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
	is it Workloadidentity				
	Examples:				
workloadIdentity	- false	true		No	boolean
	- true				

global secretNames

Description

Azure PaaS Key-Vault Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
redis	Redis Secret Names			No	object

global secretNames redis

Description

Redis Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Name of password key in Vault				
mgmtSecretName	Examples: - password	OrderedDict()		No	string

global logging

Description

PaaS logging association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable logging association				
enabled	Examples: - false - true		false	No	boolean
fluentd	Fluentd-Configurations			No	object
elastic	Elasticsearch association			No	object
enableAddlTargets	Enable/disable additional destinations		false	No	boolean
addlTargets	Additional logging output destination configuration			No	array
alerts	Alerts configuration			No	object

global logging fluentd

Description

Fluentd-Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	Fluentd-Buffer Configurations			No	object

global logging fluentd buffer

Description

Fluentd-Buffer Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Total buffer size. Maximum amount of buffer space each fluentd thread would use to keep logs. After this space is exhausted, fluentd would start deleting oldest logs to make room for new logs.	32m		No	string
retryWait	Interval(seconds) at which the buffer flush is retried in case of failure.	10s		No	string
maxRetries	Max number of retries to flush a buffer chunk. After this is exhausted, fluentd would delete the chunk.	1		No	integer

global logging elastic

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ip	Elasticsearch IP address				
	Examples:			No	string
	- 10.15.10.161				
Port	Elasticsearch port	9200		No	integer

global logging addITargets

Description

Additional logging output destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			No	object

global logging addITargets forward

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
host	Hostname or IP Address of the forward server for sending logs to additional targets in parallel with elastic			No	string
port	Port of the forward server	24224		No	integer

global logging alerts

Description

Alerts configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable event alerts	false		No	boolean
	Examples:				
	- true				
host	Elasticsearch IP address or host			No	string
	Examples:				
	- 10.15.10.161				
port	Elasticsearch port	3030		No	integer
realert	Re-alert Info			No	object
receivers	Alert receivers.			No	array
	Examples:				
	- [OrderedDict({'slack': OrderedDict({'webhookurl': ''})}), OrderedDict({'post': OrderedDict({'http_post_url': ''})})]				

global logging alerts realert

Description

Re-alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minutes	Interval in minutes to re-send an alert	1		No	integer
	Examples:				
	- 2				

global logging alerts receivers

Description

Alert receivers.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	The first anyOf schema.			No	object
	Examples:				
	- OrderedDict({'slack': OrderedDict({'webhookurl': ''})})				
1	The second anyOf schema.			No	object
	Examples:				
	- OrderedDict({'post': OrderedDict({'http_post_url': ''})})				
2	The third anyOf schema			No	object
	Examples:				
	- OrderedDict({'email': OrderedDict({'to_address': '', 'smtp_host': '', 'smtp_port': '', 'smtp_ssl': False, 'from_addr': ''})})				

global logging alerts receivers 0

Description

The first anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Slack receiver details.				
slack	Examples: - OrderedDict({'webhookurl': ''})			No	object

global logging alerts receivers 0 slack

Description

Slack receiver details.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	The webhook URL that includes your auth data and the ID of the channel (room) you want to post to.				
webhookurl	Examples: -			No	string

global logging alerts receivers 1

Description

The second anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	HTTP post alert receiver details.				
post	Examples: - OrderedDict({'http_post_url': ''})			No	object

global logging alerts receivers 1 post

Description

HTTP post alert receiver details.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	URL for HTTP post.				
http_post_url	Examples: -			No	string

global logging alerts receivers 2

Description

The third anyOf schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Mail alert receiver Info.				
email	Examples: - OrderedDict({'to_address': '', 'smtp_host': '', 'smtp_port': '', 'smtp_ssl': False, 'from_addr': ''})			No	object

global logging alerts receivers 2 email

Description

Mail alert receiver Info.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
to_address	An address or list of addresses to sent the alert to.	user1@example.com		No	string
	Examples: - user1@example.com				
smtp_host	SMTP host details.	1.1.1.1		No	string
	Examples: - 1.1.1.1				
smtp_port	SMTP port info	25		No	string
	Examples: - 25				
smtp_ssl	Enable/disable SSL to SMTP server.	false		No	boolean
	Examples: - false				
from_addr	This sets the from header in the email. By default, the from address is ElastAlert@ and the domain will be set by the smtp server	user2@example.com		No	string
	Examples: - user2@example.com				

global grafana

Description

PaaS Grafana association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association	true		No	boolean
url	Exposed grafana URL			No	string
	Examples: - https://10.15.10.161:3000				
prometheusinfo	Prometheus server association			No	object

global grafana prometheusinfo

Description

Prometheus server association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
url	Prometheus server URL	https://prometheus.fed-prometheus:9090		No	string
	Examples: - https://prometheus.fed-prometheus:9090				

global monitoring

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association			No	object

[global monitoring prometheus](#)

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable prometheus monitoring	true		No	boolean

[global registry](#)

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

[global registry docker](#)

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string
imagePullSecret	Pull an image from a private registry			No	string
username	Username for private docker registry			No	string
password	Password for private docker registry			No	string

[global envVars](#)

Description

Environment variables

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Federation type				
fedType	Examples: - paas	paas		No	string
	Federation unique name				
fedUniqueName	Examples: - redis-cluster-default	redis-cluster-default		No	string

[global topologySpreadConstraints constraints](#)

Description

Pod topology Spread Constraints

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Pod topology Spread Constraints			No	object

global topologySpreadConstraints constraints 0

Description

Pod topology Spread Constraints

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxSkew	Maxskew	1		No	integer
topologyKey	topologyKey for pod topologySpreadConstraints	kubernetes.io/hostname		No	string
whenUnsatisfiable	whenUnsatisfiable value for pod topologySpreadConstraints	ScheduleAnyway		No	string

global mesh

Description

Istio mesh configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio configuration			No	object

global mesh istio

Description

Istio configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGw	Service mesh ingress gateway				
	Examples: - ingress-gateway			No	string
ingressGwIP	Istio ingress gateway IP				
	Examples: -			No	string
ingressGwFQDN	Istio ingress gateway FQDN				
	Examples:			No	string
ingressGwPort	Istio ingress gateway port				
	Examples:	9343		No	['integer', 'null']
ingressGwProtocol	Istio ingress gateway protocol				
	Examples:	TCP		No	string
mtlsEnabled	MTLS flag.				
	Examples: - false	false		No	boolean
ingressGwTLS	Istio ingress gateway TLS			No	object
egressGwTLS	Istio egress gateway TLS			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
	Istio ingress gateway service loadbalancer sharing key.				
loadBalancerSharingKey	Examples: - pass	pass		No	string

global mesh istio ingressGwTLS

Description

Istio ingress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enabling Istio ingress gateway TLS				
enabled	Examples: - true - false	true		No	boolean
	Istio ingress gateway TLS mode.				
mode	Examples: - MUTUAL	MUTUAL		No	string
certManager	certManager Configuration			No	object
userProvided	userProvided CERTIFICATES			No	object

global mesh istio ingressGwTLS certManager

Description

certManager Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/Disable Flag for certManager configuration				
enabled	Examples: - true - false	true		No	boolean
certDuration	certDuration Configuration	10h		No	string
renewBefore	renewBefore Configuration	1h		No	string
	organization Configuration				
organization	Examples: - affirmednetworks	affirmednetworks		No	string
	issuerName				
issuerName	Examples: - affirmed-clusterissuer	affirmed-clusterissuer		No	string
	issuerType				
issuerType	Examples: - vault			No	string

global mesh istio ingressGwTLS userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvided Certificates				
	Examples:				
	- false	false		No	boolean
	- true				
cacert	cacert Configuration				
	Examples:				
	- Copy and Paste End User generated Certificate			No	string
tlsCRT	tlsCRT configuration				
	Examples:				
	- Copy and Paste End User generated Certificate			No	string
tlskey	tlskey configuration				
	Examples:				
	- Copy and Paste End User generated Certificate			No	string

global mesh istio egressGwTLS

Description

Istio egress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio egress gateway TLS				
	Examples:				
	- true	true		No	boolean
	- false				
mode	Istio egress gateway TLS mode.				
	Examples:				
	- MUTUAL	MUTUAL		No	string
certManager	certManager Configuration			No	object
userProvided	userProvided CERTIFICATES			No	object

global mesh istio egressGwTLS certManager

Description

certManager Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for certManager configuration				
	Examples:				
	- true	true		No	boolean
	- false				
certDuration	certDuration Configuration	10h		No	string
renewBefore	renewBefore Configuration	1h		No	string
organization	organization Configuration				
	Examples:				
	- affirmednetworks	affirmednetworks		No	string
issuerName	issuerName				
	Examples:				
	- affirmed-clusterissuer	affirmed-clusterissuer		No	string

global mesh istio egressGwTLS userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvided Certificates				
	Examples:				
	- false	false		No	boolean
	- true				
cacert	cacert Configuration				
	Examples:				
	- Copy and Paste End User generated Certificate			No	string
tls crt	tls crt configuration				
	Examples:				
	- Copy and Paste End User generated Certificate			No	string
tls key	tls key configuration				
	Examples:				
	- Copy and Paste End User generated Certificate			No	string

pod-redis_cluster

Description

pod-redis_cluster parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rbacEnabled	RBAC elabled/disabled flag	true		No	boolean
overrideEnabled	Enable over ride of names of few k8s resources created as specified in fullnameOverride field	true		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
nameOverride	Redis Cluster name	node-for-redis		No	string
fullNameOverride	Redis Cluster fullName	node-for-redis		No	string
numberOfPrimaries	Number of Primaries	3		No	integer
replicationFactor	Number of Replicas	2		No	integer
imagePullPolicy	ImagePull policy for redis cluster	IfNotPresent		No	string
prometheus	Prometheus monitoring association			No	object
serviceAccount	Redis cluster serviceAccount			No	object
resources	Resources configuration			No	object
metrics	Redis cluster metrics			No	object
redis	Redis configuration			No	object

[pod-redis_cluster](#) prometheus

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable prometheus monitoring	true		No	boolean

[pod-redis_cluster](#) serviceAccount

Description

Redis cluster serviceAccount

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Redis cluster serviceAccount name	node-for-redis		No	string

[pod-redis_cluster](#) resources

Description

Resources configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
limits	Resource limits			No	object
requests	Resource requests			No	object

[pod-redis_cluster](#) resources limits

Description

Resource limits

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	CPU limit				
cpu	Examples: - 1	1		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
Memory limit					
memory	Examples: - 4Gi	4Gi		No	string

pod-redis_cluster resources requests

Description

Resource requests

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
CPU resuests					
cpu	Examples: - 1	1		No	string
Memory requests					
memory	Examples: - 4Gi	4Gi		No	string

pod-redis_cluster metrics

Description

Redis cluster metrics

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Enable/disable logging association					
enabled	Examples: - false - true	true		No	boolean

pod-redis_cluster redis

Description

Redis configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
configuration	Redis configuration			No	object
rbac	Turn On predefined user based Authentication using Redis ACL.			No	object

pod-redis_cluster redis configuration

Description

Redis configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
file	Redis configuration file name			No	string
valueMap	Redis configuration			No	object

pod-redis_cluster redis

Description

Redis configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
save	Redis Bgsave snapshot values to store data into disk			No	string

pod-redis_cluster redis rbac

Description

Turn On predefined user based Authentication using Redis ACL.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable rbac and Supported source is AKV only				
	Examples:				
enabled	- false	false		No	boolean
	- true				

fed-redis_operator Helm Documentation

fed-redis_operator values

Contents

- [Global Parameters](#)
- [pod-redis_operator parameters](#)

global

Description

Global Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	defaultRbacEnabled Flag				
	Examples:				
defaultRbacEnabled	- false	false		No	boolean
	- true				
metricsScrapeInterval	Metrics scrape interval in ServiceMonitors. Setting a lower value would result in faster refreshes of metrics at the cost of more overhead for both prometheus and the application.	1m		No	string
istio	Istio related configurations			No	object
mesh	PaaS service mesh associations			No	object
logging	PaaS logging association			No	object
vault	vault			No	object
secretNames	Azure PaaS Key-Vault Secret Names			No	object
grafana	PaaS Grafana association			No	object
monitoring	PaaS Monitoring associations			No	object
registry	PaaS container registry associations			No	object
envVars	Environment variables			No	object
podPriorityEnabled	Flag to enable/disable pod priority at a fed level	true		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
topologySpreadConstraints	Pod topology Spread values			No	object

[global](#) istio

Description

Istio related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtls	Istio mutual TLS related configuration			No	object

[global](#) istio mtls

Description

Istio mutual TLS related configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable istio mutual TLS	false		No	boolean

[global](#) mesh

Description

PaaS service mesh associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio service mesh association			No	object

[global](#) mesh istio

Description

Istio service mesh association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtlsEnabled	Enable/disable istio mutual TLS	false		No	boolean

[global](#) logging

Description

PaaS logging association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable logging association				
enabled	Examples: - false - true	false		No	boolean
fluentd	Fluentd-Configurations			No	object
elastic	Elasticsearch association			No	object
enableAddlTargets	Enable/disable additional destinations	false		No	boolean
addlTargets	Additional logging output destination configuration			No	array
alerts	Alerts configuration			No	object

[global logging fluentd](#)

Description

Fluentd-Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	Fluentd-Buffer Configurations			No	object

[global logging fluentd buffer](#)

Description

Fluentd-Buffer Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Total buffer size. Maximum amount of buffer space each fluentd thread would use to keep logs. After this space is exhausted, fluentd would start deleting oldest logs to make room for new logs.	32m		No	string
retryWait	Interval(seconds) at which the buffer flush is retried in case of failure.	10s		No	string
maxRetries	Max number of retries to flush a buffer chunk. After this is exhausted, fluentd would delete the chunk.	1		No	integer

[global logging elastic](#)

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Elasticsearch IP address				
IP	Examples: - 10.15.10.161			No	string
Port	Elasticsearch port	9200		No	integer

[global logging addITargets](#)

Description

Additional logging output destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			No	object

[global logging addITargets forward](#)

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
host	Hostname or IP Address of the forward server for sending logs to additional targets in parallel with elastic			No	string
port	Port of the forward server	24224		No	integer

[global logging alerts](#)

Description

Alerts configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable event alerts	false		No	boolean
	Examples:				
	- true				
host	Elasticsearch IP address or host			No	string
	Examples:				
	- 10.15.10.161				
port	Elasticsearch port	3030		No	integer
realert	Re-alert Info			No	object
receivers	Alert receivers.			No	array
	Examples:				
	- [OrderedDict({'slack': OrderedDict({'webhookurl': ''})}), OrderedDict({'post': OrderedDict({'http_post_url': ''})})]				

global logging alerts realert

Description

Re-alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minutes	Interval in minutes to re-send an alert	1		No	integer
	Examples:				
	- 2				

global logging alerts receivers

Description

Alert receivers.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	The first anyOf schema.			No	object
	Examples:				
	- OrderedDict({'slack': OrderedDict({'webhookurl': ''})})				
1	The second anyOf schema.			No	object
	Examples:				
	- OrderedDict({'post': OrderedDict({'http_post_url': ''})})				
2	The third anyOf schema			No	object
	Examples:				
	- OrderedDict({'email': OrderedDict({'to_address': '', 'smtp_host': '', 'smtp_port': '', 'smtp_ssl': False, 'from_addr': ''})})				

global logging alerts receivers 0

Description

The first anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Slack receiver details.				
slack	Examples: - OrderedDict({'webhookurl': ''})			No	object

global logging alerts receivers 0 slack

Description

Slack receiver details.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	The webhook URL that includes your auth data and the ID of the channel (room) you want to post to.				
webhookurl	Examples: -			No	string

global logging alerts receivers 1

Description

The second anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	HTTP post alert receiver details.				
post	Examples: - OrderedDict({'http_post_url': ''})			No	object

global logging alerts receivers 1 post

Description

HTTP post alert receiver details.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	URL for HTTP post.				
http_post_url	Examples: -			No	string

global logging alerts receivers 2

Description

The third anyOf schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
email	Mail alert receiver Info.				
	Examples:			No	object
	- OrderedDict({'to_address': '', 'smtp_host': '', 'smtp_port': '', 'smtp_ssl': False, 'from_addr': ''})				

global logging alerts receivers 2 email

Description

Mail alert receiver Info.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
to_address	An address or list of addresses to sent the alert to.				
	Examples:	user1@example.com		No	string
	- user1@example.com				
smtp_host	SMTP host details.				
	Examples:	1.1.1.1		No	string
	- 1.1.1.1				
smtp_port	SMTP port info				
	Examples:	25		No	string
	- 25				
smtp_ssl	Enable/disable SSL to SMTP server.				
	Examples:	false		No	boolean
	- false				
from_addr	This sets the from header in the email. By default, the from address is ElastAlert@ and the domain will be set by the smtp server				
	Examples:	user2@example.com		No	string
	- user2@example.com				

global vault

Description

vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	vault Enabled				
	Examples:				
	- false	false		No	boolean
	- true				
	hashicorpVault			No	object
azureKeyVault	azureKeyVault			No	object

global vault hashicorpVault

Description

hashicorpVault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	hashicorpVault Enabled				
	Examples:				
	- false	false		No	boolean
	- true				
serverUrl	Address of Vault Server				
	Examples:			No	string
	- https://test.vault.com:8200				
role	JWT Role created on Vault Server			No	string
authMountPath	JWT mount path on Vault server			No	string
vaultNamespace	Vault Namespace configured on Vault server for multi-tenancy support			No	string

global azure azureKeyVault

Description

azureKeyVault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	azureKeyVault Enabled				
	Examples:				
	- false	false		No	boolean
	- true				
aksCluster	Is it AKS cluster				
	Examples:				
	- false	false		No	boolean
	- true				
keyVaultName	key vault name			No	string
tenantID	tenant id where akv created			No	string
userManagerId	User manager ID			No	string
workloadIdentity	is it Workloadidentity				
	Examples:				
	- false	true		No	boolean
	- true				

global secretNames

Description

Azure PaaS Key-Vault Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
redis	Redis Secret Names			No	object

global secretNames redis

Description

Redis Secret Names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Name of password key in Vault				
mgmtSecretName	Examples: - password	OrderedDict()		No	string

[global grafana](#)

Description

PaaS Grafana association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association	true		No	boolean
	Exposed grafana URL				
url	Examples: -			No	string
prometheusinfo	Prometheus server association			No	object

[global grafana prometheusinfo](#)

Description

Prometheus server association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Prometheus server URL				
url	Examples: -			No	string

[global monitoring](#)

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association			No	object

[global monitoring prometheus](#)

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable prometheus monitoring	true		No	boolean

[global registry](#)

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

[global registry](#) docker

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string
imagePullSecret	Pull an image from a private registry			No	string
username	Username for private docker registry			No	string
password	Password for private docker registry			No	string

[global](#) envVars

Description

Environment variables

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Federation type				
fedType	Examples: - paas	paas		No	string
	Federation unique name				
fedUniqueName	Examples: - redis-operator-default	redis-operator-default		No	string

[global](#) topologySpreadConstraints

Description

Pod topology Spread values

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Flag to enable/disable topologySpreadConstraints at a fed level				
enabled	Examples: - false - true	true		No	boolean
constraints	Pod topology Spread Constraints			No	array

[global topologySpreadConstraints](#) constraints

Description

Pod topology Spread Constraints

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Pod topology Spread Constraints			No	object

global topologySpreadConstraints constraints 0

Description

Pod topology Spread Constraints

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxSkew	Maxskew	1		No	integer
topologyKey	topologyKey for pod topologySpreadConstraints	kubernetes.io/hostname		No	string
whenUnsatisfiable	whenUnsatisfiable value for pod topologySpreadConstraints	ScheduleAnyway		No	string

pod-redis_operator

Description

pod-redis_operator parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rbacEnabled	RBAC elabled/disabled flag	true		No	boolean
redis	Redis configuration			No	object
replicaCount	Number of replicas	3		No	integer
imagePullPolicy	ImagePull policy for redis operator	IfNotPresent		No	string
logLevel	Verbosity of logging for the Redis operator	6		No	integer
args	Arguments to be passed to operator			No	array
prometheus	Prometheus monitoring association			No	object
resources	Resources configuration			No	object
livenessProbe	livenessProbe			No	object
readinessProbe	ReadinessProbe			No	object
	zoneAwareReplication: elabled/disabled flag				
	Examples:				
zoneAwareReplication:	- false	true		No	boolean
	- true				
printRedisClusterInfo	Print Redis cluster shard mappings and some stats in non leader operator pods			No	object

pod-redis_operator redis

Description

Redis configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rbac	Turn On predefined user based Authentication using Redis ACL.			No	object

pod-redis_operator redis rbac

Description

Turn On predefined user based Authentication using Redis ACL.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
Enable/disable user based authentication using Redis ACL					
enabled	Examples:	false		No	boolean
	- false				
	- true				

pod-redis_operator prometheus

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable prometheus monitoring	true		No	boolean

pod-redis_operator resources

Description

Resources configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
limits	Resource limits			No	object
requests	Resource requests			No	object

pod-redis_operator resources limits

Description

Resource limits

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cpu	CPU limit				
	Examples:	200m		No	string
	- 200m				
memory	Memory limit				
	Examples:	256Mi		No	string
	- 256Mi				

pod-redis_operator resources requests

Description

Resource requests

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
CPU resuests					
cpu	Examples:	100m		No	string
	- 100m				

Parameter	Description	Default	Value/Range	Mandatory	Type
	Memory requests				
memory	Examples: - 100Mi	100Mi		No	string

pod-redis_operator livenessProbe

Description

livenessProbe

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
initialDelaySeconds:	initialDelaySeconds for livenessProbe	30		No	integer

pod-redis_operator readinessProbe

Description

ReadinessProbe

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
initialDelaySeconds:	initialDelaySeconds for readinessProbe	5		No	integer

pod-redis_operator printRedisClusterInfo

Description

Print Redis cluster shard mappings and some stats in non leader operator pods

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable printing Redis cluster shard mappings	true		No	boolean
intervalMin:	interval to print Redis cluster shard mappings and some stats	1		No	integer

Rook Ceph Helm Documentation

fed-rook_ceph values

Contents

- [Global Parameters](#)
- [Pod-rook_ceph parameters](#)

global

Description

Global Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
registry	PaaS container registry associations			No	object
grafana	PaaS Grafana association			No	object
metricsScrapeInterval	Prometheus metrics scraping interval	1m		No	string
topologySpreadConstraints	Pod topology spread constraints control how pods of given microservice type are spread across the cluster among failure-domains such as regions, zones, nodes, and other user-defined topology domains. This can help to achieve high availability as well as efficient resource utilization.			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
podPriorityEnabled	global flag to enable/disable pod priority	true		No	boolean
	Examples:				
	- true				
	- false				
monitoring	PaaS Monitoring associations			No	object

global registry

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

global registry docker

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string

global grafana

Description

PaaS Grafana association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association	true		No	boolean
url	Exposed grafana URL			No	string
	Examples:				
	- https://10.15.10.161:3000				
prometheusinfo	Prometheus server association			No	object

global grafana prometheusinfo

Description

Prometheus server association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
url	Prometheus server URL			No	string
	Examples:				
	- https://prometheus.fed-prometheus:9090				

global topologySpreadConstraints

Description

Pod topology spread constraints control how pods of given microservice type are spread across the cluster among failure-domains such as regions, zones, nodes, and other user-defined topology domains. This can help to achieve high availability as well as efficient resource utilization.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable pod topology spread constraints	true		No	boolean
	Examples:				
	- false				
	- true				
constraints	List of pod topology spread constraints to be applied.			No	array

global topologySpreadConstraints constraints

Description

List of pod topology spread constraints to be applied.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Definition of pod topology spread constraint to be applied to the pod specification.			No	object

global topologySpreadConstraints constraints 0

Description

Definition of pod topology spread constraint to be applied to the pod specification.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxSkew	Describes the degree to which pods may be unevenly distributed. It's the maximum permitted difference between the number of matching pods in any two topology domains of a given topology type. It must be greater than zero. Examples: - 1	1		No	integer
topologyKey	Its the key of node labels. If two nodes are labelled with this key and have identical values for that label, the Kubernetes scheduler treats both nodes as being in the same topology. The scheduler tries to place a balanced number of Pods into each topology domain. Examples: - kubernetes.io/hostname	kubernetes.io/hostname		No	string
whenUnsatisfiable	Indicates how to deal with a pod if it doesn't satisfy the defined pod topology spread constraint. Examples: - ScheduleAnyway - DoNotSchedule	ScheduleAnyway		No	string

global monitoring

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association			No	object

global monitoring prometheus

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable prometheus monitoring	true		No	boolean

pod-rook_ceph

Description

Pod-rook_ceph parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cephImageRepoPath	Ceph Docker image repository path (not including the image name and trailing slash)			No	string
cephImage	Ceph Docker image			No	string
deviceFilter	Regular expression for device kernel names that will be consumed by the Ceph Object Storage Daemons (OSDs)	vdb		No	string
dashboardEnabled	Boolean control for enabling the Ceph dashboard for viewing cluster status	true		No	boolean
storageClass	Storage class			No	object
journalSizeMB	The size in MB of a filestore journal. The value can be removed for environments with normal sized disks (20 GB or larger)			No	string
databaseSizeMB	The size in MB of the Ceph bluestore database. The value can be removed for environments with normal sized disks (100 GB or larger)			No	string
service	Service resource			No	object
resources	Pod Resources			No	object
operator	Operator configurations			No	object
monCount	Number of Ceph monitor replicas to start	3		No	integer
mgrCount	Number of Ceph manager replicas to start	2		No	integer
livenessProbe	Configure timeoutSeconds for liveness probe for mon,osd and mgr pods			No	object
podPriority	Pod Priority for rook ceph			No	object
cephConfig	Custom ceph configuration settings			No	object
failureDomain	Failure domain settings for CephFilesystem pool and for CephBlockPool - translates to chooseleaf_firstn setting in CRUSH			No	object
metadataServer	Metadata server (MDS) topology keys used for placement			No	object

pod-rook_ceph storageClass

Description

Storage class

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cephFileSystemName	Name of ceph File system to create storage class for file system	rook-cephfs		No	string
cephBlockPoolName	Name of ceph block storage to create storage class for cephblockpool	rook-cephbp		No	string

pod-rook_ceph service

Description

Service resource

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
externalIpAddress	External IP where Ceph dashboard is accessible from			No	string
loadBalancer	Load balancer properties			No	object

pod-rook_ceph service loadBalancer

Description

Load balancer properties

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Boolean control to expose the Ceph dashboard thru an external load balancer			No	boolean
loadBalancerIP	IP address of the external load balancer to expose the Ceph dashboard from			No	string
loadBalancerFQDN	FQDN of the external load balancer to expose the Ceph dashboard from			No	string
loadBalancerSharingKey	The external load balancer sharing key used by the Ceph dasboard and other services	paas		No	string

pod-rook_ceph resources

Description

Pod Resources

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
osd	OSD pod resource requests and limits			No	object

pod-rook_ceph resources osd

Description

OSD pod resource requests and limits

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
limits	OSD pod resource limits			No	object
requests	OSD pod resource requests			No	object

pod-rook_ceph resources osd limits

Description

OSD pod resource limits

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
memory	OSD pod memory limit	6Gi		No	string

pod-rook_ceph resources osd requests

Description

OSD pod resource requests

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
memory	OSD pod memory request	4Gi		No	string

pod-rook_ceph operator

Description

Operator configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rookLogLevel	applies log level by setting ROOK_LOG_LEVEL parameter in operator	ERROR		No	string

pod-rook_ceph livenessProbe

Description

Configure timeoutSeconds for liveness probe for mon,osd and mgr pods

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rookLogLevel	configures the liveness probe timeoutSeconds for mon,osd and mgr pods	9		No	integer

pod-rook_ceph podPriority

Description

Pod Priority for rook ceph

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
priorityClassNames	Pod priority class names			No	object

pod-rook_ceph podPriority priorityClassNames

Description

Pod priority class names

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cluster	ceph cluster priority types			No	object
operator	Priority classname for for operator			No	string
toolbox	Priority classname for toolbox			No	string
mds	Priority classname for mds			No	string
csiPlugin	Priority classname for csiPlugin			No	string
csiProvisioner	Priority classname for csiProvisioner			No	string

pod-rook_ceph podPriority priorityClassNames cluster

Description

ceph cluster priority types

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
all	Priority classname for mon osd and mgr			No	string

pod-rook_ceph cephConfig

Description

Custom ceph configuration settings

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
global	global level custom ceph configuration settings			No	object

pod-rook_ceph cephConfig global

Description

global level custom ceph configuration settings

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
monOsdDownOutSubtreeLimit	The smallest CRUSH unit type that Ceph will not automatically mark out. For instance, if set to host and if all OSDs of a host are down, Ceph will not automatically mark out these OSDs.	root		No	string
monOsdDownOutInterval	The number of seconds Ceph waits before marking a Ceph OSD Daemon down and out if it doesn't respond. Provided in seconds	600		No	string
monOsdMinUpRatio	The minimum ratio of up Ceph OSD Daemons before Ceph will mark Ceph OSD Daemons down.	0.3		No	string
monOsdMinInRatio	The minimum ratio of in Ceph OSD Daemons before Ceph will mark Ceph OSD Daemons out.	0.75		No	string

pod-rook_ceph failureDomain

Description

Failure domain settings for CephFilesystem pool and for CephBlockPool - translates to chooseleaf_firstn setting in CRUSH

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
fs	CephFilesystem pool failure domain			No	object
block	CephBlockPool failure domain	host		No	string
mgr	CephBlockPool failure domain for mgr pool	host		No	string

pod-rook_ceph failureDomain fs

Description

CephFilesystem pool failure domain

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
data	CephFilesystem pool failure domain for data pool	host		No	string
metadata	CephBlockPool failure domain for metadata pool	host		No	string

pod-rook_ceph metadataServer

Description

Metadata server (MDS) topology keys used for placement

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
preferredTopologyKey	topologyKey for preferredDuringSchedulingIgnoredDuringExecution for MDS pods	host		No	string
requiredTopologyKey	topologyKey for requiredDuringSchedulingIgnoredDuringExecution for MDS pods	host		No	string

SMF Helm Documentation

fed-smf values

Contents

- [Global Parameters](#)
- [File Server Parameters](#)
- [Unified Load Balancer Parameters](#)
- [On-premises deployment.](#)
- [pod cdpln](#)
- [Pod routing](#)

- [pod-interface_mgr](#)
- [LB PPE Parameters](#)
- [Configuration Manager Parameters](#)
- [Istio Gateway Parameters](#)
- [Istio LI Gateway Parameters](#)
- [NRF Agent Parameters](#)
- [Subscriber Analyzer Parameters](#)
- [Timer Parameters](#)
- [PFCP-C Parameters](#)
- [SMF Call Control Parameters](#)
- [SMF Call Control Parameters](#)
- [Radius Agent Parameters](#)
- [CHF Agent Parameters](#)
- [CDR Agent Parameters](#)
- [SFTP Microservice Parameters](#)
- [GTPC Agent Parameters](#)
- [LI X1 Parameters](#)
- [LI X2 Parameters](#)
- [Kafka Replay Agent Parameters](#)
- [Diameter Base Parameters](#)

global

Description

Global parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
vault	Vault Related attributes			No	object
secretNames	Name of secrets to be pulled from AKV or Hashicorp Vault			No	object
defaultRbacEnabled	Configuring defaultRbacEnabled to true will create clusterrolebinding. Configuring defaultRbacEnabled to false, clusterrolebinding will not be created. Examples: - false	true		No	boolean
enablePdb	Enable/disable pod disruption budgets(PDB) for fed-smf pods Examples: - false	true		No	boolean
enableNfEgressCommunication	Configuration to enable/disable the communication through the Istio Egress Gateways with the external hosts learnt through the yang configuration in SMF. Examples: - false	false		No	boolean
enableStaticNfEgressCommunication	Configuration to enable/disable the communication through the Istio Egress Gateways with the external hosts learnt dynamically through either NRF or PCF Examples: - false	false		No	boolean
defaultClusterRole	clusterrole and PSP for is created as a part of fed-rbac. defaultClusterRole options are restricted-cr, permissive-network-cr, permissive-full-cr Examples: - permissive-network-cr	permissive-network-cr		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
defaultServiceAccountName	serviceaccount will be created by default. defaultServiceAccountName configuration is used to create default serviceaccount per namespace Examples: - fed-smf-serviceaccount	fed-smf-serviceaccount		No	string
onPrem	Enable On-premises deployment. Examples: - true - false	true		No	boolean
kargoProfileTag	This enables creation of specific kargo-default-profile for fed-smf			No	string
opentelemetry				No	object
ingressNetworkPolicy	network policies configuration			No	object
udsf	Udsf-Redis DB Server Details			No	object
tabdb	PaaS Tabular database associations			No	object
filesaver	PaaS filesaver associations			No	object
mesh	PaaS service mesh associations			No	object
monitoring	PaaS Monitoring associations			No	object
diameterGroups	This deployment variable ensures diameter service names are known to application monitors. The diameter group names given here are referenced in pod-diameter_base scope. If a group name is added to/removed from the below list, user must make sure to add/remove the corresponding entry in diameterGroups of pod-diameter_base scope as well. This is because the group name in below list is referenced by the pod-diameter_base scope.			No	array
metricsScrapeInterval	Prometheus metrics scrape interval Examples: - 5s	30s		No	string
registry	PaaS container registry associations			No	object
envVars	Environment variables			No	object
encryptDecryptKey	Secret pass phrase used for Encryption/Decryption of LI Data only. This is a private key needed in case AKV is not enabled and encryptPaasDataForLI is enabled.			No	object
smfset	Global smfSet parameters			No	object
grafana	PaaS Grafana association			No	object
logging	PaaS logging association			No	object
license	PaaS License Server Selector			No	object
loadBalancerSourceRanges	Comma separated IP ranges that are allowed to access the load balancer. More info here - https://kubernetes.io/docs/tasks/access-application-cluster/configure-cloud-provider-firewall/#restrict-access-for-loadbalancer-service Examples: - 130.211.204.1/32	[]		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
enableExternalChfInterface	Use this variable to enable/disable the 5G charging functionality of interacting with external CHF servers. Examples: - true	true		No	boolean
enableLocalCdrsInterface	Use this variable to enable/disable the local CDR generation functionality. Examples: - false	false		No	boolean
enableLIX1	Use this variable to enable/disable the li-x1 microservice. Examples: - true	true		No	boolean
enableLIX2	Use this variable to enable/disable the li-x2 microservice. Examples: - true	true		No	boolean
enableExternalLB	Use this variable to enable/disable external LB resources Examples: - true - false	true		No	boolean
enableGtpcAgent	Use this variable to enable/disable gtpcagent Examples: - true - false	true		No	boolean
enableNchfUsageReplay	Use this variable to enable/disable the Nchf interface usage replay functionality. Refer to CHF Agent configuration documentation for more information on this functionality. Examples: - true - false	true		No	boolean
enableLivenessProbe	Use this variable to enable/disable the Liveness Probe. Examples: - true - false	true		No	boolean
resource	Default limits and request for each container			No	object
test	Test			No	object
topologySpreadConstraints	Pod topology spread constraints control how pods of given microservice type are spread across the cluster among failure-domains such as regions, zones, nodes, and other user-defined topology domains. This can help to achieve high availability as well as efficient resource utilization.			No	object
externalGtpcSvc	External service parameters			No	array
externalPfcpSvc	External service parameters			No	array

global vault

Description

Vault Related attributes

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Vault feature				
	Examples:				
	- false	false		No	boolean
	- true				
hashicorpVault	HashicorpVault related configurations			No	object
azureKeyVault	AzureKeyVault related configurations			No	object

global vault hashicorpVault

Description

HashicorpVault related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	HashicorpVault Enable/Disable flag				
	Examples:				
	- false	true		No	boolean
	- true				
serverUrl	Address of Vault Server				
	Examples:				
	- https: //test.vault.com:8200			No	string
role	JWT Role created on Vault Server			No	string
authMountPath	JWT mount path on Vault server			No	string
vaultNamespace	Vault Namespace configured on Vault server for multi-tenancy support			No	string

global azure azureKeyVault

Description

AzureKeyVault related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	AzureKeyVault Enable/Disable flag				
	Examples:				
	- false	false		No	boolean
	- true				
tenantID	Tenant ID of Customer where AzureKeyVault is deployed			No	string
keyVaultName	KeyVault of Customer where secrets are stored			No	string
aksCluster	Azure Kuberetes Cluster				
	Examples:				
	- false	true		No	boolean
	- true				

Parameter	Description	Default	Value/Range	Mandatory	Type
userManagedId	ClientID of User managed ID			No	string
	workload Identity				
	Examples:				
workloadIdentity	- false	true		No	boolean
	- true				

global secretNames

Description

Name of secrets to be pulled from AKV or Hashicorp Vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cfgmgr	Name of secrets used by configuration manager			No	object
ingressgw	Ingress GW			No	object
egressgw	Engress GW			No	object
ingressgwli	Ingress GW Li			No	object
egressgwli	Engress GW Li			No	object
likey	Name of the secrets used by LI when Hashicorp Vault is enabled			No	object
sftp	Name of the secrets used by SFTP Microservice in pull mode when AKV Vault is enabled			No	object

global secretNames cfgmgr

Description

Name of secrets used by configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
confdKey	Vault Secret Name for confd AES key			No	string
encryptConfigKeySecretName	Vault Secret Name for Encrypt Config key			No	string
adminDomainCAkeySecretName	Vault Secret Name for Admin Domain CA key			No	string
liadminDomainCAkeySecretName	Vault Secret Name for LI Admin Domain CA key			No	string
maintDomainCAkeySecretName	Vault Secret Name for Maint domain CA key			No	string
limaintDomainCAkeySecretName	Vault Secret Name for LI Maint domain CA key			No	string
rootDomainCAkeySecretName	Vault Secret Name for root domain CA key			No	string
rootPasswdSecretName	Vault Secret Name for root password			No	string
rootPubkeySecretName	Vault Secret Name for root public key			No	string
m2mPubkeySecretName	Vault Secret Name for m2m public key			No	string
adminUsers	List of Admin users for configuration manager			No	array
liadminUsers	List of LI Admin users for configuration manager			No	array
operUsers	List of Oper users for configuration manager			No	array
lioperUsers	List of LI Oper users for configuration manager			No	array
readonlyUsers	List of read-only users for configuration manager			No	array
userProvided	Secret Name of certificates used by RESTCONF			No	object

global secretNames cfgmgr adminUsers

Description

List of Admin users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

[global secretNames cfgmgr liadminUsers](#)

Description

List of LI Admin users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

[global secretNames cfgmgr operUsers](#)

Description

List of Oper users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

[global secretNames cfgmgr lioperUsers](#)

Description

List of LI Oper users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

[global secretNames cfgmgr readonlyUsers](#)

Description

List of read-only users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

[global secretNames cfgmgr userProvided](#)

Description

Secret Name of certificates used by RESTCONF

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
tls crtSecretName	Secret Name of server TLS certificate			No	string
tls keySecretName	Secret Name of server TLS key			No	string
ca crtSecretName	Secret Name of CA certificate			No	string

global secretNames ingressgw

Description

Ingress GW

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mountCSI	Enables mounting of CSI Volume(SecretProviderClass) on the vault helper	false		No	boolean
userProvided	userProvided CERTIFICATES			No	object

global secretNames ingressgw/userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ca crtSecretName	ca crtSecretName Configuration				
	Examples:			No	string
tls crtSecretName	ca crtSecretName configuration				
	Examples:			No	string
tls keySecretName	ca crtSecretName configuration				
	Examples:			No	string

global secretNames egressgw

Description

Egress GW

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mountCSI	Enables mounting of CSI Volume(SecretProviderClass) on the vault helper	false		No	boolean
userProvided	userProvided CERTIFICATES			No	object

global secretNames egressgw/userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ca crtSecretName	ca crtSecretName Configuration				
	Examples:			No	string
tls crtSecretName	tls crtSecretName configuration				
	Examples:			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
tlskeySecretName	tlskeySecretName configuration				
	Examples:			No	string

global secretNames ingressgwli

Description

Ingress GW Li

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mountCSI	Enables mounting of CSI Volume(SecreProviderClass) on the vault helper	false		No	boolean
userProvided	userProvided CERTIFICATES			No	object

global secretNames ingressgwli/userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cacertSecretName	cacertSecretName Configuration				
	Examples:			No	string
tls crtSecretName	cacertSecretName configuration				
	Examples:			No	string
tlskeySecretName	cacertSecretName configuration				
	Examples:			No	string

global secretNames egressgwli

Description

Engress GW Li

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mountCSI	Enables mounting of CSI Volume(SecreProviderClass) on the vault helper	false		No	boolean
userProvided	userProvided CERTIFICATES			No	object

global secretNames egressgwli/userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cacertSecretName	cacert Configuration				
	Examples:			No	string
tls crtSecretName	tls crtSecretName configuration				
	Examples:			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
tlskeySecretName	tlskeySecretName configuration				
	Examples:			No	string

global secretNames likey

Description

Name of the secrets used by LI when Hashicorp Vault is enabled

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mountCSI	Enables mounting of CSI Volume(SecreProviderClass) on the vault helper	true		No	boolean
secretName	vault secret name for latest li key			No	string
prevSecretName	vault secret name for previous li key			No	string

global secretNames sftp

Description

Name of the secrets used by SFTP Microservice in pull mode when AKV Vault is enabled

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mountCSI	Enables mounting of CSI Volume(SecreProviderClass) on the vault helper	false		No	boolean
configureduser	vault secret name for configured user name for SFTP Pull			No	string
publickey	vault secret name for configured user public key authentication for SFTP Pull			No	string

global opentelemetry

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable opentelemetry	true		No	boolean
tlsEnabled	Enable mTLS on opentelemetry	false		No	boolean
tracing	Configuration options for opentelemetry traces			No	object

global opentelemetry tracing

Description

Configuration options for opentelemetry traces

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable opentelemetry tracing	true		No	boolean
host	opentelemetry fqdn			No	string
port	opentelemetry port	80		No	integer

global ingressNetworkPolicy

Description

network policies configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabled network policy	true		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressTrafficNamespaces	Namespaces which are required to be allowed for ingress traffic			No	array

global udsf

Description

Udsf-Redis DB Server Details

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
server	Redis DB Server Details			No	object
	Enable/disable Udsf Monitoring				
monitoringEnabled	Examples: - false	true		No	boolean

global udsf server

Description

Redis DB Server Details

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Redis DB Server Address				
host	Examples: - redis-cluster.fed-redis-cluster.svc.cluster.local	redis-cluster.fed-redis-cluster.svc.cluster.local		No	string
port	Redis DB Server Port	6379		No	string

global tabdb

Description

PaaS Tabular database associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
etcd	Etcd database association			No	object

global tabdb etcd

Description

Etcd database association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Etcd db instance name				
name	Examples: - etcd-server	etcd-server		No	string
	Tab-DB service path				
svc	Examples: - etcd-cluster-client.fed-db-etcd.svc.cluster.local	etcd-cluster-client.fed-db-etcd.svc.cluster.local		No	string
port	Tab-DB service port	2379		No	string
targetPort	Tab-DB service target port	31869		No	string

global fileserver

Description

PaaS fileserver associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ui	Fileserver UI association			No	object
nfs	NFS fileserver association			No	object
cephfs	CephFS configuration - CephFS is an actual mountable POSIX-compliant filesystem layered on top of a Ceph storage cluster			No	object

global fileserver ui

Description

Fileserver UI association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
loadBalancerPort	Fileserver UI load balancer port	85		No	string
serviceAnnotations	Service annotations			No	object

global fileserver ui serviceAnnotations

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

global fileserver nfs

Description

NFS fileserver association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
remoteHost	Fileserver remote host address				
	Examples:			No	string
	- 1.1.1.100				
remotePath	Fileserver remote file path				
	Examples:	/filestore		No	string
	- /filestore				
remotePort	Fileserver remote host port	85		No	string

global fileserver cephfs

Description

CephFS configuration - CephFS is an actual mountable POSIX-compliant filesystem layered on top of a Ceph storage cluster

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable CephFS				
enabled	Examples: - true	false		No	boolean

global mesh

Description

PaaS service mesh associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio service mesh association			No	object

global mesh istio

Description

Istio service mesh association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGwLi	Istio service mesh LI ingress GW			No	object
	Service mesh ingress gateway				
ingressGw	Examples: - ingress-gateway			No	string
	Specific IP requested for Ingress Gateway LoadBalancer service				
ingressGwIP	Examples: -			No	string
	Http max concurrent steams per connections for Ingress Gateway.				
	Calculated as TPS*Latency/Number of connections, eg: for 72k TPS, 120 connections, 3 sec latency we get 1800 streams	1536		No	integer
	HTTP initial flow-control window size per stream for Ingress Gateway.				
	Value is in octets.	262144		No	integer
	FQDN to be added as annotation to the Ingress Gateway LoadBalancer service				
ingressGwFQDN	Examples: -	smf.com		No	string
	Enable/disable istio mutual TLS	false		No	boolean
mtlsEnabled					
ingressGwHttpEnabled	Enable/disable to operate istio in http with https	true		No	boolean
	HTTP Port that should be used in dual mode.	8080		No	integer
egressGwTLS	Istio egress gateway TLS			No	object
ingressGwTLS	Istio ingress gateway TLS			No	object
egressGwTLSLi	Istio egress gateway TLS for LI			No	object

global mesh istio ingressGwLi

Description

Istio service mesh LI ingress GW

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGwIP	Specific IP requested for LI Ingress Gateway LoadBalancer service				
	Examples:			No	string
	-				
ingressGwLiMaxConcurrentStreams	Http max concurrent steams per connections for Ingress Gateway Li.				
Calculated as TPS*Latency/Number of connections, eg: for 72k TPS, 120 connections, 3 sec latency we get 1800 streams	1536		No	integer	
serviceAnnotations	Service annotations			No	object

[global mesh istio](#) ingressGwLi/serviceAnnotations

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

[global mesh istio](#) egressGwTLS

Description

Istio egress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio egress gateway TLS				
	Examples:			No	boolean
	- true	false			
mode	Istio egress gateway TLS mode.				
	Examples:	MUTUAL		No	string
	- MUTUAL				
certManager	certManager Configuration			No	object
userProvided	userProvided CERTIFICATES			No	object

[global mesh istio](#) egressGwTLS certManager

Description

certManager Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for certManager configuration	true		No	boolean
	Examples:				
	- true				
certDuration	certDuration Configuration	2160h		No	string
renewBefore	renewBefore Configuration	648h		No	string
organization	organization Configuration	affirmednetworks		No	string
	Examples:				
	- affirmednetworks				
issuerName	issuerName	affirmed-clusterissuer-sbi		No	string
	Examples:				
	- affirmed-clusterissuer-sbi				
issuerType	issuerType	vault		No	string
	Examples:				
	- vault				
pkiAlgorithm	Algorithm for PKI certs -RSA or ECDSA	RSA		No	string
	Examples:				
	- RSA				
pkiKeySize	PKI Key size for certs, if Alogirthm is RSA, valid inputs are 2048,4096,8192. If Alogrithm is ECDSA, valid input is 256	4096		No	string

global mesh istio egressGwTLS userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvided Certificates	false		No	boolean
	Examples:				
	- false				
cacert	cacert Configuration			No	string
	Examples:				
	- Copy and Paste End User generated Certificate				

Parameter	Description	Default	Value/Range	Mandatory	Type
tlscrt configuration					
tlscrt	Examples: - Copy and Paste End User generated Certificate			No	string
tlskey configuration					
tlskey	Examples: - Copy and Paste End User generated Certificate			No	string

global mesh istio ingressGwTLS

Description

Istio ingress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Enabling Istio ingress gateway TLS					
enabled	Examples: - true - false	false		No	boolean
Istio ingress gateway TLS mode.					
mode	Examples: - MUTUAL	MUTUAL		No	string
certManager	certManager Configuration			No	object
userProvided	userProvided CERTIFICATES			No	object

global mesh istio ingressGwTLS certManager

Description

certManager Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Enable/Disable Flag for certManager configuration					
enabled	Examples: - true - false	true		No	boolean
certDuration	certDuration Configuration	2160h		No	string
renewBefore	renewBefore Configuration	648h		No	string
organization Configuration					
organization	Examples: - affirmednetworks	affirmednetworks		No	string
issuerName					
issuerName	Examples: - affirmed-clusterissuer-sbi	affirmed-clusterissuer-sbi		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
issuerType	issuerType				
	Examples:				
	- vault	vault		No	string
pkiAlgorithm	Algorithm for PKI certs -RSA or ECDSA				
	Examples:				
	- RSA	RSA		No	string
pkiKeySize	- ECDSA				
	PKI Key size for certs, if Alogirthm is RSA, valid inputs are 2048,4096,8192. If Alogrithm is ECDSA, valid input is 256				
	Examples:				
	- 256				
	- 2048	4096		No	string
	- 4096				
	- 8192				

global mesh istio ingressGwTLS userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvided Certificates				
	Examples:				
	- false	false		No	boolean
	- true				
cacert	cacert Configuration				
	Examples:			No	string
	- Copy and Paste End User generated Certificate				
tls crt	tls crt configuration				
	Examples:			No	string
	- Copy and Paste End User generated Certificate				
tls key	tls key configuration				
	Examples:			No	string
	- Copy and Paste End User generated Certificate				

global mesh istio egressGwTLSLi

Description

Istio egress gateway TLS for LI

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
Enabling Istio egress gateway TLS for LI					
enabled	Examples: - true - false	false		No	boolean
Istio egress gateway TLS mode for LI.					
mode	Examples: - MUTUAL	MUTUAL		No	string
certManager	certManager Configuration			No	object

global mesh istio egressGwTLSLi [certManager](#)

Description

certManager Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Enable/Disable Flag for certManager configuration					
enabled	Examples: - true - false	false		No	boolean
certDuration	certDuration Configuration	2160h		No	string
renewBefore	renewBefore Configuration	648h		No	string
organization Configuration					
organization	Examples: - affirmednetworks	affirmednetworks		No	string
issuerName					
issuerName	Examples: - affirmed-clusterissuer-li	affirmed-clusterissuer-li		No	string
issuerType					
issuerType	Examples: - vault	vault		No	string
Algorithm for PKI certs -RSA or ECDSA					
pkiAlgorithm	Examples: - RSA - ECDSA	RSA		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
pkiKeySize	PKI Key size for certs, if Alogirthm is RSA, valid inputs are 2048,4096,8192. If Alogrithm is ECDSA, valid input is 256	4096		No	string
	Examples:				
	- 256				
	- 2048				
	- 4096				
	- 8192				

global monitoring

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association			No	object

global monitoring prometheus

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
namespace	Monitoring namespace	fed-prometheus		No	string
	Examples:				
	- fed-prometheus				
enabled	Enable/disable prometheus monitoring	true		No	boolean

global diameterGroups

Description

This deployment variable ensures diameter service names are known to application monitors. The diameter group names given here are referenced in pod-diameter_base scope. If a group name is added to/removed from the below list, user must make sure to add/remove the corresponding entry in diameterGroups of pod-diameter_base scope as well. This is because the group name in below list is referenced by the pod-diameter_base scope.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
groupName	Name of diameter-base group			Yes	string
	Examples:				
	- group1				
enabled	Enable/disable diameter-base group			Yes	boolean
	Examples:				
	- true				
	- false				

global registry

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

[global registry](#) [docker](#)

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string
imagePullSecret	Pull an image from a private registry			No	string
username	Username for private docker registry			No	string
password	Password for private docker registry			No	string

[global envVars](#)

Description

Environment variables

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
fedType	Federation type		Enumerations:		
	Examples:	smf	- amf	No	string
	- smf		- smf		
			- upf		
			- nrf		
			- nssf		
fedUniqueName	Federation unique name				
	Examples:	default		No	string
	- smf				
serviceRegistryNamespace	Service registry namespace				
	Examples:	fed- service- reg		No	string
	- fed-service-reg				
nfSetId	Id of the NFSet to which this Federation belongs to				
	Examples:			No	string
	- north-12				
encryptPaasDataForLI	Enable / Disable LI paas content encryption/decryption. When encryption is enabled, and AKV vault is in use the encryption/decryption key value(Secret pass phrase) will be retrieved from the vault. If AKV vault is not in use it is mandatory to provide a secret pass phrase in the encryptDecryptKey field as a input	true		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
configDataEncryptionEnable	Enable config JSON file encryption. When true, also requires injection of encryption key as kubernetes secret or it won't encrypt.	false		No	boolean
	Examples:				
	- true - false				

global encryptDecryptKey

Description

Secret pass phrase used for Encryption/Decryption of LI Data only. This is a private key needed in case AKV is not enabled and encryptPaasDataForLI is enabled.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable creation of Kubernetes secret for encryptDecryptKey.key	true		No	boolean
Encryption Key value (secret pass phrase). It can be alphanumeric and case sensitive.					
key	Examples:			No	string
	- abcd1234PQRS				

global smfset

Description

Global smfSet parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Unique Set ID of SMF Set					
uniqueSetId	Examples:			No	string
	- north-12				

global grafana

Description

PaaS Grafana association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association	true		No	boolean
Exposed grafana URL					
url	Examples:			No	string
	- http://1.1.1.1:3000				
prometheusinfo	Prometheus server association			No	object

global grafana prometheusinfo

Description

Prometheus server association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
url	Prometheus server URL				
	Examples:	http: //prometheus.fed-prometheus:9090		No	string
	- http: //prometheus.fed-prometheus:9090				

global logging

Description

PaaS logging association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable logging association				
	Examples:	false		No	boolean
	- false				
fluentd	fluentd configurations			No	object
elastic	Elasticsearch association			No	object
enableAddITargets	Enable/disable additional destinations				
	Examples:	false		No	boolean
	- true - false				
addITargets	Additional logging output destination configuration			No	array
alerts	Alerts configuration			No	object

global logging fluentd

Description

fluentd configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	fluentd buffer configurations			No	object

global logging fluentd buffer

Description

fluentd buffer configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Total buffer size. Maximum amount of buffer space each fluentd thread would use to keep logs. After this space is exhausted, fluentd would start deleting oldest logs to make room for new logs.	32m		No	string
retryWait	Interval(seconds) at which the buffer flush is retried in case of failure.	10s		No	string
maxRetries	Max number of retries to flush a buffer chunk. After this is exhausted, fluentd would delete the chunk.	1		No	integer

global logging elastic

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ip	Elasticsearch IP address				
	Examples:			No	string
	- 10.15.10.161				
Port	Elasticsearch port	9200		No	integer

global logging addITargets

Description

Additional logging output destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			Yes	object

global logging addITargets forward

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
host	Hostname or IP Address of the forward server				
	Examples:			No	string
	- 192.168.1.1 - forward-server.com				
port	Port of the forward server				
	Examples:	24224		No	integer
	- 24224				

global logging alerts

Description

Alerts configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable event alerts				
	Examples:	false		No	boolean
	- true				
host	Elasticsearch Host address				
	Examples:			No	string
	- 10.15.10.161				
port	Elasticsearch port	3030		No	integer
realert	Re-alert Info			No	object
receivers	Receiver type to send alerts, Currently supported are slack as 'slack', email as 'email' and HTTP-POST as 'post'			No	array

global logging alerts realert

Description

Re-alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Interval in minutes to re-send an alert				
minutes	Examples: - 2	1		No	integer

global logging alerts receivers

Description

Receiver type to send alerts, Currently supported are slack as 'slack', email as 'email' and HTTP-POST as 'post'

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
slack	Slack alert Info			No	object
email	Mail alert Info			No	object
post	HTTP post alert Info			No	object

global logging alerts receivers slack

Description

Slack alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	The webhook URL that includes your auth data and the ID of the channel (room) you want to post to.				
webhookurl	Examples: - xxxx			No	string

global logging alerts receivers email

Description

Mail alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	An address or list of addresses to sent the alert to				
to_address	Examples: - user1@example.com			No	string
	SMTP host info				
smtp_host	Examples: - 1.1.1.1			No	string
	SMTP port info				
smtp_port	Examples: - 25			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
smtp_ssl	Enable/disable SSL to SMTP server	false		No	boolean
	Examples:				
	- true				
from_addr	This sets the from header in the email. By default, the from address is ElastAlert@ and the domain will be set by the smtp server			No	string
	Examples:				
	- user2@example.com				

global logging alerts receivers post

Description

HTTP post alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
http_post_url	URL for HTTP post			No	string
	Examples:				
	- XXXX				

global license

Description

PaaS License Server Selector

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
flexera	Flexera license server information			No	object

global license flexera

Description

Flexera license server information

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
remoteHost	Flexera license server host			No	string
	Examples:				
	- 10.163.67.251				
remotePort	Flexera license server port			No	string
	Examples:				
	- 7070				
enabled	Use this variable to enable/disable the SMF license.			No	boolean
	Examples:				
	- false				
	- true				

global resource

Description

Default limits and request for each container

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
defaultlimit	Default CPU & memory limits for each container			No	object
defaultrequest	Default CPU & memory request for each container			No	object

global resource defaultlimit

Description

Default CPU & memory limits for each container

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Default CPU limits for each container					
cpu	Examples: - 1	8		No	integer
Default memory limits for each container					
memory	Examples: - 4Gi	2Gi		No	string

global resource defaultrequest

Description

Default CPU & memory request for each container

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Default CPU request for each container					
cpu	Examples: - 10m	10m		No	string
Default memory request for each container					
memory	Examples: - 10Mi	10Mi		No	string

global/test

Description

Test

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
fedSMFHookvalidate	fed-smf hook validation configuration			No	object

global/test/fedSMFHookvalidate

Description

fed-smf hook validation configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
preUpgradeHook	pre-upgrade hook for fed-smf hook validation configuration			No	object
postUpgradeHook	post-upgrade hook for fed-smf hook validation configuration			No	object

global/test/fedSMFHookvalidate/preUpgradeHook

Description

pre-upgrade hook for fed-smf hook validation configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
validate	pre-upgrade hook for fed-smf hook validation is on	true		No	boolean
reporting	pre-upgrade fed-smf hook reporting			No	object
config	pre-upgrade hook for fed-smf hook config			No	object
SMFMonitor	SMFMonitor for pre-upgrade hook for fed-smf			No	object
pod	Pods that has to validate. Validation would be based on percent of pods that would be in ready			No	array
kpi	KPI that has to validate. Validation would be based on percent of pods that would be in ready			No	array

global/test/fedSMFHookvalidate/preUpgradeHook/reporting

Description

pre-upgrade fed-smf hook reporting

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
nfMonitor	Report NF Monitor status at preupgrade hook	true		No	boolean
pod	Report pod status at preupgrade hook	true		No	boolean
kpi	Report kpi status at preupgrade hook	true		No	boolean

global/test/fedSMFHookvalidate/preUpgradeHook/config

Description

pre-upgrade hook for fed-smf hook config

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
max_retry	Number of times that pre-hook validation would check before declaring failure	4		No	integer
retry_interval	how many seconds that we wait unit re-check validation	30		No	integer
kpi_min_metric_value	minimum value needed at metric for KPI calculation	100		No	integer
kpi_sampling_interval	time period that we sample metric for KPI calculation	60		No	integer

global/test/fedSMFHookvalidate/preUpgradeHook/nfMonitor

Description

SMFMonitor for pre-upgrade hook for fed-smf

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
validate	SMFMonitor for pre-upgrade hook for fed-smf validation	true		No	boolean

global/test/fedSMFHookvalidate/preUpgradeHook/pod

Description

Pods that has to validate. Validation would be based on percent of pods that would be in ready

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Pods Name				
	Examples:			Yes	string
	- chf_agent				
activate	Enable/disable pod varification				
	Examples:	true		No	boolean
	- false				
value	percent of pods that has to be ready for passing vali				
	Examples:	100		Yes	integer
	- 90				

global/test/fedSMFHookvalidate/preUpgradeHook/kpi

Description

KPI that has to validate. Validation would be based on percent of pods that would be in ready

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	KPI Name				
	Examples:			Yes	string
	- smfcc_nsmf_pdu_session_update_sm_context_percentage				
activate	Enable/disable KPI varification				
	Examples:	false		No	bool
	- false				
value	value that kpi will compare with				
	Examples:	80		Yes	integ
	- 70				
operation	How to calcuklate KPI from metrics for now two operations (percent, acceptable_failure_percent)				
	Examples:	acceptable_failure_percent		Yes	string
	- acceptable_failure_percent				
metric1	name of first metric that used for calculate metric				
	Examples:	smfcc_nsmf_pdu_session_update_sm_context_successes		Yes	string
	- smfcc_nsmf_pdu_session_update_sm_context_successes				
metric2	name of second metric that used for calculate metric				
	Examples:	smfcc_nsmf_pdu_session_update_sm_context_attempt		Yes	string
	- smfcc_nsmf_pdu_session_update_sm_context_attempt				

global/test/fedSMFHookvalidate/postUpgradeHook

Description

post-upgrade hook for fed-smf hook validation configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
validate	post-upgrade hook for fed-smf hook validation is on	true		No	boolean
config	post-upgrade hook for fed-smf hook config			No	object
smfMonitor	SMFMonitor for post-upgrade hook for fed-smf			No	object
pod	Pods that has to validate. Validation would be based on percent of pods that would be in ready			No	array
kpi	KPI that has to validate. Validation would be based on percent of pods that would be in ready			No	array

global/test/fedSMFHookvalidate/postUpgradeHook/config

Description

post-upgrade hook for fed-smf hook config

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
max_retry	Number of times that post-hook validation would check before declaring failure	6		No	integer
retry_interval	how many seconds that we wait unit re-check validation	30		No	integer
kpi_min_metric_value	minimum value needed at metric for KPI calculation	100		No	integer
kpi_sampling_interval	time period that we sample metric for KPI calculation	60		No	integer

global/test/fedSMFHookvalidate/postUpgradeHook/nfMonitor

Description

SMFMonitor for post-upgrade hook for fed-smf

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
validate	smfMonitor for post-upgrade hook for fed-smf validation	true		No	boolean

global/test/fedSMFHookvalidate/postUpgradeHook/pod

Description

Pods that has to validate. Validation would be based on percent of pods that would be in ready

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Pods Name				
name	Examples: - chf_agent			Yes	string
	Enable/disable pod varification				
activate	Examples: - false	true		No	boolean
	percent of pods that has to be ready for passing valid				
value	Examples: - 90	100		Yes	integer

global/test/fedSMFHookvalidate/postUpgradeHook/kpi

Description

KPI that has to validate. Validation would be based on percent of pods that would be in ready

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	KPI Name				
	Examples:			Yes	string
	- smfcc_nsmf_pdu_session_update_sm_context_percentage				
activate	Enable/disable KPI varification				
	Examples:	false		No	boolean
	- false				
value	value that kpi will compare with				
	Examples:	80		Yes	integer
	- 70				
operation	How to calcuklate KPI from metrics for now two operations (percent, acceptable_failure_percent)				
	Examples:	acceptable_failure_percent		Yes	string
	- acceptable_failure_percent				
metric1	name of first metric that used for calculate metric				
	Examples:	smfcc_nsmf_pdu_session_update_sm_context_successes		Yes	string
	- smfcc_nsmf_pdu_session_update_sm_context_successes				
metric2	name of second metric that used for calculate metric				
	Examples:	smfcc_nsmf_pdu_session_update_sm_context_attempt		Yes	string
	- smfcc_nsmf_pdu_session_update_sm_context_attempt				

[global topologySpreadConstraints](#)

Description

Pod topology spread constraints control how pods of given microservice type are spread across the cluster among failure-domains such as regions, zones, nodes, and other user-defined topology domains. This can help to achieve high availability as well as efficient resource utilization.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable pod topology spread constraints				
	Examples:	true		No	boolean
	- false				
	- true				
constraints	List of pod topology spread constraints to be applied.			No	array

[global topologySpreadConstraints](#) constraints

Description

List of pod topology spread constraints to be applied.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Definition of pod topology spread constraint to be applied to the pod specification.			No	object

global topologySpreadConstraints constraints 0

Description

Definition of pod topology spread constraint to be applied to the pod specification.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxSkew	Describes the degree to which pods may be unevenly distributed. It's the maximum permitted difference between the number of matching pods in any two topology domains of a given topology type. It must be greater than zero. Examples: - 1	1		No	integer
topologyKey	Its the key of node labels. If two nodes are labelled with this key and have identical values for that label, the Kubernetes scheduler treats both nodes as being in the same topology. The scheduler tries to place a balanced number of Pods into each topology domain. Examples: - kubernetes.io/hostname	kubernetes.io/hostname		No	string
whenUnsatisfiable	Indicates how to deal with a pod if it doesn't satisfy the defined pod topology spread constraint. Examples: - ScheduleAnyway - DoNotSchedule	ScheduleAnyway		No	string

global externalGtpcSvc

Description

External service parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable external service Examples: - false	true		Yes	boolean
name	Name of external gtpc agent service Examples: - sgw	pgw	Enumerations: - pgw - s11-mme - sgw - s2b-pgw - s5-s8-s2a-s2b-pgw - s5-s8-sgw - s11-sgw	Yes	string
loadBalancerIP	IP for the load balancer. More info here - https://kubernetes.io/docs/tasks/access-application-cluster/create-external-load-balancer/ Examples: - 1.1.1.1			Yes	string

Parameter	Description	Default	Value/Range	Mandatory	Type
serviceAnnotations	Service annotations			No	object
	If specified, this is added as an annotation to the gtpc_agent service. Other applications can then query to find the FQDN through which external peers can reach this application				
loadBalancerFQDN	Examples: - pgw.affirmed.com			No	string
type	Interface type for gtpc_agent microservice			Yes	array

global externalGtpcSvc serviceAnnotations

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

global externalPfcpSvc

Description

External service parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable external service				
enabled	Examples: - true	true		Yes	boolean
	Name of external pfcp service				
name	Examples: - sxa-sxb-n4	sxa-sxb-n4	Enumerations: - sxa-sxb-n4	Yes	string
	IP for the load balancer. More info here - https://kubernetes.io/docs/tasks/access-application-cluster/create-external-load-balancer/				
loadBalancerIP	Examples: - 1.1.1.1			Yes	string
serviceAnnotations	Service annotations			No	object
	If specified, this is added as an annotation to the pfcp service. Other applications can then query to find the FQDN through which external peers can reach this application				
loadBalancerFQDN	Examples: - smf.sxa-sxb-n4.msft.com			No	string
type	Interface type for pfcp microservice			Yes	array

global externalPfcpSvc serviceAnnotations

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

pod-fileserver

Description

PaaS Fileserver microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable fileserver				
enabled	Examples: - false	true		No	boolean
deployment	Deployment parameters			No	object
pvc	Persistent Volume Claim (PVC) configuration			No	object

[pod-fileserver deployment](#)

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer

[pod-fileserver pvc](#)

Description

Persistent Volume Claim (PVC) configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
web	PVC web configuration			No	object
cfg	PVC cfg configuration			No	object

[pod-fileserver pvc web](#)

Description

PVC web configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Requests storage for pvc				
requestsStorage	Examples: - 25Gi	5Gi		No	string
	Storage class name for pvc				
storageClassName	Examples: - rook-cephfs	web		No	string

[pod-fileserver pvc cfg](#)

Description

PVC cfg configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
requestsStorage	Requests storage for pvc				
	Examples:	5Gi		No	string
	- 25Gi				
storageClassName	Storage class name for pvc				
	Examples:	cfg		No	string
	- rook-cephfs				

pod-ulb

Description

Unified Load Balancer Microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable Unified Load Balancer microservice				
	Examples:	true		No	boolean
	- false				
rbacEnabled	Configuring rbacEnabled to true will create clusterrolebinding. Configuring rbacEnabled to false, clusterrolebinding will not be created.				
	Examples:	true		No	boolean
	- false				
clusterRole	clusterrole and PSP for is created as a part of fed-rbac. clusterrole options are restricted-cr, permissive-network-cr, permissive-full-cr				
	Examples:	permissive-network-cr		No	string
	- permissive-network-cr - permissive-full-cr				
serviceAccountName	serviceAccountName configuration is used to create serviceaccount per service type				
	Examples:	ulb-serviceaccount		No	string
	- ulb-serviceaccount				
deployment	Deployment parameters			No	object

pod-ulb deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
config	List configs related to deployments of ULB			No	object

pod-ulb deployment config

Description

List configs related to deployments of ULB

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
additionalNetworks	Networks defined over Multus managed interfaces.			No	array
deploymentGroups	List of deployment groups			No	array

pod-ulb deployment config [additionalNetworks](#)

Description

Networks defined over Multus managed interfaces.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Name of the network.				
name	Examples: - corenet			Yes	string
	Network attachment definition name to identify the interface pool from which interfaces are assigned by Multus.				
netAttachDefName	Examples: - net-sr1			No	string
	Network attachment definition namespace to identify the interface pool from which interfaces are assigned by Multus.				
netAttachDefNamespace	Examples: - {{- .Release.Namespace }}			No	string
	Resource name to identify the network-attachment-definition.				
resourceName	Examples: - sr1			No	string
	Prefix used to address SR-IOV network resources.				
resourcePrefix	Examples: - dataplane.io			No	string
	VLAN identifier to be used on the secondary interface.				
vlanId	Examples: - 1480	0		No	integer
	Flag to specify if SR-IOV mode is enabled.				
sriovEnabled	Examples: - true	false		No	boolean
	Flag to specify if network attach definition needs to be created.				
createSriovNetAttachDefs	Examples: - true	false		No	boolean

pod-ulb deployment config [deploymentGroups](#)

Description

List of deployment groups

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
Name of the deployment group					
name	Examples: - access			Yes	string
scalingPolicy	Scaling policy of the deployment group			No	object
schedulingPolicy	Scheduling policy of the deployment group			No	object
Endpoints info					
endpoints	Examples: - [OrderedDict({'ips': ['10.163.68.34'], 'defaultGw': '10.163.68.1', 'prefixLength': 24, 'udp': OrderedDict({'enabled': True, 'ports': [8000, 8010]}), 'frontEnd': OrderedDict({'multus': OrderedDict({'networkName': 'accessnet1', 'lbExtDevice': 'net2'})})})]			Yes	array
frontEnd	Type of frontEnd to use for the deployment group			No	object

pod-ulb deployment config deploymentGroups scalingPolicy

Description

Scaling policy of the deployment group

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Number of replicas for a deploement group					
replicas	Examples: - 1			No	integer
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

pod-ulb deployment config deploymentGroups scalingPolicy hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Enable/disable HPA					
enabled	Examples: - true - false	true		No	boolean
Infra container HPA CPU requests					
infraCpuRequests	Examples: - 10m	10m		No	string
Worker container HPA CPU requests					
workerCpuRequests	Examples: - 980m	980m		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
workerCpuLimits	Worker container HPA CPU limits				
	Examples:	1000m		No	string
	- 1000m				
maxReplicas	Pod maximum replicas				
	Examples:	1	min: 0	No	integer
	- 5				
minReplicas	Pod mininum replicas				
	Examples:	1	min: 0	No	integer
	- 2				
averageUtilization	Pod average utilization				
	Examples:	75	min: 0 max: 100	No	integer
	- 75				

pod-ulb deployment config deploymentGroups schedulingPolicy

Description

Scheduling policy of the deployment group

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
nodeSelector	Node selector to schedule the pod on a specific node.			No	array

pod-ulb deployment config deploymentGroups schedulingPolicy nodeSelector

Description

Node selector to schedule the pod on a specific node.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
label	Label name to select the node				
	Examples:			No	string
	- kubernetes.io/hostname				
value	Value of the label to select the node				
	Examples:			No	string
	- aks-worker-33339762-vmss000000				

pod-ulb deployment config deploymentGroups endpoints

Description

Endpoints info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ips	List of Endpoint IP addresses (IPv4/IPv6)				
	Examples:			Yes	array
	- ['10.163.68.34', '2275:0:ca:12b:3e94:d505:14e2:8ff0']				

Parameter	Description	Default	Value/Range	Mandatory	Type
	Default Gateway IP				
defaultGw	Examples: - 10.163.68.1 - 2275:0:ca:12b::1			No	string
	Prefix Length				
prefixLength	Examples: - 24 - 64			No	integer
udp	UDP protocol			No	object
	Type of frontEnd to use for the endpoint				
frontEnd	Examples: - OrderedDict({'multus': OrderedDict({'networkName': 'accessnet1', 'lbExtDevice': 'net2'})})			No	object

pod-ulb deployment config deploymentGroups endpoints udp

Description

UDP protocol

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable UDP protocol for the endpoint				
enabled	Examples: - true	false		No	boolean
ports	List of udp ports			No	array

pod-ulb deployment config deploymentGroups endpoints frontEnd

Description

Type of frontEnd to use for the endpoint

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Multus frontEnd.				
multus	Examples: - OrderedDict({'networkName': 'accessnet', 'lbExtDevice': 'net2'})			No	object

pod-ulb deployment config deploymentGroups endpoints frontEnd multus

Description

Multus frontEnd.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	AdditionalNetwork name which is already defined.				
networkName	Examples: - accessnet			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
lbExtDevice	Pod network interface device used for external communication.				
	Examples: - net2			No	string
mtu	MTU for pod network interface device used for external communication. Range is 1280-9216. Default is to not set the MTU on the interface.		min: 1280 max: 9216	No	integer
	Examples: - 9008				

pod-ulb deployment config deploymentGroups frontEnd

Description

Type of frontEnd to use for the deployment group

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
hostMapped	Host Mapped Frontend				
	Examples: - OrderedDict({'lbEthDevice': 'ens3', 'lbExtDevice': 'ens6', 'networkMode': 'hostPort'})			No	object
externalLb	External Load Balancer Frontend.				
	Examples: - OrderedDict({'empty': 'true'})			No	object
multus	Multus frontEnd.				
	Examples: - OrderedDict({'networkName': 'accessnet', 'lbExtDevice': 'net2'})			No	object

pod-ulb deployment config deploymentGroups frontEnd hostMapped

Description

Host Mapped Frontend

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
lbEthDevice	Pod network interface device used for internal communication (eth0 is used if this value is not specified).				
	Examples: - ens3			No	string
lbExtDevice	Pod network interface device used for external communication. This field is mandatory in case networkMode is hostNetwork.				
	Examples: - ens6			No	string
networkMode	Network mode .				
	Examples: - hostPort - hostNetwork			No	string

pod-ulb deployment config deploymentGroups frontEnd externalLb

Description

External Load Balancer Frontend.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Empty field to select externalLb mode.				
empty	Examples: - true			No	boolean

pod-ulb deployment config deploymentGroups frontEnd multus

Description

Multus frontEnd.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	AdditionalNetwork name which is already defined.				
networkName	Examples: - accessnet			No	string
	Pod network interface device used for external communication.				
lbExtDevice	Examples: - net2			No	string
	MTU for pod network interface device used for external communication. Range is 1280-9216. Default is to not set the MTU on the interface.				
mtu	Examples: - 9008			No	integer
			min: 1280 max: 9216		

onPrem

Description

On-premises deployment.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable On-premises deployment				
enabled	Examples: - true	true		No	boolean

pod-cdpln

Description

pod cdpln

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable Pod cdpln				
enabled	Examples: - true	true		No	boolean

pod-routing

Description

Pod routing

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Enable/disable Pod routing					
enabled	Examples: - true	true		No	boolean
deployment	deploment			No	object

[pod-routing](#) deployment

Description

deploment

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas					
replicas	Examples: - 1	1		No	integer

pod-interface_mgr

Description

pod interface mgr

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Enable/disable pod interface mgr					
enabled	Examples: - true	true		No	boolean
deployment	deploment			No	object

[pod-interface_mgr](#) deployment

Description

deploment

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas					
replicas	Examples: - 1	1		No	integer

pod-lb_ppe

Description

LB PPE microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable LB PPE microservice				
enabled	Examples: - true	true		No	boolean
rbacEnabled	Configuring rbacEnabled to true will create clusterrolebinding. Configuring rbacEnabled to false, clusterrolebinding will not be created. Examples: - false	true		No	boolean
clusterRole	clusterrole and PSP for is created as a part of fed-rbac. clusterrole options are restricted-cr, permissive-network-cr, permissive-full-cr Examples: - permissive-full-cr	permissive-full-cr		No	string
serviceAccountName	serviceAccountName configuration is used to create serviceaccount per pod Examples: - ppe-serviceaccount	ppe-serviceaccount		No	string
ppeFirstWorker	First core dataplane that will be allowed to use. This is not a physical core number; it is a core number within the range allocated to the pod. I.e if a dataplane pod is allocated 10 cores, the first core has to be in the 0-9 range Examples: - 1	1		No	string
ppeNumWorkers	Number of cores allocated to dataplane, including the first core. E.g. if first core is 2 and ppeNumWorkers is 7, then cores 2,3,4,5,6,7,8,9 will be allocated to dataplane Examples: - 2	2		No	string
ppeloScaling	Dataplane I/O resource distribution. Options: 1. grouped: all ports' rx queues are handled by a single I/O core. 2. shared-cores: there are as many I/O cores as rx-queues on each interfaces. The Xth queue of each interfaces share the Xth I/O core. 3. separated-cores: there are as many I/O cores as there rx-queues total. Each rx-queue is placed on an individual I/O core Examples: - separated-cores	separated-cores	Enumerations: - grouped - shared-cores - separated-cores	No	string
vlanStripping	Enable/disable vlan stripping on dataplane ports Examples: - true	false		No	boolean
enableJumboFrames	Enable/disable jumbo frame support Examples: - true	false		No	boolean
deployment	Deployment parameters			No	object
resources	The Resources Schema			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
guaranteedScheduling	Define CPU & memory limits for 3 containers: ppe, infra and ulb. All 3 need to follow the config presented in https://kubernetes.io/docs/tasks/configure-pod-container/quality-service-pod/#create-a-pod-that-gets-assigned-a-qos-class-of-guaranteed Note: If a Container specifies its own memory limit, but does not specify a memory request, Kubernetes automatically assigns a memory request that matches the limit. Similarly, if a Container specifies its own CPU limit, but does not specify a CPU request, Kubernetes automatically assigns a CPU request that matches the limit. Don't specify requests.			No	object
sriov	SRIOV parameters			No	array
netAttachDefs	Networking attachment configuration for the VM node. Supported drivers are Intel and Mellanox			No	object
tracing	Tracing parameters			No	object

pod-lb_ppe deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer
	Enable/disable capture-agent deployment				
deployCaptureAgent	Examples: - true	false		No	boolean
config	List configs related to deployments of LB PPE			No	object

pod-lb_ppe deployment config

Description

List configs related to deployments of LB PPE

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
deploymentGroups	List of deployment groups for LB PPE			No	array

pod-lb_ppe deployment config deploymentGroups

Description

List of deployment groups for LB PPE

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Name of the deployment group				
name	Examples: - external-ips			Yes	string
	Endpoints info				
endpoints	Examples: - [OrderedDict({'ips': ['10.163.68.34'], 'defaultGw': '10.163.68.1', 'udp': OrderedDict({'enabled': True, 'ports': [8000, 8010]}))}]			Yes	array

pod-lb_ppe deployment config deploymentGroups endpoints

Description

Endpoints info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ips	List of Endpoint IP addresses (IPv4/IPv6)				
	Examples:			Yes	array
	- ['10.163.68.34', '2275:0:ca:12b:3e94:d505:14e2:8ff0']				
defaultGw	Default Gateway IP				
	Examples:			No	string
	- 10.163.68.1 - 2275:0:ca:12b::1				
udp	UDP protocol			No	object

pod-lb_ppe deployment config deploymentGroups endpoints udp

Description

UDP protocol

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable UDP protocol for the endpoint				
	Examples:	false		No	boolean
	- true				
ports	List of udp ports			No	array

pod-lb_ppe resources

Description

The Resources Schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
hugepagesType	Huge pages type				
	Examples:	2Mi		No	string
	- 2Mi				
ppeCpuRequests	LB PPE container CPU usage threshold				
	Examples:	1100m		No	string
	- 1500m				
ppeCpuLimits	LB PPE container CPU usage maximum Limit				
	Examples:	2000m		No	string
	- 2000m				
ulbCpuRequests	LB ULB container CPU usage threshold				
	Examples:	1000m		No	string
	- 1500m				

Parameter	Description	Default	Value/Range	Mandatory	Type
ppeMemory	Allocated memory for LB PPE container	2Gi		No	string
	Examples: - 4Gi				
ppeHugepagesSize	Huge pages size. More information here - https://wiki.debian.org/Hugepages	4Gi		No	string
	Examples: - 4Gi				

pod-lb_ppe guaranteedScheduling

Description

Define CPU & memory limits for 3 containers: ppe, infra and ulb. All 3 need to follow the config presented in <https://kubernetes.io/docs/tasks/configure-pod-container/quality-service-pod/#create-a-pod-that-gets-assigned-a-qos-class-of-guaranteed> Note: If a Container specifies its own memory limit, but does not specify a memory request, Kubernetes automatically assigns a memory request that matches the limit. Similarly, if a Container specifies its own CPU limit, but does not specify a CPU request, Kubernetes automatically assigns a CPU request that matches the limit. Don't specify requests.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable guaranteedScheduling for LB PPE microservice	true		No	boolean
	Examples: - true				
infraCpuLimit	Infra container CPU usage maximum Limit	100m		No	string
	Examples: - 100m				
infraMemoryLimit	Infra container memory usage maximum Limit	256Mi		No	string
	Examples: - 2Gi				
ulbCpuLimit	ULB container CPU usage maximum Limit	3000m		No	string
	Examples: - 1000m				
ulbMemoryLimit	ULB container memory usage maximum Limit	2Gi		No	string
	Examples: - 2Gi				
ppeCpuLimit	LB PPE container CPU usage maximum Limit	2000m		No	string
	Examples: - 2000m				
ppeMemoryLimit	LB PPE container memory usage maximum Limit	8Gi		No	string
	Examples: - 2Gi				

pod-lb_ppe sriov

Description

SRIOV parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
labels	SRIOV label names configured on cluster				
	Examples:			Yes	string
	- label1				
nbIfc	Number of interfaces/NICs on n3 or n6				
	Examples:	1		Yes	string
	- 1				

pod-lb_ppe netAttachDefs

Description

Networking attachment configuration for the VM node. Supported drivers are Intel and Mellanox

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable non-default network driver. The default driver is intel. Intel needs this disabled.				
	Examples:	false		No	boolean
	- true				
annotation	SR-IOV network driver parameters				
	Examples:	sriov-net1, sriov-net2		No	string
	- sriov-net1, sriov-net2				

pod-lb_ppe tracing

Description

Tracing parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable tracing				
	Examples:	false		No	boolean
	- false				
samplerType	Sampler type. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration		Enumerations:		
	Examples:	probabilistic	- const - probabilistic - ratelimiting - remote	No	string
	- probabilistic				
samplerParam	Sampler parameter. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration				
	Examples:	1.0		No	string
	- 1.0				
agentPort	UDP port exposed by jaeger-agent				
	Examples:	6831		No	string
	- 6831				

Parameter	Description	Default	Value/Range	Mandatory	Type
logEnabled	Enable/disable jaeger logging	false	Enumerations:	No	string
	Examples: - false		- true - false		

pod-cfgmgr

Description

Config Manager microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable cfgmgr	true		No	boolean
	Examples: - false				
confd	Conf parameters			No	object
rbacEnabled	Configuring rbacEnabled to true will create clusterrolebinding. Configuring rbacEnabled to false, clusterrolebinding will not be created.	true		No	boolean
	Examples: - false				
clusterRole	clusterrole and PSP for is created as a part of fed-rbac. clusterrole options are restricted-cr, permissive-network-cr, permissive-full-cr	permissive-full-cr		No	string
	Examples: - permissive-full-cr				
serviceAccountName	serviceAccountName configuration is used to create serviceaccount per pod	cfgmgr-serviceaccount		No	string
	Examples: - cfgmgr-serviceaccount				
deployment	Deployment parameters			No	object
security	Tacacs Service parameters			No	object
service	Service parameters			No	object
tlscipherSuite	Set the cipherSuiteString for TLS that terminates the RESTCONF interface on the cfgmr pod confd process. The ciphers are colon delimited, and this set in this yaml file is the full set of 5 supported by confd. An operator can easily remove entries to remove any considered weak. This string will replace the entire string in the config file at cfgmgr pod startup time. It is not a merge, it's an overwrite			No	object
sshdcipherSuite	Set the cipherSuiteString for sshd that terminates ssh connections (for CLI or NETCONF) on the cfgmgr pod sshd process. The ciphers are comma delimited and the set in this yaml file is defaulted to the recommended 3 ciphers. An operator can easily remove entries to remove any considered weak. This string will replace the entire string in the config file at cfgmgr pod startup time. It is not a merge, it's an overwrite			No	object
cfgmgrFQDN	FQDN for config manager endpoint.	cfgmgr.com		No	string
	Examples: - cfgmgr.com				
certManager	certManager Configuration			No	object

[pod-cfgmgr](#) confd

Description

Confd parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
aes256cfb128Key	encoded confd aes256cfb128Key, echo f9c4065f6592b38cc3dbaf2033f73b6c54751c4425faf688857704004306d65a	base64 -w 100			No

pod-cfgmgr deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer

pod-cfgmgr security

Description

Tacacs Service parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
tacacs_protocol	Tacacs Service Protocol			No	string
tacacs_service	Tacacs Service Name			No	string
enable_tacacs_accounting	enable/disable Tacacs Accounting			No	string
tacacs_servers	Tacacs Servers Parameters			No	array

pod-cfgmgr security tacacs_servers

Description

Tacacs Servers Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
auth_timeout	Tacacs Auth Timeout			No	string
auth_type	Tacacs Auth Type			No	string
ip_address	Tacacs IP Address			No	string
key	Tacacs Key			No	string
port	Tacacs Port			No	string

pod-cfgmgr service

Description

Service parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Load Balancer IP address				
loadBalancerIP	Examples: - 10.1.1.101			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
	If specified, this is added as an annotation to the cfgmgr service. Other applications can then query to find the FQDN through which external peers can reach this application				
loadBalancerFQDN	Examples: - cfgmgr.smf.affirmed.com			No	string
serviceAnnotations	Service annotations			No	object

pod-cfgmgr [service](#) serviceAnnotations

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

pod-cfgmgr [tls](#) cipherSuite

Description

Set the cipherSuiteString for TLS that terminates the RESTCONF interface on the cfgmgr pod confd process. The ciphers are colon delimited, and this set in this yaml file is the full set of 5 supported by confd. An operator can easily remove entries to remove any considered weak. This string will replace the entire string in the config file at cfgmgr pod startup time. It is not a merge, it's an overwrite

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable tlsCipherSuite config				
enabled	Examples: - false	true		No	boolean
cipherString	Colon separated ciphers for TLS that terminates the RESTCONF interface on the cfgmgr pod confd process Examples: - DHE-DSS-AES256-SHA:DHE-RSA-AES256-SHA:DHE-DSS-AES128-SHA256:DHE-RSA-AES128-SHA256:DHE-RSA-AES128-SHA	DHE-DSS-AES256-SHA:DHE-RSA-AES256-SHA:DHE-DSS-AES128-SHA256:DHE-RSA-AES128-SHA256:DHE-RSA-AES128-SHA		No	string

pod-cfgmgr [ssh](#) dcipherSuite

Description

Set the cipherSuiteString for sshd that terminates ssh connections (for CLI or NETCONF) on the cfgmgr pod sshd process. The ciphers are comma delimited and the set in this yaml file is defaulted to the recommended 3 ciphers. An operator can easily remove entries to remove any considered weak. This string will replace the entire string in the config file at cfgmgr pod startup time. It is not a merge, it's an overwrite

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable sshdcipherSuite config				
enabled	Examples: - false	true		No	boolean
cipherString	Comma separated ciphers to set the cipherSuiteString for sshd that terminates ssh connections (for CLI or NETCONF) on the cfgmgr pod sshd process Examples: - aes256-ctr,aes192-ctr	aes256-ctr,aes192-ctr,aes128-ctr		No	string

pod-cfgmgr certManager

Description

certManager Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for certManager configuration	true		No	boolean
	Examples:				
	- true				
	- false				
certDuration	certDuration Configuration			No	string
	Examples:				
	- 10h				
renewBefore	renewBefore Configuration			No	string
	Examples:				
	- 1h				
organization	organization Configuration	affirmednetworks		No	string
	Examples:				
	- affirmednetworks				
issuerName	issuerName			No	string
	Examples:				
	- affirmed-clusterissuer-sbi				
issuerType	issuerType			No	string
	Examples:				
	- vault				
pkiAlgorithm	Algorithm for PKI certs -RSA or ECDSA	RSA		No	string
	Examples:				
	- RSA				
	- ECDSA				
pkiKeySize	PKI Key size for certs, if Alogirthm is RSA, valid inputs are 2048,4096,8192. If Alogrithm is ECDSA, valid input is 256	4096		No	string
	Examples:				
	- 256				
	- 2048				
	- 4096				
	- 8192				

pod-istio_gw

Description

Istio Gateway microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable istio-gw	true		No	boolean
	Examples:				
	- false				
podDisruptionBudget	Pod Disruption Budget parameters			No	object
istioNspace	Istio namespace	fed-istio		No	string
	Examples:				
	- fed-istio				
ingressGateway	Ingress gateway parameters			No	object
egressGateway	Egress gateway parameters			No	object
paasSelector	PAAS parameters			No	object

pod-istio_gw podDisruptionBudget

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	1		No	string

pod-istio_gw ingressGateway

Description

Ingress gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable ingress gateway	true		No	boolean
	Examples:				
	- false				

pod-istio_gw egressGateway

Description

Egress gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable egress gateway	true		No	boolean
	Examples:				
	- false				

pod-istio_gw paasSelector

Description

PAAS parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
jaegerHostName	Jaeger host (IP or FQDN)	fqdn.com		No	string
	Examples:				
	- 10.10.10.10				
	- fqdn.com				

pod-istio_gw_li

Description

Istio LI Gateway microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable istio-gw-li	true		No	boolean
	Examples:				
	- false				
podDisruptionBudget	Pod Disruption Budget parameters			No	object
mesh	PaaS service mesh associations			No	object
istioNspace	Istio namespace	fed-istio		No	string
	Examples:				
	- fed-istio				
ingressGateway	Ingress LI gateway parameters			No	object
egressGateway	Egress LI gateway parameters			No	object
paasSelector	PAAS parameters			No	object

[pod-istio_gw_li](#) [podDisruptionBudget](#)

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	1		No	string

[pod-istio_gw_li](#) [mesh](#)

Description

PaaS service mesh associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio service mesh association			No	object

[pod-istio_gw_li](#) [mesh](#) [istio](#)

Description

Istio service mesh association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGw	Service mesh ingress gateway LI				
	Examples: - ingress-gateway			No	string
ingressGwIP	Specific IP requested for Ingress Gateway LI LoadBalancer service				
	Examples: -			No	string
ingressGwFQDN	FQDN to be added as annotation to the Ingress Gateway LI LoadBalancer service				
	Examples: -	smfli.com		No	string
mtlsEnabled	Enable/disable istio mutual TLS	false		No	boolean

pod-istio_gw_li ingressGateway

Description

Ingress LI gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable LI ingress gateway				
	Examples: - false	true		No	boolean

pod-istio_gw_li egressGateway

Description

Egress LI gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable egress LI gateway				
	Examples: - false	true		No	boolean
hpa	Egress LI gateway hpa parameters			No	object

pod-istio_gw_li egressGateway hpa

Description

Egress LI gateway hpa parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable egress LI gateway HPA				
	Examples: - false	true		No	boolean
workerCpuRequests	CPU request egress application				
	Examples: - 200m	200m		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
minReplicas	Specify the minimum replica count for egress LI gateway	1		No	integer
	Examples:				
	- 3				
maxReplicas	Specify the maximum replica count for egress LI gateway	5		No	integer
	Examples:				
	- 5				
averageUtilization	Specify the target CPU utilization level when hpa would trigger	80		No	integer
	Examples:				
	- 80				

pod-istio_gw paasSelector

Description

PAAS parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
jaegerHostName	Jaeger host (IP or FQDN)	fqdn.com		No	string
	Examples:				
	- 10.10.10.10				
	- fqdn.com				

pod-nrf_agent

Description

NRF Agent microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable NRF agent	true		No	boolean
	Examples:				
	- false				
podDisruptionBudget	Pod Disruption Budget parameters			No	object
deployment	Deployment parameters			No	object

pod-nrf_agent podDisruptionBudget

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	1		No	string

pod-nrf_agent deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer
	Examples:				
	- 1				
strategy	Deployment Update strategy			No	object

pod-nrf_agent deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-nrf_agent deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	1		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	1		No	string

pod-sub_analyzer

Description

Sub Analyzer microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable sub-analyzer	true		No	boolean
	Examples:				
	- false				
podDisruptionBudget	Pod Disruption Budget parameters			No	object
deployment	Deployment parameters			No	object
upgrade	Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicator are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

pod-sub_analyzer podDisruptionBudget

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	1		No	string

pod-sub_analyzer deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer
strategy	Deployment Update strategy			No	object
	Virtual service host (IP or FQDN)				
apiServiceHost	Examples: - analyzer.com	1		No	string

pod-sub_analyzer deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-sub_analyzer deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	1		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	1		No	string

pod-sub_analyzer upgrade

Description

Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable canary sequence				
	Examples:	false		No	boolean
	- false				
canaryVersWeight	Canary pod weight percentage	0	min: 0 max: 100	No	integer
stableVersWeight	Stable pod weight percentage	0	min: 0 max: 100	No	integer
stableVersion	Stable pod image version				
	Examples:			No	string
	- 0.0.0				
stableInfralImage	Infra container stable image				
	Examples:			No	string
	-				
stableWorkerImage	Worker container stable image				
	Examples:			No	string
	-				

pod-sub_analyzer hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA				
	Examples:	true		No	boolean
	- true				
infraCpuRequests	Infra container HPA CPU requests				
	Examples:	20m		No	string
	- 20m				
workerCpuRequests	Worker container HPA CPU requests				
	Examples:	200m		No	string
	- 200m				
workerCpuLimits	Worker container HPA CPU limits				
	Examples:	1000m		No	string
	- 1000m				
maxReplicas	The maximum number of simultaneous instances of this pod allowed				
	Examples:	0		No	integer
	- 5				

Parameter	Description	Default	Value/Range	Mandatory	Type
minReplicas	The minimum number of simultaneous instances of this pod allowed	1		No	integer
	Examples:				
	- 1				
averageUtilization	Pod average utilization	80		No	integer
	Examples:				
	- 80				

pod-timer

Description

Timer microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable timer microservice	true		No	boolean
	Examples:				
	- false				
cnaInfraThreadPoolSizeDbClient	Infra thread pool size count	1000		No	string
	Examples:				
	- 1000				
strategy	Deployment Update strategy			No	object
deployment	Deployment parameters			No	object

[pod-timer deployment strategy](#)

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

[pod-timer deployment strategy rollingUpdate](#)

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	1		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	1		No	string

[pod-timer deployment](#)

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	3		No	integer

pod-pfcp_c

Description

PFCP-C microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable PFCP-C microservice				
enabled	Examples: - false	true		No	boolean
podDisruptionBudget	Pod Disruption Budget parameters			No	object
deployment	Deployment parameters			No	object
service	Service parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
tracing	Tracing parameters			No	object
upgrade	Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.			No	object

[pod-pfcp_c](#) podDisruptionBudget

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	1		No	string

[pod-pfcp_c](#) deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer

Parameter	Description	Default	Value/Range	Mandatory	Type
strategy	Deployment Update strategy			No	object

[pod-pfcp_c deployment strategy](#)

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

[pod-pfcp_c deployment strategy rollingUpdate](#)

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	1		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	1		No	string

[pod-pfcp_c service](#)

Description

Service parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Load Balancer IP address				
loadBalancerIP	Examples: - 10.1.1.101			No	string
	If specified, this is added as an annotation to the PFCP service. Other applications can then query to find the FQDN through which external peers can reach this application				
externalFqdn	Examples: - pfcp.smf.affirmed.com			No	string
serviceAnnotations	Service annotations			No	object

[pod-pfcp_c service serviceAnnotations](#)

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

[pod-pfcp_c hpa](#)

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA	false		No	boolean
	Examples:				
	- false				
infraCpuRequests	Infra container HPA CPU requests	10m		No	string
	Examples:				
	- 10m				
workerCpuRequests	Worker container HPA CPU requests	390m		No	string
	Examples:				
	- 390m				
workerCpuLimits	Worker container HPA CPU limits	1000m		No	string
	Examples:				
	- 1000m				
maxReplicas	The maximum number of simultaneous instances of this pod allowed	6		No	integer
	Examples:				
	- 6				
minReplicas	The mininum number of simultaneous instances of this pod allowed	1		No	integer
	Examples:				
	- 1				
averageUtilization	Pod average utilization	80		No	integer
	Examples:				
	- 80				

pod-pfcp_c tracing

Description

Tracing parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable tracing	true		No	boolean
	Examples:				
	- true				
samplerType	Sampler type. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration	probabilistic		No	string
	Examples:				
	- probabilistic				
samplerParam	Sampler parameter. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration	1.0		No	string
	Examples:				
	- 1.0				

Parameter	Description	Default	Value/Range	Mandatory	Type
agentPort	UDP port exposed by jaeger-agent	6831		No	string
	Examples: - 6831				
logEnabled	Enable/disable jaeger logging	false	Enumerations:		
	Examples: - false		- true - false		

pod-pfcp_c upgrade

Description

Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicator are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable canary sequence	false		No	boolean
	Examples: - false				
canaryVersWeight	Canary pod weight percentage	0	min: 0 max: 100	No	integer
stableVersWeight	Stable pod weight percentage	0	min: 0 max: 100	No	integer
stableVersion	Stable pod image version			No	string
	Examples: - 0.0.0				
stableInfralImage	Infra container stable image			No	string
	Examples: -				
stableWorkerImage	Worker container stable image			No	string
	Examples: -				

pod-event_exposure

Description

SMF-CC microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable SMF-CC microservice	true		No	boolean
	Examples: - false				
podDisruptionBudget	Pod Disruption Budget parameters			No	object
cnaInfraThreadPoolSizeDbClient	Infra thread pool size count	1000		No	string
	Examples: - 1000				
deployment	Deployment parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
tracing	Tracing parameters			No	object
upgrade	Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.			No	object

pod-event_exposure podDisruptionBudget

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	1		No	string

pod-event_exposure deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer
	Examples:				
	- 1				
strategy	Deployment Update strategy			No	object

pod-event_exposure deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

[pod-event_exposure deployment strategy](#) [rollingUpdate](#)

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	1		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	1		No	string

[pod-event_exposure](#) [hpa](#)

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA	false		No	boolean
	Examples: - true				
infraCpuRequests	Infra container HPA CPU requests	10m		No	string
	Examples: - 10m				
workerCpuRequests	Worker container HPA CPU requests	390m		No	string
	Examples: - 390m				
workerCpuLimits	Worker container HPA CPU limits	1000m		No	string
	Examples: - 1000m				
maxReplicas	The maximum number of simultaneous instances of this pod allowed	6		No	integer
	Examples: - 6				
minReplicas	The mininum number of simultaneous instances of this pod allowed	1		No	integer
	Examples: - 1				
averageUtilization	Pod average utilization	80		No	integer
	Examples: - 80				

[pod-event_exposure](#) [tracing](#)

Description

Tracing parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable tracing	true		No	boolean
	Examples:				
	- true				
agentPort	UDP port exposed by jaeger-agent	6831		No	string
	Examples:				
	- 6831				
logEnabled	Enable/disable jaeger logging	false	Enumerations:	No	string
	Examples:		- true		
	- false		- false		

pod-event_exposure upgrade

Description

Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable canary sequence	false		No	boolean
	Examples:				
	- false				
canaryVersWeight	Canary pod weight percentage	0	min: 0 max: 100	No	integer
stableVersWeight	Stable pod weight percentage	0	min: 0 max: 100	No	integer
stableVersion	Stable pod image version	0.0.0		No	string
	Examples:				
	- 0.0.0				
stableInfraImage	Infra container stable image			No	string
	Examples:				
	-				
stableWorkerImage	Worker container stable image			No	string
	Examples:				
	-				

pod-smfcc

Description

SMF-CC microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable SMF-CC microservice	true		No	boolean
	Examples: - false				
podDisruptionBudget	Pod Disruption Budget parameters			No	object
cnaInfraThreadPoolSizeDbClient	Infra thread pool size count	1000		No	string
	Examples: - 1000				
kafkaClient	Enable MTLS Communication with Kafka Broker for SMFCC			No	object
deployment	Deployment parameters			No	object
alert	Alert rule parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
tracing	Tracing parameters			No	object
smfset	pod-smfcc smfset parameters			No	object
upgrade	Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.			No	object
outlierDetection	Istio Circuit Breaking configuration applied by Istio Ingress Gateway			No	object
gateway	Istio request timeout configuration applied by Istio Ingress Gateway			No	object

pod-smfcc podDisruptionBudget

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	1%		No	string

pod-smfcc kafkaclient

Description

Enable MTLS Communication with Kafka Broker for SMFCC

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
brokers	Kafka Broker To Which The Messages Should be Sent To			No	string

pod-smfcc deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer
	Examples:				
	- 1				
strategy	Deployment Update strategy			No	object

[pod-smfcc deployment strategy](#)

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

[pod-smfcc deployment strategy](#) [rollingUpdate](#)

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	1%		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	3%		No	string

[pod-smfcc alert](#)

Description

Alert rule parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minPduSesionCreateSuccessRate	SMF PDU Session Create success rate - lower threshold	90		No	integer
	Examples:				
	- 95				

[pod-smfcc hpa](#)

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA	false		No	boolean
	Examples:				
	- true				

Parameter	Description	Default	Value/Range	Mandatory	Type
infraCpuRequests	Infra container HPA CPU requests				
	Examples:	10m		No	string
	- 10m				
workerCpuRequests	Worker container HPA CPU requests				
	Examples:	390m		No	string
	- 390m				
workerCpuLimits	Worker container HPA CPU limits				
	Examples:	1000m		No	string
	- 1000m				
maxReplicas	The maximum number of simultaneous instances of this pod allowed				
	Examples:	6		No	integer
	- 6				
minReplicas	The minimum number of simultaneous instances of this pod allowed				
	Examples:	1		No	integer
	- 1				
averageUtilization	Pod average utilization				
	Examples:	80		No	integer
	- 80				

pod-smfcc tracing

Description

Tracing parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable tracing				
	Examples:	true		No	boolean
	- true				
agentPort	UDP port exposed by jaeger-agent				
	Examples:	6831		No	string
	- 6831				
logEnabled	Enable/disable jaeger logging		Enumerations:		
	Examples:	false	- true	No	string
	- false		- false		

pod-smfcc smfset

Description

pod-smfcc smfset parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
maxInstancesInSmfSet	Maximum number of instances in a given smfset	3	min: 1 max: 3	No	integer
smfSetInstanceId	smf instance id which needs to be unique per smfset	1	min: 1	No	integer

pod-smfcc upgrade

Description

Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable canary sequence	false		No	boolean
	Examples: - false				
canaryVersWeight	Canary pod weight percentage	0	min: 0 max: 100	No	integer
stableVersWeight	Stable pod weight percentage	0	min: 0 max: 100	No	integer
stableVersion	Stable pod image version	0.0.0		No	string
	Examples: - 0.0.0				
stableInfraImage	Infra container stable image			No	string
	Examples: -				
stableWorkerImage	Worker container stable image			No	string
	Examples: -				

pod-smfcc outlierDetection

Description

Istio Circuit Breaking configuration applied by Istio Ingress Gateway

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
baseEjectionTime	Minimum ejection duration for a blocked endpoint.				

Parameter	Description	Default	Value/Range	Mandatory	Type
	During node-reboot case, Kubernetes control plane takes 20s to detect node is not ready and 170s is the default toleration period, so baseEjectionTime set to 190 seconds(20+170) to keep the endpoint in blocked state after which it is added to the load balancer to serve the traffic. This variable needs to be modified based on the node-monitor-grace-period and default-not-ready-toleration-seconds as explained here.	190s	No		string

pod-smfcc gateway

Description

Istio request timeout configuration applied by Istio Ingress Gateway

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
requestTimeout	Request timeout duration used by Istio Ingress Gateway for all its transactions towards smfcc.	0s		No	string

pod-radius_agent

Description

Radius Agent microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Infra thread pool size count				
cnalnfraThreadPoolSizeDbClient	Examples: - 1000	1000		No	string
	Enable/disable Radius Agent microservice				
enabled	Examples: - false	true		No	boolean
service	Service parameters			No	object
podDisruptionBudget	Pod Disruption Budget parameters			No	object
deployment	Deployment parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
tracing	Tracing parameter			No	object
upgrade	Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.			No	object

pod-radius_agt service

Description

Service parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
loadBalancerIP	Load Balancer IP address				
	Examples:			No	string
	- 10.1.1.101				
serviceAnnotations	Service annotations			No	object

[pod-radius_agt service](#) serviceAnnotations

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

[pod-radius_agent podDisruptionBudget](#)

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	1		No	string

[pod-radius_agent deployment](#)

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count				
	Examples:	0		No	integer
	- 1				
strategy	Deployment Update strategy			No	object

[pod-radius_agent deployment strategy](#)

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

[pod-radius_agent deployment strategy](#) rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	1		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	1		No	string

pod-radius_agent hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA				
	Examples:	true		No	boolean
	- false				
minReplicas	The minimum number of simultaneous instances of this pod allowed				
	Examples:	1		No	integer
	- 1				
maxReplicas	The maximum number of simultaneous instances of this pod allowed				
	Examples:	5		No	integer
	- 3				
infraCpuRequests	Infra container HPA CPU requests				
	Examples:	100m		No	string
	- 100m				
workerCpuRequests	Worker container HPA CPU requests				
	Examples:	800m		No	string
	- 800m				
averageUtilization	Pod average utilization				
	Examples:	80		No	integer
	- 80				

pod-radius_agent tracing

Description

Tracing parameter

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable tracing				
	Examples:	true		No	boolean
	- false				
agentPort	UDP port exposed by jaeger-agent				
	Examples:	6831		No	string
	- 6831				

Parameter	Description	Default	Value/Range	Mandatory	Type
logEnabled	Enable/disable jaeger logging	false	Enumerations:	No	string
	Examples:		- true		
	- false		- false		

pod-radius_agent upgrade

Description

Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicator are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable canary sequence	false		No	boolean
	Examples:				
	- false				
canaryVersWeight	Canary pod weight percentage	0	min: 0 max: 100	No	integer
stableVersWeight	Stable pod weight percentage	0	min: 0 max: 100	No	integer
stableVersion	Stable pod image version	0.0.0		No	string
	Examples:				
	- 0.0.0				
stableInfralImage	Infra container stable image			No	string
	Examples:				
	-				
stableWorkerImage	Worker container stable image			No	string
	Examples:				
	-				

pod-chf_agent

Description

CHF Agent microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cnaInfraThreadPoolSizeDbClient	Infra thread pool size count	1000		No	string
	Examples:				
	- 1000				
podDisruptionBudget	Pod Disruption Budget parameters			No	object
deployment	Deployment parameters			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
tracing	Tracing parameter			No	object
kafkaClient	Enable MTLS Communication with Kafka Broker for CHFAgent			No	object
upgrade	Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.			No	object

[pod-chf_agent](#) podDisruptionBudget

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	1		No	string

[pod-chf_agent](#) deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	0		No	integer
strategy	Deployment Update strategy			No	object

[pod-chf_agent](#) deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

[pod-chf_agent](#) deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	1		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	1		No	string

pod-chf_agent hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA	true		No	boolean
	Examples:				
	- false				
minReplicas	The minimum number of simultaneous instances of this pod allowed	1		No	integer
	Examples:				
	- 1				
maxReplicas	The maximum number of simultaneous instances of this pod allowed	5		No	integer
	Examples:				
	- 3				
infraCpuRequests	Infra container HPA CPU requests	100m		No	string
	Examples:				
	- 100m				
kafkaCpuRequests	Kafka client container HPA CPU requests	100m		No	string
	Examples:				
	- 100m				
workerCpuRequests	Worker container HPA CPU requests	800m		No	string
	Examples:				
	- 800m				
averageUtilization	Pod average utilization	80		No	integer
	Examples:				
	- 80				

pod-chf_agent tracing

Description

Tracing parameter

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable tracing	true		No	boolean
	Examples:				
	- false				

Parameter	Description	Default	Value/Range	Mandatory	Type
agentPort	UDP port exposed by jaeger-agent	6831		No	string
	Examples:				
	- 6831				
logEnabled	Enable/disable jaeger logging	false	Enumerations:	No	string
	Examples:		- true		
	- false		- false		

pod-chf_agent kafkaclient

Description

Enable MTLS Communication with Kafka Broker for CHFAgent

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
brokers	Kafka Broker To Which The Messages Should be Sent To			No	string

pod-chf_agent upgrade

Description

Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable canary sequence	false		No	boolean
	Examples:				
	- false				
canaryVersWeight	Canary pod weight percentage	0	min: 0 max: 100	No	integer
stableVersWeight	Stable pod weight percentage	0	min: 0 max: 100	No	integer
stableVersion	Stable pod image version	0.0.0		No	string
	Examples:				
	- 0.0.0				
stableInfraImage	Infra container stable image			No	string
	Examples:				
	-				
stableWorkerImage	Worker container stable image			No	string
	Examples:				
	-				

pod-cdr_agent

Description

CDR Agent microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
deployment	Deployment parameters			No	object
podDisruptionBudget	Pod Disruption Budget parameters			No	object
nfs	NFS fileserver association			No	object
storage	Storage for cdr files.			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
tracing	Tracing parameter			No	object
upgrade	Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicator are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.			No	object

[pod-cdr_agent deployment](#)

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	0		No	integer
strategy	Deployment Update strategy			No	object

[pod-cdr_agent deployment strategy](#)

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

[pod-cdr_agent deployment strategy rollingUpdate](#)

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	1		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	1		No	string

pod-cdr_agent podDisruptionBudget

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	1		No	string

pod-cdr_agent nfs

Description

NFS fileserver association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
storage	Examples: - 5Gi	5Gi		No	string
storageClass	Examples: - cdr-nfs	cdr-nfs		No	string
lcdrPath	Examples: - /filestore/local-cdr-charging	/filestore/local-cdr-charging		No	string
pvName	Examples: - cdr-nfs-pv	cdr-nfs-pv		No	string
pvcName	Examples: - cdr-nfs-pvc	cdr-nfs-pvc		No	string
directory	Examples: - /user/accounting/lcdr	/user/accounting/lcdr		No	string

pod-cdr_agent storage

Description

Storage for cdr files.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
type	Examples: - local	local		No	string
storageClassName	Examples: - rook-cephfs	rook-cephfs		No	string
cdrStorageSize	Examples: - 5Gi	5Gi		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
directory	Examples: - /user/accounting/lcdr	/user/accounting/lcdr		No	string
pvcName	Examples: - cdr-cephfs-pvc	cdr-cephfs-pvc		No	string

pod-cdr_agent hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA Examples: - false	true		No	boolean
minReplicas	The mininum number of simultaneous instances of this pod allowed Examples: - 1	1		No	integer
maxReplicas	The maximum number of simultaneous instances of this pod allowed Examples: - 5	5		No	integer
infraCpuRequests	Infra container HPA CPU requests Examples: - 10m	10m		No	string
workerCpuRequests	Worker container HPA CPU requests Examples: - 460m	460m		No	string
averageUtilization	Pod average utilization Examples: - 50	50		No	integer

pod-cdr_agent tracing

Description

Tracing parameter

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable tracing Examples: - false	true		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
samplerType	Sampler type. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration	probabilistic	Enumerations: - const	No	string
	Examples: - probabilistic		- probabilistic - ratelimiting - remote		
samplerParam	Sampler parameter. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration Examples: - 1.0	1.0		No	string
agentPort	UDP port exposed by jaeger-agent Examples: - 6831	6831		No	string
logEnabled	Enable/disable jaeger logging Examples: - false	false	Enumerations: - true - false	No	string

pod-cdr_agent upgrade

Description

Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable canary sequence	false		No	boolean
	Examples: - false				
canaryVersWeight	Canary pod weight percentage	0	min: 0 max: 100	No	integer
stableVersWeight	Stable pod weight percentage	0	min: 0 max: 100	No	integer
stableVersion	Stable pod image version Examples: - 0.0.0	0.0.0		No	string
stableInfraImage	Infra container stable image Examples: -			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
Worker container stable image					
Examples:					
stableWorkerImage				No	string
-					

pod-sftp

Description

SFTP microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable SFTP Microservice				
	Examples:	false		No	boolean
	- true				
name	Name of the SFTP microservice				
	Examples:	sftp		No	string
	- sftp-service				
sftp	SFTP Microservice Internal Control Parameters			No	object

[pod-sftp sftp](#)

Description

SFTP Microservice Internal Control Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
accessMode	Access mode for the SFTP microservice			No	object
deployment	Deployment parameters			No	object

[pod-sftp sftp accessMode](#)

Description

Access mode for the SFTP microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
pull	Control Parameters for SFTP Pull Mode			No	object

[pod-sftp sftp accessMode pull](#)

Description

Control Parameters for SFTP Pull Mode

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Enable/Disable SFTP Pull Mode					
enabled	Examples:	true	No	boolean	
	- false				
service	Service Parameters for Pull			No	object

pod-sftp sftp accessMode pull service

Description

Service Parameters for Pull

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
servicePort	External Load Balancer Port for SFTP	8888		No	integer
	Examples:				
	- 6666				
annotations	Service Annotations			No	object

pod-sftp sftp accessMode pull service annotations

Description

Service Annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Service Annotations	true		No	boolean
	Examples:				
	- false				
azureLoadBalancerInternal	Enable/Disable Azure Load Balancer Internal	true		No	boolean
	Examples:				
	- false				
azureLoadBalancerInternalSubnet	Azure Load Balancer Internal Subnet	none		No	string
	Examples:				
	- subnet-utils-lb				

pod-sftp sftp deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer
	Examples:				
	- 1				
enableSftpDebugLogs	Enable/Disable SFTP Debug Logs	true		No	boolean
	Examples:				
	- false				
strategy	Deployment Update strategy			No	object

pod-sftp sftp deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

[pod-sftp sftp deployment strategy](#) [rollingUpdate](#)

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	1		No	integer
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	1		No	integer

[pod-gtpc_agent](#)

Description

GTPC Agent microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable PMNDeployment				
	Examples:				
PMNDeployment	- true	false		No	boolean
	- false				
deployment	Deployment parameters			No	object
podDisruptionBudget	Pod Disruption Budget parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
tracing	Tracing parameters			No	object

[pod-gtpc_agent deployment](#)

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples:	1		No	integer
	- 1				
strategy	Deployment Update strategy			No	object

[pod-gtpc_agent deployment strategy](#)

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-gtpc_agent deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	1		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	1		No	string

pod-gtpc_agent podDisruptionBudget

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	1		No	string

pod-gtpc_agent hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA	false		No	boolean
	Examples:				
	- false				
infraCpuRequests	Infra container HPA CPU requests	10m		No	string
	Examples:				
	- 10m				
workerCpuRequests	Worker container HPA CPU requests	460m		No	string
	Examples:				
	- 460m				
workerCpuLimits	Worker container HPA CPU limits	1000m		No	string
	Examples:				
	- 1000m				
maxReplicas	The maximum number of simultaneous instances of this pod allowed	3		No	integer
	Examples:				
	- 3				
minReplicas	The mininum number of simultaneous instances of this pod allowed	1		No	integer
	Examples:				
	- 1				

Parameter	Description	Default	Value/Range	Mandatory	Type
	Pod average utilization				
averageUtilization	Examples: - 80	80		No	integer

pod-gtpc_agent tracing

Description

Tracing parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable tracing				
enabled	Examples: - false	false		No	boolean
	Sampler type. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration				
samplerType	Examples: - probabilistic	probabilistic	Enumerations: - const - probabilistic - ratelimiting - remote	No	string
	Sampler parameter. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration				
samplerParam	Examples: - 1.0	1.0		No	string
	UDP port exposed by jaeger-agent				
agentPort	Examples: - 6831	6831		No	string
	Enable/disable jaeger logging				
logEnabled	Examples: - false	false	Enumerations: - true - false	No	string

pod-li_x1

Description

LI X1 microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Configuring rbacEnabled to true will create clusterrolebinding. Configuring rbacEnabled to false, clusterrolebinding will not be created.				
rbacEnabled	Examples: - false	true		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
clusterRole	clusterrole and PSP for is created as a part of fed-rbac. clusterrole options are restricted-cr, permissive-network-cr, permissive-full-cr Examples: - permissive-network-cr	permissive-network-cr		No	string
serviceAccountName	serviceAccountName configuration is used to create serviceaccount per pod Examples: - li-x1-serviceaccount	li-x1-serviceaccount		No	string
cnaInfraThreadPoolSizeDbClient	Infra thread pool size count Examples: - 1000	1000		No	string
deployment	Deployment parameters			No	object
podDisruptionBudget	Pod Disruption Budget parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
upgrade	Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicatory are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.			No	object

pod-li_x1 deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer

pod-li_x1 podDisruptionBudget

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	1		No	string

pod-li_x1 hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA				
	Examples:	false		No	boolean
	- false				
infraCpuRequests	Infra container HPA CPU requests				
	Examples:	10m		No	string
	- 10m				
workerCpuRequests	Worker container HPA CPU requests				
	Examples:	460m		No	string
	- 460m				
workerCpuLimits	Worker container HPA CPU limits				
	Examples:	1000m		No	string
	- 1000m				
maxReplicas	The maximum number of simultaneous instances of this pod allowed				
	Examples:	1		No	integer
	- 3				
minReplicas	The mininum number of simultaneous instances of this pod allowed				
	Examples:	1		No	integer
	- 1				
averageUtilization	Pod average utilization				
	Examples:	80		No	integer
	- 80				

pod-li_x1 upgrade

Description

Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicatory are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable canary sequence				
	Examples:	false		No	boolean
	- false				
canaryVersWeight	Canary pod weight percentage	0	min: 0 max: 100	No	integer
stableVersWeight	Stable pod weight percentage	0	min: 0 max: 100	No	integer

Parameter	Description	Default	Value/Range	Mandatory	Type
	Stable pod image version				
stableVersion	Examples: - 0.0.0			No	string
	Infra container stable image				
stableInfraImage	Examples: -			No	string
	Worker container stable image				
stableWorkerImage	Examples: -			No	string

pod-li_x2

Description

LI X2 microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rbacEnabled	Configuring rbacEnabled to true will create clusterrolebinding. Configuring rbacEnabled to false, clusterrolebinding will not be created. Examples: - false	true		No	boolean
podDisruptionBudget	Pod Disruption Budget parameters			No	object
clusterRole	clusterrole and PSP for is created as a part of fed-rbac. clusterrole options are restricted-cr, permissive-network-cr, permissive-full-cr Examples: - permissive-network-cr	permissive-network-cr		No	string
serviceAccountName	serviceAccountName configuration is used to create serviceaccount per pod Examples: - li-x2-serviceaccount	li-x2-serviceaccount		No	string
cnalInfraThreadPoolSizeDbClient	Infra thread pool size count Examples: - 1000	1000		No	string
deployment	Deployment parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object

Parameter	Description	Default	Value/Range	Mandatory	Type
upgrade	Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicatory are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.			No	object

pod-li_x2 podDisruptionBudget

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	1		No	string

pod-li_x2 deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer

pod-li_x2 hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA				
	Examples: - false	false		No	boolean
infraCpuRequests	Infra container HPA CPU requests				
	Examples: - 10m	10m		No	string
workerCpuRequests	Worker container HPA CPU requests				
	Examples: - 460m	460m		No	string
workerCpuLimits	Worker container HPA CPU limits				
	Examples: - 1000m	1000m		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
The maximum number of simultaneous instances of this pod allowed					
maxReplicas	Examples: - 3	1		No	integer
The minimum number of simultaneous instances of this pod allowed					
minReplicas	Examples: - 1	1		No	integer
Pod average utilization					
averageUtilization	Examples: - 80	80		No	integer

pod-li_x2 upgrade

Description

Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Enable/disable canary sequence					
canary	Examples: - false	false		No	boolean
canaryVersWeight	Canary pod weight percentage	0	min: 0 max: 100	No	integer
stableVersWeight	Stable pod weight percentage	0	min: 0 max: 100	No	integer
Stable pod image version					
stableVersion	Examples: - 0.0.0			No	string
Infra container stable image					
stableInfraImage	Examples: -			No	string
Worker container stable image					
stableWorkerImage	Examples: -			No	string

pod-kafka_rplay_agt

Description

This microservice deals with the consumption of replay messages from the Kafka Message Broker and the delivery of these messages to the required destinations.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
deployment	Deployment parameters			No	object
podDisruptionBudget	Pod Disruption Budget parameters			No	object
commitServerRspCodeList	KRA will commit message if CHF servers send any of below configured cause codes			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
tracing	Tracing parameters			No	object
upgrade	Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicator are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.			No	object

pod-kafka_rplay_agt deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer
strategy	Deployment Update strategy			No	object

pod-kafka_rplay_agent deployment strategy

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-kafka_rplay_agent deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	1		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	1		No	string

pod-kafka_rplay_agt podDisruptionBudget

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	1		No	string

pod-kafka_rplay_agt commitServerRspCodeList

Description

KRA will commit message if CHF servers send any of below configured cause codes

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
causecode	Set CHF server's allowed response codes as comma separated values without providing any space			No	string

pod-kafka_rplay_agt hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable HPA				
enabled	Examples: - false	true		No	boolean
	The mininum number of simultaneous instances of this pod allowed				
minReplicas	Examples: - 1	1		No	integer
	The maximum number of simultaneous instances of this pod allowed				
maxReplicas	Examples: - 3	5		No	integer
	Infra container HPA CPU requests				
infraCpuRequests	Examples: - 50m	50m		No	string
	Kafka client container HPA CPU requests				
kafkaCpuRequests	Examples: - 200m	200m		No	string
	Worker container HPA CPU requests				
workerCpuRequests	Examples: - 700m	700m		No	string
	Pod average utilization				
averageUtilization	Examples: - 80	80		No	integer

pod-kafka_rplay_agt tracing

Description

Tracing parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable tracing	true		No	boolean
	Examples: - false				
samplerType	Sampler type. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration	probabilistic	Enumerations: - const - probabilistic - ratelimiting - remote	No	string
	Examples: - probabilistic				
samplerParam	Sampler parameter. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration	1.0		No	string
agentPort	UDP port exposed by jaeger-agent	6831		No	string
	Examples: - 6831				
logEnabled	Enable/disable jaeger logging	false	Enumerations: - true - false	No	string

pod-kafka_rplay_agt upgrade

Description

Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicatory are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable canary sequence	false		No	boolean
	Examples: - false				
canaryVersWeight	Canary pod weight percentage	0	min: 0 max: 100	No	integer
stableVersWeight	Stable pod weight percentage	0	min: 0 max: 100	No	integer
stableVersion	Stable pod image version	0.0.0		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
stableInfraImage	Infra container stable image				
	Examples:			No	string
	-				
stableWorkerImage	Worker container stable image				
	Examples:			No	string
	-				

pod-diameter_base

Description

Diameter Base Microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
diameterGroups	Diameter Groups parameters			No	array

[pod-diameter_base](#) diameterGroups

Description

Diameter Groups parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
groupName	Name of diameter-base group				
	Examples:			Yes	string
	- group1				
enabled	Enable/disable diameter-base group				
	Examples:			Yes	boolean
	- true				
	- false				
ratelimit	Rate limiting related variables. quota determines the number of incoming requests for this microservice that will be allowed per configured interval from the microservice configured as the sourceApp.			Yes	object
transport	diameter-base transport protocol				
	Examples:				
	- sctp	sctp		Yes	string
	- tcp				
sctpEncapType	SCTP enapsulation type				
	Examples:				
	- sctp_lb	sctp_lb		Yes	string
	- rfc6951				

Parameter	Description	Default	Value/Range	Mandatory	Type
role	Role of diameter-base group1	client		Yes	string
	Examples:				
	- client				
reserveStreamId0	Reserve stream ID	true		No	string
	Examples:				
	- true				
externallpServiceId	Service ID	s6-fqdn		Yes	string
	Examples:				
	- s6-fqdn				
deployment	Deployment parameters			Yes	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			Yes	object
tracing	Tracing parameters			No	object

pod-diameter_base diameterGroups ratelimit

Description

Rate limiting related variables. quota determines the number of incoming requests for this microservice that will be allowed per configured interval from the microservice configured as the sourceApp.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable ratelimiting	true		No	boolean
	Examples:				
	- true				
quota	Number of incoming requests allowed	100		No	integer
	Examples:				
	- 100				
interval	Configured time interval	10s		No	string
	Examples:				
	- 10s				
sourceApp	Source app	istio-ingressgateway		No	string
	Examples:				
	- istio-ingressgateway				

pod-diameter_base diameterGroups deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
Deployment replica count					
Examples:					
replicas	- 1	1	min: 0	No	integer
	- 2				

pod-diameter_base diameterGroups hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA				
	Examples:				
	- true	true		No	boolean
	- false				
infraCpuRequests	Infra container HPA CPU requests				
	Examples:	10m		No	string
	- 10m				
workerCpuRequests	Worker container HPA CPU requests				
	Examples:	980m		No	string
	- 980m				
workerCpuLimits	Worker container HPA CPU limits				
	Examples:	1000m		No	string
	- 1000m				
minReplicas	Pod mininum replicas				
	Examples:				
	- 1	1	min: 0	No	integer
	- 2				
maxReplicas	Pod maximum replicas				
	Examples:				
	- 1	1	min: 0	No	integer
	- 2				
averageUtilization	Pod average utilization				
	Examples:				
	- 50	75	min: 0 max: 100	No	integer
	- 75				

pod-diameter_base diameterGroups tracing

Description

Tracing parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable tracing	true		No	boolean
	Examples:				
	- true				
samplerType	- false	probabilistic	Enumerations: - const - probabilistic - ratelimiting - remote	No	string
	Sampler type. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration				
	Examples: - probabilistic				
samplerParam	Sampler parameter. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration	1.0		No	string
	Examples:				
	- 1.0				
agentPort	UDP port exposed by jaeger-agent	6831		No	string
	Examples:				
	- 6831				
logEnabled	Enable/disable jaeger logging	false		No	string
	Examples:				
	- true				
	- false				

fed-timer Helm Documentation

fed-timer values

Contents

- [Global Parameters](#)
- [Istio Gateway Parameters](#)
- [Timer Parameters](#)

global

Description

Global Parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
defaultRbacEnabled	Configuring defaultRbacEnabled to true will create clusterrolebinding. Configuring defaultRbacEnabled to false, clusterrolebinding will not be created.	true		No	boolean
	Examples:				
	- false				

Parameter	Description	Default	Value/Range	Mandatory	Type
defaultClusterRole	clusterrole is created as a part of fed-rbac. defaultClusterRole options are restricted-cr, permissive-network-cr, permissive-full-cr Examples: - permissive-network-cr	permissive-network-cr		No	string
defaultServiceAccountName	serviceaccount will be created by default. defaultServiceAccountName configuration is used to create default serviceaccount per namespace Examples: - fed-timer-serviceaccount	fed-timer-serviceaccount		No	string
ingressNetworkPolicy	network policies configuration			No	object
logging	PaaS logging association			No	object
grafana	PaaS Grafana association			No	object
enablePdb	Enable/disable pod disruption budgets(PDB) for fed-timer pods Examples: - false	true		No	boolean
istio	Istio related configurations			No	object
mesh	Istio mesh configuration			No	object
monitoring	PaaS Monitoring associations			No	object
metricsScrapeInterval	Prometheus metrics scrape interval Examples: - 5s	30s		No	string
registry	PaaS container registry associations			No	object
deployment	Node affinity deployment			No	object
envVars	Environment variables			No	object
podPriorityEnabled	Flag to enable/disable pod priority at a fed level Examples: - false - true	true		No	boolean
topologySpreadConstraints	Pod topology spread constraints control how pods of given microservice type are spread across the cluster among failure-domains such as regions, zones, nodes, and other user-defined topology domains. This can help to achieve high availability as well as efficient resource utilization.			No	object

[global](#) ingressNetworkPolicy

Description

network policies configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabled network policy	true		No	boolean
ingressTrafficNamespaces	Namespaces which are required to be allowed for ingress traffic			No	array

[global](#) logging

Description

PaaS logging association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable logging association	false		No	boolean
	Examples:				
	- false				
fluentd	Fluentd-Configurations			No	object
elastic	Elasticsearch association			No	object
enableAddlTargets	Enable/disable additional destinations	false		No	boolean
addlTargets	Additional logging output destination configuration			No	array
alerts	Alerts configuration			No	object

global logging fluentd

Description

Fluentd-Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	Fluentd-Buffer Configurations			No	object

global logging fluentd buffer

Description

Fluentd-Buffer Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Total buffer size. Maximum amount of buffer space each fluentd thread would use to keep logs. After this space is exhausted, fluentd would start deleting oldest logs to make room for new logs.	512m		No	string
retryWait	Interval(seconds) at which the buffer flush is retried in case of failure.	180s		No	string
maxRetries	Max number of retries to flush a buffer chunk. After this is exhausted, fluentd would delete the chunk.	10		No	integer

global logging elastic

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
IP	Elasticsearch IP address			No	string
	Examples:				
	- 10.15.10.161				
Port	Elasticsearch port	9200		No	integer

global logging addlTargets

Description

Additional logging output destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			Yes	object

[global logging addITargets](#) [forward](#)

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
host	Hostname or IP Address of the forward server for sending logs to additional targets in parallel with elastic			No	string
port	Port of the forward server	24224		No	integer

[global logging](#) [alerts](#)

Description

Alerts configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable event alerts				
enabled	Examples: - true	false		No	boolean
	Elasticsearch IP address or host				
host	Examples: - 10.15.10.161			No	string
port	Elasticsearch port	3030		No	integer
realert	Re-alert Info			No	object
	Alert receivers.				
receivers	Examples: - [OrderedDict({'slack': OrderedDict({'webhookurl': ''})}), OrderedDict({'post': OrderedDict({'http_post_url': ''})})]			No	array

[global logging alerts](#) [realert](#)

Description

Re-alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Interval in minutes to re-send an alert				
minutes	Examples: - 2	1		No	integer

[global logging alerts](#) [receivers](#)

Description

Alert receivers.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	The first anyOf schema.				
	Examples:			No	object
	- OrderedDict({'slack': OrderedDict({'webhookurl': ''})})				
1	The second anyOf schema.				
	Examples:			No	object
	- OrderedDict({'post': OrderedDict({'http_post_url': ''})})				
2	The third anyOf schema				
	Examples:			No	object
	- OrderedDict({'email': OrderedDict({'to_address': '', 'smtp_host': '', 'smtp_port': '', 'smtp_ssl': False, 'from_addr': ''})})				

global logging alerts receivers 0

Description

The first anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
slack	Slack receiver details.				
	Examples:			No	object
	- OrderedDict({'webhookurl': ''})				

global logging alerts receivers 0 slack

Description

Slack receiver details.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
webhookurl	The webhook URL that includes your auth data and the ID of the channel (room) you want to post to.				
	Examples:			No	string
	-				

global logging alerts receivers 1

Description

The second anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
post	HTTP post alert receiver details.				
	Examples:			No	object
	- OrderedDict({'http_post_url': ''})				

global logging alerts receivers 1 post

Description

HTTP post alert receiver details.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	URL for HTTP post.				
http_post_url	Examples: -			No	string

global logging alerts receivers 2

Description

The third anyOf schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Mail alert receiver Info.				
email	Examples: - OrderedDict({'to_address': '', 'smtp_host': '', 'smtp_port': '', 'smtp_ssl': False, 'from_addr': ''})			No	object

global logging alerts receivers 2 email

Description

Mail alert receiver Info.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	An address or list of addresses to sent the alert to.				
to_address	Examples: - user1@example.com	user1@example.com		No	string
	SMTP host details.				
smtp_host	Examples: - 1.1.1.1	1.1.1.1		No	string
	SMTP port info				
smtp_port	Examples: - 25	25		No	string
	Enable/disable SSL to SMTP server.				
smtp_ssl	Examples: - false	false		No	boolean
	This sets the from header in the email. By default, the from address is ElastAlert@ and the domain will be set by the smtp server				
from_addr	Examples: - user2@example.com	user2@example.com		No	string

global grafana

Description

PaaS Grafana association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association	true		No	boolean
	Exposed grafana URL				
url	Examples: - https: //10.15.10.161:3000			No	string
prometheusinfo	Prometheus server association			No	object

[global grafana](#) prometheusinfo

Description

Prometheus server association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Prometheus server URL				
url	Examples: - https: //prometheus.fed-prometheus:9090	http: //prometheus.fed-prometheus:9090		No	string

[global istio](#)

Description

Istio related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mtls	Istio mutual TLS related configuration			No	object

[global istio](#) mtls

Description

Istio mutual TLS related configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable istio mutual TLS	false		No	boolean

[global mesh](#)

Description

Istio mesh configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio configuration			No	object

[global mesh](#) istio

Description

Istio configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGw	Service mesh ingress gateway				
	Examples:			No	string
	- ingress-gateway				
ingressGwIP	Istio ingress gateway IP				
	Examples:			No	string
	-				
ingressGwFQDN	Istio ingress gateway FQDN				
	Examples:	timer-gr.com		No	string
	- timer-gr.com				
egressGwFQDN	Istio egress gateway FQDN				
	Examples:	timer-gr.com		No	string
	- timer-gr.com				
mtlsEnabled	MTLS flag.				
	Examples:	false		No	boolean
	- false				
ingressGwTLS	Istio ingress gateway TLS			No	object
egressGwTLS	Istio egress gateway TLS			No	object
loadBalancerSharingKey	Istio ingress gateway service loadbalancer sharing key.				
	Examples:	pass		No	string
	- pass				

global mesh istio ingressGwTLS

Description

Istio ingress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio ingress gateway TLS				
	Examples:				
	- true	true		No	boolean
	- false				
mode	Istio ingress gateway TLS mode.				
	Examples:	MUTUAL		No	string
	- MUTUAL				
certManager	certManager Configuration			No	object
userProvided	userProvided CERTIFICATES			No	object

global mesh istio ingressGwTLS certManager

Description

certManager Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for certManager configuration				
	Examples:				
	- true	true		No	boolean
	- false				
certDuration	certDuration Configuration	10h		No	string
renewBefore	renewBefore Configuration	1h		No	string
organization	organization Configuration				
	Examples:				
	- affirmednetworks	affirmednetworks		No	string
issuerName	issuerName				
	Examples:				
	- affirmed-clusterissuer	affirmed-clusterissuer		No	string

global mesh istio ingressGwTLS userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvided Certificates				
	Examples:				
	- false	false		No	boolean
	- true				
cacert	cacert Configuration				
	Examples:				
	- Copy and Paste End User generated Certificate			No	string
tls crt	tls crt configuration				
	Examples:				
	- Copy and Paste End User generated Certificate			No	string
tls key	tls key configuration				
	Examples:				
	- Copy and Paste End User generated Certificate			No	string

global mesh istio egressGwTLS

Description

Istio egress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio egress gateway TLS	true		No	boolean
	Examples:				
	- true				
	- false				
mode	Istio egress gateway TLS mode.	MUTUAL		No	string
	Examples:				
	- MUTUAL				
certManager	certManager Configuration			No	object
userProvided	userProvided CERTIFICATES			No	object

[global mesh istio egressGwTLS](#) [certManager](#)

Description

certManager Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for certManager configuration	true		No	boolean
	Examples:				
	- true				
	- false				
certDuration	certDuration Configuration	10h		No	string
renewBefore	renewBefore Configuration	1h		No	string
organization	organization Configuration	affirmednetworks		No	string
	Examples:				
	- affirmednetworks				
issuerName	issuerName	affirmed-clusterissuer		No	string
	Examples:				
	- affirmed-clusterissuer				

[global mesh istio egressGwTLS](#) [userProvided](#)

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvided Certificates	false		No	boolean
	Examples:				
	- false				
	- true				
cacert	cacert Configuration			No	string
	Examples:				
	- Copy and Paste End User generated Certificate				

Parameter	Description	Default	Value/Range	Mandatory	Type
tlsrct configuration					
tlsrct	Examples: - Copy and Paste End User generated Certificate			No	string
tlskey configuration					
tlskey	Examples: - Copy and Paste End User generated Certificate			No	string

global monitoring

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association			No	object

global monitoring prometheus

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable prometheus monitoring	true		No	boolean
Monitoring namespace					
namespace	Examples: - fed-prometheus	fed-prometheus		No	string

global registry

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

global registry docker

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string
imagePullSecret	Pull an image from a private registry			No	string
username	Username for private docker registry			No	string
password	Password for private docker registry			No	string

global deployment

Description

Node affinity deployment

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
nodeDataplaneAffinity	Flag to enable/disable node affinity. If set to 'true' pods will be deployed on nodes with no dataplane labels	false		No	string

[global](#) envVars

Description

Environment variables

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
fedType	Federation type				
	Examples:	paas		No	string
	- paas				
fedUniqueName	Federation unique name				
	Examples:	timer-default		No	string
	- timer-default				

[global](#) topologySpreadConstraints

Description

Pod topology spread constraints control how pods of given microservice type are spread across the cluster among failure-domains such as regions, zones, nodes, and other user-defined topology domains. This can help to achieve high availability as well as efficient resource utilization.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable pod topology spread constraints				
	Examples:				
	- false	true		No	boolean
	- true				
constraints	List of pod topology spread constraints to be applied.			No	array

[global](#) [topologySpreadConstraints](#) constraints

Description

List of pod topology spread constraints to be applied.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Definition of pod topology spread constraint to be applied to the pod specification.			No	object

[global](#) [topologySpreadConstraints](#) [constraints](#) 0

Description

Definition of pod topology spread constraint to be applied to the pod specification.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
maxSkew	Describes the degree to which pods may be unevenly distributed. It's the maximum permitted difference between the number of matching pods in any two topology domains of a given topology type. It must be greater than zero. Examples: - 1	1		No	integer
topologyKey	Its the key of node labels. If two nodes are labelled with this key and have identical values for that label, the Kubernetes scheduler treats both nodes as being in the same topology. The scheduler tries to place a balanced number of Pods into each topology domain. Examples: - kubernetes.io/hostname	kubernetes.io/hostname		No	string
whenUnsatisfiable	Indicates how to deal with a pod if it doesn't satisfy the defined pod topology spread constraint. Examples: - ScheduleAnyway - DoNotSchedule	ScheduleAnyway		No	string

pod-istio_gw

Description

Istio Gateway microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable istio-gw Examples: - false	true		No	boolean
istioNspace	Istio namespace Examples: - fed-istio	fed-istio		No	string
ingressGateway	Ingress gateway parameters			No	object
egressGateway	Egress gateway parameters			No	object
podDisruptionBudget	Pod Disruption Budget parameters			No	object
externalHosts	ExternalHosts Configurations			No	array
paasSelector	PAAS parameters			No	object

[pod-istio_gw](#) ingressGateway

Description

Ingress gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable ingress gateway Examples: - false	true		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
podPriority	Configuration of pod priority for Ingress GW pod			No	object

pod-istio_gw ingressGateway podPriority

Description

Configuration of pod priority for Ingress GW pod

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable the Ingress GW pod priority with the configured priorityClassName	false		No	boolean

pod-istio_gw egressGateway

Description

Egress gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable egress gateway				
enabled	Examples: - false	false		No	boolean

pod-istio_gw podDisruptionBudget

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	10%		No	string

pod-istio_gw externalHosts

Description

ExternalHosts Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	The first anyOf schema.			No	object
1	The second anyOf schema.			No	object

pod-istio_gw externalHosts 0

Description

The first anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
host	host is 'timer-gr-.com'			No	string
server	istio-ingressGW IP of fist Remote Site			No	string
ports	Port and Scheme Configurations for first Remote Site.			No	array

pod-istio_gw externalHosts 0 ports

Description

Port and Scheme Configurations for first Remote Site.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	The first anyOf schema.			No	object

pod-istio_gw externalHosts anyOf/0 ports 0

Description

The first anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
number	Number is the port serving traffic on the istio-ingressGW of First Remote site	80		No	integer
scheme	scheme is http/https. It dictates whether TLS is used for the First Remote site connections. If TLS is not enabled, scheme is http. If TLS is enabled, scheme is https.	http		No	string

pod-istio_gw externalHosts 1

Description

The second anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
host	host is 'timer-gr-.com'			No	string
server	istio-ingressGW IP of Second Remote Site			No	string
ports	Port and Scheme Configurations for Second Remote Site.			No	array

pod-istio_gw externalHosts 1 ports

Description

Port and Scheme Configurations for Second Remote Site.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	The first anyOf schema.			No	object

pod-istio_gw externalHosts anyOf/1 ports 0

Description

The first anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
number	Number is the port serving traffic on the istio-ingressGW of Second Remote site	80		No	integer
scheme	scheme is http/https. It dictates whether TLS is used for the Second Remote site connections. If TLS is not enabled, scheme is http. If TLS is enabled, scheme is https.	http		No	string

pod-istio_gw paasSelector

Description

PAAS parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
jaegerHostName	Jaeger host (IP or FQDN)	fqdn.com		No	string
	Examples:				
	- 10.10.10.10 - fqdn.com				

pod-timer

Description

Timer Microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable timer microservice	true		No	boolean
	Examples:				
	- true - false				
name	Service Name of the timer pod	timer-gr		No	string
	Examples:				
	- timer-gr				
deployment	Deployment parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) is currently not supported on timer pod.If hpa enabled is set to true, then given value of cpu/memory requests/limits will be used for Chronos container and infra container.			No	object
podPriority	Configuration of pod priority for chronos operator pod			No	object
podDisruptionBudget	Pod Disruption Budget parameters			No	object
consistentHashing	Consistent Hashing parameters			No	object
geoRdntEncryptionEnabled	Enable/disable istio-proxy side car in Chronos pod to support TLS encryption during replication across sites	false		No	boolean
	Examples:				
	- true - false				
geoRedundancy	Configuration of Geo Redundant related parameters.			No	object
rbacEnabled	Configuring rbacEnabled to true will create clusterrolebinding. If set to false, clusterrolebinding will not be created.	true		No	boolean
	Examples:				
	- false				
role	clusterrole is created as a part of fed-rbac.	chronos-operator-role		No	string
	Examples:				
	- chronos-operator-role				
serviceAccountName	serviceAccountName configuration is used to create serviceaccount per pod	chronos-operator-serviceaccount		No	string
	Examples:				
	- chronos-operator-serviceaccount				

[pod-timer deployment](#)

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	3	min: 0	No	integer

pod-timer hpa

Description

Horizontal Pod Autoscaler (HPA) is currently not supported on timer pod.If hpa enabled is set to true, then given value of cpu/memory requests/limits will be used for Chronos container and infra container.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable HPA to set value of cpu/memory requests/limits of Chronos container and infra container				
enabled	Examples: - true - false	true		No	boolean
	Infra container CPU requests				
infraCpuRequests	Examples: - 10m	10m		No	string
	Chronos container CPU requests				
workerCpuRequests	Examples: - 10m	10m		No	string
	Chronos container CPU limits				
workerCpuLimits	Examples: - 2	2		No	string
	Chronos container Memory requests				
workerMemoryRequests	Examples: - 10Mi	10Mi		No	string
	Chronos container Memory limits				
workerMemoryLimits	Examples: - 2Gi	2Gi		No	string

pod-timer podPriority

Description

Configuration of pod priority for chronos operator pod

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable the chronos operator pod priority with the configured priorityClassName	true		No	boolean

pod-timer podDisruptionBudget

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	1		No	string

pod-timer consistentHashing

Description

Consistent Hashing parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Minimum number of hashes to place on the consistent hash ring				
minRingSize	Examples: - 1048576	1048576		No	integer

pod-timer geoRedundancy

Description

Configuration of Geo Redundant related parameters.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable geoRedundancy parameters				
enabled	Examples: - true - false	true		No	boolean
	The name of the local Chronos cluster				
localSiteName	Examples: -			No	string
remoteSites	RemoteSite Configurations			No	array

pod-timer geoRedundancy remoteSites

Description

RemoteSite Configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	The first anyOf schema.			No	object
1	The second anyOf schema.			No	object

pod-timer geoRedundancy remoteSites 0

Description

The first anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
siteName	Cluster Name of fist Remote Site			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
endpoint	endpoint (IpAddress) of fist Remote Site			No	string

pod-timer geoRedundancy remoteSites 1

Description

The second anyOf schema.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
siteName	Cluster Name of Second Remote Site			No	string
endpoint	endpoint (IpAddress) of Second Remote Site			No	string

UPF Helm Documentation

fed-upf values

Contents

- [Global Parameters](#)
- [File Server Parameters](#)
- [Configuration Manager Parameters](#)
- [Istio Gateway Parameters](#)
- [Istio LI Gateway Parameters](#)
- [Timer Parameters](#)
- [NRF Parameters](#)
- [PCFP-U Parameters](#)
- [Interface Manager Parameters](#)
- [PPE Parameters](#)
- [L3rm Parameters](#)
- [Routing Parameters](#)
- [UPF Monitor Parameters](#)
- [AzureMgr Parameters](#)
- [LI X1 Parameters](#)

global

Description

Global parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
defaultRbacEnabled	Configuring defaultRbacEnabled to true will create clusterrolebinding. Configuring defaultRbacEnabled to false, clusterrolebinding will not be created. Examples: - false	true		No	boolean
enableNfEgressCommunication	Configuration to enable NF external communication through Istio Egress Gateway for use cases like mTLS communication Examples: - true	false		No	boolean
enableStaticNfEgressCommunication	Configuration to enable statically configured NF external communication through Istio Egress Gateway for use cases like mTLS communication Examples: - true	false		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
vault	Vault Related attributes			No	object
secretNames	Name of secrets to be pulled from AKV or Hashicorp Vault			No	object
enablePdb	Enable/disable pod disruption budgets(PDB) for fed-upf pods Examples: - false	true		No	boolean
nodeDataplaneAffinity	If some worker nodes have been assigned a nodetype of "dataplane", and this variable is "true", dataplane pods will be exclusively assigned to those dataplane nodes.	false		No	boolean
kargoProfileTag	This enables creation of specific kargo-default-profile for fed-upf			No	string
defaultClusterRole	clusterrole and PSP for is created as a part of fed-rbac. defaultClusterRole options are restricted-cr, permissive-network-cr, permissive-full-cr Examples: - permissive-network-cr	permissive-network-cr		No	string
defaultServiceAccountName	serviceaccount will be created by default. defaultServiceAccountName configuration is used to create default serviceaccount per namespace Examples: - fed-upf-serviceaccount	fed-upf-serviceaccount		No	string
opentelemetry				No	object
ingressNetworkPolicy	network policies configuration			No	object
tabdb	PaaS Tabular database associations			No	object
fileserv	PaaS fileserv associations			No	object
helm	Properties to let a pod access the Helm Chart Museum			No	object
mesh	PaaS service mesh associations			No	object
monitoring	PaaS Monitoring associations			No	object
metricsScrapeInterval	Prometheus metrics scrape intrval Examples: - 5s	30s		No	string
registry	PaaS container registry associations			No	object
envVars	Environment variables			No	object
encryptDecryptKey	Secret pass phrase used for Encryption/Decryption of LI Data only. This is a private key and usage is within NF scope.			No	object
grafana	PaaS Grafana association			No	object
logging	PaaS logging association			No	object
fileCheckPath	Need to set only while using Mellanox NIC. Directory where multus config file is present on local node Examples: - /etc/cni/net.d	/etc/cni/net.d		No	string
fileCheckFile	Need to set only while using Mellanox NIC. Name of the multus config file on local node Examples: - 00-multus.conf			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
loadBalancerSourceRanges	Comma separated IP ranges that are allowed to access the load balancer. More info here - https://kubernetes.io/docs/tasks/access-application-cluster/configure-cloud-provider-firewall/#restrict-access-for-loadbalancer-service Examples: - 130.211.204.1/32	[]		No	string
license	PaaS License Server Selector			No	object
enableLIX1	Use this variable to enable/disable the li-x1 microservice. Examples: - true	true		No	boolean
enableLivenessProbe	Use this variable to enable/disable the Liveness Probe. Examples: - true - false	true		No	boolean
resource	Default limits and request for each container			No	object
topologySpreadConstraints	Pod topology spread constraints control how pods of given microservice type are spread across the cluster among failure-domains such as regions, zones, nodes, and other user-defined topology domains. This can help to achieve high availability as well as efficient resource utilization.			No	object
numSessMgrInstancesPerPpe	Set the number of SessionMgr instances in each PPE pod. Larger settings increase the maximum session transaction rate supported by each PPE. PPE CPU resource allocation should be revisited when changing this setting. Valid range [1..4]. Any value outside of the range will result in the default setting. Examples: - 1 - 2 - 3 - 4	1		No	integer
sessionPersistenceEnabled	enable or disable session persistence across PPE failures. Examples: - false	true		No	boolean
sessionPersistenceType	Session Persistence Type - Active/Standby or External DB based. Examples: - EXTERNAL_DB - ACTIVE_STANDBY	ACTIVE_STANDBY		No	string
externalPfcpSvc	External service parameters			No	array

[global vault](#)

Description

Vault Related attributes

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Vault feature	false		No	boolean
	Examples:				
	- false				
	- true				
hashicorpVault	HashicorpVault related configurations			No	object
azureKeyVault	AzureKeyVault related configurations			No	object

global vault hashicorpVault

Description

HashicorpVault related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	HashicorpVault Enable/Disable flag	true		No	boolean
	Examples:				
	- false				
	- true				
serverUrl	Address of Vault Server			No	string
	Examples:				
	- https://test.vault.com:8200				
role	JWT Role created on Vault Server			No	string
authMountPath	JWT mount path on Vault server			No	string
vaultNamespace	Vault Namespace configured on Vault server for multi-tenancy support			No	string

global azure azureKeyVault

Description

AzureKeyVault related configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	AzureKeyVault Enable/Disable flag	false		No	boolean
	Examples:				
	- false				
	- true				
tenantID	Tenant ID of Customer where AzureKeyVault is deployed			No	string
keyVaultName	KeyVault of Customer where secrets are stored			No	string
aksCluster	Azure Kuberetes Cluster	true		No	boolean
	Examples:				
	- false				
	- true				
userManagedId	ClientID of User managed ID			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
	workload Identity				
	Examples:				
workloadIdentity	- false	true		No	boolean
	- true				

global secretNames

Description

Name of secrets to be pulled from AKV or Hashicorp Vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cfgmgr	Name of secrets used by configuration manager			No	object
likey	Name of the secrets used by LI when Hashicorp Vault is enabled			No	object

global secretNames cfgmgr

Description

Name of secrets used by configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
confdKey	Vault Secret Name for confd AES key			No	string
encryptConfigKeySecretName	Vault Secret Name for Encyrpt Config key			No	string
adminDomainCAkeySecretName	Vault Secret Name for Admin Domain CA key			No	string
liadminDomainCAkeySecretName	Vault Secret Name for LI Admin Domain CA key			No	string
maintDomainCAkeySecretName	Vault Secret Name for Maint domain CA key			No	string
limaintDomainCAkeySecretName	Vault Secret Name for LI Maint domain CA key			No	string
rootDomainCAkeySecretName	Vault Secret Name for root domain CA key			No	string
rootPasswdSecretName	Vault Secret Name for root password			No	string
rootPubkeySecretName	Vault Secret Name for root public key			No	string
m2mPubkeySecretName	Vault Secret Name for m2m public key			No	string
adminUsers	List of Admin users for configuration manager			No	array
liadminUsers	List of LI Admin users for configuration manager			No	array
operUsers	List of Oper users for configuration manager			No	array
lioperUsers	List of LI Oper users for configuration manager			No	array
readonlyUsers	List of read-only users for configuration manager			No	array
userProvided	Secret Name of certificates used by RESTCONF			No	object

global secretNames cfgmgr adminUsers

Description

List of Admin users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

[global secretNames cfgmgr liadminUsers](#)

Description

List of LI Admin users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

[global secretNames cfgmgr operUsers](#)

Description

List of Oper users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

[global secretNames cfgmgr lioperUsers](#)

Description

List of LI Oper users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

[global secretNames cfgmgr readonlyUsers](#)

Description

List of read-only users for configuration manager

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
usernameSecretName	Vault Secret Name storing username of the user			No	string
passwdSecretName	Vault Secret Name storing password of the user			No	string
pubkeySecretName	Vault Secret Name storing public key of the user			No	string

[global secretNames cfgmgr userProvided](#)

Description

Secret Name of certificates used by RESTCONF

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
tlscrtSecretName	Secret Name of server TLS certificate			No	string
tlskeySecretName	Secret Name of server TLS key			No	string
cacertSecretName	Secret Name of CA certificate			No	string

[global secretNames likey](#)

Description

Name of the secrets used by LI when Hashicorp Vault is enabled

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
mountCSI	Enables mounting of CSI Volume(SecretProviderClass) on the vault helper	true		No	boolean
secretName	vault secret name for latest li key			No	string
prevSecretName	vault secret name for previous li key			No	string

[global](#) opentelemetry

Description

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable opentelemetry	true		No	boolean
tlsEnabled	Enable mTLS on opentelemetry	false		No	boolean
tracing	Configuration options for opentelemetry traces			No	object

[global](#) opentelemetry tracing

Description

Configuration options for opentelemetry traces

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable opentelemetry tracing	true		No	boolean
host	opentelemetry fqdn			No	string
port	opentelemetry port	80		No	integer

[global](#) ingressNetworkPolicy

Description

network policies configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabled network policy	true		No	boolean
ingressTrafficNamespaces	Namespaces which are required to be allowed for ingress traffic			No	array

[global](#) tabdb

Description

PaaS Tabular database associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
etcd	Etcd database association			No	object

[global](#) tabdb etcd

Description

Etcd database association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Etcd db instance name	etcd-server		No	string
	Tab-DB service path				
svc	Examples: - etcd-cluster-client.fed-db-etcd.svc.cluster.local	etcd-cluster-client.fed-db-etcd.svc.cluster.local		No	string
port	Tab-DB service port	2379		No	string
targetPort	Tab-DB service target port	31869		No	string

global fileserver

Description

PaaS fileserver associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
ui	Fileserver UI association			No	object
nfs	NFS fileserver association			No	object
cephfs	CephFS configuration - CephFS is an actual mountable POSIX-compliant filesystem layered on top of a Ceph storage cluster			No	object

global fileserver ui

Description

Fileserver UI association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
loadBalancerPort	Fileserver UI load balancer port	85		No	string
serviceAnnotations	Service annotations			No	object

global fileserver ui serviceAnnotations

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

global fileserver nfs

Description

NFS fileserver association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Fileserver remote host address				
remoteHost	Examples: - 1.1.1.100			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
	Fileserver remote file path				
remotePath	Examples: - /filestore	/filestore		No	string
remotePort	Fileserver remote host port	85		No	string

global fileserver cephfs

Description

CephFS configuration - CephFS is an actual mountable POSIX-compliant filesystem layered on top of a Ceph storage cluster

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable CephFS				
enabled	Examples: - true	false		No	boolean

global helm

Description

Properties to let a pod access the Helm Chart Museum

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	URL to the chart museum				
url	Examples: - http: //1.1.1.1:8080/path/	http: //10.1.1.226:8081/artifactory/cnhelm-dev/		No	string

global mesh

Description

PaaS service mesh associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
istio	Istio service mesh association			No	object

global mesh istio

Description

Istio service mesh association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Service mesh ingress gateway				
ingressGw	Examples: - ingress-gateway			No	string
	Specific IP requested for Ingress Gateway LoadBalancer service				
ingressGwIP	Examples: -			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
ingressGwLiIP	Specific IP requested for Ingress Gateway LI service				
	Examples:			No	string
	-				
ingressGwFQDN	FQDN to be added as annotation to the Ingress Gateway LoadBalancer service				
	Examples:	upf.com		No	string
	-				
mtlsEnabled	Enable/disable istio mutual TLS	false		No	boolean
egressGwTLS	Istio egress gateway TLS			No	object
egressGwTLSLi	Istio LI Egress Gateway TLS Helm Configuration			No	object
ingressGwTLS	Istio ingress gateway TLS			No	object
ingressGwTLSLi	Istio LI Ingress Gateway TLS Helm Configuration			No	object
serviceAnnotations	Service annotations			No	object

[global mesh istio egressGwTLS](#)

Description

Istio egress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio egress gateway TLS				
	Examples:			No	boolean
	- true	false			
mode	Istio egress gateway TLS mode.				
	Examples:	MUTUAL		No	string
	- MUTUAL				
certManager	certManager Configuration			No	object
userProvided	userProvided CERTIFICATES			No	object

[global mesh istio egressGwTLS certManager](#)

Description

certManager Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for certManager configuration				
	Examples:			No	boolean
	- true	true			
certDuration	certDuration Configuration	10h		No	string
	Examples:				
	- false				
renewBefore	renewBefore Configuration	1h		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
organization	organization Configuration				
	Examples:				
	- affirmednetworks	affirmednetworks		No	string
issuerName	issuerName				
	Examples:	affirmed-clusterissuer		No	string
	- affirmed-clusterissuer				
issuerType	issuerType				
	Examples:	vault		No	string
	- vault				
pkiAlgorithm	Algorithm for PKI certs - RSA or ECDSA				
	Examples:	RSA		No	string
	- RSA				
pkiKeySize	- ECDSA				
	PKI Key size for certs, if Algorithm is RSA, valid inputs are 2048,4096,8192. if Algorithm is ECDSA, valid input is 256				
	Examples:				
	- 256	4096		No	string
	- 2048				
	- 4096				
	- 8192				

global mesh istio egressGwTLS userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvided Certificates				
	Examples:	false		No	boolean
	- false				
	- true				
cacert	cacert Configuration				
	Examples:			No	string
	- Copy and Paste End User generated Certificate				
tlsctx	tlsctx configuration				
	Examples:			No	string
	- Copy and Paste End User generated Certificate				
tlskey	tlskey configuration				
	Examples:			No	string
	- Copy and Paste End User generated Certificate				

global mesh istio egressGwTLSLi

Description

Istio LI Egress Gateway TLS Helm Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio egress gateway LI TLS	false		No	boolean
	Examples:				
	- true - false				
mode	Istio egress gateway LI TLS mode.	MUTUAL		No	string
	Examples:				
	- MUTUAL				
userProvided	Helm configuration for user provided certificates, directly provided as helm values			No	object
userProvidedVault	Helm configuration to use user provided certificates configured in vault			No	object

global mesh istio egressGwTLSLi userProvided

Description

Helm configuration for user provided certificates, directly provided as helm values

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvided Certificates	false		No	boolean
	Examples:				
	- false - true				
cacert	cacert Configuration			No	string
	Examples:				
	- Copy and Paste End User generated Certificate				
tls crt	tls crt configuration			No	string
	Examples:				
	- Copy and Paste End User generated Certificate				
tlskey	tlskey configuration			No	string
	Examples:				
	- Copy and Paste End User generated Certificate				

global mesh istio egressGwTLSLi userProvidedVault

Description

Helm configuration to use user provided certificates configured in vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvidedVault Certificates	false		No	boolean
	Examples:				
	- false				
	- true				
egressCert	Names of the secrets configured in vault			No	object

global mesh istio egressGwTLSLi userProvidedVault egressCert

Description

Names of the secrets configured in vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
tlscrtSecretName	TLS cert name configured in vault			No	string
tlskeySecretName	TLS key name configured in vault			No	string
cacertSecretName	CA cert name configured in vault			No	string

global mesh istio ingressGwTLS

Description

Istio ingress gateway TLS

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio ingress gateway TLS	false		No	boolean
	Examples:				
	- true				
	- false				
mode	Istio ingress gateway TLS mode.	MUTUAL		No	string
	Examples:				
	- MUTUAL				
certManager	certManager Configuration			No	object
userProvided	userProvided CERTIFICATES			No	object

global mesh istio ingressGwTLS certManager

Description

certManager Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for certManager configuration	true		No	boolean
	Examples:				
	- true				
	- false				
certDuration	certDuration Configuration		10h	No	string
renewBefore	renewBefore Configuration		1h	No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
organization	organization Configuration				
	Examples:	affirmednetworks		No	string
	- affirmednetworks				
issuerName	issuerName				
	Examples:	affirmed-clusterissuer		No	string
	- affirmed-clusterissuer				
issuerType	issuerType				
	Examples:	vault		No	string
	- vault				
pkiAlgorithm	Algorithm for PKI certs - RSA or ECDSA				
	Examples:				
	- RSA	RSA		No	string
	- ECDSA				
pkiKeySize	PKI Key size for certs, if Algorithm is RSA, valid inputs are 2048,4096,8192. if Algorithm is ECDSA, valid input is 256				
	Examples:				
	- 256	4096		No	string
	- 2048				
	- 4096				
	- 8192				

global mesh istio ingressGwTLS userProvided

Description

userProvided CERTIFICATES

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvided Certificates				
	Examples:	false		No	boolean
	- false				
	- true				
cacert	cacert Configuration				
	Examples:			No	string
	- Copy and Paste End User generated Certificate				
tls crt	tls crt configuration				
	Examples:			No	string
	- Copy and Paste End User generated Certificate				
tlskey	tlskey configuration				
	Examples:			No	string
	- Copy and Paste End User generated Certificate				

global mesh istio ingressGwTLSLi

Description

Istio LI Ingress Gateway TLS Helm Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enabling Istio ingress gateway LI TLS	false		No	boolean
	Examples:				
	- true - false				
mode	Istio ingress gateway LI TLS mode.	MUTUAL		No	string
	Examples:				
	- MUTUAL				
userProvided	Helm configuration for user provided certificates, directly provided as helm values			No	object
userProvidedVault	Helm configuration to use user provided certificates configured in vault			No	object

global mesh istio ingressGwTLSLi userProvided

Description

Helm configuration for user provided certificates, directly provided as helm values

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvided Certificates	false		No	boolean
	Examples:				
	- false - true				
cacert	cacert Configuration			No	string
	Examples:				
	- Copy and Paste End User generated Certificate				
tls crt	tls crt configuration			No	string
	Examples:				
	- Copy and Paste End User generated Certificate				
tlskey	tlskey configuration			No	string
	Examples:				
	- Copy and Paste End User generated Certificate				

global mesh istio ingressGwTLSLi userProvidedVault

Description

Helm configuration to use user provided certificates configured in vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable Flag for userProvidedVault Certificates	false		No	boolean
	Examples:				
	- false				
	- true				
ingressCert	Names of the secrets configured in vault			No	object

global mesh istio ingressGwTLSLi userProvidedVault ingressCert

Description

Names of the secrets configured in vault

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
tlscrtSecretName	TLS cert name configured in vault			No	string
tlskeySecretName	TLS key name configured in vault			No	string
cacertSecretName	CA cert name configured in vault			No	string

global service serviceAnnotations

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from		none	No	string

global monitoring

Description

PaaS Monitoring associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
prometheus	Prometheus monitoring association			No	object

global monitoring prometheus

Description

Prometheus monitoring association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
namespace	Monitoring namespace	fed-prometheus		No	string
	Examples:				
	- fed-prometheus				
enabled	Enable/disable prometheus monitoring	true		No	boolean

global registry

Description

PaaS container registry associations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
docker	Docker registry association			No	object

[global registry](#) docker

Description

Docker registry association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
repoPath	Registry path	<registry_docker_path>		No	string
imagePullSecret	Pull an image from a private registry			No	string
username	Username for private docker registry			No	string
password	Password for private docker registry			No	string

[global envVars](#)

Description

Environment variables

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
fedType	Federation type Examples: - smf	upf	Enumerations: - amf - smf - upf - nrf - nssf	No	string
fedUniqueName	Federation unique name Examples: - upf	default		No	string
serviceRegistryNamespace	Service registry namespace Examples: - fed-service-reg	fed-service-reg		No	string
configDataEncryptionEnable	Enable config JSON file encryption. When true, also requires injection of encryption key as kubernetes secret or it won't encrypt. Examples: - true - false	false		No	boolean

[global encryptDecryptKey](#)

Description

Secret pass phrase used for Encryption/Decryption of LI Data only. This is a private key and usage is within NF scope.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/Disable creation of Kubernetes secret for encryptDecryptKey.key	true		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
key	Encryption Key value (secret pass phrase). It can be alphanumeric and case sensitive.				
	Examples:			No	string
	- abcd1234PQRS				

global grafana

Description

PaaS Grafana association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable grafana association	true		No	boolean
url	Exposed grafana URL				
	Examples:			No	string
	- http://1.1.1.1:3000				
prometheusinfo	Prometheus server association			No	object

global grafana prometheusinfo

Description

Prometheus server association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
url	Prometheus server URL				
	Examples:	http://prometheus.fed-prometheus:9090		No	string
	- http://prometheus.fed-prometheus:9090				

global logging

Description

PaaS logging association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable logging association				
	Examples:	false		No	boolean
	- false				
fluentd	fluentd configurations			No	object
elastic	Elasticsearch association			No	object
enableAddlTargets	Enable/disable additional destinations				
	Examples:	true		No	boolean
	- true				
addlTargets					
	Additional logging output destination configuration				
				No	array
alerts	Alerts configuration			No	object

global logging fluentd

Description

fluentd configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
buffer	fluentd buffer configurations			No	object

global logging fluentd buffer

Description

fluentd buffer configurations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
bufferLimit	Total buffer size. Maximum amount of buffer space each fluentd thread would use to keep logs. After this space is exhausted, fluentd would start deleting oldest logs to make room for new logs.	32m		No	string
retryWait	Interval(seconds) at which the buffer flush is retried in case of failure.	10s		No	string
maxRetries	Max number of retries to flush a buffer chunk. After this is exhausted, fluentd would delete the chunk.	1		No	integer

global logging elastic

Description

Elasticsearch association

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
IP	Elasticsearch IP address				
	Examples:			No	string
	- 10.15.10.161				
Port	Elasticsearch port	9200		No	integer

global logging addITargets

Description

Additional logging output destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
forward	Additional forward destination configuration			Yes	object

global logging addITargets forward

Description

Additional forward destination configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
name	Name of the forward server	fluentd		No	string
host	Hostname or IP Address of the forward server				
	Examples:				
	- 192.168.1.1			No	string
	- forward-server.com				

Parameter	Description	Default	Value/Range	Mandatory	Type
	Port of the forward server				
port	Examples: - 24224	24224		No	integer

global logging alerts

Description

Alerts configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable event alerts				
enabled	Examples: - true	false		No	boolean
	Elasticsearch Host address				
host	Examples: - 10.15.10.161			No	string
port	Elasticsearch port	3030		No	integer
realert	Re-alert Info			No	object
receivers	Receiver type to send alerts, Currently supported are slack as 'slack', email as 'email' and HTTP-POST as 'post'			No	array

global logging alerts realert

Description

Re-alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Interval in minutes to re-send an alert				
minutes	Examples: - 2	1		No	integer

global logging alerts receivers

Description

Receiver type to send alerts, Currently supported are slack as 'slack', email as 'email' and HTTP-POST as 'post'

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
slack	Slack alert Info			No	object
email	Mail alert Info			No	object
post	HTTP post alert Info			No	object

global logging alerts receivers slack

Description

Slack alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
webhookurl	The webhook URL that includes your auth data and the ID of the channel (room) you want to post to.				
	Examples:			No	string
	- xxxx				

global logging alerts receivers email

Description

Mail alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
to_address	An address or list of addresses to sent the alert to				
	Examples:			No	string
	- user1@example.com				
smtp_host	SMTP host info				
	Examples:			No	string
	- 1.1.1.1				
smtp_port	SMTP port info				
	Examples:			No	string
	- 25				
smtp_ssl	Enable/disable SSL to SMTP server				
	Examples:	false		No	boolean
	- true				
from_addr	This sets the from header in the email. By default, the from address is ElastAlert@ and the domain will be set by the smtp server				
	Examples:			No	string
	- user2@example.com				

global logging alerts receivers post

Description

HTTP post alert Info

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
http_post_url	URL for HTTP post				
	Examples:			No	string
	- XXXX				

global license

Description

PaaS License Server Selector

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
flexera	Flexera license server information			No	object

[global license](#) flexera

Description

Flexera license server information

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Flexera license server host				
remoteHost	Examples: - 10.163.67.251			No	string
	Flexera license server port				
remotePort	Examples: - 7070			No	string

[global resource](#)

Description

Default limits and request for each container

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
defaultlimit	Default CPU & memory limits for each container			No	object
defaultrequest	Default CPU & memory request for each container			No	object

[global resource](#) defaultlimit

Description

Default CPU & memory limits for each container

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Default CPU limits for each container				
cpu	Examples: - 1	8		No	integer
	Default memory limits for each container				
memory	Examples: - 4Gi	2Gi		No	string

[global resource](#) defaultrequest

Description

Default CPU & memory request for each container

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Default CPU request for each container				
cpu	Examples: - 10m	10m		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
memory	Default memory request for each container	10Mi		No	string
	Examples:				
	- 10Mi				

global topologySpreadConstraints

Description

Pod topology spread constraints control how pods of given microservice type are spread across the cluster among failure-domains such as regions, zones, nodes, and other user-defined topology domains. This can help to achieve high availability as well as efficient resource utilization.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable pod topology spread constraints	true		No	boolean
	Examples:				
	- false				
	- true				
constraints	List of pod topology spread constraints to be applied.			No	array

global topologySpreadConstraints constraints

Description

List of pod topology spread constraints to be applied.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
0	Definition of pod topology spread constraint to be applied to the pod specification.			No	object

global topologySpreadConstraints constraints 0

Description

Definition of pod topology spread constraint to be applied to the pod specification.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxSkew	Describes the degree to which pods may be unevenly distributed. It's the maximum permitted difference between the number of matching pods in any two topology domains of a given topology type. It must be greater than zero.	1		No	integer
	Examples:				
	- 1				
topologyKey	Its the key of node labels. If two nodes are labelled with this key and have identical values for that label, the Kubernetes scheduler treats both nodes as being in the same topology. The scheduler tries to place a balanced number of Pods into each topology domain.	kubernetes.io/hostname		No	string
	Examples:				
	- kubernetes.io/hostname				

Parameter	Description	Default	Value/Range	Mandatory	Type
	Indicates how to deal with a pod if it doesn't satisfy the defined pod topology spread constraint.				
whenUnsatisfiable	Examples: - ScheduleAnyway - DoNotSchedule	ScheduleAnyway		No	string

global externalPfcpsvc

Description

External service parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable external service				
enabled	Examples: - true	true		Yes	boolean
	Name of external pfcpsvc service				
name	Examples: - sxa-sxb-n4	sxa-sxb-n4	Enumerations: - sxa-sxb-n4	Yes	string
	IP for the load balancer. More info here - https://kubernetes.io/docs/tasks/access-application-cluster/create-external-load-balancer/				
loadBalancerIP	Examples: - 1.1.1.1			Yes	string
serviceAnnotations	Service annotations			No	object
	If specified, this is added as an annotation to the pfcpsvc service. Other applications can then query to find the FQDN through which external peers can reach this application				
loadBalancerFQDN	Examples: - smf.sxa-sxb-n4.msft.com			No	string
type	Interface type for pfcpsvc microservice			Yes	array

global externalPfcpsvc serviceAnnotations

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

pod-fileserver

Description

PaaS Fileserver microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable fileserver	true		No	boolean
	Examples:				
	- false				
deployment	Deployment parameters			No	object
pvc	Persistent Volume Claim (PVC) configuration			No	object

pod-fileserver deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer

pod-fileserver pvc

Description

Persistent Volume Claim (PVC) configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
web	PVC web configuration			No	object
cfg	PVC cfg configuration			No	object

pod-fileserver pvc web

Description

PVC web configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
requestsStorage	Requests storage for pvc	5Gi		No	string
	Examples:				
	- 25Gi				
storageClassName	Storage class name for pvc	web		No	string
	Examples:				
	- rook-cephfs				

pod-fileserver pvc cfg

Description

PVC cfg configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
requestsStorage	Requests storage for pvc	5Gi		No	string
	Examples:				
	- 25Gi				

Parameter	Description	Default	Value/Range	Mandatory	Type
	Storage class name for pvc				
storageClassName	Examples: - rook-cephfs	cfg		No	string

pod-cfgmgr

Description

Config Manager microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable cfgmgr				
enabled	Examples: - false	true		No	boolean
confd	Confd parameters			No	object
	Configuring rbacEnabled to true will create clusterrolebinding. Configuring rbacEnabled to false, clusterrolebinding will not be created.				
rbacEnabled	Examples: - false	true		No	boolean
	Configuring preLoginSSHBanner to true will add banner to cfgmgr ssh sessions.				
preLoginSSHBanner	Examples: - true	false		No	boolean
	clusterrole and PSP for is created as a part of fed-rbac. clusterrole options are restricted-cr, permissive-network-cr, permissive-full-cr				
clusterRole	Examples: - permissive-full-cr	permissive-full-cr		No	string
	serviceAccountName configuration is used to create serviceaccount per pod				
serviceAccountName	Examples: - cfgmgr-serviceaccount	cfgmgr-serviceaccount		No	string
deployment	Deployment parameters			No	object
service	Service parameters			No	object
tlscipherSuite	TLS cipher suite parameters			No	object
sshdcipherSuite	SSHD cipher suite parameters			No	object

[pod-cfgmgr confd](#)

Description

Confd parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
aes256cfb128Key	encoded confd aes256cfb128Key, echo f9c4065f6592b38cc3dbaf2033f73b6c54751c4425faf688857704004306d65a	base64 -w 100		No	

[pod-cfgmgr deployment](#)

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	3		No	integer

pod-cfgmgr service

Description

Service parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
loadBalancerIP	Load Balancer IP address				
	Examples: - 10.1.1.101			No	string
loadBalancerFQDN	If specified, this is added as an annotation to the cfgmgr service. Other applications can then query to find the FQDN through which external peers can reach this application				
	Examples: - cfgmgr.upf.affirmed.com			No	string
serviceAnnotations	Service annotations			No	object

pod-cfgmgr service serviceAnnotations

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

pod-cfgmgr tlscipherSuite

Description

TLS cipher suite parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable TLS cipher suite				
	Examples: - false	true		No	boolean
cipherString	TLS cipher Suite String				
	Examples: - DHE-DSS-AES256-SHA	DHE-DSS-AES256-SHA:DHE-RSA-AES256-SHA:DHE-DSS-AES128-SHA256:DHE-RSA-AES128-SHA256:DHE-RSA-AES128-SHA		No	string

pod-cfgmgr sshdcipherSuite

Description

SSHD cipher suite parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable SSHD cipher suite				
	Examples:	true		No	boolean
	- false				
cipherString	SSHD cipher Suite String				
	Examples:	aes256-ctr,aes192-ctr,aes128-ctr		No	string
	- aes256-ctr				

pod-istio_gw

Description

Istio Gateway microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable istio-gw	true		No	boolean
	Examples:				
	- false				
istioNspace	Istio namespace	fed-istio		No	string
	Examples:				
	- fed-istio				
ingressGateway	Ingress gateway parameters			No	object
egressGateway	Egress gateway parameters			No	object
podDisruptionBudget	Pod Disruption Budget parameters			No	object
paasSelector	PAAS parameters			No	object

[pod-istio_gw](#) [ingressGateway](#)

Description

Ingress gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable ingress gateway	true		No	boolean
	Examples:				
	- false				

[pod-istio_gw](#) [egressGateway](#)

Description

Egress gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable egress gateway	true		No	boolean
	Examples:				
	- false				

pod-istio_gw podDisruptionBudget

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	10%		No	string

pod-istio_gw paasSelector

Description

PAAS parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Jaeger host (IP or FQDN)				
	Examples:				
jaegerHostName	- 10.10.10.10	fqdn.com		No	string
	- fqdn.com				

pod-istio_gw_li

Description

Istio LI Gateway microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable istio-gw-li				
enabled	Examples: - false	true		No	boolean
podDisruptionBudget	Pod Disruption Budget parameters			No	object
	Configuring rbacEnabled to true will create clusterrolebinding. Configuring rbacEnabled to false, clusterrolebinding will not be created.				
rbacEnabled	Examples: - false	true		No	boolean
	Istio namespace				
istioNspace	Examples: - fed-istio	fed-istio		No	string
ingressGateway	Ingress LI gateway parameters			No	object
egressGateway	Egress LI gateway parameters			No	object
paasSelector	PAAS parameters			No	object

pod-istio_gw_li podDisruptionBudget

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	10%		No	string

pod-istio_gw_li ingressGateway

Description

Ingress LI gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable LI ingress gateway				
enabled	Examples: - false	true		No	boolean

pod-istio_gw_li egressGateway

Description

Egress LI gateway parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable egress LI gateway				
enabled	Examples: - false	true		No	boolean

pod-istio_gw_li paasSelector

Description

PAAS parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Jaeger host (IP or FQDN)				
jaegerHostName	Examples: - 10.10.10.10 - fqdn.com	fqdn.com		No	string

pod-timer

Description

Timer microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable timer microservice				
enabled	Examples: - false	true		No	boolean
deployment	Deployment parameters			No	object

pod-timer deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	3		No	integer

pod-nrf_agent

Description

NRF microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable NRF microservice				
enabled	Examples: - false	true		No	boolean
deployment	Deployment parameters			No	object
podDisruptionBudget	Pod Disruption Budget parameters			No	object

[pod-nrf_agent deployment](#)

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer

[pod-nrf_agent podDisruptionBudget](#)

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	10%		No	string

pod-pfcp_u

Description

PFCP-U microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable PFCP-U microservice				
enabled	Examples: - false	true		No	boolean

Parameter	Description	Default	Value/Range	Mandatory	Type
deployment	Deployment parameters			No	object
podDisruptionBudget	Pod Disruption Budget parameters			No	object
service	Service parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
upgrade	Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.			No	object
tracing	Tracing parameters			No	object

[pod-pfcp_u deployment](#)

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer
strategy	Deployment Update strategy			No	object

[pod-pfcp_u deployment strategy](#)

Description

Deployment Update strategy

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

[pod-pfcp_u deployment strategy rollingUpdate](#)

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	0		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	1		No	string

[pod-pfcp_u podDisruptionBudget](#)

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	10%		No	string

pod-pfcp_u service

Description

Service parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Load Balancer IP address				
loadBalancerIP	Examples: - 10.1.1.101			No	string
	If specified, this is added as an annotation to the PFCP service. Other applications can then query to find the FQDN through which external peers can reach this application				
externalFqdn	Examples: - pfcp.upf.affirmed.com			No	string
serviceAnnotations	Service annotations			No	object

pod-pfcp_u service serviceAnnotations

Description

Service annotations

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
service.beta.kubernetes.io/azure-load-balancer-internal-subnet	Specify which Azure load balancer subnet to allocate from	none		No	string

pod-pfcp_u hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable HPA				
enabled	Examples: - false	false		No	boolean
	Infra container HPA CPU requests				
infraCpuRequests	Examples: - 10m			No	string
	Worker container HPA CPU requests				
workerCpuRequests	Examples: - 800m			No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
workerCpuLimits	Worker container HPA CPU limits				
	Examples:			No	string
	- 1000m				
maxReplicas	The maximum number of simultaneous instances of this pod allowed				
	Examples:	0		No	integer
	- 1				
minReplicas	The minimum number of simultaneous instances of this pod allowed				
	Examples:	0		No	integer
	- 1				
averageUtilization	Pod average utilization				
	Examples:	0		No	integer
	- 80				

pod-pfcp_u upgrade

Description

Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable canary sequence				
	Examples:	false		No	boolean
	- false				
canaryVersWeight	Canary pod weight percentage				
	Examples:	0		No	integer
	- 20				
stableVersWeight	Stable pod weight percentage				
	Examples:	0		No	integer
	- 80				
stableVersion	Stable pod image version				
	Examples:			No	string
	- 0.0.0				
stableInfraImage	Infra container stable image				
	Examples:			No	string
	- cna-infra:1.0.0.0-349.rel				
stableWorkerImage	Worker container stable image				
	Examples:			No	string
	- cna-pfcp:1.0.0.0-158.rel				

pod-pfcp_u tracing

Description

Tracing parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable tracing	false		No	boolean
	Examples: - true				
samplerType	Sampler type. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration Examples: - probabilistic	probabilistic		No	string
samplerParam	Sampler parameter. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration Examples: - 1.0	1.0		No	string
agentPort	UDP port exposed by jaeger-agent Examples: - 6831	6831		No	string
logEnabled	Enable/disable jaeger logging Examples: - false	false		No	string

pod-interface_mgr

Description

Interface Manager microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable Interface Manager microservice	true		No	boolean
	Examples: - false				
deployment	Deployment parameters			No	object

pod-interface_mgr deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer

pod-ppe

Description

PPE microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable PPE microservice				
enabled	Examples: - false	true		No	boolean
certs	security certs for pod-ppe microservice			No	object
	Configuring rbacEnabled to true will create clusterrolebinding. Configuring rbacEnabled to false, clusterrolebinding will not be created.				
rbacEnabled	Examples: - false	true		No	boolean
	clusterrole and PSP for is created as a part of fed-rbac. clusterrole options are restricted-cr, permissive-network-cr, permissive-full-cr				
clusterRole	Examples: - permissive-full-cr	permissive-full-cr		No	string
podDisruptionBudget	Pod Disruption Budget parameters			No	object
	serviceAccountName configuration is used to create serviceaccount per pod				
serviceAccountName	Examples: - ppe-serviceaccount	ppe-serviceaccount		No	string
	tlsEnabled configuration is used to enable TLS over Li X3/X2				
tlsEnabled	Examples: - true	false		No	boolean
	First core dataplane that will be allowed to use. This is not a physical core number; it is a core number within the range allocated to the pod. I.e if a dataplane pod is allocated 10 cores, the first core has to be in the 0-9 range				
ppeFirstWorker	Examples: - 1	1		No	string
	Number of cores allocated to dataplane, including the first core. E.g. if first core is 2 and ppeNumWorkers is 7, then cores 2,3,4,5,6,7,8,9 will be allocated to dataplane				
ppeNumWorkers	Examples: - 2	2		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
ppeloScaling	Dataplane I/O resource distribution. Options: 1. grouped: all ports' rx queues are handled by a single I/O core. 2. shared-cores: there are as many I/O cores as rx-queues on each interfaces. The Xth queue of each interfaces share the Xth I/O core. 3. separated-cores: there are as many I/O cores as there rx-queues total. Each rx-queue is placed on an individual I/O core Examples: - separated-cores	separated-cores	Enumerations: - grouped - shared-cores - separated-cores	No	string
numRxQueuesPerInterface	Number of rx queues per interface Examples: - 1	1		No	string
vlanStripping	Enable/disable vlan stripping on dataplane ports Examples: - true	false		No	boolean
enableJumboFrames	Enable/disable jumbo frame support Examples: - true	false		No	boolean
ppeHyperthreadAlign	Aligns the pkt engine with hyperthreads. 1. preferred (hyperthread alignment in best effort approach). 2. none (default)1 Examples: - preferred	none	Enumerations: - preferred - none	No	string
dplnHeapSize	Size of the dataplane pkt engine heap, in GBytes Examples: - 10G	10G		No	string
dplnBuffersPerNuma	Number of pkt buffers per NUMA allocated by the pkt engine. Note: sufficient hugepages have to be available for the buffers (dplnHugepagesSize may need to be increased to accommodate additional buffers per NUMA) Examples: - 160000	160000		No	string
ppeBfdReflectionMode	Enable/Disable BFD Reflection mode. Examples: - true	true		No	boolean
ppeFlowDistribution	Enable/Disable PPE FLOW DISTRIBUTION feature. Examples: - true	true		No	boolean
ppeCoreSchema	Roles assigned to PPE's VPP CPU cores Examples: - IO_N_SAC_PLUS_FAC	IO_N_SAC_PLUS_FAC		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
ppeMaxUrrsIntended	Maximum number of URRs supported	400000		No	string
	Examples: - 400000				
ppeMaxFarsIntended	Maximum number of FARs supported	400000		No	string
	Examples: - 400000				
ppeloWorker	Enable/Disable PPE IO WORKER feature.	false		No	boolean
	Examples: - true				
dataplaneWrkVecOpt	Enable/Disable Dataplane Worker Vector Optimization feature.	false		No	boolean
	Examples: - true				
dataplaneEnableTxIpCsumOffload	Enable/Disable Dataplane Tx Ip Csum Offload.	false		No	boolean
	Examples: - true				
l3am	Layer 3 Affinity Mode parameters			No	object
cnaInfraThreadPoolSizeDbClient	Infra thread pool size count	1000		No	string
	Examples: - 1000				
dpiSignatureUpgradeEnabled	Enable/Disable DPI SIGNATURE UPGRADE capability.	true		No	boolean
	Examples: - true				
deployment	Deployment parameters			No	object
resources	The Resources Schema			No	object
storage	Storage option to store pcap rules			No	object
imageStorage	Storage option to store images			No	object
guaranteedScheduling	Define CPU & memory limits for 4 containers: ppe, infra and istio-proxy and proxy-init. All 3 need to follow the config presented in https://kubernetes.io/docs/tasks/configure-pod-container/quality-service-pod/#create-a-pod-that-gets-assigned-a-qos-class-of-guaranteed Note: If a Container specifies its own memory limit, but does not specify a memory request, Kubernetes automatically assigns a memory request that matches the limit. Similarly, if a Container specifies its own CPU limit, but does not specify a CPU request, Kubernetes automatically assigns a CPU request that matches the limit. Don't specify requests.			No	object
sriov	SRIOV parameters			No	array
netAttachDefs	Networking attachment configuration for the VM node. Supported drivers are Intel and Mellanox			No	object
tracing	Tracing parameters			No	object
tdef	Traffic detection enforced function			No	object
tvs	Transparent video shaping function			No	object
imgmgmt	PVC imgmgmt configuration			No	object

pod-ppe certs

Description

security certs for pod-ppe microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
cacert	certificate authority cert			No	string
tlscrt	tls cert			No	string
tlskey	tls key			No	string

pod-ppe podDisruptionBudget

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.the minAvailable has to be set to n-1 if there are n PPE pods deployed in the UPF	1		No	integer

pod-ppe l3am

Description

Layer 3 Affinity Mode parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable Layer 3 Affinity Mode. Must be set to the same value as pod-l3rm/l3am/enabled				
enabled	Examples: - true	true		No	boolean

pod-ppe deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer
	Enable/disable capture-agent deployment				
deployCaptureAgent	Examples: - true	false		No	boolean
readinessProbe	Readiness Probe Configuration			No	object
strategy	Deployment Update strategy. PPE will be upgraded one at a time.			No	object

pod-ppe deployment readinessProbe

Description

Readiness Probe Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable or Disable readiness probe configuration.	true		No	boolean
	Examples: - true				
initialDelaySeconds	Number of seconds after the container has started before readiness probes is initiated	180		No	integer
periodSeconds	Periodic interval in seconds at which the probe request is sent to the container	10		No	integer
successThreshold	Number of success responses to figure the readiness of the container	1		No	integer
timeoutSeconds	Timeout interval before which the response should be received otherwise probe fails	10		No	integer
failureThreshold	Number of consecutive probe failures resulting in container restart	15		No	integer

pod-ppe deployment strategy

Description

Deployment Update strategy. PPE will be upgraded one at a time.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rollingUpdate	Rolling Update Configuration			No	object

pod-ppe deployment strategy rollingUpdate

Description

Rolling Update Configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
maxUnavailable	Specifies the maximum number of Pods that can be unavailable during the update process.	1		No	string
maxSurge	Specifies the maximum number of Pods that can be created over the desired number of Pods.	0		No	string

pod-ppe resources

Description

The Resources Schema

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
hugepagesType	Huge pages type	2Mi		No	string
	Examples: - 2Mi				
ppeCpuRequests	PPE container CPU usage threshold	3		No	integer
	Examples: - 3				
ppeCpuLimits	PPE container CPU usage maximum Limit	3		No	integer
	Examples: - 3				
ppeMemory	Allocated memory for PPE container	8Gi		No	string
	Examples: - 4Gi				

Parameter	Description	Default	Value/Range	Mandatory	Type
	Huge pages size. More information here - https://wiki.debian.org/Hugepages				
ppeHugepagesSize	Examples: - 4Gi	4Gi		No	string

pod-ppe storage

Description

Storage option to store pcap rules

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Three storage type can be configured. Those are local, remote or rook				
	Examples: - nfs - remote - rook				
type		nfs		No	string
	Set any convenient value Storage class name if stoare type is local or remote. But if storage type is rook, mandatorily set it to the storage class name of File system storage that gets deployed with fed-rook-ceph. Default value is rook-cephfs				
	Examples: - ppe-local - rook-cephfs - ppe-remote	ppe-local		No	string
storageClassName					
pcapStorageSize	pcapStorageSize is storage limit	5Gi		No	string
	External Storage provisioner. Configure this field only if storage type is remote. Any file system storage provisioner can be configured.				
provisioner	Examples: - kubernetes.io/azure-file			No	string
	PersistentVolumes that are dynamically created by a StorageClass will have the reclaim policy specified in the reclaimPolicy field				
	Examples: - Delete - Retain	Retain		No	string
reclaimPolicy					
parameters	External storage specific parameters. By default azure-file parameters are given. Any other key/value pair can be configured by modifying values.yaml			No	object

pod-ppe storage parameters

Description

External storage specific parameters. By default azure-file parameters are given. Any other key/value pair can be configured by modifying values.yaml

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
customParameters	Both key/value pair can be configured. Since any filesystem type provisioner can be configured, it's corresponding parameters can be set under this section. By default azure-file parameters are given			No	object

pod-ppe storage parameters customParameters

Description

Both key/value pair can be configured. Since any filesystem type provisioner can be configured, it's corresponding parameters can be set under this section. By default azure-file parameters are given

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
skuName	Azure storage account Sku tier. Default is empty			No	string
location	Azure storage account location. Default is empty.			No	string
storageAccount	Azure storage account name. Default is empty. If a storage account is not provided, all storage accounts associated with the resource group are searched to find one that matches skuName and location			No	string

pod-ppe imageStorage

Description

Storage option to store images

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
type	Three storage type can be configured. Those are local, remote or rook				
	Examples:				
	- nfs	nfs		No	string
	- remote				
storageClassName	- rook				
	Set Storage class name as imgmgmt if storage type is nfs. But if storage type is rook, mandatorily set it to the storage class name of File system storage that gets deployed with fed-rook-ceph. Default value is rook-cephfs				
	Examples:	imgmgmt		No	string
	- imgmgmt				
storageSize	- rook-cephfs				
	- ppe-remote				
	storageSize is storage limit	3Gi		No	string
	External Storage provisioner. Configure this field only if storage type is remote. Any file system storage provisioner can be configured.				
provisioner	Examples:			No	string
	- kubernetes.io/azure-file				
	PersistentVolumes that are dynamically created by a StorageClass will have the reclaim policy specified in the reclaimPolicy field				
	Examples:	Retain		No	string
reclaimPolicy	- Delete				
	- Retain				
	External image storage specific parameters. By default azure-file parameters are given. Any other key/value pair can be configured by modifying values.yaml			No	object
	parameters				

pod-ppe imageStorage parameters

Description

External image storage specific parameters. By default azure-file parameters are given. Any other key/value pair can be configured by modifying values.yaml

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
customParameters	Both key/value pair can be configured. Since any filesystem type provisioner can be configured, it's corresponding parameters can be set under this section. By default azure-file parameters are given			No	object

[pod-ppe imageStorage parameters](#) [customParameters](#)

Description

Both key/value pair can be configured. Since any filesystem type provisioner can be configured, it's corresponding parameters can be set under this section. By default azure-file parameters are given

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
skuName	Azure storage account Sku tier. Default is empty			No	string
location	Azure storage account location. Default is empty.			No	string
storageAccount	Azure storage account name. Default is empty. If a storage account is not provided, all storage accounts associated with the resource group are searched to find one that matches skuName and location			No	string

[pod-ppe guaranteedScheduling](#)

Description

Define CPU & memory limits for 4 containers: ppe, infra and istio-proxy and proxy-init. All 3 need to follow the config presented in <https://kubernetes.io/docs/tasks/configure-pod-container/quality-service-pod/#create-a-pod-that-gets-assigned-a-qos-class-of-guaranteed> Note: If a Container specifies its own memory limit, but does not specify a memory request, Kubernetes automatically assigns a memory request that matches the limit. Similarly, if a Container specifies its own CPU limit, but does not specify a CPU request, Kubernetes automatically assigns a CPU request that matches the limit. Don't specify requests.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable guaranteedScheduling for PPE microservice				
	Examples: - true	false		No	boolean
infraCpuLimit	Infra container CPU usage maximum Limit				
	Examples: - 100m	100m		No	string
infraMemoryLimit	Infra container memory usage maximum Limit				
	Examples: - 2Gi	256Mi		No	string
kafkaCpuLimit	Kafka container CPU usage maximum Limit				
	Examples: - 100m	100m		No	string
kafkaMemoryLimit	Kafka container memory usage maximum Limit				
	Examples: - 2Gi	256Mi		No	string
proxyCPULimit	Proxy container CPU usage maximum Limit				
	Examples: - 200m	200m		No	string

Parameter	Description	Default	Value/Range	Mandatory	Type
proxyMemoryLimit	Proxy container memory usage maximum Limit	256Mi		No	string
	Examples: - 2Gi				
proxyInitCPULimit	Proxy-Init container CPU usage maximum Limit	100m		No	string
	Examples: - 100m				
proxyInitMemoryLimit	Proxy-Init container memory usage maximum Limit	128Mi		No	string
	Examples: - 2Gi				
ppeCpuLimit	PPE container CPU usage maximum Limit	3		No	integer
	Examples: - 3				
ppeMemoryLimit	PPE container memory usage maximum Limit	8Gi		No	string
	Examples: - 2Gi				

pod-ppe sriov

Description

SRIOV parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
labels	SRIOV label names configured on cluster			Yes	string
	Examples: - label1				
nblfc	Number of interfaces/NICs on n3 or n6	1		Yes	string
	Examples: - 1				

pod-ppe netAttachDefs

Description

Networking attachment configuration for the VM node. Supported drivers are Intel and Mellanox

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable non-default network driver. The default driver is intel. Intel needs this disabled.	false		No	boolean
	Examples: - true				
annotation	SR-IOV network driver parameters	sriov-net1, sriov-net2		No	string
	Examples: - sriov-net1, sriov-net2				

pod-ppe tracing

Description

Tracing parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable tracing	false		No	boolean
	Examples: - false				
samplerType	Sampler type. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration	probabilistic	Enumerations: - const - probabilistic - ratelimiting - remote	No	string
	Examples: - probabilistic				
samplerParam	Sampler parameter. More information here - https://www.jaegertracing.io/docs/1.14/sampling/#client-sampling-configuration	1.0		No	string
	Examples: - 1.0				
agentPort	UDP port exposed by jaeger-agent	6831		No	string
	Examples: - 6831				
logEnabled	Enable/disable jaeger logging	false	Enumerations: - true - false	No	string
	Examples: - false				

pod-ppe tdef

Description

Traffic detection enforced function

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable traffic detection enforced function	false		No	boolean
	Examples: - true				
name	name of the microservice being deployed as integrated PPE	ippe		No	string
	Examples: - ippe				
numProxyInstances	Number of proxy instances	3		No	integer
	Examples: - 1				

Parameter	Description	Default	Value/Range	Mandatory	Type
ppeMode	PPE integrated with proxy or decoupled	integrated		No	string
	Examples: - integrated				
maxProxyPods	Number of proxy pods per PPE	2		No	integer
	Examples: - 1				
proxy	Proxy container CPU usage maximum Limit			No	object

pod-ppe tdef proxy

Description

Proxy container CPU usage maximum Limit

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
resources	The Resources Schema for proxy microservice			No	object
guaranteedScheduling	Define CPU & memory limits for proxy and other containers. Note - All containers within the PPE pod need to follow the config presented in https://kubernetes.io/docs/tasks/configure-pod-container/quality-service-pod/#create-a-pod-that-gets-assigned-a-qos-class-of-guaranteed Note: If a Container specifies its own memory limit, but does not specify a memory request, Kubernetes automatically assigns a memory request that matches the limit. Similarly, if a Container specifies its own CPU limit, but does not specify a CPU request, Kubernetes automatically assigns a CPU request that matches the limit. Don't specify requests.			No	object

pod-ppe tdef proxy resources

Description

The Resources Schema for proxy microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
proxyCpuRequests	Proxy container CPU usage threshold	3		No	integer
	Examples: - 3				
proxyCpuLimits	Proxy container CPU usage maximum Limit	3		No	integer
	Examples: - 3				
proxyMemory	Allocated memory for proxy container	4Gi		No	string
	Examples: - 4Gi				

pod-ppe tdef proxy guaranteedScheduling

Description

Define CPU & memory limits for proxy and other containers. Note - All containers within the PPE pod need to follow the config presented in https://kubernetes.io/docs/tasks/configure-pod-container/quality-service-pod/#create-a-pod-that-gets-assigned-a-qos-class-of-guaranteed Note: If a Container specifies its own memory limit, but does not specify a memory request, Kubernetes automatically assigns a memory request that matches the limit. Similarly, if a Container specifies its own CPU limit, but does not specify a CPU request, Kubernetes automatically assigns a CPU request that matches the limit. Don't specify requests.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable guaranteedScheduling for PPE microservice	false		No	boolean
	Examples:				
	- true				
tdefProxyCpuLimit	Proxy container CPU usage maximum Limit	4		No	integer
	Examples:				
	- 3				
tdefProxyMemoryLimit	Proxy container memory usage maximum Limit	8Gi		No	string
	Examples:				
	- 2Gi				

pod-ppe tvs

Description

Transparent video shaping function

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable transparent video shaping function	false		No	boolean
	Examples:				
	- true				

pod-ppe imgmgmt

Description

PVC imgmgmt configuration

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
requestsStorage	Requests storage for pvc	3Gi		No	string
	Examples:				
	- 25Gi				
storageClassName	Storage class name for pvc	imgmgmt		No	string
	Examples:				
	- rook-cephfs				

pod-l3rm

Description

L3rm microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable L3rm microservice	true		No	boolean
	Examples:				
	- false				
l3am	Layer 3 Affinity Mode parameters		No		object
deployment	Deployment parameters		No		object

pod-l3rm l3am

Description

Layer 3 Affinity Mode parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable Layer 3 Affinity Mode. Must be set to the same value as pod-ppe/l3am/enabled	true		No	boolean
	Examples: - true				
maxPpe	Maximum number of PPE pods expected in this UPF.	1		No	integer
	Examples: - 4				
spreadFactor	The number of L3AM Resource Blocks that will be assigned to each PPE pod. Each resource block encapsulates an N3 loopback as well as the UE Pool chunks from the UE Pools configured on the N6 network instances. The range is [1, (maxPpe - 1)], inclusive. Recommended value is (maxPpe - 1).	1		No	integer
	Examples: - 3				
ppeNodeZoneResiliencyEnabled	enable or disable zone/rack level resiliency for PPE failures. By default it will be disabled.	false		No	boolean
	Examples: - true				
tinyPoolSize	UE IP-POOL Size within this value will be considered as Tiny Pool and will be assigned to only One Resource Block.	512		No	integer
	Examples: - 1028				
smallPoolSize	UE IP-POOL Size greater than TinyPoolSize and within this value will be considered as Small Pool and will be assigned to only Two Resource Blocks.	4096		No	integer
	Examples: - 8192				
mediumPoolSize	UE IP-POOL Size greater than the SmallPoolSize and within this value will be considered as Medium Pool and will be assigned to only Four Resource Blocks.	16384		No	integer
	Examples: - 32768				

pod-l3rm deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer

pod-routing

Description

Routing microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable Routing microservice				
enabled	Examples: - false	true		No	boolean
deployment	Deployment parameters			No	object

[pod-routing](#) deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer

pod-upf_monitor

Description

UPF Monitor microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable UPF Monitor microservice				
enabled	Examples: - false	true		No	boolean
	Guage update interval				
gaugeUpdateInterval	Examples: - 300	300		No	integer
activePpe	Minimum Active Ppe			No	object

[pod-upf_monitor](#) activePpe

Description

Minimum Active Ppe

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
-----------	-------------	---------	-------------	-----------	------

Parameter	Description	Default	Value/Range	Mandatory	Type
	Minimum Active Ppe count				
minimumCount	Examples: - 1	1		No	integer

pod-upf_azure_mgr

Description

AzureMgr microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Enable/disable AzureMgr microservice				
enabled	Examples: - false	false		No	boolean
azureProfile	azureProfile parameters			No	object
upfAzureSubnetProfile	upfAzureSubnetProfile parameters			No	object
	SA to handle Auth for AzureMgr microservice				
serviceAccountName	Examples: - upf-azure-mgr-sa	upf-azure-mgr-sa		No	string
	UAMI Client ID to bind with SA used for AzureMgr microservice				
serviceAccountUAMIClientId	Examples: - d7044fc5-7554-490d-8deb-aa8fe67a45e3	d7044fc5-7554-490d-8deb-aa8fe67a45e3		No	string
deployment	Deployment parameters			No	object

[pod-upf_azure_mgr](#) [azureProfile](#)

Description

azureProfile parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Location of the Azure resource				
azureLocation	Examples: - South Central US	South Central US		No	string

[pod-upf_azure_mgr](#) [upfAzureSubnetProfile](#)

Description

upfAzureSubnetProfile parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	N6 RG of Route Table Name				
n6ResGrpOfRouteTableName	Examples: - n6_rg_rt	n6_rg_rt		No	string

[pod-upf_azure_mgr](#) [deployment](#)

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
	Deployment replica count				
replicas	Examples: - 1	1		No	integer

pod-li_x1

Description

LI X1 microservice

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
rbacEnabled	Configuring rbacEnabled to true will create clusterrolebinding. Configuring rbacEnabled to false, clusterrolebinding will not be created. Examples: - false	true		No	boolean
clusterRole	clusterrole and PSP for is created as a part of fed-rbac. clusterrole options are restricted-cr, permissive-network-cr, permissive-full-cr Examples: - permissive-network-cr	permissive-network-cr		No	string
serviceAccountName	serviceAccountName configuration is used to create serviceaccount per pod Examples: - li-x1-serviceaccount	li-x1-serviceaccount		No	string
cnaInfraThreadPoolSizeDbClient	Infra thread pool size count Examples: - 1000	1000		No	string
deployment	Deployment parameters			No	object
podDisruptionBudget	Pod Disruption Budget parameters			No	object
hpa	Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all			No	object
upgrade	Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicatory are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.			No	object

[pod-li_x1](#) deployment

Description

Deployment parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
replicas	Deployment replica count	1		No	integer

pod-li_x1 podDisruptionBudget

Description

Pod Disruption Budget parameters

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
minAvailable	Set the minimum number of replicas which must be available, even during a voluntary disruption.	10%		No	string

pod-li_x1 hpa

Description

Horizontal Pod Autoscaler (HPA) - when enabled, the number of replicas are automatically scaled between the specified minReplicas and maxReplicas based on whether the CPU utilization is above or below the specified threshold percentage relative to the sum of CPU requests of all

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
enabled	Enable/disable HPA	true		No	boolean
	Examples:				
	- false				
infraCpuRequests	Infra container HPA CPU requests	10m		No	string
	Examples:				
	- 10m				
workerCpuRequests	Worker container HPA CPU requests	460m		No	string
	Examples:				
	- 460m				
workerCpuLimits	Worker container HPA CPU limits	1000m		No	string
	Examples:				
	- 1000m				
maxReplicas	The maximum number of simultaneous instances of this pod allowed	1		No	integer
	Examples:				
	- 3				
minReplicas	The minimum number of simultaneous instances of this pod allowed	1		No	integer
	Examples:				
	- 1				
averageUtilization	Pod average utilization	80		No	integer
	Examples:				
	- 80				

pod-li_x1 upgrade

Description

Upgrade controls for pod - when set is used to enable 'shadow' deployment running previous (stable) pod version to the new (canary) version. The parameters allow a campaign to perform an upgrade (canary or rolling) depending on the settings. The version weight variables allow transition of traffic from the stable version to the canary. The stable and canary pods will scale based on replica variables or automatically via HPA if in use. The campaign proceeds and the traffic weight is gradually transferred from stable to canary (checkpointed at each step in the campaign). Once the canary is carrying 100% of the traffic and all indicators are good, then the campaign can be completed, and the stable version terminates leaving the canary (new version) as the running (stable) version.

Parameters

Parameter	Description	Default	Value/Range	Mandatory	Type
canary	Enable/disable canary sequence				
	Examples:	false		No	boolean
	- false				
canaryVersWeight	Canary pod weight percentage	0	min: 0 max: 100	No	number
stableVersWeight	Stable pod weight percentage	0	min: 0 max: 100	No	number
stableVersion	Stable pod image version			No	string
stableInfraImage	Examples:			No	string
	-				
	Worker container stable image				
stableWorkerImage	Examples:			No	string
	-				