Fernwick Field Service 7.3

Technician and Administrator Guide

Document FFS-7.3-TAG
Applies to the Fernwick Field Service mobile app 7.3
Published 30 September 2026 by Fernwick Mobile

Contents

1. Overview
2. Device and Server Requirements
3. Installation and Enrollment
4. Signing In
5. Work Orders
6. Offline Mode and Sync
7. Photos, Signatures and Scanning
8. Parts and Van Stock
9. Location, Battery and Data Use
10. Troubleshooting and Error Codes
11. Release Notes for 7.3

Sample document for AI knowledge-retrieval testing. The product, company and all specifications are fictional.

1. Overview

Fernwick Field Service is the mobile app technicians use to receive work orders, record work, capture photos and signatures, and use van stock. It connects to **Fernwick Dispatch Server**, which dispatchers use to plan work.

2. Device and Server Requirements

Requirement	Value
Android	Android 12 (API level 31) or later
iOS / iPadOS	16 or later
Memory	4 GB RAM minimum
Free storage	2 GB minimum (more if offline maps are used)

App version	Minimum Dispatch Server	Newest server tested
7.3	11.2	12.0
7.2	11.0	11.4
7.1	10.6	11.2

App 7.3 refuses to connect to a Dispatch Server older than 11.2 and shows error FW-102.

3. Installation and Enrollment

Deploy the app through your mobile device management (MDM) system with these managed configuration keys:

Key	Type	Default	Description
fernwick.server_url	string	(none)	Dispatch Server URL, e.g. https://dispatch.example.com
fernwick.tenant_id	string	(none)	Your tenant identifier
fernwick.sso_enabled	boolean	true	Sign in with your company identity provider
fernwick.allow_personal_devices	boolean	false	Allow enrollment of personally owned devices
fernwick.offline_days	integer	21	Days before unsynced data is purged (allowed range 7-45)

Without MDM, an administrator can enroll a device by scanning an enrollment QR code from Dispatch Server. Enrollment QR codes are valid for 15 minutes.

4. Signing In

Technicians sign in with single sign-on, then set a 6-digit app PIN for quick unlock. Fingerprint or face unlock can replace the PIN if the administrator allows it.

Important: After **10 incorrect PIN entries** the app wipes all local data and the device must be enrolled again. Unsynced work on the device is lost.

5. Work Orders

A work order moves through these statuses: Assigned, En Route, On Site, Paused, and finally Completed or Cannot Complete.

- Checking in (On Site) requires the device's GPS position to be within **150 metres** of the site. Outside the geofence the app shows FW-301; a supervisor can override, and the override is logged.
- Time entries are rounded to the nearest 6 minutes (0.1 hour).
- If a dispatcher reassigns the work order, the technician sees FW-404; pull to refresh.

6. Offline Mode and Sync

The app keeps up to 500 work orders on the device. While online it syncs every 15 minutes, and immediately when the device joins Wi-Fi.

Data that has not synced for 21 days is purged from the device. Administrators can change this with fernwick.offline_days (7 to 45 days).

Field type	Who wins in a sync conflict
Schedule fields (date, time, assignee)	Server
Technician notes and measurements	Device

Conflicts that need a person to decide show FW-215 and appear on the Conflicts screen.

7. Photos, Signatures and Scanning

- Up to **12 photos** per work order, each up to 10 MB.
- Photos are resized so the longest edge is 2048 pixels and saved as JPEG at quality 85.
- Video attachments are not supported; add a link to the video instead.
- A customer signature is required to mark a work order Completed, unless the work order type is Internal.

Supported barcode types: Code 128, QR, Data Matrix and EAN-13. PDF417 is **not** supported.

8. Parts and Van Stock

Parts used on a job are deducted from the technician's van stock when the work order syncs. Van stock cannot go below zero unless the administrator enables the allow_negative_van_stock setting on Dispatch Server.

9. Location, Battery and Data Use

Status	Location update interval
En Route	Every 60 seconds
On Site	Every 5 minutes
Off shift	Location tracking off

Typical mobile data use is about 150 MB per month per technician, not counting offline map downloads.

10. Troubleshooting and Error Codes

Code	Meaning	Fix
FW-102	Dispatch Server version too old	Upgrade the server to 11.2 or later.
FW-215	Sync conflict	Resolve it on the Conflicts screen.
FW-301	Outside the site geofence	Move closer or ask a supervisor to override.
FW-404	Work order was reassigned	Pull to refresh.
FW-512	Device storage full	Free at least 500 MB.
FW-777	Device not compliant (rooted or jailbroken)	The app blocks access on this device.

To send diagnostics: open Settings > About, tap the version number 7 times, then choose Send diagnostics. Logs are kept on the device for 3 days.

11. Release Notes for 7.3

- New: offline map tiles, with a cache of up to 2 GB.
- Changed: the photo limit per work order was raised from 8 to 12.
- Removed: Android 11 support.
- Fixed: a duplicate customer signature bug (FW-38102).