
Example 3 – DHCP Server and Relay



NOTE – the files for this example are in:

esercitazione-2010/example3-lab/ To start the lab use: ./start_lab

At first boot the DHCP RELAY won't start...

```
lab.conf:
router1[0]=A
router1[1]=B
router1[mem]=64
router2[0]=C
router2[1]=A
router2[mem]=64
dhcprelay[0]=C
dhcprelay[mem] = 64
pc1[0]=A
pc2[0]=B
pc3[0]=C
pc1.startup, pc2.startup, pc3.startup:
dhclient eth0
```

router1.startup: ip link set eth0 up ip link set eth1 up ip address add 10.0.0.1/16 dev eth0 ip address add 10.1.0.1/16 dev eth1 ip route add 10.2.0.0/16 via 10.0.0.2 /etc/init.d/dhcp3-server start echo 1 > /proc/sys/net/ipv4/ip forward


```
router1/etc/dhcp3/dhcpd.conf:
default-lease-time 3600;
subnet 10.0.0.0 netmask 255.255.0.0 {
      range 10.0.0.100 10.0.0.254;
      option routers 10.0.0.1;
subnet 10.1.0.0 netmask 255.255.0.0 {
      range 10.1.0.100 10.1.0.254;
      option routers 10.1.0.1;
subnet 10.2.0.0 netmask 255.255.0.0 {
      range 10.2.0.100 10.2.0.254;
      option routers 10.2.0.1;
```

```
ip link set eth0 up
ip link set eth1 up
ip address add 10.2.0.1/16 dev eth0
ip address add 10.0.0.1/16 dev eth1
ip route add 10.1.0.0/16 via 10.0.0.1
echo 1 > /proc/sys/net/ipv4/ip forward
dhcprelay.startup:
ip link set eth0 up
ip address add 10.2.0.2/16 dev eth0
ip route add default via 10.2.0.1
#!! No dchp relay configured and run!
```

router2.startup:

PC3 couldn't contact DHCP server...

SURE! The DHCP server is not in LAN C and broadcast packets doesn't get through the router....



How to make pc3 get IP configuration from the DHCP server

Install dhcrelay package on dhcprelay VM (the files are in /root).

```
dhcprelay:~# dpkg -i *.deb
(ignore the configuration wizard..)
```

Run dhcrelay manually:

```
dhcprelay:~# dhcrelay -d -i eth0 10.0.0.1
```

usage:

```
dhcrelay [options] DHCP_SERVER_ADDRESS
-i <ifaces>: interface to listen on
-d: don't go in background
```

Run dhcrp client on pc3:

pc3:~# dhclient eth0

