Project 2 Hints

Jingke Li

Portland State University

Basic Information

• The Infrastructure —

Same as Project 1's, but with two more packages:

- ast --- the source-language's AST nodes
- astpsr --- the AST parser program
- symbol --- the symbol table package
- checker --- the typechecking package
- ir --- the IR tree nodes
- irgen --- the irgen code
- tst --- a set of test programs
- New Issues
 - new objects
 - method declarations
 - · method invocations
 - object fields
 - "this" node
 - variable references



New Objects

A NewObj node should be translated into a call to "malloc" with a single argument representing the size of the object, followed by a sequence of statements for initializing its instance variables.

Note that the initialization expressions saved in the the symbol table need to be translated into IR expressions before they can be used to initialize the instance variables. This translation should be conducted in the proper scope environment — the IrgenVisitor variable currClass needs to point to the object's class.

Method Declarations

- Create an unique label for the method by concatenating class name and method name together, with an underscore (_) in between.
 - Look up the corresponding MethodRec in the symbol table. To do this, you need to know what class this method decl belongs. (Recall the use of variable currClass in the typechecking project).

```
MethodRec currMethod = currClass.getMethod(n.mid);
```

• Call the "uniqueMethodName()" method of the symbol table.

```
String label =
  symTable.uniqueMethodName(currClass, currMethod.id());
```

Note that for the main method, this step is skipped.

Method Declarations (cont.)

- Compute the values of varCnt and argCnt.
 - varCnt is the local variable count, and argCnt is the maximum number of arguments of a single Call/CallStmt node (excluding calls to system routines) in current method's body. Both values are needed in the later Codegen module for calculating frame size.
 - You can compute varCnt by calling the "localCnt()" method of the corresponding MethodRec.
 - The value of argCnt has to come from recursive visit to the method's body. You need to declare a class variable, say maxArgCnt, at the top level, and if necessary, update the value every time a Call or CallStmt node is encountered:

```
if (maxArgCnt <= argCnt)
  maxArgCnt = argCnt + 1;</pre>
```

In the above code, argCnt is the Call node's arg count, and the extra 1 is for passing the 'access link'.

Method Invocations

Create the same unique label for the method.

Again, you should look up the symbol table for the MethodRec and use the "uniqueMethodName()" method. However, you first need to figure out the class that the method belongs to (which could be a different class than currClass. The proper steps are:

 Perform typechecking on the obj component of the Call/CallStmt node, which should return an ObjType representing the obj's class. An Important Detail: The TypeVisitor program has its own copy of currClass and currMethod. These two variables need to be set to the current environment before typechecking can work. Do the following:

```
typeChecker.setClass(currClass);
typeChecker.setMethod(currMethod);
```

- 2. Look up the MethodRec with the class info.
- 3. Finally, concatenate class name and method name together.

Method Invocations (cont.)

• Add a pointer to the object record as the 0th element of the argument list (*i.e.* set up the access link).

```
EXPlist el = new EXPlist();
el.add(n.obj.accept(this));
```

CallStmt is translated similarly, except that it returns a CALLST node.

Object Field and "This" Node

 Object field in the form of a Field node is translated into a FIELD node

(Field obj var) => (FIELD <obj's record> <var's idx>)

Note that to compute the variable's index, you need to know which class the variable belongs to. Do similar things as in Call nodes, i.e. performing typechecking on the obj component, and get the class info.

• "This" node should point to the current class object. We assume that it is only used within a method's body. Hence it should be translated into PARAM(0).

Variable References

Standing-along variables, as represented by Id nodes, are translated into FIELD, PARAM, or VAR nodes; all with an index.

 A standing-alone class variable is translated into a FIELD node referencing from the current object:

```
(FIELD PARAM(0) <var's idx>-1)
```

In this case, it is equivalent to having a "This." prefix in front of the variable.

Note that when an Id node appears inside a Field node, it is taken care of by the visit routine of the Field node. In that case, there is no need to recursively visit the Id node.

- A parameter is simply translated into a PARAM node.
- A local variable is simply translated into a VAR node.

A variable's index value can be looked up from the symbol table with the "v.idx()" method.