# **SDN Experiment 3**

```
SDN Experiment 3
   1前言
   2 实验环境
       2.1 virtualbox & ubuntu
          2.1.1 virtuablbox
          2.1.2 ubuntu16.04
       2.2编写P4程序
          2.2.1 header
          2.2.2 parser
          2.2.3 ingress
          2.2.4 main
       2.3 Wireshark
       2.3 VS Code
       2.4 Mininet
          2.4.1 常用命令
          2.4.2 自定义拓扑
       2.5 bmv2
       2.6 p4c
       2.7 P4Runtime
   3 实验内容
       3.1 实验1
          题目
          说明
       3.2 实验2
          题目
          说明
   4总结
   5 扩展资料
```

# 1 前言

- 《软件定义网络》课程实验总计四次,这是第三次的实验指导书
- 实验完成情况可当场验收,可提交实验报告,鼓励当场验收
- 实验虚拟机请提前在moodle下载,建议使用个人电脑运行
- 实验内容要求各位提前准备,机房现场主要负责答疑和验收
- 实验需独自完成,鼓励互相学习和交流,严禁抄袭
- 关于实验部分的疑问或反馈或Anything请发送邮件至: <u>sdnexp2019@outlook.com</u>标题格式:

cs60-小胖-关于xxx

# 2 实验环境

本次实验主要用到的工具如下所示,提供安装好所需工具的虚拟机,也可自行参考文档手动安装

• 虚拟机及系统

virtualbox(free, GPL)

ubuntu16.04

• 网络模拟

Mininet

- -软件交换机 bmv2
- -P4程序编译器 p4c
- 控制器

grpc

• 抓包工具

Wireshark (或tcpdump)

• 文本编辑器

虚拟机中安装了VS Code, 自选均可

以下内容为上述工具的基本教程,有熟悉的章节自行跳过

#### 2.1 virtualbox & ubuntu


#### 2.1.1 virtuablbox

安装


根据自己的操作系统选择virtualbox下载,默认选项安装(以下教程在6.0.4版本测试通过)

• 虚拟机导入

从moodle下载的虚拟机,按照下图所示导入。可根据电脑配置在设置中分配更多的核心数和内存,其余选项默认



导入后根据显示器的分辨率调整缩放至合适的大小,也可安装virtualbox的增强工具自适应调整分辨率



• 虚拟机导出

在机房电脑进行实验的同学每次结束后需将虚拟机关闭后导出,保存到自己的U盘中,下次实验再次导入继续实验

#### 2.1.2 ubuntu16.04

本次实验使用虚拟机下载:

```
链接: https://pan.baidu.com/s/1NKeJuuZddqY3ThUTbhQirw
提取码: 7gsr
```

实验虚拟机镜像基于ubuntu16.04 64位制作,各工具均安装在~/p4

用户名: sdn ,密码: sdn

#### 2.2编写P4程序

P4是一种声明式编程语言,它主要用于编写程序以下达指令给数据平面的设备(如交换机、网卡、防火墙、过滤器等)如何处理数据包。在 /home/sdn/p4/p4\_program 下可以看到一个简单的L2路由实例, simple\_router.p4 和 simple\_router-16 分别用P4-14和P4-16实现。以下简单介绍P4-16实现的版本,也更推荐大家使用P4-16。

#### 2.2.1 header

可以自定义包头的域和各个字段以及元数据:

```
//定义ethernet
header ethernet_t {
   macAddr_t dstAddr;
   macAddr_t srcAddr;
   bit<16> etherType;
}
//定义ipv4
header ipv4_t {
   bit<4> version;
   bit<4> ihl;
   bit<8> diffserv;
   bit<16> totalLen;
   bit<16> identification;
   bit<3> flags;
   bit<13> fragOffset;
   bit<8> ttl;
   bit<8> protocol;
   bit<16> hdrChecksum;
   ip4Addr_t srcAddr;
   ip4Addr_t dstAddr;
}
struct headers {
   ethernet_t ethernet;
   ipv4_t ipv4;
}
```

#### 2.2.2 parser

定义包头如何解析:

```
parser MyParser(packet_in packet,
                out headers hdr,
                inout metadata meta,
                inout standard_metadata_t standard_metadata) {
    state start {
        transition parse_ethernet;
   state parse_ethernet {
        packet.extract(hdr.ethernet);
        transition select(hdr.ethernet.etherType) {
            TYPE_IPV4: parse_ipv4;
            default: accept;
        }
    }
    state parse_ipv4 {
        packet.extract(hdr.ipv4);
        transition accept;
    }
}
```

### 2.2.3 ingress

定义转发表table,定义动作action,以及各个表之间的关系apply。:

```
control MyIngress(inout headers hdr,
                inout metadata meta,
                inout standard_metadata_t standard_metadata) {
   action drop() {
       mark_to_drop(standard_metadata);
   //交换机必须对每个数据包执行以下操作:(i)更新源和目标MAC地址,(ii)递减IP头中的生存时间(TTL),以
及(iii)将数据包转发到适当的端口。
   action ipv4_forward(macAddr_t dstAddr, egressSpec_t port) {
       standard_metadata.egress_spec = port;
       hdr.ethernet.srcAddr = hdr.ethernet.dstAddr;
       hdr.ethernet.dstAddr = dstAddr;
       hdr.ipv4.ttl = hdr.ipv4.ttl - 1;
   }
   table ipv4_lpm {
       key = {
           hdr.ipv4.dstAddr: lpm;
       actions = {
           ipv4_forward;
```

```
drop;
    NoAction;
}
size = 1024;
default_action = drop();
}
apply {
    if (hdr.ipv4.isValid()) {
        ipv4_lpm.apply();
    }
}
```


#### 2.2.4 main


```
V1Switch(
MyParser(),
MyVerifyChecksum(),
MyIngress(),
MyEgress(),
MyComputeChecksum(),
MyDeparser()
) main;
```

# 2.3 Wireshark

用Mininet搭建网络拓扑后,Wireshark可以抓取控制器和交换机通讯的数据包,也可以抓取指定交换机端口上的数据包

- 选择合适的端口
- 抓取loopback时需root权限,故 sudo wireshark 启动
- 可以查看数据包的各个字段,验证数据包经过交换机是否被正确处理





#### 2.3 VS Code

这里选择自己习惯的文本编辑器即可

若选择VS Code

- 建议安装推荐的Python Extension
- Python Interpreter切换至 /usr/bin/python
   这样练习时可以参考提供的示例,同时VSC可以提供舒服的命令补全

#### 2.4 Mininet

Mininet的基本教程请阅读官网提供的walkthrough, 安装方式推荐源码安装

#### 2.4.1 常用命令

```
# shell prompt
mn -h # 查看mininet命令中的各个选项
sudo mn -c # 不正确退出时清理mininet

# 下面的命令可以在'sudo mn'新建的简单拓扑上查看运行结果
```

```
# mininet CLI
net # 显示当前网络拓扑
dump # 显示当前网络拓扑的详细信息
xterm h1 # 给节点h1打开一个终端模拟器
sh [COMMAND] # 在mininet命令行中执行COMMAND命令
h1 ping -c3 h2 # 即h1 ping h2 3次
pingall # 即ping all
h1 ifconfig # 查看h1的网络端口及配置
h1 arp # 查看h1的arp表
link s1 h1 down/up # 断开/连接s1和h1的链路
exit # 退出mininet CLI
```

```
*** Adding controller
*** Adding hosts:
h1 h2
*** Adding switches:
f(h1, s1) (h2, s1)
*** Configuring hosts
h1 h2
*** Starting controller
cookie=0x0, duration=28.872s, table=0, n packets=0, n bytes=0, idle_timeout=60, priority=65535, arp, in port="s1-eth2", vlan_tci=0x0000, dls.rc=46:39:a6:27:3a:5d, dlst=2e:74:ec:72:5b:92, arp_spa=10.0.0.2, arp_tpa=10.0.0.1, arp_op=2 actions=outpu t:"s1-eth1"
cookie=0x0, duration=23.736s, table=0, n packets=0, n bytes=0, idle_timeout=60, priority=65535, arp, in port="s1-eth2", vlan_tci=0x0000, dl_src=46:39:a0:27:3a:5d, dlst=2e:74:ec:72:5b:92, arp_spa=10.0.0.2, arp_tpa=10.0.0.1, arp_op=2 actions=outpu t:"s1-eth1"
cookie=0x0, duration=23.724s, table=0, n packets=0, n bytes=0, idle_timeout=60, priority=65535, arp, in port="s1-eth1", vlan_tci=0x0000, dl_src=2e:74:ec:72:5b:92, arp_spa=10.0.0.2, arp_tpa=10.0.0.1, arp_op=1 actions=outpu t:"s1-eth1"
cookie=0x0, duration=23.724s, table=0, n packets=0, n bytes=0, idle_timeout=60, priority=65535, arp, in port="s1-eth1", vlan_tci=0x0000, dl_src=2e:74:ec:72:5b:92, arp_spa=10.0.0.2, arp_tpa=10.0.0.1, arp_op=1 actions=outpu t:"s1-eth1"
cookie=0x0, duration=23.724s, table=0, n packets=0, n bytes=0, idle_timeout=60, priority=65535, arp, in port="s1-eth1", vlan_tci=0x0000, dl_src=2e:74:ec:72:5b:92, arp_spa=10.0.0.2, arp_tpa=10.0.0.1, arp_op=1 actions=outpu t:"s1-eth1"
cookie=0x0, duration=23.724s, table=0, n packets=2, n bytes=106, idle_timeout=60, priority=65535, idle=0, n packets=2, n bytes=106, idle_timeout=60, n packets=
```

#### 2.4.2 自定义拓扑

• 简单的写法

示例位于 /home/sdn/p4/behavioral-model/mininet/1sw\_demo.py,定义了一个单个交换机,主机数量由参数指定的拓扑,默认的交换机model由sw\_path指定,运行的p4交换机代码由json\_path指定,thrift\_port指定thrift server 绑定的端口,不同的交换机设备需要绑定不同的端口,部分代码如下,:

```
class SingleSwitchTopo(Topo):
    "Single switch connected to n (< 256) hosts."
   def __init__(self, sw_path, json_path, thrift_port, pcap_dump, n, **opts):
        # Initialize topology and default options
        Topo.__init__(self, **opts)
        switch = self.addSwitch('s1',
                                sw_path = sw_path,
                                json_path = json_path,
                                thrift_port = thrift_port,
                                pcap_dump = pcap_dump)
        for h in xrange(n):
            host = self.addHost('h%d' % (h + 1),
                                ip = "10.0.%d.10/24" % h,
                                mac = '00:04:00:00:00:%02x' %h)
           self.addLink(host, switch)
def main():
```

#### 运行拓扑的命令为:

```
cd ~/p4/behavioral-model/mininet
sudo python 1sw_demo.py --behavioral-exe ../targets/simple_router/simple_router --json
../targets/simple_router/simple_router.json
```

创建4台主机1交换机的拓扑,在mininet终端下输入 pingall 测试连通性:

```
sdn@ubuntu: ~/p4/behavioral-model/mininet
sdn@ubuntu:~/p4/behavioral-model/mininet$ sudo python 1sw_demo.py --behavioral-e
xe ../targets/simple_router/simple_router --json ../targets/simple_router/simple
_router.json --n 4
*** Creating network
*** Adding hosts:
h1 h2 h3 h4
*** Adding switches:
s1
*** Adding links:
(h1, s1) (h2, s1) (h3, s1) (h4, s1)
*** Configuring hosts
h1 h2 h3 h4
*** Starting controller
*** Starting 1 switches
s1 Starting P4 switch s1.
../targets/simple_router/simple_router -i 1@s1-eth1 -i 2@s1-eth2 -i 3@s1-eth3 -i
4@s1-eth4 --thrift-port 9090 --nanolog ipc:///tmp/bm-0-log.ipc --device-id 0 ..
/targets/simple_router/simple_router.json
P4 switch s1 has been started.
******
h1
default interface: eth0 10.0.0.10
                                       00:04:00:00:00:00
******
******
h2
default interface: eth0 10.0.1.10
                                        00:04:00:00:00:01
******
h3
default interface: eth0 10.0.2.10
                                        00:04:00:00:00:02
*******
******
h4
default interface: eth0 10.0.3.10
                                       00:04:00:00:00:03
Ready !
*** Starting CLI:
mininet> pingall
*** Ping: testing ping reachability
h1 -> X X X
h2 -> X X X
h3 -> X X X
*** Results: 100% dropped (0/12 received)
mininet>
```

此时主机之间不连通,因为交换机上还没有流表。

#### 2.5 hmv2

bmv2是一款P4软件交换机,可以直接执行p4c编译P4程序生成的JSON文件,并且提供直观的CLI来控制交换机运行时状态和行为。

● 用bmv2来执行一个P4程序编译的JSON程序,例如使用simple\_switch模型,与表示与交换机绑定的端口(eg:port0 and port1):

```
cd ~/p4/behavioral-model/targets/simple_switch
sudo ./simple_switch -i 0@<iface0> -i 1@<iface1> <path to JSON file>
```

• 使用CLI下发流表。CLI连接到在每个交换机进程中运行的Thrift RPC服务器。9090是默认值(例如2.4.2中CLI运行在9090),但当然,如果在计算机上运行多个交换机设备,则需要为每个设备提供不同的端口。一个CLI实例只能连接到一个交换机设备。可以这样使用CLI:

```
cd ~/p4/behavioral-model/tools/
./runtime_CLI.py --thrift-port 9090
```

打开另一个terminal,2.4.2中拓扑交换机默认绑定端口为9090,打开2.4.2拓扑中的p4交换机的CLI:

```
😰 🖃 🗊 sdn@ubuntu: ~/p4/behavioral-model/tools
sdn@ubuntu:~$ cd ~/p4/behavioral-model/tools/
sdn@ubuntu:~/p4/behavioral-model/tools$ ./runtime CLI.py --thrift-port 9090
Obtaining JSON from switch...
Control utility for runtime P4 table manipulation
RuntimeCmd: help
Documented commands (type help <topic>):
_____
act_prof_add_member_to_group
                                  shell
act_prof_create_group
                                  show actions
act_prof_create_member
                                  show_ports
act_prof_delete_group
                                  show_tables
act_prof_delete_member
                                  swap_configs
act_prof_dump
                                  switch info
                                  table add
act_prof_dump_group
act prof dump member
                                  table clear
act prof modify member
                                  table delete
act prof remove member from group table dump
counter read
                                  table dump entry
                                  table_dump_entry from key
counter reset
                                  table_dump_group
counter_write
help
                                  table_dump_member
load new config file
                                  table indirect add
```

CLI是使用python的cmd模块实现的,支持自动补全。它支持查看table,查看action,增删流表等操作,也可以通过'help'查看支持的命令,部分命令示例如下:

```
- table_set_default  <action name> <action parameters>
```

- table\_add <action name> <match fields> => <action parameters> [priority]
- table\_delete <entry handle>

在CLI中下发并查看流表,更多操作的使用方式可以输入指令直接查询:

```
🔊 🖨 🗊 sdn@ubuntu: ~/p4/behavioral-model/tools
port add
                                 table info
                                 table modify
port_remove
                                 table_num_entries
register_read
register_reset
                                 table_reset_default
                                 table_set_default
register_write
reset_state
serialize_state
                                 table_set_timeout
                                 table_show_actions
set_crc16_parameters
                                 write config to file
set crc32 parameters
Undocumented commands:
EOF greet
RuntimeCmd: table_set_default ipv4_lpm _drop
Setting default action of ipv4_lpm
action:
                    drop
runtime data:
RuntimeCmd: table_add ipv4_lpm set_nhop 10.0.0.10/32 => 10.0.0.10 1
Adding entry to lpm match table ipv4_lpm
match key:
                    LPM-0a:00:00:0a/32
action:
                    set_nhop
runtime data:
                    0a:00:00:0a
                                      00:01
Entry has been added with handle 0
Adding entry to lpm match table ipv4_lpm
match key:
                    LPM-0a:00:01:0a/32
action:
                    set nhop
runtime data:
                    0a:00:01:0a
                                      00:02
Entry has been added with handle 1
RuntimeCmd: table dump ipv4 lpm
_____
TABLE ENTRIES
******
Dumping entry 0x0
Match key:
* ipv4.dstAddr
                    : LPM
                                0a00000a/32
Action entry: set_nhop - 0a00000a, 01
Dumping entry 0x1
Match key:
                     : LPM
                                0a00010a/32
* ipv4.dstAddr
Action entry: set_nhop - 0a00010a, 02
=======
Dumping default entry
Action entry: _drop -
=======
RuntimeCmd:
```

也可以将指令写入txt文件,打开CLI同时下发流表,可以打开文件 vim /home/sdn/p4/behavioral-model/targets/simple\_router/command.txt 查看具体的流表项:

```
cd targets/simple_router
./runtime_CLI.py --thrift-port 9090 < ../targets/simple_router/commands.txt</pre>
```

```
sdn@ubuntu:~/p4/behavioral-model/tools$ ./runtime CLI.py --thrift-port 9090 < ..</pre>
/targets/simple router/commands.txt
Obtaining JSON from switch...
Done
Control utility for runtime P4 table manipulation
RuntimeCmd: Setting default action of send_frame
action:
                     _drop
runtime data:
RuntimeCmd: Setting default action of forward
action:
                     _drop
runtime data:
RuntimeCmd: Setting default action of ipv4 lpm
action:
                     _drop
runtime data:
RuntimeCmd: Adding entry to exact match table send frame
match key:
                     EXACT-00:01
action:
                     rewrite mac
runtime data:
                     00:aa:bb:00:00:00
Entry has been added with handle 0
RuntimeCmd: Adding entry to exact match table send_frame
match key:
                     EXACT-00:02
action:
                     rewrite mac
runtime data:
                     00:aa:bb:00:00:01
Entry has been added with handle 1
RuntimeCmd: Adding entry to exact match table forward
match key:
                     EXACT-0a:00:00:0a
action:
                     set dmac
runtime data:
                     00:04:00:00:00:00
Entry has been added with handle 0
RuntimeCmd: Adding entry to exact match table forward
match key:
                     EXACT-0a:00:01:0a
action:
                     set dmac
runtime data:
                     00:04:00:00:00:01
Entry has been added with handle 1
RuntimeCmd: Adding entry to lpm match table ipv4_lpm
                     LPM-0a:00:00:0a/32
match kev:
action:
                     set nhop
runtime data:
                     0a:00:00:0a
                                         00:01
Invalid table operation (DUPLICATE_ENTRY)
RuntimeCmd: Adding entry to lpm match table ipv4_lpm
                     LPM-0a:00:01:0a/32
match key:
action:
                     set_nhop
runtime data:
                     0a:00:01:0a
                                         00:02
Invalid table operation (DUPLICATE_ENTRY)
RuntimeCmd:
sdn@ubuntu:~/p4/behavioral-model/tools$
```

此时流表已经填充。可以在Mininet中运行Pingall或在主机h1和h2之间使用iperf发送TCP流来检查网络的连通性:

```
sdn@ubuntu: ~/p4/behavioral-model/mininet
h3
default interface: eth0 10.0.2.10
                                   00:04:00:00:00:02
*******
h4
default interface: eth0 10.0.3.10
                                       00:04:00:00:00:03
Ready !
*** Starting CLI:
mininet> pingall
*** Ping: testing ping reachability
h1 -> X X X
h2 -> X X X
h3 -> X X X
h4 -> X X X
*** Results: 100% dropped (0/12 received)
mininet> pingall
*** Ping: testing ping reachability
h1 -> h2 X X
h2 -> h1 X X
h3 -> X X X
h4 -> X X X
*** Results: 83% dropped (2/12 received)
mininet>
```

可以看到下发流表后h1,h2之连通,其他主机之间不通,具体原因如果想要其他主机之间也连通,还需要编写流表并下发。

# 2.6 p4c

p4c是用于编译p4语言的编译器,它同时支持P4-14和P4-16。默认P4语言版本为p4-16,如果需要编译p4-14,需要通过--std p4-14指定。可以通过一下命令编译p4程序:

```
p4c-bm2-ss xx.p4 -o xx.json
```

或

```
p4c xx.p4 -o xxx
```

通过第二种方式编译,如果成功编译,会生成一个文件夹,包含以下几个文件:后缀为.p4i的文件,它是在P4程序上运行预处理器时的输出。后缀为.p4rt的文件,它是一种二进制格式,包含P4程序中具有自动生成的控制平面API的表和其他对象的描述。后缀为.json的文件,是bmv2交换机模型simple\_switch所期望的json文件格式文件。可以通过p4c --help或p4c --target-helpc查看p4c支持的其他命令:

```
p4c --help
p4c --target-help
```

```
sdn@ubuntu: ~/p4/p4_program/simple_router-1.json
sdn@ubuntu: ~/p4/p4_program$ ls
simple_router.p4
sdn@ubuntu: ~/p4/p4_program$ sudo p4c-bm2-ss simple_router.p4 --std p4-14 --toJS
ON simple_router.json
sdn@ubuntu: ~/p4/p4_program$ ls
simple_router.json simple_router.p4
sdn@ubuntu: ~/p4/p4_program$ sudo p4c simple_router.p4 --std p4-14 -o simple_router-1.json
sdn@ubuntu: ~/p4/p4_program$ ls
simple_router-1.json simple_router.p4
sdn@ubuntu: ~/p4/p4_program$ cd simple_router-1.json/
sdn@ubuntu: ~/p4/p4_program/simple_router-1.json$ ls
simple_router.json simple_router.p4i
sdn@ubuntu: ~/p4/p4_program/simple_router-1.json$
```

## 2.7 P4Runtime

# 3 实验内容

第一次实验主要为验证性实验,要求各位在学习第2部分内容的基础上完成下面两道题目

# 3.1 实验1

#### 题目

- 参考2.1的示例,实现mytunnel路由,填充部分代码,要求实现以下功能:
  - o 添加了一个名为mytunnel\_t的新头部字段类型,其中包含两个16位字段: proto\_id和dst\_id。
  - o mytunnel头部需要添加到headers结构中。
  - o 更新解析器,根据Ethernet头部中的ethertype字段解析mytunnel头部或ipv4头部。与mytunnel头段对应的ethertype是0x1212。如果mytunnel的proto\_id==type\_ipv4(即0x0800),解析器还应在mytunnel头部之后解析ipv4头部。
  - o 定义一个名为mytunnel\_forward的新的action,该动作只需将出口端口(即standard\_metadata的 egress\_spec字段)设置为控制平面提供的端口号。
  - o 定义一个名为mytunnel\_exact的新的table,该表根据mytunnel头部的dst\_id字段执行精确匹配 (exact)。如果表中存在匹配项,则此表应调用myTunnel\_forward转发动作,否则应调用Drop动作。
  - o 更新myIngress控制模块中的apply语句,使得在myTunnel头部有效的情况下应用新定义的mytunnel\_exact表。否则,如果ipv4头部有效,则调用ipv4\_lpm表。
  - o 更新deparser,由于头部的有效性是由隐集解析器提取,因此,这里不需要检查头部有效性。

#### 说明

• 验收(二选一)

o 当场验收:请指导老师查看运行结果和代码即可

o 提交报告:报告中需包括姓名学号、代码、拓扑截图及总结,命名格式 cs60-小胖-exp11.pdf

#### 3.2 实验2

#### 题目

编译实验1实现的p4程序,仿照/home/sdn/p4/behavioral-model/minnet/1sw.py,重新实现一个拓扑,交换机数量不小于3,两个主机之间最好有多条路径,在mininet中查看拓扑。并且运行拓扑,交换机执行实验1生成的json代码。并且手动向各个交换机下发流表,使主机之间连通。在两台主机之间发送数据包,并用wireshark抓包。

#### 说明

- 不同交换机设备需要绑定不同的端口,可以在程序中设置默认值或用过参数指定,使得在相应端口运行thrift server可以控制相应的交换机
- 根据下发的流表,可以分别根据mytunnel或ipv4转发,需要构造数据包(包含mytunnel,不含mytunnel。可用Python scapy构造)在主机之间发包。
- 验收(二选一)

o 当场验收:请指导老师查看运行结果和代码

o 提交报告:报告中需包括姓名学号、代码、wireshark抓包截图及总结,命名格式 cs60-小胖-exp12.pdf

## 4 总结

#### 希望本次实验大家能掌握以下知识点:

• 能够编写简单的P4程序

- 利用Mininet的API自定义P4网络拓扑
- 学会使用P4相关工具
- 二层自学习交换机的基本原理

# 5 扩展资料

• sdn论坛: <u>sdnlab</u>

• 关于Mininet的更多资料: Mininet Doc, Mininet API

关于P4的更多资料: p4 languageSDN网络的部署案例: Google P4