Teampafex API Documentation v1

Version: 1.0
Last Updated: September 15, 2026
Public API Base URL: **https://teampafex.in/api/v1**
Credential Base URL: **https://teampafex.in/api/auth**

This document describes the Teampafex public shipping API, credential/session endpoints, API key management endpoints, webhook management endpoints, and shipment lifecycle endpoints available in the backend.

Authentication Summary

Public shipping endpoints use the **X-API-Key** header. Dashboard management endpoints use **Authorization: Bearer <user_access_token>**. Credential endpoints are called before a bearer token exists unless a refresh token is being used.

Login Example

```
curl -X POST "https://teampafex.in/api/auth/request-password-login" \
-H "Content-Type: application/json" \
-d '{
"email": "merchant@example.com",
"password": "your_password"
}'
```

API Key Example

```
curl -X POST "https://teampafex.in/api/v1/shipping/rates" \
-H "Content-Type: application/json" \
-H "X-API-Key: ccart_your_api_key_here" \
-d '{
"destination": "400001",
"origin": "110001",
"payment_type": "prepaid",
"weight": 500,
"length": 10,
"breadth": 10,
"height": 10,
"shipment_type": "b2c"
}'
```

All Endpoints

Credential And Session Endpoints

Method	Endpoint	Authentication	Purpose
POST	/api/auth/request-password-login	None	Login with email and password. Returns user, access token, and refresh token when credentials are valid.
POST	/api/auth/verify-user-email	None	Verify email token and complete password based authentication when verification is required.
POST	/api/auth/request-otp	None	Request an email OTP for OTP based login or signup.
POST	/api/auth/verify-otp	None	Verify OTP and return user session tokens.
POST	/api/auth/signin-with-google	None	Authenticate using a Google OAuth authorization code.
POST	/api/auth/refresh-token	Refresh token	Issue a new access token and refresh token.
POST	/api/auth/logout	Refresh token	Invalidate the current refresh token and log out.

API Key Management

Method	Endpoint	Authentication	Purpose
POST	/api/v1/api-keys	Bearer token	Create a new API key for the authenticated dashboard user.
GET	/api/v1/api-keys	Bearer token	List API keys created by the authenticated dashboard user.
PUT	/api/v1/api-keys/:id	Bearer token	Update an API key name or active status.
DELETE	/api/v1/api-keys/:id	Bearer token	Delete or revoke an API key.

Shipping And Serviceability

Method	Endpoint	Authentication	Purpose
GET	/api/v1/serviceability	X-API-Key	Check destination serviceability and available courier options.
POST	/api/v1/serviceability	X-API-Key	Check serviceability using a JSON payload.
POST	/api/v1/shipping/rates	X-API-Key	Calculate available shipping rates before order creation.

Order Management

Method	Endpoint	Authentication	Purpose
POST	/api/v1/orders	X-API-Key	Create a shipment order.
GET	/api/v1/orders	X-API-Key	List orders with pagination and filters.
GET	/api/v1/orders/track	X-API-Key	Track by AWB or order number plus contact.
GET	/api/v1/orders/:orderId	X-API-Key	Fetch full order details by UUID, order number, or order ID.
POST	/api/v1/orders/:orderId/cancel	X-API-Key	Cancel an order that is still eligible for cancellation.
POST	/api/v1/orders/:orderId/retry-manifest	X-API-Key	Retry manifest generation for an order whose manifest failed.
GET	/api/v1/orders/:orderId/label	X-API-Key	Get a temporary shipping-label download URL.

Manifest Management

Method	Endpoint	Authentication	Purpose
POST	/api/v1/manifest	X-API-Key	Generate a manifest for AWBs or order numbers.

Pickup Management

Method	Endpoint	Authentication	Purpose
POST	/api/v1/pickup-addresses	X-API-Key	Create a pickup address.
GET	/api/v1/pickup-addresses	X-API-Key	List pickup addresses.
PUT	/api/v1/pickup-addresses/:id	X-API-Key	Update a pickup address.
POST	/api/v1/pickup-addresses/request-pickup	X-API-Key	Request pickup for a pickup address and package count.

NDR And RTO

Method	Endpoint	Authentication	Purpose
GET	/api/v1/ndr	X-API-Key	List NDR events.
GET	/api/v1/ndr/timeline	X-API-Key	Fetch the NDR timeline for an order or AWB.
GET	/api/v1/rto	X-API-Key	List RTO events.

Return Orders

Method	Endpoint	Authentication	Purpose
POST	/api/v1/returns	X-API-Key	Create a return shipment.
GET	/api/v1/returns/quote	X-API-Key	Get a return quote before creating a return shipment.

Webhook Management

Method	Endpoint	Authentication	Purpose
POST	/api/v1/webhooks	Bearer token	Create a webhook subscription.
GET	/api/v1/webhooks	Bearer token	List webhook subscriptions.
GET	/api/v1/webhooks/:id	Bearer token	Fetch one webhook subscription.
PUT	/api/v1/webhooks/:id	Bearer token	Update URL, events, or active status.
DELETE	/api/v1/webhooks/:id	Bearer token	Delete a webhook subscription.
POST	/api/v1/webhooks/:id/regenerate-secret	Bearer token	Regenerate the signing secret for a webhook.

Provider Webhook

Method	Endpoint	Authentication	Purpose
POST	/api/v1/webhook/ekart/track	Provider	Receive Ekart tracking callbacks.

Common Payload Notes

Serviceability and rates: destination is required. Provide either origin pincode or pickup_id. payment_type accepts prepaid, cod, or reverse. Use order_amount for COD requests.

Create order: include order_number, payment_type, order_amount, package dimensions, courier_id, consignee, pickup, order_items, invoice fields, and optional request_auto_pickup.

Tracking: provide awb, or provide orderNumber with buyer contact.

Webhook security: store webhook secrets securely and verify request signatures before trusting webhook payloads.

Error Handling

All JSON endpoints return a success flag or an error/message field. Common status codes are 400 for validation errors, 401 for missing or invalid credentials, 403 for forbidden access, 404 for missing resources, and 500 for server errors.

Base URL Usage

Use https://teampafex.in/api/v1 for public API-key endpoints and https://teampafex.in/api/auth for credential/session endpoints.