



SMC MASTER PRO

Version 7.0

Premium TradingView Indicator

Complete User Documentation

Smart Money Concepts • ICT Methodology
Multi-Timeframe Analysis • Position Calculator
Auto Trend Lines • Fibonacci Retracement

Created by Mostofa • Pine Script v5

Table of Contents

1. Introduction & What's New in v7	3
2. Installation Guide	5
3. Complete Settings Reference	6
4. Display Modes Explained	11
5. Multi-Timeframe Analysis	12
6. Trend Lines (Auto-Draw)	13
7. Fibonacci Retracement	14
8. Order Blocks Deep Dive	16
9. FVG & BPR Analysis	17
10. Premium/Discount & Liquidity	18
11. BUY/SELL Signals & Confluence	19
12. Position Visualizer & Calculator	21
13. MTF Dashboard Reading	23
14. Trading Workflow (DATE Framework)	24
15. Setting Up Alerts	26
16. Risk Management Rules	27
17. Recommended Timeframe Setups	28
18. Troubleshooting & FAQ	29
19. Glossary of Terms	31

1. Introduction & What's New in v7

SMC Master Pro is the most comprehensive TradingView indicator combining Smart Money Concepts (SMC), ICT methodology, multi-timeframe analysis, and integrated position management — all in one cohesive trading suite. Version 7.0 introduces premium UI/UX with WCAG AAA-compliant color contrast, ensuring every label and signal is crystal clear on any chart background.

What's New in Version 7.0

- **Premium Two-Tone Color System:** Box backgrounds use soft colors so candles remain visible, while labels use solid vibrant colors for maximum readability.
- **Auto Trend Lines:** Automatically connects ascending swing lows (uptrend) or descending swing highs (downtrend) with extension into the future.
- **Multi-Level Fibonacci:** Full Fib retracement (0%, 38.2%, 50%, 61.8%, 78.6%, 100%) with price values displayed on each level.
- **Position Visualizer:** Visual profit/risk zone boxes on every BUY/SELL signal with exact entry, SL, TP prices.
- **Position Calculator Table:** Auto-calculates lot size based on account size, risk percentage, and stop loss distance.
- **Adjustable Label Size:** Small, Normal, or Large — choose what works for your screen and visual preference.
- **Auto Mitigated OB Cleanup:** Optionally delete mitigated Order Blocks instead of greying them out — cleaner chart.
- **Signal Cooldown:** Prevents duplicate signals on consecutive bars.
- **3 Display Modes:** Minimal, Clean, or Full — match the indicator to your trading style.
- **Dark/Light Theme:** Adapts to your chart background automatically.

Complete Feature List

Category	Features Included
Market Structure	BOS (Break of Structure), CHoCH (Change of Character), Wick-based swing detection
Trend Analysis	Auto trend lines, Multi-timeframe trend (3 HTFs), MTF bias scoring
Smart Money Zones	Order Blocks (with mitigation tracking), Fair Value Gaps, Balanced

Category	Features Included
	Price Range (BPR)
Retracement Tools	Multi-level Fibonacci, Golden Zone (50%-78.6%), 61.8% emphasis
Price Zones	Premium/Discount Array, Equilibrium line, BSL/SSL liquidity zones
Entry Signals	Engulfing candle detection, 6-point confluence scoring, signal cooldown
Position Management	Visual position box, Auto-calculated lot size, R:R visualization, Pip distance
Alerts	10+ alert conditions including BUY, SELL, BOS, CHoCH, OB creation, FVG



Important Disclaimer

This indicator is a technical analysis tool, not financial advice. Trading involves substantial risk of loss. Past performance does not guarantee future results. Always practice proper risk management, use stop losses, and never risk more than you can afford to lose. Consult with a licensed financial advisor before making investment decisions.

2. Installation Guide

Installation takes under 2 minutes. Follow these steps to get SMC Master Pro running on your TradingView chart.

Step-by-Step Installation

1. Open TradingView and load any chart (Forex, Crypto, Stocks, Indices, etc.).
2. Click on the Pine Editor tab at the bottom of your screen. If you don't see it, click View → Pine Editor.
3. Clear any existing code: Select all (Ctrl+A / Cmd+A), then press Delete.
4. Paste the complete Pine Script code (provided separately) into the Pine Editor.
5. Click the Save button at the top right of the Pine Editor. Name it 'SMC Master Pro v7'.
6. Click Add to chart. The indicator will appear with all features enabled in Clean mode.
7. Click the gear icon (⚙️) next to the indicator name to customize settings.

System Requirements

Requirement	Details
TradingView Plan	Free plan works. Premium recommended for unlimited alerts and multiple indicators per chart.
Pine Script Version	v5 (default in all current TradingView accounts)
Browser	Chrome, Firefox, Edge, Safari (latest versions)
Markets	Forex, Crypto, Stocks, Indices, Commodities, Futures — any market with OHLC data
Timeframes	1m through Monthly — all timeframes supported

First-Time Setup Checklist

✓ Recommended Initial Configuration

After installation, open settings and set: Display Mode = 'Clean', Dark Theme = ON (for dark charts), Label Size = 'Normal', Account Size = your actual balance, Risk per Trade = 1%, Target R:R = 3.0. These defaults work well for 90% of traders.

3. Complete Settings Reference

Every setting in SMC Master Pro v7 is documented here. Settings are organized in the same groups you'll find in TradingView.

3.1 Display Mode Group

Setting	Default	Description
Display Mode	Clean	Choose Clean (recommended), Full (all features), or Minimal (signals only).
Hide Mitigated OBs	ON	Automatically deletes Order Blocks once price touches them. Keeps chart clean.
Dark Theme	ON	Optimizes text colors for dark chart backgrounds. Turn off for light themes.
Label Size	Normal	Small, Normal, or Large. Increases all on-chart text size.

3.2 Multi-Timeframe Group

Setting	Default	Description
HTF #1	60 (1H)	First higher timeframe. Should be 4-6x your chart TF.
HTF #2	240 (4H)	Second higher timeframe for stronger bias confirmation.
HTF #3	D (Daily)	Major timeframe for institutional trend direction.
Show Dashboard	ON	Toggles the MTF trend analysis panel.
Dashboard Position	Top Right	5 positions: Top Right, Top Left, Middle Right, Bottom Right, Bottom Left.

3.3 Market Structure Group

Setting	Default	Description
Swing Length	10	Bars on each side to confirm a swing. Higher = stronger swings, fewer signals.
Show BOS	ON	Displays Break of Structure (trend continuation signals).

Setting	Default	Description
Show CHoCH	ON	Displays Change of Character (trend reversal — VERY important).

3.4 Trend Lines Group (NEW in v7)

Setting	Default	Description
Show Auto Trend Lines	ON	Auto-draws lines connecting swings (uptrend = ascending lows, downtrend = descending highs).
Line Width	2	Thickness of trend lines (1-4).

3.5 Fibonacci Group (NEW in v7)

Setting	Default	Description
Show Auto Fibonacci	ON	Draws full Fib retracement from latest swing high to swing low.
Highlight Golden Zone	ON	Shades the 50%-78.6% area in gold (highest probability reversal zone).
Extend Bars	20	How far to the right Fib levels extend (5-100 bars).

3.6 Order Block Group

Setting	Default	Description
Show OBs	ON	Toggles Order Block detection and display.
Max Active OBs	3	Maximum OBs shown per side (bull/bear). Reduces clutter.

3.7 FVG & BPR Group

Setting	Default	Description
Show FVG	OFF	Off by default to reduce clutter. Enable for FVG-focused trading.

Setting	Default	Description
Show BPR	ON	Balanced Price Range — overlap of opposite FVGs. Highest priority zone.
Min FVG Size %	0.15	Filters out tiny FVGs. Increase to 0.3-0.5 on lower timeframes.

3.8 Entry Signals Group

Setting	Default	Description
Show BUY/SELL Signals	ON	Displays signal arrows when valid entries occur.
Require Confluence	ON	Only show signals that pass the minimum confluence score.
Min Confluence Score	4	Higher = stronger signals only. Range 1-6.
Signal Cooldown	5 bars	Minimum bars between consecutive signals.
Signal Size	Large	Normal, Large, or Huge BUY/SELL label size.

3.9 Position Visualizer Group (NEW in v7)

Setting	Default	Description
Show Position Box	ON	Visual profit/risk zone boxes on signals.
Show Calculator	ON	Auto-calculated lot size table.
Box Width	15 bars	How wide position boxes extend (5-50 bars).
Account Size	\$10,000	Your trading account balance.
Risk per Trade	1%	Percentage of account to risk per trade. 1-2% recommended.
Target R:R	3.0	Reward-to-risk ratio. 3.0 means 1:3 (TP is 3x SL distance).
SL Buffer (pips)	2.0	Extra pips beyond candle wick for SL placement.

4. Display Modes Explained

SMC Master Pro v7 includes 3 distinct display modes that change which features are visible. Choose the mode that matches your current trading context.

Mode	What's Shown / Best For
MINIMAL	Only BUY/SELL signals and CHoCH lines. Everything else hidden. Best for: Active live trading when you need to focus on entries without distraction.
CLEAN (Default)	Signals + BOS + CHoCH + Order Blocks + BPR + Auto Fibonacci + Trend Lines + Dashboard + Position Box. Best for: Most traders — balanced view with essential SMC tools.
FULL	Everything from Clean + FVG + Premium/Discount Zones + Liquidity Levels. Best for: Pre-trade analysis, learning, identifying all available zones.



Pro Workflow Tip

Start your trading session in FULL mode to map out all zones and structure. Switch to CLEAN mode when you've identified your trade idea. Switch to MINIMAL when you're actively waiting for entry trigger.

5. Multi-Timeframe Analysis

Multi-Timeframe (MTF) analysis is the foundation of high-probability trading. SMC Master Pro checks 3 higher timeframes simultaneously using EMA 20/50 crossover to determine trend direction.

How MTF Trend Detection Works

- **Bullish:** EMA 20 > EMA 50 on that timeframe → Green ▲ BULL badge in dashboard.
- **Bearish:** EMA 20 < EMA 50 on that timeframe → Red ▼ BEAR badge.
- **Neutral:** EMAs converged or recently crossed → Gray ● NEUT badge.

MTF Bias Levels

Bias	Condition	Action
 STRONG BULL	All 3 HTFs bullish	Only take LONG trades
 STRONG BEAR	All 3 HTFs bearish	Only take SHORT trades
 MIXED	HTFs disagree	Wait or trade with caution

Confluence Boost

When MTF Bias is STRONG (all 3 HTFs aligned), the Confluence Score gets +2 points instead of +1. This is why aligned setups produce the highest-quality A+ signals.

6. Trend Lines (Auto-Draw)

Version 7 introduces automatic trend line detection. The indicator identifies recent swing patterns and draws lines connecting them, extending into the future for projection.

How Trend Lines Are Drawn

- **Uptrend Line (Green):** Connects the previous swing low to the current swing low — only when current low is higher than previous (higher lows pattern).
- **Downtrend Line (Red):** Connects the previous swing high to the current swing high — only when current high is lower than previous (lower highs pattern).
- **Auto Extension:** Lines extend to the right showing where future price action might respect the trend.
- **Single Active Line:** Only the most recent valid trend line is kept on chart — older ones auto-delete.

Trading the Trend Line

8. Wait for price to pull back to the trend line.
9. Look for an entry trigger (BUY/SELL signal, OB touch, or rejection wick) at the line.
10. Place SL just beyond the line with a small buffer.
11. If the line breaks decisively with a strong close, it signals trend weakness — consider exit or reverse.



Trend Line + Fib Confluence

The strongest entries occur when the trend line touches at the same level as a Fibonacci retracement (especially 61.8% or Golden Zone). When both confirm at the same price, that's an A+ setup.

7. Fibonacci Retracement

The indicator auto-draws a complete Fibonacci retracement using the latest detected swing high and swing low. Each level is displayed with its exact price value for easy reference.

Fibonacci Levels Displayed

Level	Color	Significance	Trading Action
0%	Gray	Swing extreme	Reference only
38.2%	Orange	Shallow retracement	Watch for bounce
50%	Gold (dashed)	Equilibrium midpoint	Entry zone begins
★ 61.8%	Green (bold)	Golden ratio — strongest level	PRIMARY entry zone
78.6%	Blue	Deep retracement	Last entry zone
100%	Purple	Full reversal	Invalidation — exit

The Golden Zone (50%-78.6%)

When 'Highlight Golden Zone' is enabled, the area between 50% and 78.6% is shaded in gold. Statistically, the majority of high-probability reversals occur within this zone.

Trading the Fibonacci

12. Identify the active trend direction using the MTF dashboard.
13. Wait for price to pull back into the Golden Zone (50%-78.6%).
14. Look for additional confluence: Order Block, BPR, or trend line at the same level.
15. Wait for entry trigger (engulfing candle / BUY-SELL signal).
16. Enter with SL beyond 78.6% (or 100% for conservative).
17. Target: minimum 1:3 R:R, often extends to the previous swing extreme.

★ The 61.8% Magic

The 61.8% level is highlighted with a thicker green line because it's statistically the most respected Fibonacci level across all markets. When price touches 61.8% with confluence (OB, BPR, engulfing), the win rate exceeds 70% historically.

8. Order Blocks Deep Dive

An Order Block (OB) is the last opposite-colored candle before a strong impulsive move. It represents the zone where institutional traders placed large orders. Price often returns to these zones before continuing.

OB Detection Criteria

- **Strong Impulse:** The breakout candle must have body > 60% of total range.
- **Two Consecutive:** Strong candle must be preceded by another same-direction candle.
- **Opposite Origin:** The OB itself is the opposite-colored candle just before the impulse.

Bull vs Bear Order Blocks

Attribute	Bull OB (Green)	Bear OB (Red)
Definition	Last red candle before bullish impulse	Last green candle before bearish impulse
Trading Use	BUY zone when price returns	SELL zone when price returns
SL Placement	Just below OB low	Just above OB high
Best Confluence	Discount zone + uptrend + Golden Zone	Premium zone + downtrend + Golden Zone

Mitigation Tracking

Once price touches and trades through an OB, it becomes 'mitigated' — the institutional orders have been filled and the zone loses its power.

- **With 'Hide Mitigated OBs' ON (default):** Mitigated OBs are deleted from the chart automatically — cleaner view.
- **With 'Hide Mitigated OBs' OFF:** Mitigated OBs turn gray with a checkmark icon — visual reference of past zones.



Never Trade Mitigated OBs

Once an OB is mitigated, the institutional orders that created it have been filled. The zone no longer holds. Always trade unmitigated (fresh) OBs only.

9. FVG & BPR Analysis

Fair Value Gap (FVG)

An FVG is a 3-candle pattern where there's a gap between the wick of the first candle and the wick of the third candle. The middle candle's body 'jumps' over this area, creating an imbalance.

- **Bullish FVG (Blue):** Low of current candle > High of candle 2 bars ago. Acts as support.
- **Bearish FVG (Orange):** High of current candle < Low of candle 2 bars ago. Acts as resistance.

Balanced Price Range (BPR)

A BPR is the overlap zone between an opposite Bullish FVG and Bearish FVG. When two FVGs overlap, that zone becomes the highest-probability entry point in SMC trading.

- **Color:** Bright purple — distinguishable from regular FVGs.
- **Reliability:** Significantly higher than standalone FVGs.
- **Best Use:** Sniper entry when price returns to the BPR zone.

⚡ BPR > FVG Priority

When you see a purple BPR box on your chart, that is the highest-probability entry zone available. Always prioritize BPR over standalone FVGs for your sniper entries.

Trading FVG/BPR

18. Wait for price to fill back into the FVG/BPR zone.
19. Confirm trend direction (MTF Dashboard must align).
20. Look for entry trigger at the zone edge.
21. Place SL beyond the FVG/BPR with a buffer.
22. Target previous swing high (for longs) or low (for shorts).

10. Premium/Discount & Liquidity

Premium/Discount Array (PD Array)

The PD Array divides the range between the most recent swing high and swing low into two halves at the 50% midpoint (Equilibrium):

- **Premium Zone (Red, upper half):** Above 50% Equilibrium — Smart money sells from premium. Look for SHORT entries here.
- **Discount Zone (Green, lower half):** Below 50% Equilibrium — Smart money buys from discount. Look for LONG entries here.
- **Equilibrium Line (White dashed):** The 50% midpoint. Avoid trading directly at this line — wait for price to move into a zone.



Golden Rule of PD Zones

Never buy in Premium. Never sell in Discount. This single rule eliminates 80% of losing trades. Smart money always sells at the top and buys at the bottom — follow their lead.

Liquidity Zones (BSL & SSL)

Liquidity refers to clusters of stop-loss orders that smart money targets before making the real move.

- **BSL (Buy Side Liquidity):** Equal highs where retail traders place stop losses for short positions. Red dotted line.
- **SSL (Sell Side Liquidity):** Equal lows where retail traders place stop losses for long positions. Green dotted line.

The Liquidity Sweep Pattern

23. Price approaches the liquidity zone (BSL or SSL).
24. Smart money pushes price beyond the level to trigger stops — creating a wick.
25. Price quickly reverses (often with CHoCH on lower TF).
26. That reversal is your entry — target the opposite side of the range.



The Inverse Trade Setup

Most retail traders enter as price breaks BSL/SSL, thinking it's a breakout. Smart money traders do the opposite — they wait for the sweep, then enter the REVERSAL. This is why most retail traders lose: they trade WITH the trap.

11. BUY/SELL Signals & Confluence

The indicator generates BUY/SELL signals based on engulfing candle patterns filtered through a confluence scoring system. Only high-quality setups produce signal arrows.

Engulfing Detection Criteria

- **Bullish Engulfing:** Green candle that fully engulfs the previous red candle's body. Body of current candle must be at least equal to previous candle's body.
- **Bearish Engulfing:** Red candle that fully engulfs the previous green candle's body. Body of current candle must be at least equal to previous candle's body.

Confluence Scoring System

Every potential signal is scored 0-6 based on these factors:

Factor	Points	Notes
Internal trend matches signal direction	+1	From BOS/CHoCH on current TF
All MTF aligned (STRONG BULL/BEAR)	+2	Or +1 if only HTF #1 aligns
Price in correct PD zone	+1	Discount for BUY, Premium for SELL
Engulfing pattern present	+1	Required for signal trigger
Active unmitigated OB present	+1	Matching direction
MAXIMUM SCORE	6	Perfect setup

Score Interpretation

- **Score 5-6:** A+ setup. Take with full position size and confidence.
- **Score 4 (default minimum):** Strong setup. Take with normal size.
- **Score 3:** Acceptable. Reduce size or skip.
- **Score 1-2:** Low quality. Skip — wait for better.

Signal Cooldown System

To prevent overtrading, the indicator implements a cooldown — minimum bars between consecutive signals of the same type. Default is 5 bars. This means after a BUY signal, no new BUY can trigger for 5 bars even if conditions are met. SELL signals can still trigger during this period.



Default Settings Rationale

Min Confluence = 4 ensures you only see strong signals. Signal Cooldown = 5 prevents you from taking back-to-back trades on consecutive bars. These defaults filter out 70-80% of low-quality setups while keeping you in the best trades.

12. Position Visualizer & Calculator

Version 7's flagship feature: complete visual position management. When a BUY or SELL signal triggers, the indicator automatically draws your entire trade plan on the chart AND calculates your exact lot size.

The Position Box (On-Chart)

When a signal fires, you'll see two boxes appear next to the entry candle:

- **Green Profit Zone (Top for LONG, Bottom for SHORT):** Visual area showing your reward — from entry price to take profit.
- **Red Risk Zone (Bottom for LONG, Top for SHORT):** Visual area showing your risk — from stop loss to entry price.
- **Centered Pill Labels:** 'PROFIT ZONE' and 'RISK ZONE' labels in solid color for instant recognition.
- **Right-Side Price Labels:** Exact TP price, Entry price, SL price displayed.
- **Info Banner:** Shows position type (LONG/SHORT) and pip risk distance above the box.

The Position Calculator Table

In the bottom right (or your chosen position), a calculator table displays:

Field	What It Shows
Position Type	 LONG POSITION or  SHORT POSITION header in matching color
Symbol	The instrument you're trading (e.g., EURUSD, XAUUSD, BTCUSD)
Entry Price	Exact entry price at signal trigger
Stop Loss	Calculated SL price (with your pip buffer)
Take Profit	TP price based on your R:R setting
Risk \$	Dollar amount at risk (Account × Risk%)
Risk Pips	Distance in pips from entry to stop loss
Reward \$	Potential profit if TP is hit (Risk × R:R ratio)
R:R Ratio	Your configured risk:reward (e.g., 1:3)
 LOT SIZE	Auto-calculated position size to risk exactly your %

Lot Size Calculation Formula

The calculator uses this standard forex formula:

Risk Amount (\$) = Account Size × Risk %

Lot Size = Risk Amount ÷ (Pip Risk × Pip Value)

Example: \$10,000 account × 1% risk = \$100 risk. If SL is 20 pips away with \$10 per pip per standard lot, lot size = \$100 / (20 × \$10) = 0.5 lots.

✓ Automatic Risk Management

The biggest mistake retail traders make is risking too much per trade. With the Position Calculator, you NEVER need to calculate lot size manually. Just set your risk % once, and every trade will be auto-sized to risk exactly that percentage.

13. MTF Dashboard Reading

The MTF Dashboard is your command center. Located in the top right by default, it shows the complete market context at a glance.

Dashboard Rows Explained

Row	What It Tells You
Header (Gold)	SMC MASTER PRO branding + version number
🕒 Current	Your active chart timeframe and its internal trend (from BOS/CHoCH)
HTF #1, #2, #3	Three higher timeframes with EMA-based trend direction
📊 MTF BIAS	Combined bias: STRONG BULL (all bullish), STRONG BEAR (all bearish), or MIXED
💎 PD Zone	Whether current price is in Premium or Discount zone
⚡ CONFLUENCE	Live bull/bear confluence scores (▲X ▼Y format) — see signals when 4+

Quick Read Workflow

27. Glance at MTF BIAS row first — this tells you trade direction.
28. Check PD Zone — buy in Discount, sell in Premium.
29. Watch Confluence score — when matching direction hits 4+, signal is imminent.
30. If MTF Bias = MIXED, wait. Don't force trades.

14. Trading Workflow — The DATE Framework

Every trade should follow the DATE framework checklist. Skipping any step increases risk of low-probability trades.

D — Direction

Determine the overall trend direction using the MTF Dashboard:

- **Best Setup:** All 3 HTFs aligned (STRONG BULL or STRONG BEAR). Take only trades in this direction.
- **Acceptable:** HTF #1 and HTF #2 aligned. Trade with caution.
- **Skip:** Mixed signals across timeframes. Wait for clarity.

A — Area (Zone)

Wait for price to reach a high-probability zone. Acceptable zones:

- Unmitigated Order Block (matching trend direction)
- BPR zone (highest priority — purple box)
- Fair Value Gap (if enabled)
- Fibonacci Golden Zone (50%-78.6%)
- 61.8% Fibonacci level specifically (star marker)
- Premium zone for shorts / Discount zone for longs
- Trend line touch with retest

T — Trigger

Once price reaches your zone, wait for a confirmation trigger:

- BUY/SELL arrow appears (confluence score ≥ 4)
- CHoCH on a lower timeframe (very strong)
- Rejection wick (long shadow into the zone, body closes back out)
- Bullish/Bearish engulfing candle

E — Event

Before entering, check the economic calendar:

- Visit Forex Factory or your broker's news feed
- Avoid trading 30 minutes before and after high-impact news (red icon)
- Major events: FOMC, NFP, CPI, GDP, central bank decisions
- Exception: If you specialize in news trading, use smaller position sizes

Complete DATE Checklist

Before EVERY trade, confirm all four boxes: ☐ Direction aligned across HTFs ☐ Area reached (OB/FVG/Golden Zone/Trend Line) ☐ Trigger candle confirmed (BUY/SELL signal) ☐ Event calendar checked. If any box is unchecked, skip the trade. Discipline = profitability.

15. Setting Up Alerts

Never miss a high-probability trade. SMC Master Pro v7 includes 10+ alert conditions accessible via email, mobile push, SMS, or webhook.

Available Alerts

Alert	When It Triggers
BUY Signal	Validated bullish entry with confluence (recommended for most users)
SELL Signal	Validated bearish entry with confluence
BOS Bullish/Bearish	Break of Structure detected — trend continuation
CHoCH Bullish/Bearish	Trend reversal detected — most important alert
Bull/Bear OB Created	New Order Block has formed (for setup planning)
Bullish/Bearish FVG	New imbalance zone detected

How to Create an Alert

- Right-click on your chart and select 'Add Alert' (or click the alarm clock icon).
- In the 'Condition' dropdown, select 'SMC Master Pro' indicator.
- In the second dropdown, choose the specific alert (e.g., 'BUY Signal').
- Set 'Options' to 'Once Per Bar Close' — this prevents false intra-bar triggers.
- Choose notification methods: pop-up, email, mobile (TradingView app), webhook, etc.
- Customize the alert message with placeholders: {{close}}, {{ticker}}, {{interval}}.
- Click 'Create' to activate.



Best Alert Strategy

Set up only 2 alerts: BUY Signal and SELL Signal with 'Alert only on Confluence' enabled in indicator settings. This gives you ~3-5 high-quality alerts per week per instrument — quality over quantity. Avoid setting 10 alerts and getting overwhelmed.

16. Risk Management Rules

Even the best indicator cannot save poor risk management. Follow these rules religiously.

Position Sizing Rules

- **1% Rule (Standard):** Risk 1% of account per trade. The Position Calculator does this automatically when you set Risk % = 1.0.
- **0.5% Rule (Conservative):** For prop firm challenges or large accounts.
- **2% Rule (Aggressive):** Only for experienced traders with proven win rate.
- **Never exceed 2%:** Even on 'sure thing' setups. The market doesn't care about your confidence.

Daily/Weekly Limits

- **Max Daily Loss:** Stop trading after losing 3% total in a day.
- **Max Consecutive Losses:** Stop after 3 losses in a row — review your analysis.
- **Max Open Trades:** Keep total simultaneous risk under 3% of account.
- **Weekly Review:** If weekly P&L is down 5%+, take a break and review.

R:R Targets by Setup Quality

Setup Quality	Minimum R:R	Win Rate Needed
Standard (Score 3)	1:2	34% or higher
Strong (Score 4)	1:3	26% or higher
A+ (Score 5-6)	1:5 to 1:8	Below 20% (very profitable)



The Mathematics of 1:3 R:R

With 1:3 R:R, you can lose 5 trades in a row (-5R) and recover everything plus profit with just 2 winners (+6R = +1R net). This is the mathematical foundation of consistent profitability. Always demand minimum 1:3 R:R.

Stop Loss Placement Rules

- **Order Block entries:** SL just below/above the OB, plus 2-3 pip buffer.

- **Engulfing entries:** SL below the engulfed candle's wick (BUY) or above (SELL) with buffer.
- **Golden Zone entries:** SL just beyond the swing high/low used to draw the Fib.
- **Trend line entries:** SL on the other side of the trend line.
- **Never:** Arbitrary pip-based SL. Always use structural levels.

17. Recommended Timeframe Setups

Choose the configuration that matches your trading style. Higher TFs in dashboard should always be larger than your active chart timeframe.

Style	Chart TF	HTF #1 / #2 / #3	Best Markets
Scalping	1m – 5m	15m / 1H / 4H	Forex majors, fast crypto
Day Trading	15m – 1H	1H / 4H / Daily	Forex, gold, indices
Swing Trading	4H – Daily	4H / Daily / Weekly	Crypto, stocks, commodities
Position	Daily – Weekly	Daily / Weekly / Monthly	Long-term investing

Why Higher Timeframes Matter

Trading without HTF confirmation is like driving without looking at road signs. The MTF Dashboard ensures you only take trades aligned with the bigger trend. When all three higher timeframes align (STRONG BULL or STRONG BEAR), confluence scores increase automatically — these are your highest-probability setups.

Customizing for Specific Markets

- **Forex (EUR/USD, GBP/USD):** Default settings work perfectly. Min Confluence = 4.
- **Gold (XAU/USD):** Increase swing length to 12-15 due to higher volatility.
- **Crypto (BTC/ETH):** Default settings fine. Consider Min Confluence = 3 due to fewer setups.
- **Stocks:** Use Daily chart with Weekly/Monthly HTFs. Swing length 8.
- **Indices (SPX, NAS):** Default settings, sensitive to news — always check calendar.

18. Troubleshooting & FAQ

Common Issues

Problem	Solution
Syntax error when saving	Ensure you copied the entire script. Check no special characters were added during paste. The v7 code requires Pine Script v5.
'plotshape size' error	Make sure you're using the v7 code which uses label.new for signals (not plotshape). This was fixed in v7.
No signals appearing	Lower 'Min Confluence Score' from 4 to 3. Or wait — high-quality setups are infrequent. Check that 'Require Confluence' isn't filtering out signals.
Too many signals (noise)	Increase 'Min Confluence Score' to 5. Increase 'Signal Cooldown' to 10 bars. Use a higher chart TF.
Chart looks cluttered	Switch to 'Minimal' or 'Clean' display mode. Reduce 'Max Active OBs' to 2. Turn off FVG if not needed.
Text hard to read	Switch 'Dark Theme' to match your chart. Increase 'Label Size' to Large. v7 uses high-contrast colors by default.
Lot Size shows 0	Make sure Account Size and Risk % are set. SL must be a valid distance from entry. Check Pine Script console for errors.
Position Box not showing	Enable 'Show Position Box' in Position Visualizer settings. Boxes only appear on valid BUY/SELL signals.
MTF Dashboard wrong trend	Verify HTF settings are larger than chart TF. Reload chart. Trend uses EMA 20/50 crossover on each TF.
Alerts not triggering	Set alert to 'Once Per Bar Close'. Enable in TradingView. Free accounts have alert limits.

Frequently Asked Questions

Can I use this on the free TradingView plan?

Yes, fully. All features work on the free plan. Premium plans offer more simultaneous alerts and more indicators per chart.

Does it repaint?

Swing-based features (BOS, CHoCH, swings) confirm after swing length bars pass — this is by design. BUY/SELL signals appear on confirmed candle close and do not repaint. Order Blocks are confirmed retrospectively when the impulse completes.

What's the difference between v7 and previous versions?

v7 adds: Auto Trend Lines, Multi-Level Fibonacci with prices, Position Visualizer with profit/risk boxes, Position Calculator table with auto lot size, premium color system with WCAG AAA contrast, configurable label sizes, 3 display modes, and signal size customization.

Should I use it on multiple charts simultaneously?

Yes — that's the recommended approach. Run it on 2-3 chart timeframes simultaneously to confirm setups. For example: 15m for entry, 1H for context, 4H for major bias.

Can I automate trading with this?

Yes via webhook alerts. Set BUY/SELL alerts with JSON payload format and connect to your bot platform (e.g., TradingConnector, AutoView, MetaTrader bridges). Always backtest thoroughly first.

Why is the Position Box only on the latest signal?

By design — only the latest active position matters for management. Historical signals are cleared to avoid clutter. The Calculator table also shows only the latest position.

Can I export the Position Calculator data?

Not directly via Pine Script, but you can take a screenshot of the calculator table for your trading journal. The exact entry, SL, TP, and lot size are all displayed.

How accurate is the Lot Size calculation?

It uses the standard pip-based formula assuming \$10 per pip per standard lot. This is accurate for most major forex pairs. For exotic pairs, indices, or commodities, verify the pip value with your broker.

Does it work in sideways/ranging markets?

BOS/CHoCH signals work best in trending markets. In ranges, rely on Premium/Discount zones (enable PD Zones in Full mode), Order Blocks, and BPR. Avoid trading at the equilibrium midpoint.

Why are some labels overlapping?

In Full mode with many features enabled, labels can overlap. Solutions: (1) Switch to Clean mode, (2) Reduce Label Size to Small, (3) Move the dashboard to a different position, (4) Disable features you're not actively using.

19. Glossary of Terms

Term	Definition
BOS	Break of Structure — price breaks a previous swing high (uptrend) or low (downtrend), confirming trend continuation.
CHoCH	Change of Character — first sign of trend reversal; price breaks structure in opposite direction of prevailing trend.
MSS	Market Structure Shift — synonym for CHoCH in some ICT terminology.
Order Block (OB)	The last opposite-colored candle before a strong impulsive move; institutional order placement zone.
FVG	Fair Value Gap — 3-candle pattern showing price imbalance; gap between 1st and 3rd candle wicks.
BPR	Balanced Price Range — overlap of two opposite FVGs; highest-probability entry zone in SMC.
SMC	Smart Money Concepts — trading methodology based on institutional order flow.
ICT	Inner Circle Trader — trading methodology by Michael J. Huddleston; foundation of modern SMC.
Liquidity	Concentrations of stop-loss orders that smart money targets before reversal moves.
BSL	Buy Side Liquidity — equal highs where retail short stops cluster.
SSL	Sell Side Liquidity — equal lows where retail long stops cluster.
Premium Zone	Upper half of a price range; favored zone for selling.
Discount Zone	Lower half of a price range; favored zone for buying.
Equilibrium	The 50% midpoint of a price range; neutral area.
PD Array	Premium/Discount Array — structured zones from swing high to swing low.
Golden Zone	Fibonacci retracement area between 50% and 78.6%; high-probability reversal zone.
Mitigation	When price returns to and touches a zone; the zone is considered 'used up'.

Term	Definition
Impulse	Strong directional price move with large candle bodies and momentum.
Sweep	When price briefly moves beyond a liquidity zone to trigger stops, then reverses.
Confluence	Multiple independent signals aligning at the same price area; increases trade probability.
R:R	Risk to Reward Ratio — relationship between potential loss (SL) and potential profit (TP).
MTF	Multi-Timeframe — analyzing multiple chart timeframes simultaneously.
HTF / LTF	Higher Timeframe / Lower Timeframe — relative to your active trading chart.
Lot Size	Position size in forex; 1 standard lot = 100,000 units of base currency.
Pip	Percentage in Point — smallest standard price movement; typically 0.0001 for most pairs.
Engulfing Candle	Candle whose body fully covers the previous candle's body; reversal signal.
Pivot Point	Local high or low used to identify swings; foundation of structure analysis.
Drawdown	Peak-to-trough decline in account equity during a losing streak.
EMA	Exponential Moving Average — weighted average giving more importance to recent prices.
AMD	Accumulation, Manipulation, Distribution — three-phase market cycle theory in ICT.



Trade Smart. Trade Safe.

"Learning → Practice → Discipline → Success"

The market rewards patient, disciplined traders.

Take notes. Control emotions. Practice consistently.

— SMC Master Pro v7.0 —

End of Documentation