

## Chapter 3: Configuration

The **DocP** provided with a default configuration. If desired, users can edit the default configuration options in order to customize its values by modifying the configuration file: the **dpdocproc.ini** file.

### DPDocProc.ini File

The **dpdocproc.ini** file is a configuration file in which values are assigned to the configuration options via keywords. By default, the **dpdocproc.ini** file is located in the directory where the **DocP** is installed (usually C:\Program Files\DocP\ancath).

This chapter describes every keyword contained in the **dpdocproc.ini** file and gives users the required information to correctly configure each of the keywords as desired.

The **dpdocproc.ini** file sets values for **DocP** configuration options using keywords.

Syntax:

<keyword>=<value>

Example:

AUTOANCHOR=Y

### Keywords

This section includes a table containing a list of the **dpdocproc.ini** file keywords followed by a description of each of the keywords listed.

*For information on the use of environment variables in the **dpdocproc.ini** file keyword values, refer to [chapter 7](#).*

#### NOTE:

The **#** character is used to insert comments in the **dpdocproc.ini** file. All comments following the **#** character are ignored by the **DocP**. There is no limit to the number of comments that can be entered in the **dpdocproc.ini** file.

Syntax:

#<string>

Example:

# The file was created on Monday  
# Do not change the QFSPATH settings

| INI FILE KEYWORDS      |                                                            |
|------------------------|------------------------------------------------------------|
| <b>ACTIVATION CODE</b> | For inserting the product activation code.                 |
| <b>ALTNEWLINE</b>      | For defining an alternate newline character.               |
| <b>ANCHORFIELDPOS</b>  | For specifying the position of a new subform to be loaded. |
| <b>AUTOANCHOR</b>      | For automatically activating the anchor function.          |
| <b>AUTOOVERFLOW</b>    | For setting the field overflow event in auto mode.         |

|                                         |                                                                                                                                                                                                 |
|-----------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b><u>AUTORESOLVE</u></b>               | For specifying if all variables that appear within the declaration of another variable should be solved automatically.                                                                          |
| <b><u>BARCODEESCAPECHAR</u></b>         | For inserting special characters in barcodes.                                                                                                                                                   |
| <b><u>BOILERPLATE</u></b>               | For specifying the boilerplate (the visual background of a template) to be used.                                                                                                                |
| <b><u>CHECKENDPAGE</u></b>              | For specifying if the application should check if the subform fits on the current page.                                                                                                         |
| <b><u>CMDPREFIX</u></b>                 | For specifying a command prefix character.                                                                                                                                                      |
| <b><u>CMDSUFFIX</u></b>                 | For specifying a command suffix character.                                                                                                                                                      |
| <b><u>CODE PAGE</u></b>                 | For setting the code page used by the DocPath® DocProcessor.                                                                                                                                    |
| <b><u>COMMANDFILE</u></b>               | For specifying a command file.                                                                                                                                                                  |
| <b><u>CSV DEFSTRUCT</u></b>             | For specifying if the input CSV file includes a definition of the record structure.                                                                                                             |
| <b><u>DATAPATH</u></b>                  | For specifying a path for data files.                                                                                                                                                           |
| <b><u>DEFAULT UNIT TYPE</u></b>         | For modifying the unit type default value.                                                                                                                                                      |
| <b><u>DEFTEMPPATH</u></b>               | For specifying a path for all temporary files.                                                                                                                                                  |
| <b><u>DETECTPREFIX</u></b>              | For specifying if the application should automatically detect certain prefixes in the data file.                                                                                                |
| <b><u>DICTPREFIX</u></b>                | For specifying the dictionary prefix character.                                                                                                                                                 |
| <b><u>DISCARDUNKNOWNFLD</u></b>         | For specifying if <FLD> field commands with unknown field names should be ignored or not.                                                                                                       |
| <b><u>EVENTFILENAME</u></b>             | For specifying the name of the event file.                                                                                                                                                      |
| <b><u>EVENTFILEPATH</u></b>             | For specifying the path of the event file.                                                                                                                                                      |
| <b><u>FIELDSTRIP</u></b>                | For removing control characters from data file fields.                                                                                                                                          |
| <b><u>FIELDSTRIPMODE</u></b>            | For defining which control characters will be removed from data file fields.                                                                                                                    |
| <b><u>FPPRINT INSTALLATION PATH</u></b> | For indicating the  version 3.3) installation path. Only for processing form versions prior to version 4.0. |
| <b><u>FSTCMDCFGJOB</u></b>              | Deprecated.                                                                                                                                                                                     |
| <b><u>INLINESUFFIX</u></b>              | For specifying the prefix character for inline text control commands.                                                                                                                           |
| <b><u>INPUT CODE PAGE</u></b>           | For specifying the code page of the input data file.                                                                                                                                            |
| <b><u>JOB SUMMARY FILE</u></b>          | For generating a summary line for each processed job.                                                                                                                                           |

|                         |                                                                                 |
|-------------------------|---------------------------------------------------------------------------------|
| <u>LAYERMACRO</u>       | For setting the layer macro.                                                    |
| <u>LAYERNAME</u>        | For setting the layer name.                                                     |
| <u>LOADFIRSTPAGE</u>    | For specifying if the application should load the first form page or not.       |
| <u>LOG MODE</u>         | For specifying the log mode.                                                    |
| <u>LOG PORT</u>         | For specifying the log port of the Log Service.                                 |
| <u>LOG SERVER</u>       | For specifying the log server where Log Service is running.                     |
| <u>LOG FILE</u>         | For specifying the path and name for the log file.                              |
| <u>LOG LEVEL</u>        | For specifying the type of log messages that will be recorded.                  |
| <u>LOGOPATH</u>         | For specifying the image path.                                                  |
| <u>MODE</u>             | For indicating the initial mode in which Processor processes the data.          |
| <u>MONTH</u>            | For specifying multi-lingual definitions for months.                            |
| <u>MONTHOF</u>          | For indicating the format for date entries.                                     |
| <u>NEWFIELD</u>         | For specifying the character that indicates that a new field must be processed. |
| <u>OUTLOCATION</u>      | For setting the output location.                                                |
| <u>OVERLAYFONTNAME</u>  | For setting the font to be used in overlay mode.                                |
| <u>OVERLAYFONTSIZE</u>  | For setting the height of the font to be used in overlay mode.                  |
| <u>OVRFONT</u>          | For setting the overlay font.                                                   |
| <u>OVRIGNFF</u>         | For activating or deactivating the process of carriage returns in overlay mode. |
| <u>OVRLPI</u>           | For overlay mode lines per inch.                                                |
| <u>OVRNLIN</u>          | For setting the number of lines per page.                                       |
| <u>OWNERPASSWORD</u>    | For setting the owner password.                                                 |
| <u>PERMISSIONS</u>      | For setting permissions for PDF documents.                                      |
| <u>PREAMBLE</u>         | For setting the preamble path.                                                  |
| <u>PRINTALLPAGES</u>    | For automatically printing form pages or subforms.                              |
| <u>PRINTUNKNOWNVARS</u> | For printing unknown variables.                                                 |
| <u>PROCESSINLINE</u>    | Process inline text control commands.                                           |
| <u>PROCESSPICTURES</u>  | Process mask formatting.                                                        |

|                                          |                                                                                                                         |
|------------------------------------------|-------------------------------------------------------------------------------------------------------------------------|
| <b><u>PROCESSVARIABLES</u></b>           | Process variables.                                                                                                      |
| <b><u>QFSPATH</u></b>                    | For indicating a list of paths for locating QFS forms.                                                                  |
| <b><u>RECSIZE</u></b>                    | For specifying the record size.                                                                                         |
| <b><u>REFORMAT</u></b>                   | Reformat field data.                                                                                                    |
| <b><u>RESERVEGLOBALS</u></b>             | Reserves the fields declared as globals in every new page.                                                              |
| <b><u>SOFTFONTPATH</u></b>               | Soft font path.                                                                                                         |
| <b><u>TESTCHAR</u></b>                   | For modifying the test character set with the <a href="#">-test</a> operating option.                                   |
| <b><u>TPAGE SIZE</u></b>                 | Specifies the space, in number of digits, that will occupy the content of the <a href="#">\$TPAGE</a> variable.         |
| <b><u>USE FPPRINT WITH OLD FORMS</u></b> | For specifying if <a href="#">[redacted]</a> itself must be executed for processing form versions prior to version 4.0. |
| <b><u>USERPASSWORD</u></b>               | For defining a user password for PDF documents.                                                                         |
| <b><u>V3 EVENTS CODE PAGE</u></b>        | For specifying the expected code page in version 3.3 and previous forms.                                                |
| <b><u>VAR RECORD MODE DELIM</u></b>      | For specifying the string delimiter character in variable record mode.                                                  |
| <b><u>VAR RECORD MODE SEP</u></b>        | For specifying the field separator character in variable record mode.                                                   |
| <b><u>VARPREFIX</u></b>                  | For defining a variable substitution prefix character.                                                                  |
| <b><u>WEEKDAY</u></b>                    | Weekdays for secondary language.                                                                                        |
| <b><u>YEAR2000</u></b>                   | For setting the limits for considering the dates as dates belonging to year 2000.                                       |

**IMPORTANT!** Some keyword values can be overridden by the operating options that may be employed in the command line. For information related to equivalences between keywords and operating options, refer to [Appendix 1](#) of this manual.

### **ACTIVATION CODE**

**Default**=Evaluation

For inserting the license that activates the purchased [\[redacted\]](#) functions.

Syntax:

ACTIVATION CODE=<string>

For more information on [\[redacted\]](#) activation, refer to the Activation section in chapter 2: [Installation](#).

### **ALTNEWLINE**

**Default**=~ (tilde)

Defines a character that will be processed as an alternate newline character. A newline character is a special character or sequence of characters signifying the end of a line of text.

**Syntax:**

ALTNEWLINE=<character>

**Example:**

ALTNEWLINE=%

The ALTNEWLINE keyword is set to the percent sign (%) and the data file contains the following:

```
<FLD>SampleFld.
This is a field with%an alternate new line character.
```

Consequently, the displayed result for this field in the form will be the following:

```
This is a field with
an alternate new line character.
```

## ANCHORFIELDPOS

**Default=BASE**

If the [AUTOANCHOR](#) keyword value is set to NO, the  sets all subforms loaded with the CallPage (<CPG>) event in the position of the field that was last printed (instead of using the subform's anchor). The ANCHORFIELDPOS keyword allows users to specify if the new subform is to be loaded in the upper part or at the baseline of the field that was last printed.

**Syntax:**

ANCHORFIELDPOS={TOP|BASE}

Where:

- TOP: for positioning subforms in the upper part of the field that was printed last.
- BASE: for positioning subforms at the baseline of the field that was printed last

**Example:**

ANCHORFIELDPOS=TOP

## AUTOANCHOR

**Default=Y**

Defines whether or not to automatically activate the anchor function when working with pages or subforms. Possible values are Y (yes) or N (no). When set to Y, the anchor will automatically be located below the last object drawn. When set to N, the user will need to position the anchor manually (through a call to a field) or using the [<POS>](#) command. The insertion point of subforms can be specified in two ways:

- Using the location of the last field referenced in the data stream or the location defined by the [<POS>](#) command (AUTOANCHOR=N).
- Using the position of the anchor defined in the form design to specify the insertion point (AUTOANCHOR=Y).

**Syntax:**

AUTOANCHOR={Y|N}

**Example:**

AUTOANCHOR=N

**NOTE:** When a page or subform is defined with the Anchor Loose option, the anchor will automatically be located below the last object drawn. A text defined as V-Text will move the anchor below the last line of the text in case it exceeds the anchor position or it was defined as Anchor Loose.

*For more information refer to the [<ANC>](#) (Anchor) Dynamic Form Control Command in chapter 5 of this manual.*

**AUTOOVERFLOW****Default=N**

Sets the "fieldoverflow" event in auto mode.

**Syntax:**

AUTOOVERFLOW={Y|N}

Possible values are:

- **Y (yes):** When set to Y, it is necessary to define in the "Fieldoverflow" event a call to a subform, containing a field with the same name that will *automatically* be filled in with the spilling text.
- **N (no):** When set to N(no), the spilling text will be stored in the "FieldSpillingText" variable. Then, it will be necessary to *manually* indicate the field to be filled in with the content of the variable.

**NOTE:** The "FieldSpillingText" variable used in the event code will only be operative when the AUTOOVERFLOW keyword is set to N (no).

*For more information related, refer to [FieldOverflow event in chapter 9](#).*

**Example:**

AUTOOVERFLOW=N

**NOTE:** In the Fieldoverflow event, the field to insert the exceeding text will have to be invoked, besides being indicated through the FieldSpillingText variable.

**AUTORESOLVE****Default=N**

Specifies if all variables that appear within the declaration of another variable (via the [<DEC>](#) command) should be resolved automatically. Setting this keyword to Y (yes) has the same result as inserting RESOLVE in all [<DEC>](#) commands of the form.

**Syntax:**

AUTORESOLVE={Y|N}

**Example:**

AUTORESOLVE=Y

**BARCODEESCAPECHAR****Default=\**

Sets the escape character needed to introduce special characters in barcode types Code-128 and EAN-128. An escape character is a single character which in a sequence of characters signifies that what is to follow takes an alternative interpretation.

*For more information on the creation of barcodes, refer to chapter 15 "Creating Barcode Fields" of the [Designer manual](#).*

**Syntax:**

BARCODEESCAPECHAR=<character>

**Example:**

BARCODEESCAPECHAR=\

**BOILERPLATE****Default=Y**

Defines whether or not to print boilerplate. Boilerplate refers to static or fixed objects, including text or graphics, that provide the visual background of a template.

**Syntax:**

BOILERPLATE={Y|N}

**Example:**

BOILERPLATE=N

The example above will generate a form with variable data only.

**CHECKENDPAGE****Default=Y**

Configures the [redacted] to perform a check prior to printing the subform just in case the subform were being outlined out of the current page. Possible values are Y (yes) or N (no):

- Y (Yes): The [redacted] will always verify that a subform fits on the current page before printing the subform. If the subform does not fit on the page, the [redacted] automatically loads page 1 of the form before printing the subform.
- N (No): The [redacted] will not verify that a subform fits on the current page before printing the subform.

---

**IMPORTANT!** If the [EndPage](#) event is defined in the Events file, the CHECKENDPAGE keyword will have no effect, because in that case the [redacted] will always check if a subform fits on the page prior to printing the subform.

---

**Syntax:**

CHECKENDPAGE={Y|N}

**Example:**

CHECKENDPAGE=Y

**CMDPREFIX****Default= < (less than symbol)**

Defines the Dynamic Command Prefix character.

**Syntax:**

CMDPREFIX=<character>

**Example:**

CMDPREFIX=#

**CMDSUFFIX****Default= > (greater than symbol)**

Defines the Dynamic Command Suffix character.

**Syntax:**

CMDSUFFIX=<character>

**Example:**

CMDSUFFIX=]

In case no character is defined, it will indicate that there is no command suffix. Therefore, the command will be separated by blanks, tabs or carriage returns.

**CODE PAGE****Default=0 (see Note (\*) below)**

This keyword determines the code page that is used by the [redacted]. The code page of the input data file is converted into the code page set by this keyword.

**Syntax:**

CODE PAGE=<number>

---

**NOTE:** (\*) On OS400 platforms, "0" refers to the CCSID (Coded Character Set Identifier) of the job of the DocPath® Controller. On other platforms, it refers to the default system code page.

**NOTE:** Seven-bit ASCII code pages are excluded except the standard ANSI X3.4 ASCII.

## COMMANDFILE

**Default=**No default.

Changes the language file. Changes the syntax of the commands by the selection of another language file (.LNG). They are ASCII files that contain the [REDACTED] commands and substitutes. Defines an 'alias' file for the DocProcessor commands and command line parameters. The format of these language files is the following:

```
Short_Command New_Command_Name
```

```
Parameter New_Parameter_Name
```

It is possible to use the ';' character as comment in any part of the file and it will be taken as comment till the end of the line in which it appears.

### Syntax:

```
COMMANDFILE=<file_name>
```

## CSV DEFSTRUCT

**Default=**N (no).

For specifying if the CSV (comma-separated values) input data file includes the definition of its record structure.

- Y (yes): the CSV input file contains the record structure definition and the [REDACTED] data processing mode will automatically be changed to variable record mode.
- N (no): the CSV input file does not contain the record structure definition and the initial [REDACTED] data processing mode is maintained.

### Syntax:

```
CVS DEFSTRUCT=<Y|N>
```

### Example:

```
CVS DEFSTRUCT=Y
```

The following considerations must be taken into account when using the **CSV DEFSTRUCT** keyword:

- The **CSV DEFSTRUCT** keyword modifies [REDACTED] data processing since, when its value is set to Y (yes), the initial mode in which the [REDACTED] processes the input data is automatically changed to variable record mode processing.
- The initial mode in which the [REDACTED] processes the input data is set with the [MODE](#) keyword. The [MODE](#) and **CSV DEFSTRUCT** keywords both modify the initial mode of data processing and may be incompatible generating an erroneous output. For this reason it is recommended to pay special attention when employing both keywords.
- Since CSV files are processed in variable record mode, global fields may be created. To create a global field, insert an asterisk (\*) just before the field name in the CSV file

### Example:

```
field_name1 ; *field_name2 ; field_name3 (line 1)
```

```
field_name1 ; field_name2 ; field_name3 (line 2)
```

Since the field\_name2 field is preceded by an asterisk, this field will be global.

*For more information on CSV format file processing, refer to the [CSV Data Format](#) section in chapter 4 of this manual.*



***DATAPATH*****Default**=.\data

Defines the path where data files will be located.

**Syntax:**

DATAPATH=&lt;path&gt;

**Example:**

Datapath=C:\Windows\Programfiles\docpath\data

***DEFAULT UNIT TYPE*****Default**=dotsThis keyword allows users to modify the unit type default value. This value only applies if the UNITS parameter is not specified in the [<ANC>](#), [<PIC>](#) and [<POS>](#) commands.**Syntax:**

DEFAULT UNIT TYPE=&lt;in|cm|dots&gt;

**Example:**

DEFAULT UNIT TYPE=cm

**Example:**

&lt;POS&gt; value 10

If the <POS> command in the example above appears in the data and the DEFAULT UNIT TYPE is set to "cm", the value "10" will be processed in centimeters. If the keyword value is empty, the value will be invalid. If the keyword does not appear, the default unit type (DOTS) will apply.

***DEFTEMPPATH*****Default**=Current directoryDefines the path in which the  will generate the temporary files required during  execution.**Syntax:**

DEFTEMPPATH=&lt;path&gt;

**Example:**

Windows: DEFTEMPPATH=c:\img alt="redacted" data-bbox="385 578 548 592"/&gt;

Unix/OS400: DEFTEMPPATH=/home/user1/dpctrl/temp

***DETECTPREFIX*****Default**=No

Automatically detects one of the following command prefixes or suffixes in the data file:

- Prefix: "<"
- Suffix: ">"
- Prefix: "#"
- Prefix: "^"

**Syntax:**

DETECTPREFIX={YES|NO}

***DICTPREFIX*****Default**=: (colon)

Defines the dictionary prefix character. When declaring a variable that will be stored in the data dictionary, it is possible to indicate the dictionary by indicating its name (USER, GLOBAL, ...) plus a prefix. This prefix can be changed with this keyword.

**Syntax:**

DICTPREFIX=&lt;character&gt;

**Example:**

DICTPREFIX=:

In the above example, the dictionary name would be "global:" or "user:", etc.

*For detailed information on variables and dictionaries, please refer to [Chapter 7: Variables](#) and the [<DEC>](#) command explanation in [Chapter 5: Dynamic Form Control Commands](#).*

**DISCARDUNKNOWNFLD**

**Default=ON**

When set to ON, all [<FLD>](#) field commands with an unknown field name in the current subform will be ignored. When set to OFF, [<FLD>](#) commands with an unknown field name will not be ignored, but they will fill the next field with the associated data instead, in the order defined in the form design.

**NOTE:** When the DISCARDUNKNOWNFLD keyword is set to OFF, it will only be effective if the executed form does not contain any event code.

**Syntax:**

DISCARDUNKNOWNFLD={ON|OFF}

**Example:**

DISCARDUNKNOWNFLD=OFF

**EVENTFILENAME**

**Default=None**

Defines an alternate event file (with extension .evt) to that one from the [QFS](#) file.

**Syntax:**

EVENTFILENAME=<file\_name>

**Example:**

EVENTFILENAME=nameeventcode

*For more informaton, refer to the [-eventfile](#) operating option in [Chapter 8: Operating Options](#).*

**EVENTFILEPATH**

**Default=Current directory**

Defines the path where the event file is located.

**Syntax:**

EVENTFILEPATH=<path>

**Example:**

Eventfilepath=\*C:\Windows\Programfiles\eventcode

**FIELDSTRIP**

**Default=None**

Removes control characters (code points in a character set that does not in itself represent a written symbol) or blank spaces and tabs from the beginning and end of each data file field read. All control characters may be removed or just blank spaces and tabs, depending on the values of the [FIELDSTRIPMODE](#) keyword and the [-fieldstripmode](#) operating option.

**Syntax:**

FIELDSTRIP={N|L|T|B}

Possible values for this keyword are the following:

- **N** (None): No character will be removed from the data of each field.
- **L** (Lead): Only leading characters will be removed from the data of each field.
- **T** (Trail): Only trailing characters will be removed from the data of each field.
- **B** (Both): Leading and trailing characters will be removed from the data of each field.

Example:

```
FIELDSTRIP=N
```

### ***FIELDSTRIPMODE***

**Default=CONTROL**

Specifies if the [FIELDSTRIP](#) keyword will affect all control characters (characters below 0x20 in ASCII and below 0x40 in EBCDIC) or only blank spaces and tabs.

Syntax:

```
FIELDSTRIPMODE={S|SPACES|C|CONTROL}
```

Possible values for this keyword are the following:

- **S/SPACES**: The [FIELDSTRIP](#) keyword will affect only blank spaces and tabs.
- **C/CONTROL**: The [FIELDSTRIP](#) keyword will affect all control characters.

Example:

```
FIELDSTRIPMODE=SPACES
```

### ***FPPRINT INSTALLATION PATH***

**Default=No default**

Indicates the [DocPath](#) version 3.3) installation path. The installation path is used for correctly launching [DocPath](#) when form versions are prior to version 4.0 and the [DocPath](#) is configured for executing [DocPath](#) to process form versions prior to version 4.0.

Syntax:

```
FPPRINT INSTALLATION PATH=<directory_name>
```

Example:

```
Windows: FPPRINT INSTALLATION PATH=C: Program Files\DocPath\Controller3.3\
Unix/OS400: FPPRINT INSTALLATION PATH=/usr/local/DocPath/Controller3.3/
```

### ***FSTCMD CFGJOB***

**Deprecated.**

Sets the [LOADFIRSTPAGE](#) keyword value to AUTO.

### ***INLINEPREFIX***

**Default=\** (backslash)

Defines the inline text control command prefix character. Inline text control commands are characters that enable control over the appearance of data on the printed form including font type, font size, bold, underline, etc.

Syntax:

```
INLINEPREFIX=<character>
```

Example:

```
INLINEPREFIX=\
```

---

*For more information refer to [Chapter 6: Inline Text Control Commands](#).*

---

**INPUT CODE PAGE****Default**=858

For specifying the code page that was used to create the input data file.

**Syntax:**

```
INPUT CODE PAGE=<number>
```

**Example:**

```
INPUT CODE PAGE=1252
```

The example above indicates that the data file was created with the 1252 code page.

**NOTE:** On OS/400 systems this keyword will be ignored, since the system automatically detects the correct code page for input data files.

**JOB SUMMARY FILE****Default**=No default.

For specifying the file in which a summary line will be included for each processed job. The specified file will have a CSV (comma separated values) format and will contain the following information for each job at the end of the file:

- job name.
- start date and hour.
- end date and hour.
- number of pages.
- number of documents.
- job termination return code.

**Syntax:**

```
JOB SUMMARY FILE=<file_name>
```

**Example:**

```
JOB SUMMARY FILE=.\\job_summary.csv
```

**Example Job Summary File**

```
Job Name,Beginning Date,Beginning Time,Ending Date,Ending Time,Number of Pages,Number of
Documents,Status
"JOB1","20080825","09:40:54","20080825","09:44:26","1","1","0"
"JOB2","20080825","10:00:44","20080825","10:00:47","1","1","0"
...
```

**LAYERMACRO****Default** = 25,000

For specifying the index from which specific layer macros will start to be stored in the printer.

**IMPORTANT!** This keyword is only valid for specific output types (PCL and PostScript).

**NOTE: Macros** are command sequences which are recompiled in the QFS form file to represent the fixed background of forms and subforms when generating specific (PCL and PostScript) outputs. Macros are stored in the printer by **index** references (a positive numeric value). When a form contains layers, apart from the common macros, specific **layer macros** must be stored in the printer as well. Layer macros and common macros cannot overlap to avoid one macro type from overwriting another.

**Syntax:**

```
LAYERMACRO=<number>
```

**Example:**

```
LAYERMACRO=100
```

**LAYERNAME****Default**=First layer (main)

Defines the default layer. In multiple-layer forms, this entry allows you to determine the default layer. There are two ways to specify the default layer:

- Using the layer's logical name that is determined when a layer is created.
- Entering the layer number according to the order of the labels shown in the "Layer" tab in

**Syntax:**

LAYERNAME=&lt;string&gt;

**Example:**

LAYERNAME=English

In the above example, the name of the layer to be processed is "English".

**LOADFIRSTPAGE****Default**=Y

Determines if the will load the first page of the form automatically or not.

Possible values are:

- **Y (Yes):** the will automatically load the first page of the form before processing the data.
- **N (No):** the will not load any page before data processing. The data file must load the page explicitly, either by directly including the [<NPG>](#) command or by launching an event in which the [<NPG>](#) command is used.  
If a page needs to be loaded to enable the execution of a command, [<FLD>](#) for example, and the page has not been loaded previously, an error message will appear in the log and the form will not be executed.
- **A (Auto):** the will not load the first page of the form (as defined in the form design) automatically. As a result, a different page may be loaded instead via the data file or event code. However, as opposed to keyword value N(No) above, if a page needs to be loaded to enable the execution of a command, the first page of the form (as defined in the form design) will automatically be loaded and the execution will not be aborted.

**Syntax:**

LOADFIRSTPAGE={Y|N|A}

**Example:**

LOADFIRSTPAGE=Y

**LOG FILE****Default**=dpdocproc.log

Defines the path and name for the log file that will be generated by the

**Syntax:**

LOG FILE=&lt;path&gt;

**Example:**

Windows: LOG FILE=C:\Program Files\DocPath\Controller\dpdocproc.log

Unix - 0S/400: LOG FILE=/home/user1/dpctrl/dpdocproc.log

**LOG LEVEL****Default**= 10

Defines the log level. Messages will be filtered depending on their type.

**Syntax:**

LOG LEVEL=&lt;number&gt;

Where <number> may be:

- 0: only errors are recorded.
- 1: only errors and warnings are recorded.
- 10: only errors, warnings and informative messages are recorded.
- 100: all messages are recorded (errors, warnings, informative and trace/debug messages).

Example:

```
LOG LEVEL=1
```

### LOG MODE

**Default=FILE**

Defines the way in which [redacted] will send the messages to the log service.

Syntax:

```
LOG MODE={UDP|TCP|FILE}
```

Where:

- UDP: [redacted] will send the messages to the log service via the UDP protocol and will create a local log file.
- TCP: [redacted] will send the messages to the log service via the TCP protocol and will create a local log file.
- FILE: [redacted] will only create a local log file, no messages are sent to the log server.

### LOG PORT

**Default=514**

Defines the Log Port of the [redacted] Log Service.

Syntax:

```
LOG PORT=<port_number>
```

Example:

```
LOG PORT=1252
```

### LOG SERVER

**Default=No default** (by default, there is no log server).

Defines the log server where [redacted] Log Service is running. It is possible to specify the IP address or the name of the server to use.

Syntax:

```
LOG SERVER=<log_server>
```

Example:

```
LOG SERVER=DPLOGSERVICE
```

### LOGOPATH

**Default=No default.**

For specifying the full path for graphic files referenced in the data file.

Syntax:

```
LOGOPATH=<path>
```

Example:

Windows: LOGOPATH=c:\Program files [redacted] \logos

Unix/OS400: LOGOPATH=/home/user1/dpctrl/logos

**MODE****Default**=T (Tagged Mode)

Indicates the mode in which the [redacted] processes the input data.

**Syntax:**

MODE={T|F|V|C|O}

Available modes are:

- T: Tagged Mode
- F: Fixed Record Mode
- V: (Variable) Record Mode
- C: Overlay with Carriage Control Mode
- O: Overlay without Carriage Control Mode

**Example:**

MODE=T

*For information on these modes refer to [chapter 4](#) of this manual.***MONTH****Default**=English

Defines the months in 2 strings.

**Syntax:**

MONTH=&lt;string1&gt;,&lt;string2&gt;

The first string (<string1>) refers to each month in the abbreviated form. The second one (<string2>) refers to the same month completely spelled out. "String1" can be up to 12 characters and "String2" can be up to 28 characters.

**Example:**

Month=Nov,Novembre (French)

**IMPORTANT!** There must be 12 entries for both "String1" and "String2". Any less number of entries makes [redacted] automatically fills them with the months in **English** (the **default language**).

**MONTHOF****Default**=ofRefers to the format for date entries. This entry applies to [\\$Date](#) Variable Text command formats.**Syntax:**

MONTHOF=&lt;string&gt;

**Example:**

MONTHOF= 5/10/2008

In the example above, date will be shown as 5 of October, 2008.

**NEWFIELD****Default**=` (back accent mark)

Defines the character indicating the beginning of a new field (new field character). When the character defined as the new field character is encountered, the current field is ended and the [redacted] goes to the next field. The order in the field process when using the 'NextField' entry is defined in the form design.

**Syntax:**

NEWFIELD=&lt;character&gt;

**Example:**

NEWFIELD=`

## OVERLAYFONTNAME

**Default=Courier**

For specifying the font name to be used in forms generated in overlay mode. If a value is set for the OVERLAYFONTNAME keyword without setting a value for the [OVERLAYFONTSIZE](#) keyword, the [OVERLAYFONTSIZE](#) default value (10) will be used.

---

*For more information on [Overlay Mode](#), refer to [chapter 4](#) of this manual.*

---

There are three ways to set the font to be used in overlay mode (from major to minor priority):

- with the OVERLAYFONTNAME and [OVERLAYFONTSIZE](#) keywords.
- with the [OVRFONT](#) keyword.
- in the QFS file itself during the form design using the  "Select Overlay Font" option.

Thus, the OVERLAYFONTNAME keyword value will overwrite both the overlay mode font with the  "Select Overlay Font" option and the value set with the [OVRFONT](#) keyword.

---

**IMPORTANT!** The font specified with the OVERLAYFONTNAME keyword must be included in the corresponding QFS file.

---

### Syntax:

OVERLAYFONTNAME=<font\_name>

Where:

font\_name: the name of the font to be used in overlay mode.

### Example:

OVERLAYFONTNAME=Arial

## OVERLAYFONTSIZE

**Default=10**

For specifying the height of the font to be used in forms generated with overlay mode. If a value is set for the OVERLAYFONTSIZE keyword without setting a value for the [OVERLAYFONTNAME](#) keyword, the [OVERLAYFONTNAME](#) default value (Courier) will be used.

---

*For more information on [Overlay Mode](#), refer to [chapter 4](#) of this manual.*

---

There are three ways to set the font to be used in overlay mode (from major to minor priority):

- with the [OVERLAYFONTNAME](#) and OVERLAYFONTSIZE keywords.
- with the [OVRFONT](#) keyword.
- in the QFS file itself during the form design using the  "Select Overlay Font" option.

Thus, the OVERLAYFONTSIZE keyword value will overwrite both the overlay mode font with the  "Select Overlay Font" option and the value set with the [OVRFONT](#) keyword.

---

**IMPORTANT!** The font set with the OVERLAYFONTSIZE keyword must be included in the corresponding QFS file.

---

### Syntax:

OVERLAYFONTSIZE=<font\_size>

Where:

font\_size: the font size, in dots, to be used in overlay mode.

### Example:

OVERLAYFONTSIZE=12



### **OUTLOCATION**

Sets the location of the generated output.

**Syntax:**

OUTLOCATION=<path>

**NOTE:** The **OUTLOCATION** keyword is **deprecated**; it is considered obsolete, and its use is discouraged although the keyword is still supported by the current version of the software.

### **OVRFONT**

**Default=** The first font in the font table of the QFS file.

For specifying a font set to use in overlay mode. It will override the font set specified in the QFS form file.

**Syntax:**

OVRFONT=<number>

**Where:**

- number: is the number assigned to the font set to use.

**Example:**

OVRFONT=25

### **OVRIGNFF**

**Default=**No default

Ignores carriage returns when processing a file in overlay mode.

**Syntax:**

OVRIGNFF={YES|NO}

**Example:**

OVRIGNFF=YES

### **OVRLPI**

**Default=**6

Specifies number of lines per **inch** to print in "Overlay mode".

**Syntax:**

OVRLPI=<number>

**Example:**

OVRLPI=6

### **OVRNLIN**

**Default=**58

Specifies the number of lines per **page** to print in "Overlay mode".

**Syntax:**

OVRNLIN=<number>

**Example:**

OVRNLIN=45

### **OWNERPASSWORD**

**Default=**No default.

Defines the owner password to use with PDF documents. This keyword must be used to set permissions for modifying, saving, printing or copying documents, etc.

**Syntax:**

```
OWNERPASSWORD=<string>
```

**Example:**

```
OWNERPASSWORD=DocPath
```

**PERMISSIONS****Default=**No default.

Defines permissions for PDF and QMF documents. To change these permissions it is required to enter a value in OWNERPASSWORD.

**Syntax:**

```
PERMISSIONS=<string>
```

Possible values for this keyword are the following:

- **Print:** enables to print the document.
- **Change:** enables to make changes to the document different from adding or changing text notes and AcroForm fields.
- **Copy:** enables to copy text and graphics from the document.
- **Text:** enables to add and change text notes and AcroForm fields.

**Example:**

```
PERMISSIONS=Print, Change, Copy, Text
```

**PREAMBLE****Default=** No default.

Defines full path and name for the preamble file. The preamble file may be used to define the structures and variables declaration. If a preamble file is not used, leave this entry blank or remove the keyword from the INI file.

**Syntax:**

```
PREAMBLE=<full_path>
```

**Example:**

```
Windows: PREAMBLE=c:\Program Files\██████████\Preamble
Unix/OS400: PREAMBLE=/home/user1/dpctrl/preamble
```

**PRINTALLPAGES****Default=**OFF

For automatically printing form pages and subforms.

**Syntax:**

```
PRINTALLPAGES={OFF|ON}
```

Possible values are:

- **OFF:** No pages will be printed automatically. All pages and subforms to be printed must be loaded manually via the [<NPG>](#) and [<CPG>](#) commands.
- **ON:** After having processed the data file, the ██████████ will automatically print all pages and subforms that have not been manually loaded yet with the [<NPG>](#) and [<CPG>](#) commands. All pages and subforms will be loaded and printed in the order defined in the form design starting from the last page printed.

**Example:**

```
PRINTALLPAGES=ON
```

**NOTE:** By default, the **LOADFIRSTPAGE** keyword automatically loads the first page of a form before processing the data file. To modify this behavior, use the [LOADFIRSTPAGE](#) keyword or [-loadfirstpage](#) operating option.

---

### **PRINTUNKNOWNVARS**

**Default=NO**

For printing variables that have not been defined by a variable text.

**Syntax:**

PRINTUNKNOWNVARS={YES|NO}

Possible values are Y (yes) or N (no).

**Example:**

Sample text is @sampletext.

In the previous example the following can happen:

- In case the variable has not been previously defined and the PRINTUNKNOWNVARS keyword is set to yes, the variable will be printed as it is: *Sample text is @sampletext.*
- In case the variable has not been previously defined and this keyword is set to "no" the result will be as follows: *Sample text is.*

### **PROCESSINLINE**

**Default=N**

For defining whether or not "Inline Text Control commands" are processed. Possible values are Y (yes) or N (no). For detailed information on [Inline Commands](#), please refer to Chapter 6.

**Syntax:**

PROCESSINLINE={Y|N}

**Example:**

PROCESSINLINE=Y

### **PROCESSPICTURES**

**Default= Y**

Activates or deactivates mask processing. Possible values are Y (yes) or N (no).

**Syntax:**

PROCESSPICTURES={Y|N}

**Example:**

PROCESSPICTURES=N

### **PROCESSVARIABLES**

**Default=Y**

Defines variable substitution processing.

**Syntax:**

PROCESSVARIABLES={Y|N}

Possible values are Y (yes) or N (no).

---

**NOTE:** The difference between this keyword and [PRINTUNKNOWNVARS](#) is that the last one requires the PROCESSVARIABLES keyword activated.

---

**QFSPATH****Default**=Current forms path.

For indicating a list of paths where the compiled QFS forms are located. The keyword value will be used not only for the forms referenced in data but also for those referenced in the command line. The paths in the keyword value must be separated by a colon (;).

The [redacted] will search for forms in the directories indicated by the QFSPATH keyword. The directories will be scanned in the order in which they appear in the keyword value. Consequently, if forms of the same name appear in different directories, the first directory listed in the QFSPATH keyword in which the required form appears will be considered the correct directory and the form in that directory will be used for processing.

**Syntax:**

```
QFSPATH=<path1>[;<path2>;<path3>;...]
```

**Example:**

```
Windows: QFSPATH=c:\Program files\ [redacted] Designer\Forms;c:\forms
Unix/OS400: QFSPATH=home/user1/dpctrl/forms;/home/user1/forms
```

**RECSIZE****Default**=32768

Defines the maximum size of the buffer in which the records read from the file are stored when working in **Record Mode**. If the value entered is less than 64, it is assumed that the indicated value is expressed in kilobytes.

**Syntax:**

```
RECSIZE=<number>
```

**Example:**

```
RECSIZE=1024
```

**REFORMAT****Default**=Off

Changes the way in which the [redacted] formats field text for printing.

**Syntax:**

```
REFORMAT={ Y | YES | N | NO | O | OFF | F | FOLD | C | CLIP | T | TRUNC | OVERFLOW }
```

Possible values are:

- Y/YES
- N/NO
- O/OFF
- F/FOLD
- C/CLIP
- T/TRUNCATE
- OVERFLOW

*For further details concerning the previously mentioned options, refer to the equivalent ["NEWLINEMODE"](#) operating option.*

**Example:**

```
REFORMAT=T
```

The previous example sets the REFORMAT keyword to TRUNC. This way, data exceeding the boundaries of the field will be rejected.

### **RESERVEGLOBALS**

**Default=N**

The **RESERVEGLOBALS**, when using NEXTFIELD, reserves the fields declared as global fields in every new page required.

**Syntax:**

RESERVEGLOBALS=[Y|N]

**Example:**

RESERVEGLOBALS=Y

### **SOFTFONTPATH**

**Default=Current Directory**

Indicates full path for the "Soft Font" directory, used in the design.

**Syntax:**

SOFTFONTPATH=<file\_path>

**Example:**

Windows: SOFTFONTPATH=c:\DocPath\Designer\Forms

Unix/OS400: SOFTFONTPATH=/home/user1/dpctrl/forms

---

**NOTE:** The specified path in this entry overrides the predetermined "Soft Font" path in the QFS file, when SOFTFONTLOC=FILE entry is used.

---

### **TESTCHAR**

**Default="X" for text fields and "9" for numeric fields.**

For modifying the test character printed in form fields when the **TESTCHAR** is executed with the [-test](#) operating option.

**Syntax:**

TESTCHAR=<char>

**Where:**

- **char:** to be substituted by any printable character.

**Example:**

TESTCHAR=A

### **TPAGE SIZE**

**Default=1**

Specifies the space, in number of digits, that will occupy the content of the [\\$TPAGE](#) variable, mainly to calculate correct positioning of the variable within the text.

**Syntax:**

TPAGE SIZE=<number>

**Example:**

TPAGE SIZE=3

In the example above, the size of the \$TPAGE variable (which specifies the total number of pages) will be of three numeric characters. As a result, the variable value will be a numeric value of hundreds (a three-digit group).

### **USERPASSWORD**

**Default=No default.**

Specifies the user password needed for PDF documents when applying restrictions.

**Syntax:**

USERPASSWORD=<string>

---

**USE FPPRINT WITH OLD FORMS****Default=NO**

For specifying if [redacted] (version 3.3) must be launched for processing compiled QFS forms generated with a [redacted] version prior to version 4.0, or if the [redacted] must be executed instead. When the keyword value is set to "YES", the [redacted] will always launch [redacted] for processing form versions prior to version 4.0. When set to "NO", the [redacted] itself will process form versions prior to version 4.0.

**NOTE:** For the [redacted] to correctly execute [redacted] (version 3.3), the [FPPRINT INSTALLATION PATH](#) INI file keyword must be correctly configured.

**Syntax:**

```
USE FPPRINT WITH OLD FORMS={YES|NO}
```

**Example:**

```
USE FPPRINT WITH OLD FORMS=NO
```

**V3 EVENTS CODE PAGE****Default=858**

Modifies the expected code page of the event code in forms of version 3.3 and previous versions.

**Syntax:**

```
V3 EVENTS CODE PAGE=<code_page_number>
```

**Where:**

- code\_page\_number: the expected code page of the event code in forms of version 3.3 and previous versions.

**Example:**

```
V3 EVENTS CODE PAGE=1252
```

**VAR RECORD MODE DELIM****Default=double quotation mark (")**

For specifying the string delimiter character in variable record mode. A string delimiter character indicates the beginning and end of a character string in a record. The string delimiter character can be defined with an hexadecimal value of the "0xNN" type, "NN" being the hexadecimal character value.

**Syntax:**

```
VAR RECORD MODE DELIM=<character>
```

**Example:**

```
VAR RECORD MODE DELIM=#
```

**VAR RECORD MODE SEP****Default=a semicolon (;).**

For specifying the field separator character in variable record mode. A field separator character indicates that the current field has ended and that the data of the next field will be processed, except when the separator character is located between two string delimiter characters. The field separator character can be defined with an hexadecimal value of the "0xNN" type, "NN" being the hexadecimal character value.

**Syntax:**

```
VAR RECORD MODE SEP=<character>
```

**Example:**

```
VAR RECORD MODE SEP=,
```

**VARPREFIX****Default=** @ (“at” symbol)

Defines the Variable Substitution Prefix Character.

Syntax:

VARPREFIX=&lt;character&gt;

Example:

VARPREFIX=@

**WEEKDAY****Default=** English

Defines the language for the weekdays by means of 2 strings.

Syntax: WEEKDAY=&lt;string1&gt;,&lt;string2&gt;

Where:

- string1: refers to the abbreviated form of the weekday
- string2: refers to the same day completely spelled out. “String1” and “String2” can be up to 12 and 28 characters respectively.

Example:

```
(Spanish)
WEEKDAY=Dom,Domingo
WEEKDAY=Lun,Lunes
.....
WEEKDAY=Sab,Sabado
```

**IMPORTANT!** There must be 7 entries for each string. Any number less than 7 makes automatically fills them with the weekdays in English (“default language”).

**YEAR2000****Default=** 51

Sets the limit for considering the dates defined with just two digits as dates belonging to year 20xx or 19xx.

Syntax:

YEAR2000=&lt;number&gt;

Example:

YEAR2000=30

The example above indicates that when the user inserts a date using two digits between 31 and 99, this date will be considered as a year between 1931 and 1999. When the user inserts a date with two digits between 00 and 30, the date will be considered as a year between 2000 and 2030.

**Example**The example below is a sample *dpdocproc.ini* file.

```
[MAIN]
#
# MANAGEMENT OPTIONS
```

```
#
MODE=N
BUFFERSIZE=16
RECSIZE=1024
NUMBERINGBUF=20
MACRO=1,T
OFFSET=0.0,0.0
REFORMAT=F
QFSPATH=forms
DATAPATH=data
LOGOPATH=logos
MACROMEM=512
LOG LEVEL=10
PRTALLPAGES=Y
SETFIELDATTR=Y
PRINTUNKNOWNVARS=Y
PROCESSINLINE=Y
PROCESSPICTURES=Y
PROCESSVARIABLES=Y
SOFTFONTLOC=FILE
SOFTFONTPATH=sfont

#LOG FILE=dpdocproc.log
#LOG SERVER=logserver
#LOG PORT=1514
#LOG MODE=UDP
AUTOANCHOR=Y
AUTOOVERFLOW=N
FIELDSTRIP=None
CHECKENDPAGE=Y
#
# DELIMITER OPTIONS
#
SYMBOLLOCATION=L
NEWFIELD=`
ALTNEWLINE=~
CMDPREFIX=<
CMDSUFFIX=>
DICTPREFIX=:
INLINEPREFIX=\
VARPREFIX=@
#
# OVERLAY OPTIONS
#
```



```
OVRLIN=58
OVLPI=6
OVRFONT=1
#
# CALENDAR OPTIONS FOR ALTERNATIVE LANGUAGE
#
MONTH=Jan, January
MONTH=Feb, February
MONTH=Mar, March
MONTH=Apr, April
MONTH=May, May
MONTH=Jun, June
MONTH=Jul, July
MONTH=Aug, August
MONTH=Sep, September
MONTH=Oct, October
MONTH=Nov, November
MONTH=Dec, December
MONTHOF=of
WEEKDAY=Sun, Sunday
WEEKDAY=Mon, Monday
WEEKDAY=Tue, Tuesday
WEEKDAY=Wed, Wednesday
WEEKDAY=Thu, Thursday
WEEKDAY=Fri, Friday
WEEKDAY=Sat, Saturday

ACTIVATION CODE=EVALUATION
```