# End User Guide

Dynamics Queue Admin: the console a queue organization uses to register a loading place, check drivers in, dispatch vehicles, manage orders and shipper requests, bid on behalf of shippers, run reports, watch the real-time connection, and finish its security and settings tasks (dispatch-queue web console, v1.0.0)

| | |
|---|---|
| **Document** | **UG-1.0.0**: End User Guide (dispatch-queue console) |
| **Application** | Dynamics Queue Admin: dispatch-queue web console, product version **1.0.0** |
| **Intended reader** | Queue Organization Admin and Queue Dispatcher staff of a loading place (organization) on the Dynamics freight marketplace; platform administrators may also sign in for oversight |
| **Languages** | The console itself runs in English or Amharic (chosen on the sign-in screen or in Settings). This guide is written in English. |
| **Screenshots** | Marked **[Screenshot: …]** — insert captures of the named screen/state before final submission. |
| **Related documents** | Software Requirements Specification (SRS), Software Design Description (SDD), Technical Design / Low-Level Design (TDD/LLD), Security Documentation. |
| **Submitting entity** | Dynamics Transport |
| **Contact person** | Marew Masresha, General Manager, `mmarew@gmail.com`, `0983222221` |
| **Date of preparation** | 15 October 2026 |
| **Date of submission** | 15 October 2026 |

# Contents


| | |
|---|---|
| 1 | Introduction |
| 2 | Getting started |
| 3 | Signing in |
| 4 | Creating and registering a loading place |
| 5 | The dashboard |
| 6 | The live queue board |
| 7 | Check-in |
| 8 | Running the queue |
| 9 | Orders and shipper requests |
| 10 | Bidding on behalf of shippers |
| 11 | Reporting and analytics |
| 12 | Real-time notifications and connection status |
| 13 | Security compliance view |
| 14 | Settings |
| 15 | Language and appearance |
| 16 | Troubleshooting and FAQ |
| 17 | Glossary and support contacts |


**How to read this guide**

Each section takes one part of the console and walks you through it with numbered steps. Dashed boxes like **[Screenshot: …]** mark where a screenshot of the named screen should be inserted. On-screen labels are shown in the console's English wording; where the same feature is also known by another name, both are given (for example, the sidebar item labelled **Live Queue** is the queue board). The support contacts in §17 are those of Dynamics Transport.

# 1. Introduction

## 1.1 What this guide is for

This guide explains how to use **Dynamics Queue Admin**, the web console that a loading place uses to run its vehicle dispatch queue on the Dynamics freight marketplace. A loading place is a queue organization: a customs terminal, factory, cement yard, depot, mine, farm or port. You start by creating the loading place and signing in, then move on to checking drivers in, dispatching vehicles to orders, managing orders and shipper requests, bidding on behalf of shippers, reading reports, watching the live connection, using the security compliance view, and adjusting settings, language and appearance.

## 1.2 Who uses the console

Staff of a registered queue organization use the console for their day-to-day work. Two queue-staff roles cover that work; platform administrators can also sign in when they need to oversee things or approve an organization.

| Role | Role ID | What they do in the console |
|---|---|---|
| Queue Organization Admin | 11 | Owns the loading place: profile and members, queue operations, orders, bidding on behalf of shippers and reports. Can approve or suspend the organization (queue admins only). |
| Queue Dispatcher | 12 | Runs day-to-day queue operations: checks drivers in, dispatches vehicles, overrides and removes entries, and handles orders and shipper requests. Cannot open bidding on behalf of shippers. |
| Platform Admin / Super Admin | 3 / 6 | Signs in for oversight: reviews queue organizations, approves, suspends or rejects them, and views the same operational screens. |

## 1.3 What the console does

- Registers a loading place (queue organization) and its location as a queue gate.
- Checks drivers into the queue and assigns each one a queue position.
- Dispatches waiting vehicles to orders, with override and removal controls.
- Creates and manages orders and shipper requests for the loading place.
- Opens bidding on behalf of shippers and accepts a driver bid for the owning organization.
- Reports on drivers, waiting vehicles, orders and organizations.
- Tracks the live queue connection and shows real-time updates.

> **What the console does not do**
>
> This console is one piece of the Dynamics platform. It is not the driver mobile application and not the shipper application, it does not process payments, and it does not give you a live GPS feed. When something is missing or switched off, this guide says so instead of glossing over it. See §14 (settings that are not enabled) and §16 (troubleshooting).

### 1.4 Before you begin

- Your loading place must be registered, and approved by an administrator, before drivers can be dispatched.
- You need a supported modern browser (Chrome, Edge, Firefox or Safari).
- You need the mobile number registered to your account to receive a one-time code.
- To create an order you need the shipper's phone number, the cargo, the quantity in quintals, the vehicle type and the pickup and delivery places.

# 2. Getting started

## 2.1 The screen layout

Once you are signed in you get a left sidebar, a top bar and a main work area. The sidebar is where you navigate; it groups everything the organization can do. The exact wording of those sidebar items is listed below.

| Sidebar item | Area it opens | Covered in |
|---|---|---|
| Dashboard | Organization overview and the list of loading places you can access | §5 |
| Live Queue | The real-time queue board for a loading place | §6, §7, §8 |
| Orders | Orders and shipper requests, including bidding | §9, §10 |
| Organizations | Manage a loading place: profile, members and approval | §4 |
| Reports | Summary metrics and the organization report list | §11 |
| Security | INSA security compliance view | §13 |
| Settings | Account, language and appearance | §14, §15 |

**[Screenshot: Dashboard shell — left sidebar with Dashboard, Live Queue, Orders, Organizations, Reports, Security and Settings, top bar, and an empty main work area]**

## 2.2 The top bar

- **Organization selector**: switches which loading place the queue board and orders apply to.
- **Language selector**: switches the interface between English and Amharic (§15).
- **Profile / Menu**: opens your account area and the sign-out action (§14).

## 2.3 Your first run-through

1. Open the console in your browser and sign in with your phone number and one-time code (§3).
2. If you have not yet created the loading place, complete **Setup Organization** (§4).
3. Open **Live Queue** and confirm the organization is selected (§6).
4. Check drivers in as they arrive at the gate (§7).
5. Dispatch waiting vehicles to orders, or create a new order first (§8, §9).

> **On a narrow screen**
>
> The console is built desktop-first, but it adapts. Shrink the window and the sidebar collapses into a menu button, the queue board turns into cards, and panels stack on top of each other. Every action described in this guide works the same way at any screen size.

# 3. Signing in

You get in with your phone number and the one-time code (OTP) sent to it. There is no password and no role picker: your role belongs to your account, so access stays tied to the number registered to your organization.

### 3.1 Enter your phone number

1. Open the console. The sign-in screen appears.
2. Enter your Ethiopian mobile number. The console validates the international format `+251` followed by nine digits.
3. Select **Sending OTP** / **Send OTP** to request the code.

**[Screenshot: Login screen — phone number field with the +251 country code and a partially entered number, with the Send OTP button]**

### 3.2 Enter the one-time code

1. A screen asks for the six-digit verification code sent to your phone.
2. Type the six digits. The code boxes accept digits only, move focus forward as you type, and move back when you press backspace. You can also paste the whole code and it is distributed across the boxes.
3. When the sixth digit is entered the code is submitted automatically and you are signed in.
4. If the code does not arrive, wait for the resend countdown to finish (60 seconds), then choose **Resend OTP**.
5. To change the number you started with, use the back arrow.

**[Screenshot: OTP verification screen — six digit boxes with a code entered, the resend countdown, and the Verify button]**

| Field / control | Rule |
|---|---|
| Phone number | Required. Ethiopian international format: `+251` plus 9 digits. |
| Verification code | Required. Exactly 6 digits. Submitted automatically when the sixth digit is entered. |
| Resend OTP | Available after the 60-second countdown expires; sends a fresh code to the same number. |

### 3.3 Sessions and signing out

- Sign-in establishes a secure, HTTP-only session cookie. No access token is stored in or exposed to the browser's JavaScript, and there is no separate refresh step.
- Session lifetime depends on the role: platform administrators (roles 3 and 6) are signed out after **24 hours**; queue staff (roles 11 and 12) remain signed in for up to **365 days**.
- If your session ends, you are returned to the sign-in screen and must request a new code.
- To sign out, open your account area or go to **Settings** → **Sign Out** (§14).

| Role | Session lifetime |
| --- | --- |
| Queue Organization Admin (11), Queue Dispatcher (12) | 365 days |
| Platform Admin (3), Super Admin (6) | 24 hours |

**Keep your number current**

The code goes to the mobile number on your account. If you change that number, you will not be able to sign in until the account has been updated to match.

# 4. Creating and registering a loading place

A loading place is a *queue organization*: the site whose vehicle queue you manage. Create one before you touch the queue board, and get an administrator to approve it before any driver can be dispatched.

### 4.1 Create the organization

1. On first sign-in, if your account has no organization yet, the console opens the **Setup Organization** screen (also shown as a **Create Organization** dialog from the dashboard).
2. Enter the organization name (for example, "Addis Freight Terminal").
3. Choose the organization type from the list below.
4. Optionally enter a contact phone number for the loading place.
5. Enter the address and select the matching suggestion from the address search. Selecting a suggestion records the location's latitude and longitude, and that is the site reference the queue uses as well as the check-in gate.
6. Select **Create Organization**. A new organization starts in **pending** approval status.

**[Screenshot: Setup Organization screen — name, type, phone, and address search with a selected suggestion showing the resolved location]**

| Field | Required | Notes |
|---|---|---|
| Organization name | Yes | The display name used across the console. |
| Organization type | Yes | One of the types listed in §4.2. |
| Contact phone | No | Ethiopian format, `+251` plus digits. |
| Address (with location) | Yes | Chosen from the address search; the selected suggestion supplies the latitude and longitude that define the site location. |

### 4.2 Organization types

You can pick one of the following loading-place types.

| Type (label) | Type (stored value) |
|---|---|
| Customs | `customs` |
| Factory | `factory` |
| Cement | `cement` |
| Depot | `depot` |
| Mine | `mine` |
| Farm | `farm` |
| Port | `port` |
| Other | `other` |

> **Check-in radius**
>
> The check-in gate works from a radius around the organization's location. That radius is a platform setting, not something you type on the create-organization form, and it defaults to **15 km**. If your operation needs a different radius, ask the platform administrator to change it.

### 4.3 Approval statuses

Every organization carries an approval status. You will see it as a badge on the manage page and in the organization list.

| Status | Meaning |
|---|---|
| Pending | Newly created; awaiting administrator review. The queue is not enabled. |
| Approved | The organization is enabled and its queue is live. |
| Rejected | The application was declined by an administrator. |
| Suspended | An approved organization whose queue has been disabled by an administrator. |

### 4.4 Managing a loading place

Open **Organizations** and pick a loading place to get to its manage page. You get the organization profile, the member list and, if you are a queue administrator, the approval controls.

- **Profile**: update name, type, phone and address/location. Saving a new address updates the site location.
- **Members**: add a member by user identifier and role, then deactivate, reactivate or remove them. Membership itself is the permission, so a lifecycle change takes effect on the member's next request.
- **Approval (queue administrators only)**: **Approve**, **Suspend** or **Reject** the organization. Approving turns the queue on; suspending or rejecting turns it off.

**[Screenshot: Manage Organization page — profile form, members table, and the approval actions available to a queue administrator]**

> **Approval is required before dispatch**
>
> No driver can be dispatched until the organization's status reads **Approved**. While it is pending, rejected or suspended, treat the queue board as preparation only.

# 5. The dashboard

The dashboard is the first screen you land on after sign-in. Pick the loading place you want to work in from here, and read your organization's summary figures off the same page.

### 5.1 The organization overview

- **Organization cards**: each loading place you can access appears with its type, name and approval badge. Select one to open its live queue.
- **Create organization**: opens the same create dialog described in §4, for accounts that can add another loading place.
- **Summary figures**: the overview shows the organization's operating figures, including drivers, waiting vehicles and orders.

**[Screenshot: Dashboard — organization list with approval badges and the overview summary figures]**

> **Where the dashboard figures come from**
>
> The dashboard and Reports build their summary figures in the console from whatever data has loaded. They are good enough for watching the day as it runs, but treat them as working numbers rather than an audited record. See §11.

# 6. The live queue board

The live queue board (**Live Queue**) is where the day's work actually happens. It lists the vehicles sitting in the queue for the selected loading place, grouped by vehicle type, and gives you the controls to check drivers in and dispatch them.

### 6.1 The board header

- **Live / Connecting badge**: a coloured badge next to the title tells you whether the real-time connection is live. See §12.
- **New Order**: opens the create-order dialog (§9).
- **Manual Check-in**: opens the check-in dialog to add a driver to the queue (§7).

### 6.2 Vehicle-type cards

You get one card per vehicle type that has drivers in the queue, plus a card for all drivers. Each vehicle-type card shows the number of waiting vehicles and a **Dispatch** button.

- **Dispatch** is enabled only when there is at least one waiting vehicle for that type. When the waiting count is zero the button is disabled.
- The **All Drivers** card lists every driver in the queue regardless of vehicle type.
- Select a card to open the queue table for that vehicle type.

**[Screenshot: Live queue board — vehicle-type cards with waiting counts and Dispatch buttons, plus the All Drivers card and the Live badge]**

### 6.3 The queue table

Each driver in the queue appears in the table with the position they were given. On a narrow screen the table turns into stacked cards carrying the same information.

| Column | Shows |
|---|---|
| Positions | The driver's place in the queue (FIFO position). |
| Driver | The driver's name. |
| Phone | The driver's phone number. |
| Address | The driver's last known address/place. |
| Shipper Name / Phone | The shipper associated with the driver's order, if any. |
| Joined | When the driver joined the queue. |
| Status | The driver's current queue status (see §8.4). |
| Action | Row actions such as dispatch, override, remove and history. |

# 7. Check-in

Check-in is how a driver gets into the queue. On the queue board, select **Manual Check-in** to open the dialog.

### 7.1 Checking a driver in

1. On the live queue board, select **Manual Check-in**.
2. Search for the driver. The search covers the driver directory and the current queue, and matches on the details shown for each driver (such as name and phone).
3. Select the driver from the results.
4. Leave the queue number blank and the driver goes to the end of the queue under the usual first-in, first-out (FIFO) rule. Type a number only when you want them placed at a specific position.
5. Confirm the check-in. The driver appears on the queue board with their position.

**[Screenshot: Check-in dialog — driver search results, the selected driver, and the optional queue number field]**

> **Positions and the optional queue number**
>
> Leave the queue number empty and the platform hands out the next FIFO position. Only type a number when you deliberately want a driver at a particular spot. If you get it wrong, the override action (§8.3) is there to fix the position later.

# 8. Running the queue

Here is the routine work on the queue board: dispatching, overriding a position, removing an entry, and looking back at an entry's history.

### 8.1 Dispatching a vehicle

1. On the queue board, find the vehicle-type card with waiting drivers.
2. Select **Dispatch** (enabled only when at least one vehicle is waiting).
3. In the dispatch dialog, choose the order to dispatch the front waiting vehicle to. The dialog shows a summary of the shipper request for the selected order.
4. Confirm. The vehicle is dispatched and its status updates to match.

**[Screenshot: Dispatch dialog — order selection and the shipper-request summary for the chosen order]**

### 8.2 Dispatch is tied to waiting vehicles

When a vehicle-type card shows a waiting count of zero, its **Dispatch** button is greyed out. Check a driver in first (§7), or move to a different vehicle-type card that still has waiting vehicles.

### 8.3 Overriding a position

1. Open the row action for the driver and choose **Override**.
2. Enter the new queue number and a reason for the change.
3. Confirm. The driver moves to the new position and the change is recorded.

**[Screenshot: Override dialog — new queue number and reason field]**

### 8.4 Removing an entry

1. Open the row action for the driver and choose **Remove**.
2. Enter a reason when prompted and confirm.
3. The driver is removed from the queue, and the reason goes to the affected party over the live connection.

> **Removal reasons**
>
> Whatever you type as the reason is broadcast to the queue's live listeners. Keep it clear and factual so the driver's app shows an accurate explanation.

### 8.5 Entry history

Every queue entry keeps a history you cannot edit. Open the row action and choose **History** to see the recorded before-and-after snapshots for the entry, such as its original position and any override applied later.

**[Screenshot: Entry history dialog — before/after snapshots for a queue entry]**

### 8.6 Queue statuses

| Status | Meaning |
|---|---|
| Waiting | In the queue, waiting for dispatch. |
| Offered | An order has been offered to the driver. |
| Loaded | The vehicle has been loaded. |
| Removed | The entry was removed from the queue. |
| Completed | The vehicle's job is complete. |

# 9. Orders and shipper requests

The **Orders** area holds the orders and shipper requests for your loading place. This is where you create new orders and check driver requests against a shipper's request.

### 9.1 Creating an order

1. On the queue board select **New Order**, or use the create action in the Orders area.
2. Choose the **Request Type**: *individual target* (a specific vehicle slot) or *company target* (open to carriers).
3. Choose the **Dispatch Mode**: **FIFO Queue** (auto-offer to the front waiting driver) or **Open for Bidding** (a biddable job for carriers).
4. Enter the shipper's phone number and choose the vehicle type.
5. Enter the cargo details: item, quantity in quintals, cost, number of vehicles, and the shipping and delivery dates. Quantity per vehicle cannot exceed the selected vehicle type's carrying capacity.
6. Enter the origin and destination by searching the address field and selecting the matching suggestion, which records the coordinates for each place. The origin defaults to the loading place's location.
7. Select **Create Order**. The order is created and offered to the queue.

| Field | Notes |
|---|---|
| Request Type | Individual target or company target. |
| Dispatch Mode | FIFO Queue, or Open for Bidding (see §10). |
| Shipper phone | Ethiopian format, `+251` plus digits. |
| Vehicle type | Selects the queue lane the order is dispatched on. |
| Cargo and quantity | Capped by the selected vehicle type's capacity. |
| Cost and dates | Shipping and delivery dates; the shipping date cannot be in the past. |
| Origin / destination | Address search records place names and coordinates. |

**[Screenshot: Create Order dialog — request type, dispatch mode, shipper, vehicle type, cargo, and origin/destination with map coordinates]**

> **Large orders default to company target and bidding**
>
> When the number of vehicles for an individual order is set above nine, the console switches the request to a company target and turns on open bidding by itself. That is deliberate: volumes that big are offered to carriers rather than a single queue slot.

### 9.2 The orders list

Every order appears with its identifier, shipper, vehicle type, cargo, route, quantity and cost. Orders spanning several vehicles are grouped into a single batch row that summarises the vehicles and their journey stages; expand it to see each vehicle.

- **Journey stage**: each order shows its current stage (for example, accepted, loading, in transit, completed). See §17 for the journey-status glossary.
- **Bidding indicator**: orders that are open for bidding are marked as such.

**[Screenshot: Orders list — an expanded multi-vehicle batch row showing individual vehicles and their journey stages]**

### 9.3 Shipper requests and driver acceptance

1. Open a shipper's request to see its overview (cargo, route, dates and status).
2. If there are driver requests against it, each is listed with the driver's details and offer.
3. Select **Accept** on a driver request to accept that driver for the shipper request. Repeat for other drivers as needed.
4. Use **View All Orders** to open the full orders list filtered to that shipper.

**[Screenshot: Shipper requests dialog — request overview and the list of driver requests with Accept actions]**

# 10. Bidding on behalf of shippers

Once an order is open for bidding, carriers and drivers start sending offers. You review those offers on the shipper's behalf and accept the driver you judge best for the job.

### 10.1 Who can open bidding

> **Bidding is restricted**
>
> Only the **Queue Organization Admin** (role 11) gets the bidding control, and only for an order belonging to their own organization. The **Super Admin** (role 6) gets it too. A **Queue Dispatcher** (role 12) never sees the control, and the platform refuses the action if one is attempted. Dispatchers can still run the queue and orders; they just cannot open bidding on a shipper's behalf.

### 10.2 Opening an order for bidding

1. In the Orders area, select the order you want to open for bidding.
2. Use the bid toggle to turn bidding on for that order.
3. The toggle itself is per order: an order either has bidding approved or not. Turning it on publishes the order as a biddable job for carriers.

### 10.3 Reviewing offers and accepting a driver

1. Open the order's driver bids.
2. Use the toolbar to **search** by driver name, phone or plate, choose a **sort** order, and set a **display limit**.
3. Compare the offers. Each one shows the driver's details, their offer and, where it is available, distance and vehicle information.
4. Select **Accept** on the offer you want. The console accepts that specific driver's bid.

| Sort option | Orders offers by |
|---|---|
| Nearest Distance First | Closest driver to the pickup. |
| Lowest Offer First | Lowest offer amount. |
| Highest Offer First | Highest offer amount. |
| Driver Name (A–Z) | Driver name, alphabetically. |
| Default Order | The platform's default ordering. |

**[Screenshot: Driver bids board — toolbar with search, sort and display limit, and the list of driver offers with Accept actions]**

### 10.4 Bid statuses

| Status | Meaning |
| --- | --- |
| Selected | The bid was accepted for the order. |
| Not selected | The bid was reviewed but not accepted. |
| Withdrawn | The driver withdrew the bid before a decision. |
| Expired | The bid is no longer actionable. |

> **Accepting requires the exact bid**
>
> The console accepts a bid only when it can pin down the exact driver and decision from the bid list it has loaded. When it cannot, you get a clear error instead of a guess about which driver to take. Reload the bids and try again if that happens.

# 11. Reporting and analytics

The **Reports** area sums up activity for the loading place with a few key figures, a couple of simple charts, and a list of organizations you can search.

### 11.1 Key figures

| KPI card | Shows |
|---|---|
| Total Driver | The number of drivers known to the organization. |
| Waiting Now | The number of vehicles currently waiting in the queue. |
| Orders Now | The number of active orders. |
| Total Organizations | The number of loading places in the report scope. |

### 11.2 Charts and the organization list

- **Donut chart**: a proportional view of the current distribution (for example, waiting by category).
- **Monthly bar chart**: activity over recent months.
- **Organization report list**: a list of organizations with search, sortable columns and pagination (five rows per page).

**[Screenshot: Reports page — KPI cards, the donut and monthly bar charts, and the organization report list]**

> **How the figures are produced**
>
> This page works out its figures and charts in the console from the data it has loaded; there is no separate analytics service behind them. That makes them useful for operational monitoring. A built-in PDF export of these reports is not confirmed, so use your browser's print function if you need a printable copy, and keep treating the figures as working values.

# 12. Real-time notifications and connection status

The console holds a live connection to the platform, so queue changes such as check-ins, dispatches, removals, bids and organization updates show up without you refreshing the page.

### 12.1 The live connection

- The queue board shows a **Live** badge when the real-time connection is open, and a **Connecting** badge while it is re-establishing.
- Queue staff (roles 11 and 12) receive queue events through a shared queue-organization channel, so both administrators and dispatchers see the same live updates.
- When the connection drops, the console shows a disconnected state and automatically retries. It makes up to **five** reconnection attempts with a short delay between them (starting at about 1.5 seconds and backing off up to about 5 seconds).
- If the retry delivers the underlying data again, the board returns to **Live** and refreshes the affected lists.

**[Screenshot: Live queue board showing the Connecting / disconnected state and the returning Live badge]**

### 12.2 What triggers a live update

- A driver checking in or being removed from the queue.
- A vehicle being dispatched or its position overridden.
- An order or shipper request changing, or a bid being placed or accepted.
- An organization being approved, updated or its members changing.

> **If the badge stays on Connecting**
>
> Check your network and reload the page. If your session has expired, the console closes the connection on purpose and signs you out; sign in again with a one-time code (§3). See §16 for more.

# 13. Security compliance view

The **Security** area shows the console's INSA security compliance information. Think of it as a reference and tracking view: opening it does not change how secure the running system is.

### 13.1 The tabs

| Tab | Shows |
|---|---|
| Overview | A summary of the compliance position and counts. |
| Requirements | The INSA requirements grouped by the five focus areas. |
| Vulnerabilities | The tracked vulnerabilities and their status. |
| Testing | The security test checklist with pass/fail tracking. |

### 13.2 Tabs, requirements and testing

- The standard is organised into five focus areas (numbered 2.1 to 2.5). Each one comes with a set of requirements and tests, plus a set of tracked vulnerabilities.
- In the **Testing** tab you can mark each test as passed or failed. The counts and progress shown on the page are computed from those marks.

> **Where test tracking is stored**
>
> Pass/fail marks you record in the Testing tab are saved in this browser's local storage. They survive reloads on that same browser and device, but they are not shared with other users, browsers or devices. Selecting a test's active status again clears it, and a test with no mark reads as untested. Treat the marks as your own working checklist for this submission.

**[Screenshot: Security compliance view — the Testing tab with pass/fail controls and the computed progress summary]**

# 14. Settings

**Settings** is where you handle your account, language and appearance for the console.

### 14.1 What you can change

- **Language**: switch the interface between English and Amharic (§15).
- **Appearance**: switch between light and dark theme (§15).
- **Sign Out**: end your session and return to the sign-in screen.

### 14.2 Account options that are not enabled

> **Disabled in this release**
>
> Profile editing, notification preferences and two-factor authentication do appear in the account area, but they are **not enabled** in this release and each carries an explanatory label. Nothing sits behind them on the server, so no change you make there is ever saved. Do not rely on them to update your account; ask the platform administrator instead.

### 14.3 Danger zone

The danger zone holds an account-deletion action behind a confirmation dialog. It removes the whole account, so reach for it only when you genuinely want the account gone.

**[Screenshot: Settings page — language and appearance controls, Sign Out, the disabled account options with their explanatory labels, and the danger zone]**

# 15. Language and appearance

## 15.1 Language

- The console runs in **English** or **Amharic**. Pick your language on the sign-in screen or in **Settings**.
- Your choice is saved in the browser and applied the next time you open the console on that same browser and device.

## 15.2 Appearance

- There is a **light** and a **dark** theme. The theme control lives in **Settings**.
- Your theme choice is saved in the browser and applied the next time you visit on that same browser and device.

**[Screenshot: The console in dark theme with the Amharic interface selected]**

> **Saved per browser**
>
> Language and theme choices are kept in the browser, so they belong to that browser and device. They do not follow your account to another one.

# 16. Troubleshooting and FAQ

## 16.1 Common situations

| Symptom | What to do |
|---|---|
| I did not receive the one-time code. | Wait for the 60-second countdown and select **Resend OTP**. Confirm the number is correct for your account. |
| I am signed out unexpectedly. | Administrator sessions last 24 hours. Sign in again with a fresh code; queue staff sessions last much longer. |
| The Dispatch button will not activate. | That vehicle-type card has no waiting vehicles. Check a driver in (§7) or choose a card with waiting vehicles. |
| I cannot find the bidding control. | Bidding is only available to the queue administrator (and Super Admin) for their own organization; dispatchers do not see it (§10.1). |
| The Live badge stays on Connecting. | Check your network, then reload. If your session expired you will be returned to the sign-in screen (§12). |
| My theme or language reset. | These are saved per browser and device; they do not follow your account. Set them again in Settings (§15). |
| My profile or notification changes do not save. | Those options are disabled in this release and have no server endpoint (§14.2). |
| The reports figures look different from another screen. | The console works these figures out from whatever data it has loaded, so treat them as working values (§11). Refresh to pull the latest data. |

## 16.2 Frequently asked questions

- **Can I sign in with a username and password?** No. Access is by phone number and one-time code only.
- **Can a dispatcher open bidding?** No. Only the queue administrator for the owning organization (and the Super Admin) can.
- **Where is my check-in radius set?** It is a platform setting (default 15 km), not a field on the organization form (§4).
- **Are the security checklist marks shared with my team?** No. They are stored in your browser only (§13).

# 17. Glossary and support contacts

## 17.1 Glossary

| Term | Meaning |
|---|---|
| Loading place / Queue organization | The site whose vehicle queue this console manages (for example, a customs terminal, factory, depot, mine, farm or port). |
| Queue Organization Admin | Role 11: owns the loading place and can approve/suspend it. |
| Queue Dispatcher | Role 12: runs the queue but cannot manage bidding. |
| Check-in | Adding a driver to the queue and assigning a position. |
| FIFO | First-in, first-out: the default order in which waiting vehicles are dispatched. |
| Dispatch | Sending the front waiting vehicle of a vehicle type to an order. |
| Override | Deliberately changing a driver's queue position. |
| Shipper request | A shipper's request for carriage, which queue staff can accept drivers against. |
| Bidding | Carriers offering on an order; queue staff accept the chosen offer. |
| Offer / Bid | A carrier's proposal (price and details) for a biddable order. |
| OTP | The six-digit one-time code sent to your phone to sign in. |
| Journey status | The stage of a dispatched vehicle's job, from accepted through loading, in transit and completed. |

## 17.2 Support contacts

| Channel | Detail |
|---|---|
| Support email | `mmarew@gmail.com` |
| Support telephone | `0983222221` |
| Support hours | Monday–Friday, 09:00–17:00 (East Africa Time); messages outside these hours are answered the next working day |
| Escalation / account issues | Marew Masresha, General Manager, Dynamics Transport, `mmarew@gmail.com`, `0983222221` |

# Document control

This End User Guide (**UG-1.0.0**) covers Dynamics Queue Admin version **1.0.0** as it is built in the submitted release. It goes out together with the Software Requirements Specification (SRS), the Software Design Description (SDD), the Technical Design / Low-Level Design (TDD/LLD) and the Security Documentation.

| Item | Value |
|---|---|
| Document identifier | UG-1.0.0: End User Guide (dispatch-queue console) |
| Product and version | Dynamics Queue Admin web console, v1.0.0 |
| Coverage | Loading-place registration, dashboard, live queue board, check-in, dispatch and queue running, orders and shipper requests, bidding on behalf of shippers, reports, real-time connection, security compliance view, settings, language and appearance |
| Related documents | SRS, SDD, TDD/LLD, Security Documentation |
| Items to complete before submission | Screenshots marked **[Screenshot: …]** must be captured and inserted. Submitting entity, contact person, support contacts, escalation contact and dates are completed. |
| Revision | 1.0.0, initial issue |