End User Guide

Dynamics Queue Admin — how a queue organization registers a loading place, checks drivers in, dispatches vehicles, manages orders and shipper requests, bids on behalf of shippers, runs reports, tracks the real-time connection and completes security and settings tasks (dispatch-queue web console, v1.0.0)

Document	**UG-1.0.0** — End User Guide (dispatch-queue console)
Application	Dynamics Queue Admin — dispatch-queue web console, product version **1.0.0**
Intended reader	Queue Organization Admin and Queue Dispatcher staff of a loading place (organization) on the Dynamics freight marketplace; platform administrators may also sign in for oversight
Languages	The console itself runs in English or Amharic (chosen on the sign-in screen or in Settings). This guide is written in English.
Screenshots	Marked **[Screenshot: …]** — insert captures of the named screen/state before final submission.
Related documents	Software Requirements Specification (SRS), Software Design Description (SDD), Technical Design / Low-Level Design (TDD/LLD), Security Documentation.
Submitting entity	Dynamics Transport
Contact person	Marew Masresha, General Manager — `mmarew@gmail.com`, `0983222221`
Date of preparation	15 October 2026
Date of submission	15 October 2026

Contents

1	Introduction
2	Getting started
3	Signing in
4	Creating and registering a loading place
5	The dashboard
6	The live queue board
7	Check-in
8	Running the queue
9	Orders and shipper requests
10	Bidding on behalf of shippers
11	Reporting and analytics
12	Real-time notifications and connection status
13	Security compliance view
14	Settings
15	Language and appearance
16	Troubleshooting and FAQ
17	Glossary and support contacts

How to read this guide

Each section covers one area of the console and uses numbered, step-by-step instructions in the second person. Dashed boxes like **[Screenshot: …]** mark where a screenshot of the named screen should be inserted. On-screen labels are shown in the console's English wording; where the same feature is also known by another name, both are given (for example, the sidebar item labelled **Live Queue** is the queue board). The support contacts in §17 are those of Dynamics Transport.

1. Introduction

1.1 What this guide is for

This guide explains how to use **Dynamics Queue Admin**, the web console that a loading place — a queue organization such as a customs terminal, factory, cement yard, depot, mine, farm or port — uses to run its vehicle dispatch queue on the Dynamics freight marketplace. It takes you from creating the loading place and signing in, through checking drivers in, dispatching vehicles to orders, managing orders and shipper requests, bidding on behalf of shippers, reading reports, watching the live connection, using the security compliance view, and adjusting settings, language and appearance.

1.2 Who uses the console

The console is used by staff of a registered queue organization. Two queue-staff roles are defined for day-to-day work; platform administrators may also sign in for oversight and approval.

Role	Role ID	What they do in the console
Queue Organization Admin	11	Owns the loading place: profile and members, queue operations, orders, bidding on behalf of shippers and reports. Can approve or suspend the organization (queue admins only).
Queue Dispatcher	12	Runs day-to-day queue operations: checks drivers in, dispatches vehicles, overrides and removes entries, and handles orders and shipper requests. Cannot open bidding on behalf of shippers.
Platform Admin / Super Admin	3 / 6	Signs in for oversight: reviews queue organizations, approves, suspends or rejects them, and views the same operational screens.

1.3 What the console does

- Registers a loading place (queue organization) and its location as a queue gate.
- Checks drivers into the queue and assigns each one a queue position.
- Dispatches waiting vehicles to orders, with override and removal controls.
- Creates and manages orders and shipper requests for the loading place.
- Opens bidding on behalf of shippers and accepts a driver bid for the owning organization.
- Reports on drivers, waiting vehicles, orders and organizations.
- Tracks the live queue connection and shows real-time updates.

> **What the console does not do**
>
> This console is one part of the Dynamics platform. It is not the driver mobile application or the shipper application, it does not process payments, and it does not provide a live GPS feed. Where a capability is absent or disabled, this guide says so plainly. See §14 (settings that are not enabled) and §16 (troubleshooting).

1.4 Before you begin

- Your loading place must be registered, and approved by an administrator, before drivers can be dispatched.
- You need a supported modern browser (Chrome, Edge, Firefox or Safari).
- You need the mobile number registered to your account to receive a one-time code.
- To create an order you need the shipper's phone number, the cargo, the quantity in quintals, the vehicle type and the pickup and delivery places.

2. Getting started

2.1 The screen layout

After you sign in, the console presents a persistent left sidebar, a top bar and a main work area. The sidebar is your primary navigation and groups everything the organization can do. The exact sidebar wording is listed below.

Sidebar item	Area it opens	Covered in
Dashboard	Organization overview and the list of loading places you can access	§5
Live Queue	The real-time queue board for a loading place	§6, §7, §8
Orders	Orders and shipper requests, including bidding	§9, §10
Organizations	Manage a loading place: profile, members and approval	§4
Reports	Summary metrics and the organization report list	§11
Security	INSA security compliance view	§13
Settings	Account, language and appearance	§14, §15

[Screenshot: Dashboard shell — left sidebar with Dashboard, Live Queue, Orders, Organizations, Reports, Security and Settings, top bar, and an empty main work area]

2.2 The top bar

- **Organization selector** — switches which loading place the queue board and orders apply to.
- **Language selector** — switches the interface between English and Amharic (§15).
- **Profile / Menu** — opens your account area and the sign-out action (§14).

2.3 Your first run-through

1. Open the console in your browser and sign in with your phone number and one-time code (§3).
2. If you have not yet created the loading place, complete **Setup Organization** (§4).
3. Open **Live Queue** and confirm the organization is selected (§6).
4. Check drivers in as they arrive at the gate (§7).
5. Dispatch waiting vehicles to orders, or create a new order first (§8, §9).

> **Responsive by design**
>
> The console is desktop-first but responsive. On a narrow window the sidebar collapses to a menu button, the queue board switches to cards, and panels stack vertically. All actions described in this guide are the same on any screen size.

3. Signing in

Access to the console is by phone number and a one-time code (OTP) sent to that phone. There is no password and no role selection — the role is a property of your account. This keeps access tied to the number registered to your organization.

3.1 Enter your phone number

1. Open the console. The sign-in screen appears.
2. Enter your Ethiopian mobile number. The console validates the international format `+251` followed by nine digits.
3. Select **Sending OTP** / **Send OTP** to request the code.

[Screenshot: Login screen — phone number field with the +251 country code and a partially entered number, with the Send OTP button]

3.2 Enter the one-time code

1. A screen asks for the six-digit verification code sent to your phone.
2. Type the six digits. The code boxes accept digits only, move focus forward as you type, and move back when you press backspace. You can also paste the whole code and it is distributed across the boxes.
3. When the sixth digit is entered the code is submitted automatically and you are signed in.
4. If the code does not arrive, wait for the resend countdown to finish (60 seconds), then choose **Resend OTP**.
5. To change the number you started with, use the back arrow.

[Screenshot: OTP verification screen — six digit boxes with a code entered, the resend countdown, and the Verify button]

Field / control	Rule
Phone number	Required. Ethiopian international format: `+251` plus 9 digits.
Verification code	Required. Exactly 6 digits. Submitted automatically when the sixth digit is entered.
Resend OTP	Available after the 60-second countdown expires; sends a fresh code to the same number.

3.3 Sessions and signing out

- Sign-in establishes a secure, HTTP-only session cookie. No access token is stored in or exposed to the browser's JavaScript, and there is no separate refresh step.
- Session lifetime depends on the role: platform administrators (roles 3 and 6) are signed out after **24 hours**; queue staff (roles 11 and 12) remain signed in for up to **365 days**.
- If your session ends, you are returned to the sign-in screen and must request a new code.
- To sign out, open your account area or go to **Settings** → **Sign Out** (§14).

Role	Session lifetime
Queue Organization Admin (11), Queue Dispatcher (12)	365 days
Platform Admin (3), Super Admin (6)	24 hours

Keep your number current

The one-time code is sent to the mobile number on the account. If your number changes you will not be able to sign in until it is updated on the account.

4. Creating and registering a loading place

A loading place is a *queue organization* — the site whose vehicle queue you manage. It must be created before the queue board is available, and it must be approved by an administrator before drivers can be dispatched.

4.1 Create the organization

1. On first sign-in, if your account has no organization yet, the console opens the **Setup Organization** screen (also shown as a **Create Organization** dialog from the dashboard).
2. Enter the organization name (for example, "Addis Freight Terminal").
3. Choose the organization type from the list below.
4. Optionally enter a contact phone number for the loading place.
5. Enter the address and select the matching suggestion from the address search. Selecting a suggestion records the location's latitude and longitude — this location is the site reference used by the queue and as the check-in gate.
6. Select **Create Organization**. A new organization starts in **pending** approval status.

[Screenshot: Setup Organization screen — name, type, phone, and address search with a selected suggestion showing the resolved location]

Field	Required	Notes
Organization name	Yes	The display name used across the console.
Organization type	Yes	One of the types listed in §4.2.
Contact phone	No	Ethiopian format, `+251` plus digits.
Address (with location)	Yes	Chosen from the address search; the selected suggestion supplies the latitude and longitude that define the site location.

4.2 Organization types

The console accepts one of the following loading-place types.

Type (label)	Type (stored value)
Customs	`customs`
Factory	`factory`
Cement	`cement`
Depot	`depot`
Mine	`mine`
Farm	`farm`
Port	`port`
Other	`other`

> **Check-in radius**
>
> The check-in gate uses a radius around the organization's location. The radius is a system setting (default **15 km**) applied by the platform; it is not entered on the create-organization form. If your operational radius needs to differ from the default, raise it with the platform administrator.

4.3 Approval statuses

Each organization has an approval status shown as a badge on the manage page and the organization list.

Status	Meaning
Pending	Newly created; awaiting administrator review. The queue is not enabled.
Approved	The organization is enabled and its queue is live.
Rejected	The application was declined by an administrator.
Suspended	An approved organization whose queue has been disabled by an administrator.

4.4 Managing a loading place

Open **Organizations** and select a loading place to open the manage page. It contains the organization profile, the member list, and — for queue administrators — the approval controls.

- **Profile** — update name, type, phone and address/location. Saving a new address updates the site location.
- **Members** — add a member by user identifier and role, and deactivate, reactivate or remove members. Membership itself is the permission, so a lifecycle change takes effect on the member's next request.
- **Approval (queue administrators only)** — **Approve**, **Suspend** or **Reject** the organization. Approving enables the queue; suspending or rejecting disables it.

[Screenshot: Manage Organization page — profile form, members table, and the approval actions available to a queue administrator]

> **Approval is required before dispatch**
>
> Drivers can only be dispatched once the organization's status is **Approved**. While it is pending, rejected or suspended, use the queue board for preparation only.

5. The dashboard

The dashboard is where you choose which loading place to work in and see your organization's summary. It is the landing page after sign-in.

5.1 The organization overview

- **Organization cards** — each loading place you can access is shown with its type, name and approval badge. Select one to open its live queue.
- **Create organization** — opens the same create dialog described in §4 for accounts that can add another loading place.
- **Summary figures** — the overview shows the organization's operating figures, including drivers, waiting vehicles and orders.

[Screenshot: Dashboard — organization list with approval badges and the overview summary figures]

> **Dashboard figures are computed in the console**
>
> The summary figures shown on the dashboard and in Reports are calculated in the console from the data it has loaded. They are suitable for operational monitoring; treat them as working figures rather than an audited source of record. See §11.

6. The live queue board

The live queue board (**Live Queue**) is the operational heart of the console. It shows the vehicles currently in the queue for the selected loading place, grouped by vehicle type, and lets you check drivers in and dispatch them.

6.1 The board header

- **Live / Connecting badge** — a coloured badge next to the title shows whether the real-time connection is live. See §12.
- **New Order** — opens the create-order dialog (§9).
- **Manual Check-in** — opens the check-in dialog to add a driver to the queue (§7).

6.2 Vehicle-type cards

The board shows one card per vehicle type that has drivers in the queue, plus a card for all drivers. Each vehicle-type card shows the number of waiting vehicles and a **Dispatch** button.

- **Dispatch** is enabled only when there is at least one waiting vehicle for that type. When the waiting count is zero the button is disabled.
- The **All Drivers** card lists every driver in the queue regardless of vehicle type.
- Select a card to open the queue table for that vehicle type.

[Screenshot: Live queue board — vehicle-type cards with waiting counts and Dispatch buttons, plus the All Drivers card and the Live badge]

6.3 The queue table

The queue table lists each driver in the queue with their assigned position. On narrow screens the table is replaced by stacked cards that carry the same information.

Column	Shows
Positions	The driver's place in the queue (FIFO position).
Driver	The driver's name.
Phone	The driver's phone number.
Address	The driver's last known address/place.
Shipper Name / Phone	The shipper associated with the driver's order, if any.
Joined	When the driver joined the queue.
Status	The driver's current queue status (see §8.4).
Action	Row actions such as dispatch, override, remove and history.

7. Check-in

Check-in adds a driver to the queue. Use the **Manual Check-in** action on the queue board to open the check-in dialog.

7.1 Checking a driver in

1. On the live queue board, select **Manual Check-in**.
2. Search for the driver. The search covers the driver directory and the current queue, and matches on the details shown for each driver (such as name and phone).
3. Select the driver from the results.
4. Optionally enter a queue number to place the driver at a specific position. If you leave it blank, the driver is appended to the end of the queue by the usual first-in, first-out (FIFO) rule.
5. Confirm the check-in. The driver appears on the queue board with their position.

[Screenshot: Check-in dialog — driver search results, the selected driver, and the optional queue number field]

> **Positions and the optional queue number**
>
> Leaving the queue number empty means the platform assigns the next FIFO position. Enter a number only when you deliberately need to place a driver at a specific position; the override action (§8.3) is available later if you need to correct a position.

8. Running the queue

This section covers the day-to-day operations on the queue board: dispatching, overriding a position, removing an entry, and reviewing an entry's history.

8.1 Dispatching a vehicle

1. On the queue board, find the vehicle-type card with waiting drivers.
2. Select **Dispatch** (enabled only when at least one vehicle is waiting).
3. In the dispatch dialog, choose the order to dispatch the front waiting vehicle to. The dialog shows a summary of the shipper request for the selected order.
4. Confirm. The vehicle is dispatched and its status changes accordingly.

[Screenshot: Dispatch dialog — order selection and the shipper-request summary for the chosen order]

8.2 Dispatch is tied to waiting vehicles

The **Dispatch** button on a vehicle-type card is disabled whenever that card's waiting count is zero. To dispatch, first check a driver in (§7) or select a different vehicle-type card that still has waiting vehicles.

8.3 Overriding a position

1. Open the row action for the driver and choose **Override**.
2. Enter the new queue number and a reason for the change.
3. Confirm. The driver's position is updated and the change is recorded.

[Screenshot: Override dialog — new queue number and reason field]

8.4 Removing an entry

1. Open the row action for the driver and choose **Remove**.
2. Enter a reason when prompted and confirm.
3. The driver is removed from the queue. The reason is communicated to the affected party through the live connection.

> **Removal reasons**
>
> The removal dialog asks for a reason and the reason text is broadcast to the queue's live listeners. Enter a clear, factual reason so the driver's app reflects an accurate explanation.

8.5 Entry history

Each queue entry keeps an immutable history. Open the row action and choose **History** to see the recorded before-and-after snapshots for the entry — for example, its original position and any later override.

[Screenshot: Entry history dialog — before/after snapshots for a queue entry]

8.6 Queue statuses

Status	Meaning
Waiting	In the queue, waiting for dispatch.
Offered	An order has been offered to the driver.
Loaded	The vehicle has been loaded.
Removed	The entry was removed from the queue.
Completed	The vehicle's job is complete.

9. Orders and shipper requests

The **Orders** area lists the orders and shipper requests for your loading place, and is where you create new orders and review driver requests against a shipper's request.

9.1 Creating an order

1. On the queue board select **New Order**, or use the create action in the Orders area.
2. Choose the **Request Type**: *individual target* (a specific vehicle slot) or *company target* (open to carriers).
3. Choose the **Dispatch Mode**: **FIFO Queue** (auto-offer to the front waiting driver) or **Open for Bidding** (a biddable job for carriers).
4. Enter the shipper's phone number and choose the vehicle type.
5. Enter the cargo details: item, quantity in quintals, cost, number of vehicles, and the shipping and delivery dates. Quantity per vehicle cannot exceed the selected vehicle type's carrying capacity.
6. Enter the origin and destination by searching the address field and selecting the matching suggestion, which records the coordinates for each place. The origin defaults to the loading place's location.
7. Select **Create Order**. The order is created and offered to the queue.

Field	Notes
Request Type	Individual target or company target.
Dispatch Mode	FIFO Queue, or Open for Bidding (see §10).
Shipper phone	Ethiopian format, `+251` plus digits.
Vehicle type	Selects the queue lane the order is dispatched on.
Cargo and quantity	Capped by the selected vehicle type's capacity.
Cost and dates	Shipping and delivery dates; the shipping date cannot be in the past.
Origin / destination	Address search records place names and coordinates.

[Screenshot: Create Order dialog — request type, dispatch mode, shipper, vehicle type, cargo, and origin/destination with map coordinates]

> **Large orders default to company target and bidding**
>
> When the number of vehicles for an individual order is set above nine, the console automatically switches the request to a company target and turns on open bidding. This is by design — very large volumes are offered to carriers rather than a single queue slot.

9.2 The orders list

The orders list shows each order with its identifier, shipper, vehicle type, cargo, route, quantity and cost. Multi-vehicle orders are grouped into a single batch row that summarises the vehicles and their journey stages, and can be expanded to show each vehicle.

- **Journey stage** — each order shows its current stage (for example, accepted, loading, in transit, completed). See §17 for the journey-status glossary.
- **Bidding indicator** — orders that are open for bidding are marked as such.

[Screenshot: Orders list — an expanded multi-vehicle batch row showing individual vehicles and their journey stages]

9.3 Shipper requests and driver acceptance

1. Open a shipper's request to see its overview (cargo, route, dates and status).
2. If there are driver requests against it, each is listed with the driver's details and offer.
3. Select **Accept** on a driver request to accept that driver for the shipper request. Repeat for other drivers as needed.
4. Use **View All Orders** to open the full orders list filtered to that shipper.

[Screenshot: Shipper requests dialog — request overview and the list of driver requests with Accept actions]

10. Bidding on behalf of shippers

When an order is opened for bidding, carriers/drivers place offers. As the queue organization you review the offers on the shipper's behalf and accept the driver you judge best.

10.1 Who can open bidding

> **Bidding is restricted**
>
> The bidding control is available only to the **Queue Organization Admin** (role 11) for an order that belongs to their organization, and to the **Super Admin** (role 6). A **Queue Dispatcher** (role 12) does not see the control, and the platform refuses the action if attempted — a dispatcher can still run the queue and orders, but cannot open bidding on a shipper's behalf.

10.2 Opening an order for bidding

1. In the Orders area, select the order you want to open for bidding.
2. Use the bid toggle to turn bidding on for that order.
3. The toggle itself is per order: an order either has bidding approved or not. Turning it on publishes the order as a biddable job for carriers.

10.3 Reviewing offers and accepting a driver

1. Open the order's driver bids.
2. Use the toolbar to **search** by driver name, phone or plate, choose a **sort** order, and set a **display limit**.
3. Compare the offers. Each offer shows the driver's details, their offer, and — where available — distance and vehicle information.
4. Select **Accept** on the offer you want. The console accepts that specific driver's bid.

Sort option	Orders offers by
Nearest Distance First	Closest driver to the pickup.
Lowest Offer First	Lowest offer amount.
Highest Offer First	Highest offer amount.
Driver Name (A–Z)	Driver name, alphabetically.
Default Order	The platform's default ordering.

[Screenshot: Driver bids board — toolbar with search, sort and display limit, and the list of driver offers with Accept actions]

10.4 Bid statuses

Status	Meaning
Selected	The bid was accepted for the order.

Status	Meaning
Not selected	The bid was reviewed but not accepted.
Withdrawn	The driver withdrew the bid before a decision.
Expired	The bid is no longer actionable.

Accepting requires the exact bid

The console only accepts a bid when it can identify the specific driver and decision from the loaded bid list. If those identifiers are not available it reports a clear error instead of guessing which driver to accept. Reload the bids and try again if this occurs.

11. Reporting and analytics

The **Reports** area summarises activity for the loading place using key figures and simple charts, plus a searchable list of organizations.

11.1 Key figures

KPI card	Shows
Total Driver	The number of drivers known to the organization.
Waiting Now	The number of vehicles currently waiting in the queue.
Orders Now	The number of active orders.
Total Organizations	The number of loading places in the report scope.

11.2 Charts and the organization list

- **Donut chart** — a proportional view of the current distribution (for example, waiting by category).
- **Monthly bar chart** — activity over recent months.
- **Organization report list** — a list of organizations with search, sortable columns and pagination (five rows per page).

[Screenshot: Reports page — KPI cards, the donut and monthly bar charts, and the organization report list]

> **How the figures are produced**
>
> The figures and charts on this page are computed in the console from the data it has loaded, not from a dedicated analytics service. They are intended for operational monitoring. A built-in PDF export of these reports is not confirmed; use your browser's print function if a printable copy is required, and treat the figures as working values.

12. Real-time notifications and connection status

The console keeps a live connection to the platform so that queue changes — check-ins, dispatches, removals, bids and organization updates — appear without a manual refresh.

12.1 The live connection

- The queue board shows a **Live** badge when the real-time connection is open, and a **Connecting** badge while it is re-establishing.
- Queue staff (roles 11 and 12) receive queue events through a shared queue-organization channel, so both administrators and dispatchers see the same live updates.
- When the connection drops, the console shows a disconnected state and automatically retries. It makes up to **five** reconnection attempts with a short delay between them (starting at about 1.5 seconds and backing off up to about 5 seconds).
- If the retry delivers the underlying data again, the board returns to **Live** and refreshes the affected lists.

[Screenshot: Live queue board showing the Connecting / disconnected state and the returning Live badge]

12.2 What triggers a live update

- A driver checking in or being removed from the queue.
- A vehicle being dispatched or its position overridden.
- An order or shipper request changing, or a bid being placed or accepted.
- An organization being approved, updated or its members changing.

> **If the badge stays on Connecting**
>
> Check your network connection and try reloading the page. If your session has expired, the connection is closed deliberately and you are signed out — sign in again with a one-time code (§3). See §16 for more.

13. Security compliance view

The **Security** area presents the console's INSA security compliance information. It is a reference and tracking view; it does not change the security of the running system.

13.1 The tabs

Tab	Shows
Overview	A summary of the compliance position and counts.
Requirements	The INSA requirements grouped by the five focus areas.
Vulnerabilities	The tracked vulnerabilities and their status.
Testing	The security test checklist with pass/fail tracking.

13.2 Tabs, requirements and testing

- The standard is organised into five focus areas (numbered 2.1 to 2.5), with a set of requirements and tests and a set of tracked vulnerabilities.
- In the **Testing** tab you can mark each test as passed or failed. The counts and progress shown on the page are computed from those marks.

> **Where test tracking is stored**
>
> Pass/fail marks you record in the Testing tab are saved in this browser (local storage). They persist across reloads on the same browser and device, but they are not shared between users, browsers or devices. Selecting a test's active status again clears it; a test with no mark is shown as untested. Treat the marks as a local working checklist for this submission.

[Screenshot: Security compliance view — the Testing tab with pass/fail controls and the computed progress summary]

14. Settings

Settings is where you control your account, language and appearance for the console.

14.1 What you can change

- **Language** — switch the interface between English and Amharic (§15).
- **Appearance** — switch between light and dark theme (§15).
- **Sign Out** — end your session and return to the sign-in screen.

14.2 Account options that are not enabled

> **Disabled in this release**
>
> Profile editing, notification preferences and two-factor authentication appear in the account area but are **not enabled** in this release, and are shown with an explanatory label. There is no server-side endpoint behind them, so they do not save any change. Do not rely on them to update your account; contact the platform administrator for account changes.

14.3 Danger zone

A danger zone provides an account-deletion action, protected by a confirmation dialog. This is a destructive, account-level action; use it only when the account is genuinely to be removed.

[Screenshot: Settings page — language and appearance controls, Sign Out, the disabled account options with their explanatory labels, and the danger zone]

15. Language and appearance

15.1 Language

- The console runs in **English** or **Amharic**. Use the language selector on the sign-in screen or in **Settings**.
- Your choice is saved in the browser and applied on your next visit to the console on the same browser and device.

15.2 Appearance

- The console supports a **light** and a **dark** theme. The theme control is in **Settings**.
- Your theme choice is saved in the browser and applied on your next visit on the same browser and device.

[Screenshot: The console in dark theme with the Amharic interface selected]

> **Saved per browser**
>
> Language and theme choices are stored in the browser, so they are specific to this browser and device and do not follow your account to another device.

16. Troubleshooting and FAQ

16.1 Common situations

Symptom	What to do
I did not receive the one-time code.	Wait for the 60-second countdown and select **Resend OTP**. Confirm the number is correct for your account.
I am signed out unexpectedly.	Administrator sessions last 24 hours. Sign in again with a fresh code; queue staff sessions last much longer.
The Dispatch button will not activate.	That vehicle-type card has no waiting vehicles. Check a driver in (§7) or choose a card with waiting vehicles.
I cannot find the bidding control.	Bidding is only available to the queue administrator (and Super Admin) for their own organization; dispatchers do not see it (§10.1).
The Live badge stays on Connecting.	Check your network, then reload. If your session expired you will be returned to the sign-in screen (§12).
My theme or language reset.	These are saved per browser and device; they do not follow your account. Set them again in Settings (§15).
My profile or notification changes do not save.	Those options are disabled in this release and have no server endpoint (§14.2).
The reports figures look different from another screen.	Report figures are computed in the console from loaded data and are working values (§11). Refresh to load the latest data.

16.2 Frequently asked questions

- **Can I sign in with a username and password?** No. Access is by phone number and one-time code only.
- **Can a dispatcher open bidding?** No. Only the queue administrator for the owning organization (and the Super Admin) can.
- **Where is my check-in radius set?** It is a platform setting (default 15 km), not a field on the organization form (§4).
- **Are the security checklist marks shared with my team?** No. They are stored in your browser only (§13).

17. Glossary and support contacts

17.1 Glossary

Term	Meaning
Loading place / Queue organization	The site whose vehicle queue this console manages (for example, a customs terminal, factory, depot, mine, farm or port).
Queue Organization Admin	Role 11 — owns the loading place and can approve/suspend it.
Queue Dispatcher	Role 12 — runs the queue but cannot manage bidding.
Check-in	Adding a driver to the queue and assigning a position.
FIFO	First-in, first-out — the default order in which waiting vehicles are dispatched.
Dispatch	Sending the front waiting vehicle of a vehicle type to an order.
Override	Deliberately changing a driver's queue position.
Shipper request	A shipper's request for carriage, which queue staff can accept drivers against.
Bidding	Carriers offering on an order; queue staff accept the chosen offer.
Offer / Bid	A carrier's proposal (price and details) for a biddable order.
OTP	The six-digit one-time code sent to your phone to sign in.
Journey status	The stage of a dispatched vehicle's job, from accepted through loading, in transit and completed.

17.2 Support contacts

Channel	Detail
Support email	`mmarew@gmail.com`
Support telephone	`0983222221`
Support hours	Monday–Friday, 09:00–17:00 (East Africa Time); messages outside these hours are answered the next working day
Escalation / account issues	Marew Masresha, General Manager, Dynamics Transport — `mmarew@gmail.com` , `0983222221`

Document control

This End User Guide (**UG-1.0.0**) describes Dynamics Queue Admin version **1.0.0** as implemented in the submitted release. It is issued with the Software Requirements Specification (SRS), the Software Design Description (SDD), the Technical Design / Low-Level Design (TDD/LLD) and the Security Documentation.

Item	Value
Document identifier	UG-1.0.0 — End User Guide (dispatch-queue console)
Product and version	Dynamics Queue Admin web console, v1.0.0
Coverage	Loading-place registration, dashboard, live queue board, check-in, dispatch and queue running, orders and shipper requests, bidding on behalf of shippers, reports, real-time connection, security compliance view, settings, language and appearance
Related documents	SRS, SDD, TDD/LLD, Security Documentation
Items to complete before submission	Screenshots marked **[Screenshot: …]** must be captured and inserted. Submitting entity, contact person, support contacts, escalation contact and dates are completed.
Revision	1.0.0 — initial issue