Transfer Data Flow Diagrams

Leon Starr
2026-4-24/ v1.3.2

Copyright © 2025-2026, Leon Starr at
MODEL INTEGRATION, LLC

Delegated Creation Activity

A58





Initialization Sources



Copyright © 2025-2026, Leon Starr at Model Integration, LLC

A58

Added Tint/Color attributes to test setting of explicit and default scalar attribute values



A46

WAITING FOR CABIN

New transfer -> /R53/Cabin
Set destination(dest: Destination floor) -> ~UI



Copyright © 2025-2026, Leon Starr at Model Integration, LLC

A51

Changing destination before cabin moves

```
// The cabin isn't moving, so we can safely
//     relink to the new destination
&R53 Accessible Shaft Level(Floor: ^new dest; Shaft: Shaft)
Stationary update -> me
```



Copyright © 2025-2026, Leon Starr at Model Integration, LLC

A52

Check for cabin reversal

```
// If the Cabin arrives and there is a floor request in the opposite direction
// and no stop request or call in the Cabin's current travel direction,
// we must reverse the cabin's travel direction
//
call behind .= /R53/Accessible Shaft Level/R49/Floor Service(1, Direction: /R53/Cabin.Travel direction.opposite )
call fwd .= /R53/Accessible Shaft Level/R49/Floor Service(1, Direction: /R53/Cabin.Travel direction )
switch dir = (call behind and !call fwd and !/R53/Accessible Shaft Level.Stop requested)
switch dir? /R53/Cabin.Travel direction.toggle

Reversal checked -> me
```

call behind .= /R53/Accessible Shaft Level/R49/Floor Service(1, Direction: /R53/Cabin.Travel direction.opposite)



A52

Check for cabin reversal

```
// If the Cabin arrives and there is a floor request in the opposite direction
// and no stop request or call in the Cabin's current travel direction,
// we must reverse the cabin's travel direction
//
call behind .= /R53/Accessible Shaft Level/R49/Floor Service(1, Direction: /R53/Cabin.Travel direction.opposite )
call fwd .= /R53/Accessible Shaft Level/R49/Floor Service(1, Direction: /R53/Cabin.Travel direction )
switch dir = (call behind and !call fwd and !/R53/Accessible Shaft Level.Stop requested)
switch dir? /R53/Cabin.Travel direction.toggle

Reversal checked -> me
```

call fwd .= /R53/Accessible Shaft Level/R49/Floor Service(1, Direction: /R53/Cabin.Travel direction)



Copyright © 2025-2026, Leon Starr at Model Integration, LLC

A52

Check for cabin reversal

```
// If the Cabin arrives and there is a floor request in the opposite direction
// and no stop request or call in the Cabin's current travel direction,
// we must reverse the cabin's travel direction
//
call behind .= /R53/Accessible Shaft Level/R49/Floor Service(1, Direction: /R53/Cabin.Travel direction.opposite )
call fwd .= /R53/Accessible Shaft Level/R49/Floor Service(1, Direction: /R53/Cabin.Travel direction )
switch dir = call behind and !call fwd and !/R53/Accessible Shaft Level.Stop requested
switch dir? /R53/Cabin.Travel direction.toggle

Reversal checked -> me
```

switch dir = call behind and !call fwd and !/R53/Accessible Shaft Level.Stop requested



Copyright © 2025-2026, Leon Starr at Model Integration, LLC

A52

Check for cabin reversal

```
// If the Cabin arrives and there is a floor request in the opposite direction
// and no stop request or call in the Cabin's current travel direction,
// we must reverse the cabin's travel direction
//
call behind .= /R53/Accessible Shaft Level/R49/Floor Service(1, Direction: /R53/Cabin.Travel direction.opposite )
call fwd .= /R53/Accessible Shaft Level/R49/Floor Service(1, Direction: /R53/Cabin.Travel direction )
switch dir = call behind and !call fwd and !/R53/Accessible Shaft Level.Stop requested
switch dir? /R53/Cabin.Travel direction.toggle

Reversal checked -> me
```



Copyright © 2025-2026, Leon Starr at Model Integration, LLC

A53

Check for active floor service

```
Cabin arrived( Shaft, direction: /R53/Cabin.Travel direction ) -> ~UI
pending floor service .= /R53/Accessible Shaft Level/R49/Floor Service(1, Direction: /R53/Cabin.Travel direction )

pending floor service? {
   Call in progress -> me
   Cabin arrived -> pending floor service
} : {
   Stop serviced -> /R53/Accessible Shaft Level
   Wait to clear -> me
}
```



Copyright © 2025-2026, Leon Starr at Model Integration, LLC